

Standard Operating Procedure (SOP)
for
Uninstallation of SentinelOne EDR Agent from NICNET Endpoints

1. Purpose

To provide a standardized procedure for uninstallation of the existing SentinelOne Endpoint Detection and Response (EDR) Agent from NICNET endpoints running Windows, Linux and macOS.

2. Scope

This SOP covers the local uninstallation of the SentinelOne EDR Agent from supported endpoint operating systems using the procedures supplied for Windows, Linux and macOS.

- (a). Windows endpoints – command-line based uninstallation.
- (b). Linux endpoints – sentinelctl based uninstallation.
- (c). macOS endpoints – sentinelctl unprotect followed by local uninstall.

3. Prerequisites

- (a). Ensure appropriate administrative/root privileges are available on the endpoint.
- (b). Ensure the applicable SentinelOne Agent passphrase is available.
- (c). For Windows, identify the installed SentinelOne Agent version and the corresponding Agent UUID/passphrase.
- (d). For macOS, ensure the SentinelOne Agent can be unprotected using the applicable passphrase.

4. Uninstallation Procedure

4.1 Windows Endpoints

- (a). Search for the Agent Passphrase using the UUID of the Agent from the provided list of passphrases.
- (b). Open Command Prompt as Administrator.
- (c). From Windows Command Prompt, navigate to the SentinelOne Agent directory:
cd "C:\Program Files\SentinelOne\Sentinel Agent <version>"
- (d). Execute the SentinelOne Agent uninstall command:
uninstall.exe /uninstall /norestart /q /k "<passphrase>"
- (e). Replace <version> with the corresponding Agent version and <passphrase> with the corresponding Agent passphrase.
- (f). Reboot the Windows endpoint to ensure that all remnants of the Agent are removed.

4.2 Linux Endpoints

- (a). Log in as root. The supplied procedure specifies that sudo alone is not sufficient.
- (b). Run the following sentinelctl command with the applicable passphrase:

```
sudo /opt/sentinelone/bin/sentinelctl control uninstall --passphrase "Passphrase"
```

Note: A reboot is not required. The Agent can be installed again immediately after the uninstall.

4.3 macOS Endpoints

- (a). Open a Terminal application.
- (b). Use the SentinelOne Agent passphrase to unprotect the Agent:

```
$ sudo sentinelctl unprotect --passphrase "passphrase"
```
- (c). After SentinelOne protection has been disabled, uninstall the local Agent:

```
$ sudo sentinelctl uninstall --local
```

5. Post-uninstallation verification

- (a). Confirm that the SentinelOne Agent has been successfully uninstalled from the endpoint.
- (b). For Windows endpoints, reboot after uninstallation as specified in this SOP.
- (c). For Linux endpoints, no reboot is required according to the supplied procedure.
- (d). For macOS endpoints, confirm completion of the local Agent uninstall command.

6. Important Notes

Use only the agent-specific passphrase applicable to the endpoint being uninstalled.

7. Support and queries

Please contact NIC Endpoint security support team for any query or issues.

Email: epssupport@nic.in

Phone: 011-24305119/5138/5147