

DML Transaction Visualizer

Post-Deployment Configuration Guide

Document Purpose	Configure the OAuth-based Tooling API connection required by the DML Transaction Visualizer after package installation.
------------------	---

Configuration Flow

External Client App → Auth Provider → External Credential → DML_Admin Principal → Named Credential → Permission Set → Principal Authentication → Verification

One-time, per-org configuration after package installation.

1. Overview

This guide contains the required one-time configuration steps to enable Tooling API callouts after installing the DML Transaction Visualizer package in a Salesforce org.

2. Prerequisites

- The DML Transaction Visualizer package must be installed successfully.
- The user performing this setup must have the required Salesforce Setup permissions to create and configure External Client Apps, Auth Providers, External Credentials, Named Credentials, and Permission Sets.
- The Salesforce org should have My Domain configured.
- Access to a Salesforce user account that can authorize the OAuth connection is required.

3. Configuration Steps

1 Create an External Client App

1. Go to Setup.
2. In Quick Find, search for External Client Apps.
3. Open External Client Apps.
4. Click New External Client App.

Field	Value
External Client App Name	DML Tooling App
API Name	DML_Tooling_App
Contact Email	<your email address>

Enable OAuth Settings

Field	Value
Callback URL	https://login.salesforce.com/services/oauth2/callback
OAuth Scope	Manage user data via APIs (api)
OAuth Scope	Perform requests at any time (refresh_token, offline_access)

5. Click Save.
6. Open the External Client App details.
7. Locate the Consumer Key and Consumer Secret.
8. Copy and securely store both values. They are required in Step 2.

Important: Depending on the Salesforce release and org configuration, the External Client App interface may use slightly different labels. Use the OAuth configuration section within the External Client App to configure the callback URL and scopes.

2 Create an Auth Provider

1. Go to Setup.
2. In Quick Find, search for Auth. Providers.
3. Click New.
4. Select Salesforce as the Provider Type.

Field	Value
Name	DML Tooling Auth
URL Suffix	DMLToolingAuth
Consumer Key	<Consumer Key from Step 1>
Consumer Secret	<Consumer Secret from Step 1>
Authorize Endpoint URL	https://login.salesforce.com/services/oauth2/authorize
Token Endpoint URL	https://login.salesforce.com/services/oauth2/token
Default Scopes	api refresh_token

5. Click Save.
6. On the Auth Provider detail page, locate the generated Callback URL.
7. Copy the Callback URL.
8. Go to Setup → External Client Apps.
9. Open DML Tooling App → Edit.
10. Replace the temporary Callback URL from Step 1 with the Callback URL generated by the Auth Provider.
11. Save the External Client App.

3 Create an External Credential

1. Go to Setup.
2. Search for Named Credentials.
3. Open the External Credentials tab.
4. Click New.

Field	Value
Label	DML Tooling External
Name	DML_Tooling_External
Authentication Protocol	OAuth 2.0
Authentication Flow Type	Browser Flow
Scope	api refresh_token
Identity Provider	DML Tooling Auth

5. Click Save.

4 Create the DML_Admin Principal

1. Open the DML_Tooling_External External Credential.
2. Scroll to the Principals section.

3. Click New.

Field	Value
Parameter Name	DML_Admin
Sequence Number	1
Identity Type	Named Principal

4. Click Save.

Important: The DML_Admin principal must be authenticated before the package can use the Tooling API connection.

5 Create a Named Credential

1. Go to Setup → Named Credentials.

2. Click New.

Field	Value
Label	DML Tooling
Name	DML_Tooling
URL	<Salesforce My Domain URL>
External Credential	DML_Tooling_External
Generate Authorization Header	Checked

Important: The URL must point to the Salesforce org where the package is installed.

Configure Managed Package Access

In the Managed Package Access section, add the package namespace under Allowed Namespaces for Callouts:

dmlviz

Important: The dmlviz namespace is required so that the package's namespaced Apex code can use the Named Credential for callouts.

3. Click Save.

6 Create and Assign the Permission Set

Create Permission Set

1. Go to Setup.
2. Search for Permission Sets.
3. Click New.
4. Set the Label to DML Tooling Access.
5. Click Save.

Grant External Credential Principal Access

1. Open the DML Tooling Access Permission Set.
2. Open External Credential Principal Access.
3. Click Edit.
4. Move DML_Tooling_External – DML_Admin to Enabled External Credential Principals.

5. Click Save.

Assign the Permission Set

1. Click Manage Assignments.
2. Click Add Assignment.
3. Select the user who will authenticate and use the DML Transaction Visualizer.
4. Click Assign.

Important: The user who authenticates the DML_Admin principal must have the DML Tooling Access Permission Set assigned.

7 Authenticate the DML_Admin Principal

The DML_Admin principal must be authenticated to establish the OAuth connection.

1. Go to Setup → Named Credentials.
2. Open the External Credentials tab.
3. Open DML_Tooling_External.
4. In the Principals section, locate DML_Admin.
5. Open the action menu next to DML_Admin.
6. Select Authenticate.
7. Sign in using the Salesforce user who has been assigned the DML Tooling Access Permission Set.
8. Click Allow when prompted.

Verify Authentication

Confirm that the status of the DML_Admin principal is:

Authenticated

Important: Do not proceed until the DML_Admin principal shows Authenticated.

8 Verify the Configuration

After completing all configuration steps, verify the following:

Configuration	Expected Value / Status
External Client App	DML Tooling App
Auth Provider	DML Tooling Auth
External Credential	DML_Tooling_External
Principal	DML_Admin
Principal Status	Authenticated
Named Credential	DML_Tooling
Permission Set	DML Tooling Access
Package Namespace	dmlviz
Named Credential URL	Current Salesforce org's My Domain URL

Once all items are configured correctly, the DML Transaction Visualizer is ready to make the required Tooling API callouts.

9 Configuration Summary

Component	Configuration Name
External Client App	DML Tooling App
Auth Provider	DML Tooling Auth
External Credential	DML_Tooling_External
External Credential Principal	DML_Admin
Named Credential	DML_Tooling
Permission Set	DML Tooling Access
Package Namespace	dmlviz

10 Post-Deployment Checklist

Use this checklist to confirm that the deployment configuration is complete:

- ☐ OAuth configuration completed successfully
- ☐ DML_Tooling_External External Credential created
- ☐ DML_Admin principal created and Authenticated
- ☐ DML_Tooling Named Credential created with the correct org My Domain URL
- ☐ dmlviz added under Allowed Namespaces for Callouts
- ☐ DML Tooling Access Permission Set assigned to the required user
- ☐ Tooling API callout verified successfully

Configuration Complete

The DML Transaction Visualizer is ready for use once all checklist items are confirmed.