



**redhat.**<sup>®</sup>

# **OpenShift Container Platform 3.9**

## **Installation and Configuration**

OpenShift Container Platform 3.9 Installation and Configuration



# OpenShift Container Platform 3.9 Installation and Configuration

OpenShift Container Platform 3.9 Installation and Configuration

## **Legal Notice**

Copyright © 2018 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## **Abstract**

OpenShift Installation and Configuration topics cover the basics of installing and configuring OpenShift in your environment. Use these topics for the one-time tasks required to get OpenShift up and running.

## Table of Contents

<b>CHAPTER 1. OVERVIEW .....</b>	<b>21</b>
<b>CHAPTER 2. INSTALLING A CLUSTER .....</b>	<b>22</b>
<b>2.1. PLANNING</b>	<b>22</b>
2.1.1. Initial Planning	22
2.1.2. Installation Methods	22
2.1.3. Sizing Considerations	23
2.1.4. Environment Scenarios	23
2.1.4.1. Single Master and Node on One System	23
2.1.4.2. Single Master and Multiple Nodes	23
2.1.4.3. Single Master, Multiple etcd, and Multiple Nodes	23
2.1.4.4. Multiple Masters Using Native HA with Co-located Clustered etcd	24
2.1.4.5. Multiple Masters Using Native HA with External Clustered etcd	24
2.1.4.6. Stand-alone Registry	25
2.1.5. RPM Versus Containerized	25
<b>2.2. PREREQUISITES</b>	<b>25</b>
2.2.1. System Requirements	25
2.2.1.1. Red Hat Subscriptions	25
2.2.1.2. Minimum Hardware Requirements	25
2.2.1.3. Production Level Hardware Requirements	27
2.2.1.4. Red Hat Gluster Storage Hardware Requirements	28
2.2.1.5. Optional: Configuring Core Usage	28
2.2.1.6. SELinux	28
2.2.1.7. Red Hat Gluster Storage	29
Optional: Using OverlayFS	29
2.2.1.8. Security Warning	29
2.2.2. Environment Requirements	30
2.2.2.1. DNS	30
2.2.2.1.1. Configuring Hosts to Use DNS	31
2.2.2.1.2. Configuring a DNS Wildcard	32
2.2.2.2. Network Access	32
2.2.2.2.1. NetworkManager	33
2.2.2.2.2. Configuring firewalld as the firewall	33
2.2.2.2.3. Required Ports	33
2.2.2.3. Persistent Storage	36
2.2.2.4. Cloud Provider Considerations	36
2.2.2.4.1. Overriding Detected IP Addresses and Host Names	36
2.2.2.4.2. Post-Installation Configuration for Cloud Providers	37
<b>2.3. HOST PREPARATION</b>	<b>37</b>
2.3.1. Setting PATH	37
2.3.2. Operating System Requirements	38
2.3.3. Host Registration	38
2.3.4. Installing Base Packages	39
2.3.5. Installing Docker	40
2.3.6. Configuring Docker Storage	41
2.3.6.1. Configuring OverlayFS	41
2.3.6.2. Configuring Thin Pool Storage	42
2.3.6.3. Reconfiguring Docker Storage	45
2.3.6.4. Enabling Image Signature Support	45
2.3.6.5. Managing Container Logs	46
2.3.6.6. Viewing Available Container Logs	47

2.3.6.7. Blocking Local Volume Usage	47
2.3.7. Ensuring Host Access	48
2.3.8. Setting Global Proxy Values	48
2.3.9. What's Next?	49
2.4. INSTALLING ON CONTAINERIZED HOSTS	49
2.4.1. RPM Versus Containerized Installation	49
2.4.2. Install Methods for Containerized Hosts	50
2.4.3. Required Images	50
2.4.4. Starting and Stopping Containers	51
2.4.5. File Paths	51
2.4.6. Storage Requirements	51
2.4.7. Open vSwitch SDN Initialization	51
2.5. QUICK INSTALLATION	52
2.5.1. Overview	52
2.5.2. Before You Begin	52
2.5.3. Running an Interactive Installation	53
2.5.4. Defining an Installation Configuration File	54
2.5.5. Running an Unattended Installation	55
2.5.6. Verifying the Installation	56
2.5.7. Uninstalling OpenShift Container Platform	56
2.5.8. What's Next?	57
2.6. ADVANCED INSTALLATION	57
2.6.1. Overview	57
2.6.2. Before You Begin	57
2.6.3. Configuring Ansible Inventory Files	57
Image Version Policy	58
2.6.3.1. Configuring Cluster Variables	58
2.6.3.2. Configuring Deployment Type	65
2.6.3.3. Configuring Host Variables	65
2.6.3.4. Configuring Master API Port	67
2.6.3.5. Configuring Cluster Pre-install Checks	67
2.6.3.6. Configuring System Containers	69
2.6.3.6.1. Running Docker as a System Container	70
2.6.3.6.2. Running etcd as a System Container	71
2.6.3.7. Configuring a Registry Location	71
2.6.3.8. Configuring a Registry Route	72
2.6.3.9. Configuring the Registry Console	73
2.6.3.10. Configuring Red Hat Gluster Storage Persistent Storage	74
2.6.3.10.1. Configuring Container-Native Storage	74
2.6.3.10.2. Configuring Container-Ready Storage	75
2.6.3.11. Configuring an OpenShift Container Registry	76
2.6.3.11.1. Configuring Registry Storage	76
Option A: NFS Host Group	76
Option B: External NFS Host	76
Upgrading or Installing OpenShift Container Platform with NFS	77
Option C: OpenStack Platform	77
Option D: AWS or Another S3 Storage Solution	77
Option E: Container-Native Storage	78
Option F: Google Cloud Storage (GCS) bucket on Google Compute Engine (GCE)	79
2.6.3.12. Configuring Global Proxy Options	79
2.6.3.13. Configuring the Firewall	80
2.6.3.14. Configuring Schedulability on Masters	81
2.6.3.15. Configuring Node Host Labels	81

2.6.3.15.1. Configuring Dedicated Infrastructure Nodes	82
2.6.3.16. Configuring Session Options	83
2.6.3.17. Configuring Custom Certificates	84
2.6.3.18. Configuring Certificate Validity	85
2.6.3.19. Configuring Cluster Metrics	85
2.6.3.19.1. Configuring Metrics Storage	85
Option A: Dynamic	86
Option B: NFS Host Group	86
Option C: External NFS Host	86
Upgrading or Installing OpenShift Container Platform with NFS	87
2.6.3.20. Configuring Cluster Logging	87
2.6.3.20.1. Configuring Logging Storage	87
Option A: Dynamic	88
Option B: NFS Host Group	88
Option C: External NFS Host	88
Upgrading or Installing OpenShift Container Platform with NFS	89
2.6.3.21. Configuring the Service Catalog	89
2.6.3.22. Configuring the OpenShift Ansible Broker	89
2.6.3.22.1. Configuring Persistent Storage for the OpenShift Ansible Broker	89
2.6.3.22.2. Configuring the OpenShift Ansible Broker for Local APB Development	91
2.6.3.23. Configuring the Template Service Broker	91
2.6.3.24. Configuring Web Console Customization	91
2.6.4. Example Inventory Files	93
2.6.4.1. Single Master Examples	93
Single Master, Single etcd, and Multiple Nodes	93
Single Master, Multiple etcd, and Multiple Nodes	94
2.6.4.2. Multiple Masters Examples	96
Multiple Masters Using Native HA with External Clustered etcd	97
Multiple Masters Using Native HA with Co-located Clustered etcd	99
2.6.5. Running the Advanced Installation	101
2.6.5.1. Running the RPM-based Installer	101
2.6.5.2. Running the Containerized Installer	102
2.6.5.2.1. Running the Installer as a System Container	102
2.6.5.2.2. Running Other Playbooks	103
2.6.5.2.3. Running the Installer as a Docker Container	103
2.6.5.3. Running Individual Component Playbooks	105
2.6.6. Verifying the Installation	106
Verifying Multiple etcd Hosts	107
Verifying Multiple Masters Using HAProxy	107
2.6.7. Optionally Securing Builds	107
2.6.8. Uninstalling OpenShift Container Platform	108
2.6.8.1. Uninstalling Nodes	108
2.6.9. Known Issues	109
2.6.10. What's Next?	109
2.7. DISCONNECTED INSTALLATION	110
2.7.1. Overview	110
2.7.2. Prerequisites	110
2.7.3. Required Software and Components	110
2.7.3.1. Syncing Repositories	111
2.7.3.2. Syncing Images	112
2.7.3.3. Preparing Images for Export	116
2.7.4. Repository Server	117
2.7.4.1. Placing the Software	118

2.7.5. OpenShift Container Platform Systems	118
2.7.5.1. Building Your Hosts	118
2.7.5.2. Connecting the Repositories	118
2.7.5.3. Host Preparation	119
2.7.6. Installing OpenShift Container Platform	119
2.7.6.1. Importing OpenShift Container Platform Component Images	119
2.7.6.2. Running the OpenShift Container Platform Installer	119
2.7.6.3. Creating the Internal Docker Registry	120
2.7.7. Post-Installation Changes	120
2.7.7.1. Re-tagging S2I Builder Images	120
2.7.7.2. Configuring a Registry Location	120
2.7.7.3. Creating an Administrative User	122
2.7.7.4. Modifying the Security Policies	122
2.7.7.5. Editing the Image Stream Definitions	122
2.7.7.6. Loading the Container Images	123
2.7.8. Installing a Router	124
2.8. INSTALLING A STAND-ALONE DEPLOYMENT OF OPENSHIFT CONTAINER REGISTRY	124
2.8.1. About OpenShift Container Registry	124
2.8.2. Minimum Hardware Requirements	125
2.8.3. Supported System Topologies	125
2.8.4. Host Preparation	125
2.8.5. Stand-alone Registry Installation Methods	125
2.8.5.1. Quick Installation for Stand-alone OpenShift Container Registry	126
2.8.5.2. Advanced Installation for Stand-alone OpenShift Container Registry	127
<b>CHAPTER 3. SETTING UP THE REGISTRY .....</b>	<b>131</b>
3.1. REGISTRY OVERVIEW	131
3.1.1. About the Registry	131
3.1.2. Integrated or Stand-alone Registries	131
3.2. DEPLOYING A REGISTRY ON EXISTING CLUSTERS	131
3.2.1. Overview	131
3.2.2. Deploying the Registry	131
3.2.3. Deploying the Registry as a DaemonSet	132
3.2.4. Registry Compute Resources	132
3.2.5. Storage for the Registry	132
3.2.5.1. Production Use	133
3.2.5.1.1. Use Amazon S3 as a Storage Back-end	133
3.2.5.2. Non-Production Use	134
3.2.6. Enabling the Registry Console	135
3.2.6.1. Deploying the Registry Console	135
3.2.6.2. Securing the Registry Console	135
3.2.6.3. Troubleshooting the Registry Console	137
3.2.6.3.1. Debug Mode	137
3.2.6.3.2. Display SSL Certificate Path	137
3.3. ACCESSING THE REGISTRY	138
3.3.1. Viewing Logs	138
3.3.2. File Storage	138
3.3.3. Accessing the Registry Directly	140
3.3.3.1. User Prerequisites	140
3.3.3.2. Logging in to the Registry	141
3.3.3.3. Pushing and Pulling Images	141
3.3.4. Accessing Registry Metrics	142
3.4. SECURING AND EXPOSING THE REGISTRY	143

3.4.1. Overview	143
3.4.2. Manually Securing the Registry	143
3.4.3. Manually Exposing a Secure Registry	146
3.4.4. Manually Exposing a Non-Secure Registry	148
3.5. EXTENDED REGISTRY CONFIGURATION	150
3.5.1. Maintaining the Registry IP Address	150
3.5.2. Whitelisting Docker Registries	151
3.5.3. Setting the Registry Hostname	151
3.5.4. Overriding the Registry Configuration	152
3.5.5. Registry Configuration Reference	154
3.5.5.1. Log	154
3.5.5.2. Hooks	154
3.5.5.3. Storage	154
3.5.5.4. Auth	155
3.5.5.5. Middleware	155
3.5.5.5.1. CloudFront Middleware	156
3.5.5.5.2. Overriding Middleware Configuration Options	157
3.5.5.5.3. Image Pullthrough	158
3.5.5.5.4. Manifest Schema v2 Support	159
3.5.5.6. OpenShift	160
3.5.5.7. Reporting	161
3.5.5.8. HTTP	161
3.5.5.9. Notifications	161
3.5.5.10. Redis	161
3.5.5.11. Health	161
3.5.5.12. Proxy	162
3.5.5.13. Cache	162
3.6. KNOWN ISSUES	162
3.6.1. Overview	162
3.6.2. Image Push Errors with Scaled Registry Using Shared NFS Volume	162
3.6.3. Pull of Internally Managed Image Fails with "not found" Error	163
3.6.4. Image Push Fails with "500 Internal Server Error" on S3 Storage	163
3.6.5. Image Pruning Fails	164
<b>CHAPTER 4. SETTING UP A ROUTER .....</b>	<b>165</b>
4.1. ROUTER OVERVIEW	165
4.1.1. About Routers	165
4.1.2. Router Service Account	165
4.1.2.1. Permission to Access Labels	165
4.2. USING THE DEFAULT HAProxy ROUTER	166
4.2.1. Overview	166
4.2.2. Creating a Router	167
4.2.3. Other Basic Router Commands	167
4.2.4. Filtering Routes to Specific Routers	168
4.2.5. HAProxy Strict SNI	169
4.2.6. TLS Cipher Suites	169
4.2.7. Highly-Available Routers	169
4.2.8. Customizing the Router Service Ports	169
4.2.9. Working With Multiple Routers	170
4.2.10. Adding a Node Selector to a Deployment Configuration	170
4.2.11. Using Router Shards	171
4.2.11.1. Creating Router Shards	173
4.2.11.2. Modifying Router Shards	175

4.2.12. Finding the Host Name of the Router	176
4.2.13. Customizing the Default Routing Subdomain	177
4.2.14. Forcing Route Host Names to a Custom Routing Subdomain	177
4.2.15. Using Wildcard Certificates	178
4.2.16. Manually Redeploy Certificates	178
4.2.17. Using Secured Routes	179
4.2.18. Using Wildcard Routes (for a Subdomain)	181
4.2.19. Using the Container Network Stack	186
4.2.20. Exposing Router Metrics	187
4.2.21. Preventing Connection Failures During Restarts	188
4.2.22. ARP Cache Tuning for Large-scale Clusters	189
4.2.23. Protecting Against DDoS Attacks	190
4.3. DEPLOYING A CUSTOMIZED HAProxy ROUTER	191
4.3.1. Overview	191
4.3.2. Obtaining the Router Configuration Template	191
4.3.3. Modifying the Router Configuration Template	192
4.3.3.1. Background	192
4.3.3.2. Go Template Actions	192
4.3.3.3. Router Provided Information	193
4.3.3.4. Annotations	197
4.3.3.5. Environment Variables	198
4.3.3.6. Example Usage	198
4.3.4. Using a ConfigMap to Replace the Router Configuration Template	200
4.3.5. Using Stick Tables	201
4.3.6. Rebuilding Your Router	203
4.4. CONFIGURING THE HAProxy ROUTER TO USE THE PROXY PROTOCOL	203
4.4.1. Overview	203
4.4.2. Why Use the PROXY Protocol?	204
4.4.3. Using the PROXY Protocol	204
4.5. USING THE F5 ROUTER PLUG-IN	208
4.5.1. Overview	208
4.5.2. Prerequisites and Supportability	208
4.5.2.1. Configuring the Virtual Servers	210
4.5.3. Deploying the F5 Router	210
4.5.4. F5 Router Partition Paths	211
4.5.5. Setting Up F5 Native Integration	212
<b>CHAPTER 5. DEPLOYING RED HAT CLOUDFORMS .....</b>	<b>215</b>
5.1. DEPLOYING {MGMT-APP} ON OPENSHIFT CONTAINER PLATFORM	215
5.1.1. Introduction	215
5.2. REQUIREMENTS FOR RED HAT CLOUDFORMS ON OPENSHIFT CONTAINER PLATFORM	216
5.3. CONFIGURING ROLE VARIABLES	217
5.3.1. Overview	217
5.3.2. General Variables	217
5.3.3. Customizing Template Parameters	218
5.3.4. Database Variables	218
5.3.4.1. Containerized (Podified) Database	218
5.3.4.2. External Database	218
5.3.5. Storage Class Variables	219
5.3.5.1. NFS (Default)	220
5.3.5.2. NFS External	220
5.3.5.3. Cloud Provider	221
5.3.5.4. Preconfigured (Advanced)	221

5.4. RUNNING THE INSTALLER	221
5.4.1. Deploying Red Hat CloudForms During or After OpenShift Container Platform Installation	221
5.4.2. Example Inventory Files	222
5.4.2.1. All Defaults	222
5.4.2.2. External NFS Storage	222
5.4.2.3. Override PV Sizes	222
5.4.2.4. Override Memory Requirements	223
5.4.2.5. External PostgreSQL Database	223
5.5. ENABLING CONTAINER PROVIDER INTEGRATION	223
5.5.1. Adding a Single Container Provider	223
5.5.1.1. Adding Manually	224
5.5.1.2. Adding Automatically	224
5.5.2. Multiple Container Providers	224
5.5.2.1. Preparing the Script	224
5.5.2.1.1. Example	225
5.5.2.2. Running the Playbook	226
5.5.3. Refreshing Providers	226
5.6. UNINSTALLING RED HAT CLOUDFORMS	226
5.6.1. Running the Uninstall Playbook	226
5.6.2. Troubleshooting	227
<b>CHAPTER 6. MASTER AND NODE CONFIGURATION .....</b>	<b>228</b>
6.1. INSTALLATION DEPENDENCIES	228
6.2. CONFIGURING MASTERS AND NODES	228
6.3. MAKING CONFIGURATION CHANGES USING ANSIBLE	228
6.3.1. Using the htpasswd command	230
6.4. MAKING MANUAL CONFIGURATION CHANGES	232
6.5. MASTER CONFIGURATION FILES	232
6.5.1. Admission Control Configuration	233
6.5.2. Asset Configuration	234
6.5.3. Authentication and Authorization Configuration	235
6.5.4. Controller Configuration	235
6.5.5. etcd Configuration	236
6.5.6. Grant Configuration	238
6.5.7. Image Configuration	238
6.5.8. Image Policy Configuration	239
6.5.9. Kubernetes Master Configuration	239
6.5.10. Network Configuration	240
6.5.11. OAuth Authentication Configuration	242
6.5.12. Project Configuration	244
6.5.13. Scheduler Configuration	245
6.5.14. Security Allocator Configuration	246
6.5.15. Service Account Configuration	246
6.5.16. Serving Information Configuration	247
6.5.17. Volume Configuration	248
6.5.18. Basic Audit	249
6.5.19. Advanced Audit	250
6.5.20. Specifying TLS ciphers for etcd	253
6.6. NODE CONFIGURATION FILES	254
6.6.1. Pod and Node Configuration	256
6.6.2. Docker Configuration	256
6.6.3. Parallel Image Pulls with Docker 1.9+	256
6.7. PASSWORDS AND OTHER SENSITIVE DATA	257

6.8. CREATING NEW CONFIGURATION FILES	258
6.9. LAUNCHING SERVERS USING CONFIGURATION FILES	258
6.10. CONFIGURING LOGGING LEVELS	259
6.11. RESTARTING OPENShift CONTAINER PLATFORM SERVICES	263
<b>CHAPTER 7. OPENSIFT ANSIBLE BROKER CONFIGURATION .....</b>	<b>265</b>
7.1. OVERVIEW	265
7.2. MODIFYING THE OPENSIFT ANSIBLE BROKER CONFIGURATION	266
7.3. REGISTRY CONFIGURATION	266
7.3.1. Production or Development	267
7.3.2. Storing Registry Credentials	268
7.3.3. Mock Registry	270
7.3.4. Dockerhub Registry	270
7.3.5. APB Filtering	270
7.3.6. Local OpenShift Container Registry	271
7.3.7. Red Hat Container Catalog Registry	272
7.3.8. ISV Registry	272
7.3.9. Multiple Registries	272
7.4. DAO CONFIGURATION	273
7.5. LOG CONFIGURATION	273
7.6. OPENSIFT CONFIGURATION	273
7.7. BROKER CONFIGURATION	274
7.8. SECRETS CONFIGURATION	275
7.9. RUNNING BEHIND A PROXY	275
7.9.1. Registry Adapter Whitelists	275
7.9.2. Configuring the Broker Behind a Proxy Using Ansible	276
7.9.3. Configuring the Broker Behind a Proxy Manually	276
7.9.4. Setting Proxy Environment Variables in Pods	277
<b>CHAPTER 8. ADDING HOSTS TO AN EXISTING CLUSTER .....</b>	<b>278</b>
8.1. OVERVIEW	278
8.2. ADDING HOSTS USING THE QUICK INSTALLER TOOL	278
8.3. ADDING HOSTS	279
Procedure	279
8.4. ADDING ETCD HOSTS TO EXISTING CLUSTER	281
8.5. REPLACING EXISTING MASTERS WITH ETCD COLOCATED	282
8.6. MIGRATING THE NODES	284
<b>CHAPTER 9. LOADING THE DEFAULT IMAGE STREAMS AND TEMPLATES .....</b>	<b>285</b>
9.1. OVERVIEW	285
9.2. OFFERINGS BY SUBSCRIPTION TYPE	285
9.2.1. OpenShift Container Platform Subscription	285
9.2.2. xPaaS Middleware Add-on Subscriptions	286
9.3. BEFORE YOU BEGIN	286
9.4. PREREQUISITES	286
9.5. CREATING IMAGE STREAMS FOR OPENSIFT CONTAINER PLATFORM IMAGES	287
9.6. CREATING IMAGE STREAMS FOR XPAAS MIDDLEWARE IMAGES	287
9.7. CREATING DATABASE SERVICE TEMPLATES	288
9.8. CREATING INSTANT APP AND QUICKSTART TEMPLATES	288
9.9. WHAT'S NEXT?	289
<b>CHAPTER 10. CONFIGURING CUSTOM CERTIFICATES .....</b>	<b>290</b>
10.1. OVERVIEW	290
10.2. CONFIGURING CUSTOM CERTIFICATES DURING INSTALLATION	290

10.3. CONFIGURING CUSTOM CERTIFICATES FOR THE WEB CONSOLE OR CLI	290
10.4. CONFIGURING A CUSTOM MASTER HOST CERTIFICATE	292
10.5. CONFIGURING A CUSTOM WILDCARD CERTIFICATE FOR THE DEFAULT ROUTER	293
10.6. CONFIGURING A CUSTOM CERTIFICATE FOR THE IMAGE REGISTRY	294
10.7. CONFIGURING A CUSTOM CERTIFICATE FOR A LOAD BALANCER	295
10.8. RETROFIT CUSTOM CERTIFICATES INTO A CLUSTER	296
10.8.1. Retrofit Custom Master Certificates into a Cluster	296
10.8.2. Retrofit Custom Router Certificates into a Cluster	297
10.9. USING CUSTOM CERTIFICATES WITH OTHER COMPONENTS	297
<b>CHAPTER 11. REDEPLOYING CERTIFICATES .....</b>	<b>298</b>
11.1. OVERVIEW	298
11.2. CHECKING CERTIFICATE EXPIRATIONS	298
11.2.1. Role Variables	298
11.2.2. Running Certificate Expiration Playbooks	299
Other Example Playbooks	300
11.2.3. Output Formats	300
HTML Report	300
JSON Report	301
11.3. REDEPLOYING CERTIFICATES	301
11.3.1. Redeploying All Certificates Using the Current OpenShift Container Platform and etcd CA	302
11.3.2. Redeploying a New or Custom OpenShift Container Platform CA	302
11.3.3. Redeploying a New etcd CA	303
11.3.4. Redeploying Master Certificates Only	304
11.3.5. Redeploying etcd Certificates Only	304
11.3.6. Redeploying Node Certificates Only	304
11.3.7. Redeploying Registry or Router Certificates Only	305
11.3.7.1. Redeploying Registry Certificates Only	305
11.3.7.2. Redeploying Router Certificates Only	305
11.3.8. Redeploying Custom Registry or Router Certificates	305
11.3.8.1. Redeploying Registry Certificates Manually	305
11.3.8.2. Redeploying Router Certificates Manually	307
<b>CHAPTER 12. CONFIGURING AUTHENTICATION AND USER AGENT .....</b>	<b>310</b>
12.1. OVERVIEW	310
12.2. IDENTITY PROVIDER PARAMETERS	310
12.3. CONFIGURING IDENTITY PROVIDERS	311
12.3.1. Configuring identity providers with Ansible	312
12.3.2. Configuring identity providers in the master configuration file	312
12.3.3. Configuring an identity provider or method	313
12.3.3.1. Manually provisioning a user when using the lookup mapping method	313
12.3.4. Allow all	314
12.3.5. Deny all	314
12.3.6. HTPasswd	315
12.3.7. Keystone	316
12.3.7.1. Configuring authentication on the master	317
12.3.7.2. Creating Users with Keystone Authentication	319
12.3.7.3. Verifying Users	319
12.3.8. LDAP authentication	319
12.3.9. Basic authentication (remote)	322
12.3.9.1. Configuring authentication on the master	323
12.3.9.2. Troubleshooting	325
12.3.10. Request header	325

12.3.11. GitHub	333
12.3.12. Registering the application on GitHub	333
12.3.13. Configuring authentication on the master	333
12.3.14. Creating users with GitHub authentication	336
12.3.15. Verifying users	336
12.3.16. GitLab	336
12.3.17. Google	337
12.3.18. OpenID connect	338
12.4. TOKEN OPTIONS	341
12.5. GRANT OPTIONS	342
12.6. SESSION OPTIONS	343
12.7. PREVENTING CLI VERSION MISMATCH WITH USER AGENT	344
<b>CHAPTER 13. SYNCING GROUPS WITH LDAP .....</b>	<b>346</b>
13.1. OVERVIEW	346
13.2. CONFIGURING LDAP SYNC	346
13.2.1. LDAP Client Configuration	346
13.2.2. LDAP Query Definition	347
13.2.3. User-Defined Name Mapping	348
13.3. RUNNING LDAP SYNC	348
13.4. RUNNING A GROUP PRUNING JOB	349
13.5. SYNC EXAMPLES	349
13.5.1. RFC 2307	350
13.5.1.1. RFC2307 with User-Defined Name Mappings	352
13.5.2. RFC 2307 with User-Defined Error Tolerances	354
13.5.3. Active Directory	356
13.5.4. Augmented Active Directory	358
13.6. NESTED MEMBERSHIP SYNC EXAMPLE	361
13.7. LDAP SYNC CONFIGURATION SPECIFICATION	364
13.7.1. v1.LDAPSyncConfig	364
13.7.2. v1.StringSource	366
13.7.3. v1.LDAPQuery	367
13.7.4. v1.RFC2307Config	368
13.7.5. v1.ActiveDirectoryConfig	369
13.7.6. v1.AugmentedActiveDirectoryConfig	370
<b>CHAPTER 14. CONFIGURING LDAP FAILOVER .....</b>	<b>372</b>
14.1. PREREQUISITES FOR CONFIGURING BASIC REMOTE AUTHENTICATION	372
14.2. GENERATING AND SHARING CERTIFICATES WITH THE REMOTE BASIC AUTHENTICATION SERVER	372
14.3. CONFIGURING SSSD FOR LDAP FAILOVER	373
14.4. CONFIGURING APACHE TO USE SSSD	375
14.5. CONFIGURING OPENSHIFT CONTAINER PLATFORM TO USE SSSD AS THE BASIC REMOTE AUTHENTICATION SERVER	378
<b>CHAPTER 15. CONFIGURING THE SDN .....</b>	<b>380</b>
15.1. OVERVIEW	380
15.2. AVAILABLE SDN PROVIDERS	380
Installing VMware NSX-T (™) on OpenShift Container Platform	380
15.3. CONFIGURING THE POD NETWORK WITH ANSIBLE	380
15.4. CONFIGURING THE POD NETWORK ON MASTERS	381
15.5. CONFIGURING THE POD NETWORK ON NODES	382
15.6. MIGRATING BETWEEN SDN PLUG-INS	383
15.6.1. Migrating from ovs-multitenant to ovs-networkpolicy	383

15.7. EXTERNAL ACCESS TO THE CLUSTER NETWORK	384
15.8. USING FLANNEL	384
<b>CHAPTER 16. CONFIGURING NUAGE SDN .....</b>	<b>387</b>
16.1. NUAGE SDN AND OPENSHIFT CONTAINER PLATFORM	387
16.2. DEVELOPER WORKFLOW	387
16.3. OPERATIONS WORKFLOW	387
16.4. INSTALLATION	387
<b>CHAPTER 17. CONFIGURING FOR AMAZON WEB SERVICES (AWS) .....</b>	<b>390</b>
17.1. OVERVIEW	390
17.2. PERMISSIONS	390
17.3. CONFIGURING A SECURITY GROUP	391
17.3.1. Overriding Detected IP Addresses and Host Names	392
17.4. CONFIGURING AWS VARIABLES	393
17.5. CONFIGURING OPENSPLIT CONTAINER PLATFORM MASTERS FOR AWS	393
17.5.1. Configuring OpenShift Container Platform for AWS with Ansible	393
17.5.2. Manually Configuring OpenShift Container Platform Masters for AWS	394
17.5.3. Manually Configuring OpenShift Container Platform Nodes for AWS	394
17.6. SETTING KEY VALUE ACCESS PAIRS	395
17.7. APPLYING CONFIGURATION CHANGES	395
17.8. LABELING CLUSTERS FOR AWS	395
17.8.1. Resources That Need Tags	396
17.8.2. Tagging an Existing Cluster	396
<b>CHAPTER 18. CONFIGURING FOR OPENSTACK .....</b>	<b>398</b>
18.1. OVERVIEW	398
18.2. PERMISSIONS	398
18.3. CONFIGURING A SECURITY GROUP	398
18.4. CONFIGURING OPENSTACK VARIABLES	399
18.5. CONFIGURING OPENSPLIT CONTAINER PLATFORM MASTERS FOR OPENSTACK	399
18.5.1. Configuring OpenShift Container Platform for OpenStack with Ansible	399
18.5.2. Manually Configuring OpenShift Container Platform Masters for OpenStack	400
18.5.3. Manually Configuring OpenShift Container Platform Nodes for OpenStack	401
18.6. APPLYING CONFIGURATION CHANGES	401
<b>CHAPTER 19. CONFIGURING FOR GCE .....</b>	<b>403</b>
19.1. OVERVIEW	403
19.2. PERMISSIONS	403
19.3. CONFIGURING MASTERS	403
19.3.1. Configuring OpenShift Container Platform Masters for GCE with Ansible	403
19.3.2. Manually Configuring OpenShift Container Platform Masters for GCE	404
19.4. CONFIGURING NODES	405
19.5. CONFIGURING MULTIZONE SUPPORT IN A GCE DEPLOYMENT	405
19.6. APPLYING CONFIGURATION CHANGES	405
<b>CHAPTER 20. CONFIGURING FOR AZURE .....</b>	<b>407</b>
20.1. OVERVIEW	407
20.2. PERMISSIONS	407
20.3. PREREQUISITES	407
20.4. THE AZURE CONFIGURATION FILE	407
20.5. CONFIGURING MASTERS	408
20.6. CONFIGURING NODES	409
20.7. APPLYING CONFIGURATION CHANGES	409

<b>CHAPTER 21. CONFIGURING FOR VMWARE VSPHERE</b>	411
21.1. OVERVIEW	411
21.2. ENABLING VMWARE VSPHERE CLOUD PROVIDER	411
21.3. THE VMWARE VSPHERE CONFIGURATION FILE	413
21.4. CONFIGURING MASTERS	414
21.5. CONFIGURING NODES	414
21.6. APPLYING CONFIGURATION CHANGES	415
21.7. BACKUP OF PERSISTENT VOLUMES	415
<b>CHAPTER 22. CONFIGURING FOR LOCAL VOLUME</b>	417
22.1. OVERVIEW	417
22.1.1. Enable Local Volumes	417
22.1.2. Mount Local Volumes	418
22.1.3. Configure Local Provisioner	418
22.1.4. Deploy Local Provisioner	419
22.1.5. Adding New Devices	420
<b>CHAPTER 23. CONFIGURING PERSISTENT VOLUME CLAIM PROTECTION</b>	422
23.1. OVERVIEW	422
23.1.1. Enable PVC Protection	422
<b>CHAPTER 24. CONFIGURING PERSISTENT STORAGE</b>	424
24.1. OVERVIEW	424
24.2. PERSISTENT STORAGE USING NFS	424
24.2.1. Overview	424
24.2.2. Provisioning	425
24.2.3. Enforcing Disk Quotas	426
24.2.4. NFS Volume Security	426
24.2.4.1. Group IDs	427
24.2.4.2. User IDs	428
24.2.4.3. SELinux	429
24.2.4.4. Export Settings	429
24.2.5. Reclaiming Resources	430
24.2.6. Automation	431
24.2.7. Additional Configuration and Troubleshooting	431
24.3. PERSISTENT STORAGE USING RED HAT GLUSTER STORAGE	431
24.3.1. Overview	432
24.3.1.1. Container-Native Storage	432
24.3.1.2. Container-Ready Storage	432
24.3.1.3. Standalone Red Hat Gluster Storage	432
24.3.1.4. GlusterFS Volumes	433
24.3.1.5. gluster-block Volumes	433
24.3.1.6. Gluster S3 Storage	434
24.3.2. Considerations	434
24.3.2.1. Software Prerequisites	434
24.3.2.2. Hardware Requirements	434
24.3.2.3. Storage Sizing	435
24.3.2.4. Volume Operation Behaviors	436
24.3.2.5. Volume Security	436
24.3.2.5.1. POSIX Permissions	436
24.3.2.5.2. SELinux	437
24.3.3. Support Requirements	437
24.3.4. Installation	438
24.3.4.1. Container-Ready Storage: Installing Red Hat Gluster Storage Nodes	438

24.3.4.2. Using the Advanced Installer	438
24.3.4.2.1. Example: Basic Container-Native Storage Installation	440
24.3.4.2.2. Example: Basic Container-Ready Storage Installation	440
24.3.4.2.3. Example: Container-Native Storage with an Integrated OpenShift Container Registry	441
24.3.4.2.4. Example: Container-Native Storage for OpenShift Logging and Metrics	442
24.3.4.2.5. Example: Container-Native Storage for Applications, Registry, Logging, and Metrics	444
24.3.4.2.6. Example: Container-Ready Storage for Applications, Registry, Logging, and Metrics	446
24.3.5. Uninstall Container-Native Storage	448
24.3.6. Provisioning	448
24.3.6.1. Static Provisioning	448
24.3.6.2. Dynamic Provisioning	452
24.4. PERSISTENT STORAGE USING OPENSTACK CINDER	453
24.4.1. Overview	453
24.4.2. Provisioning Cinder PVs	453
24.4.2.1. Creating the Persistent Volume	453
24.4.2.2. Cinder PV format	454
24.4.2.3. Cinder volume security	455
24.5. PERSISTENT STORAGE USING CEPH RADOS BLOCK DEVICE (RBD)	456
24.5.1. Overview	456
24.5.2. Provisioning	456
24.5.2.1. Creating the Ceph Secret	456
24.5.2.2. Creating the Persistent Volume	457
24.5.3. Ceph Volume Security	459
24.6. PERSISTENT STORAGE USING AWS ELASTIC BLOCK STORE	460
24.6.1. Overview	460
24.6.2. Provisioning	460
24.6.2.1. Creating the Persistent Volume	460
24.6.2.2. Volume Format	461
24.6.2.3. Maximum Number of EBS Volumes on a Node	462
24.7. PERSISTENT STORAGE USING GCE PERSISTENT DISK	462
24.7.1. Overview	462
24.7.2. Provisioning	462
24.7.2.1. Creating the Persistent Volume	462
24.7.2.2. Volume Format	464
24.8. PERSISTENT STORAGE USING iSCSI	464
24.8.1. Overview	464
24.8.2. Provisioning	464
24.8.2.1. Enforcing Disk Quotas	465
24.8.2.2. iSCSI Volume Security	465
24.8.2.3. iSCSI Multipathing	465
24.8.2.4. iSCSI Custom Initiator IQN	465
24.9. PERSISTENT STORAGE USING FIBRE CHANNEL	466
24.9.1. Overview	466
24.9.2. Provisioning	466
24.9.2.1. Enforcing Disk Quotas	467
24.9.2.2. Fibre Channel Volume Security	467
24.10. PERSISTENT STORAGE USING AZURE DISK	467
24.10.1. Overview	467
24.10.2. Prerequisites	468
24.10.3. Provisioning	468
24.10.4. Configuring Azure Disk for regional cloud	468
24.10.4.1. Creating the Persistent Volume	468
24.10.4.2. Volume Format	470

24.11. PERSISTENT STORAGE USING AZURE FILE	470
24.11.1. Overview	470
24.11.2. Before you begin	470
24.11.3. Configuring Azure File for regional cloud	471
24.11.4. Creating the PV	471
24.11.5. Creating the Azure Storage Account secret	472
24.12. PERSISTENT STORAGE USING FLEXVOLUME PLUG-INS	473
24.12.1. Overview	473
24.12.2. FlexVolume drivers	473
24.12.2.1. FlexVolume drivers with master-initiated attach/detach	474
24.12.2.2. FlexVolume drivers without master-initiated attach/detach	477
24.12.3. Installing FlexVolume drivers	478
24.12.4. Consuming storage using FlexVolume drivers	478
24.13. USING VMWARE VSphere VOLUMES FOR PERSISTENT STORAGE	479
24.13.1. Overview	479
Prerequisites	479
24.13.2. Provisioning VMware vSphere volumes	480
24.13.2.1. Creating persistent volumes	480
24.13.2.2. Formatting VMware vSphere volumes	481
24.14. PERSISTENT STORAGE USING LOCAL VOLUME	481
24.14.1. Overview	481
24.14.2. Provisioning	482
24.14.3. Creating Local Persistent Volume Claim	482
24.14.4. Feature Status	482
24.15. DYNAMIC PROVISIONING AND CREATING STORAGE CLASSES	483
24.15.1. Overview	483
24.15.2. Available dynamically provisioned plug-ins	483
24.15.3. Defining a StorageClass	485
24.15.3.1. Basic StorageClass object definition	485
24.15.3.2. StorageClass annotations	485
24.15.3.3. OpenStack Cinder object definition	486
24.15.3.4. AWS ElasticBlockStore (EBS) object definition	486
24.15.3.5. GCE PersistentDisk (gcePD) object definition	487
24.15.3.6. GlusterFS object definition	487
24.15.3.7. Ceph RBD object definition	489
24.15.3.8. Trident object definition	489
24.15.3.9. VMware vSphere object definition	490
24.15.3.10. Azure Disk object definition	490
24.15.4. Changing the default StorageClass	491
24.15.5. Additional information and examples	492
24.16. VOLUME SECURITY	492
24.16.1. Overview	492
24.16.2. SCCs, Defaults, and Allowed Ranges	493
24.16.3. Supplemental Groups	496
24.16.4. fsGroup	499
24.16.5. User IDs	501
24.16.6. SELinux Options	503
24.17. SELECTOR-LABEL VOLUME BINDING	505
24.17.1. Overview	505
24.17.2. Motivation	505
24.17.3. Deployment	505
24.17.3.1. Prerequisites	505
24.17.3.2. Define the Persistent Volume and Claim	505

24.17.3.3. Deploy the Persistent Volume and Claim	506
<b>24.18. ENABLING CONTROLLER-MANAGED ATTACHMENT AND DETACHMENT</b>	<b>507</b>
24.18.1. Overview	507
24.18.2. Determining What Is Managing Attachment and Detachment	507
24.18.3. Configuring Nodes to Enable Controller-managed Attachment and Detachment	508
<b>24.19. PERSISTENT VOLUME SNAPSHOT</b>	<b>508</b>
24.19.1. Overview	508
24.19.2. Features	508
24.19.3. Installation and Setup	509
24.19.3.1. Starting the External Controller and Provisioner	509
24.19.3.2. Managing Snapshot Users	512
24.19.4. Lifecycle of a Volume Snapshot and Volume Snapshot Data	513
24.19.4.1. Persistent Volume Claim and Persistent Volume	513
24.19.4.1.1. Snapshot Promoter	513
24.19.4.1.2. Create Snapshot	513
24.19.4.1.3. Restore Snapshot	514
24.19.4.1.4. Delete Snapshot	515
<b>CHAPTER 25. PERSISTENT STORAGE EXAMPLES</b>	<b>516</b>
25.1. OVERVIEW	516
25.2. SHARING AN NFS MOUNT ACROSS TWO PERSISTENT VOLUME CLAIMS	516
25.2.1. Overview	516
25.2.2. Creating the Persistent Volume	516
25.2.3. Creating the Persistent Volume Claim	517
25.2.4. Ensuring NFS Volume Access	518
25.2.5. Creating the Pod	519
25.2.6. Creating an Additional Pod to Reference the Same PVC	523
25.3. COMPLETE EXAMPLE USING CEPH RBD	525
25.3.1. Overview	525
25.3.2. Installing the ceph-common Package	525
25.3.3. Creating the Ceph Secret	525
25.3.4. Creating the Persistent Volume	526
25.3.5. Creating the Persistent Volume Claim	527
25.3.6. Creating the Pod	528
25.3.7. Defining Group and Owner IDs (Optional)	529
25.3.8. Setting ceph-user-secret as Default for Projects	529
25.4. USING CEPH RBD FOR DYNAMIC PROVISIONING	530
25.4.1. Overview	530
25.4.2. Creating a pool for dynamic volumes	530
25.4.3. Using an existing Ceph cluster for dynamic persistent storage	531
25.4.4. Setting ceph-user-secret as the default for projects	534
25.5. COMPLETE EXAMPLE USING GLUSTERFS	535
25.5.1. Overview	535
25.5.2. Prerequisites	535
25.5.3. Static Provisioning	536
25.5.4. Using the Storage	539
25.6. COMPLETE EXAMPLE USING GLUSTERFS FOR DYNAMIC PROVISIONING	541
25.6.1. Overview	541
25.6.2. Prerequisites	541
25.6.3. Dynamic Provisioning	542
25.6.4. Using the Storage	543
25.7. MOUNTING VOLUMES ON PRIVILEGED PODS	545
25.7.1. Overview	545

25.7.2. Prerequisites	545
25.7.3. Creating the Persistent Volume	545
25.7.4. Creating a Regular User	546
25.7.5. Creating the Persistent Volume Claim	546
25.7.6. Verifying the Setup	547
25.7.6.1. Checking the Pod SCC	547
25.7.6.2. Verifying the Mount	548
25.8. SWITCHING AN INTEGRATED OPENSIFT CONTAINER REGISTRY TO GLUSTERFS	548
25.8.1. Overview	548
25.8.2. Prerequisites	548
25.8.3. Manually Provision the GlusterFS PersistentVolumeClaim	548
25.8.4. Attach the PersistentVolumeClaim to the Registry	552
25.9. BINDING PERSISTENT VOLUMES BY LABELS	552
25.9.1. Overview	552
25.9.1.1. Assumptions	553
25.9.2. Defining Specifications	553
25.9.2.1. Persistent Volume with Labels	553
25.9.2.2. Persistent Volume Claim with Selectors	553
25.9.2.3. Volume Endpoints	554
25.9.2.4. Deploy the PV, PVC, and Endpoints	554
25.10. USING STORAGE CLASSES FOR DYNAMIC PROVISIONING	555
25.10.1. Overview	555
25.10.2. Scenario 1: Basic Dynamic Provisioning with Two Types of StorageClasses	555
25.10.3. Scenario 2: How to enable Default StorageClass behavior for a Cluster	558
25.11. USING STORAGE CLASSES FOR EXISTING LEGACY STORAGE	562
25.11.1. Overview	562
25.11.1.1. Scenario 1: Link StorageClass to existing Persistent Volume with Legacy Data	562
25.12. CONFIGURING AZURE BLOB STORAGE FOR INTEGRATED DOCKER REGISTRY	565
25.12.1. Overview	565
25.12.2. Before You Begin	565
25.12.3. Overriding Registry Configuration	565
<b>CHAPTER 26. WORKING WITH HTTP PROXIES .....</b>	<b>567</b>
26.1. OVERVIEW	567
26.2. CONFIGURING NO_PROXY	567
26.3. CONFIGURING HOSTS FOR PROXIES	568
26.4. CONFIGURING HOSTS FOR PROXIES USING ANSIBLE	569
26.5. PROXYING DOCKER PULL	569
26.6. USING MAVEN BEHIND A PROXY	570
26.7. CONFIGURING S2I BUILDS FOR PROXIES	570
26.8. CONFIGURING DEFAULT TEMPLATES FOR PROXIES	570
26.9. SETTING PROXY ENVIRONMENT VARIABLES IN PODS	571
26.10. GIT REPOSITORY ACCESS	571
<b>CHAPTER 27. CONFIGURING GLOBAL BUILD DEFAULTS AND OVERRIDES .....</b>	<b>573</b>
27.1. OVERVIEW	573
27.2. SETTING GLOBAL BUILD DEFAULTS	573
27.2.1. Configuring Global Build Defaults with Ansible	574
27.2.2. Manually Setting Global Build Defaults	575
27.3. SETTING GLOBAL BUILD OVERRIDES	576
27.3.1. Configuring Global Build Overrides with Ansible	576
27.3.2. Manually Setting Global Build Overrides	577
<b>CHAPTER 28. CONFIGURING PIPELINE EXECUTION .....</b>	<b>579</b>

---

28.1. OVERVIEW	579
28.2. OPENSHIFT JENKINS CLIENT PLUGIN	580
28.3. OPENSHIFT JENKINS SYNC PLUGIN	580
<b>CHAPTER 29. CONFIGURING ROUTE TIMEOUTS</b>	<b>582</b>
<b>CHAPTER 30. CONFIGURING NATIVE CONTAINER ROUTING</b>	<b>583</b>
30.1. NETWORK OVERVIEW	583
30.2. CONFIGURE NATIVE CONTAINER ROUTING	583
30.3. SETTING UP A NODE FOR CONTAINER NETWORKING	584
30.4. SETTING UP A ROUTER FOR CONTAINER NETWORKING	584
<b>CHAPTER 31. ROUTING FROM EDGE LOAD BALANCERS</b>	<b>585</b>
31.1. OVERVIEW	585
31.2. INCLUDING THE LOAD BALANCER IN THE SDN	585
31.3. ESTABLISHING A TUNNEL USING A RAMP NODE	585
31.3.1. Configuring a Highly-Available Ramp Node	588
<b>CHAPTER 32. AGGREGATING CONTAINER LOGS</b>	<b>589</b>
32.1. OVERVIEW	589
32.2. PRE-DEPLOYMENT CONFIGURATION	589
32.3. SPECIFYING LOGGING ANSIBLE VARIABLES	590
32.4. DEPLOYING THE EFK STACK	599
32.5. UNDERSTANDING AND ADJUSTING THE DEPLOYMENT	600
32.5.1. Ops Cluster	600
32.5.2. Elasticsearch	600
32.5.3. Fluentd	604
32.5.4. Kibana	608
32.5.5. Curator	609
32.5.5.1. Creating the Curator Configuration	611
32.6. CLEANUP	612
32.7. TROUBLESHOOTING KIBANA	612
32.8. SENDING LOGS TO AN EXTERNAL ELASTICSEARCH INSTANCE	614
32.9. SENDING LOGS TO AN EXTERNAL SYSLOG SERVER	614
32.10. PERFORMING ADMINISTRATIVE ELASTICSEARCH OPERATIONS	617
32.11. CHANGING THE AGGREGATED LOGGING DRIVER	618
32.12. MANUAL ELASTICSEARCH ROLLOUTS	620
32.12.1. Performing an Elasticsearch Rolling Cluster Restart	620
32.12.2. Performing an Elasticsearch Full Cluster Restart	621
<b>CHAPTER 33. AGGREGATE LOGGING SIZING GUIDELINES</b>	<b>623</b>
33.1. OVERVIEW	623
33.2. INSTALLATION	623
33.2.1. Large Clusters	625
33.3. SYSTEMD-JOURNALD AND RSYSLOG	625
33.4. SCALING UP EFK LOGGING	626
33.5. STORAGE CONSIDERATIONS	627
<b>CHAPTER 34. ENABLING CLUSTER METRICS</b>	<b>629</b>
34.1. OVERVIEW	629
34.2. BEFORE YOU BEGIN	629
34.3. METRICS PROJECT	629
34.4. METRICS DATA STORAGE	629
34.4.1. Persistent Storage	630
34.4.2. Capacity Planning for Cluster Metrics	630

---

Known Issues and Limitations	632
34.4.3. Non-Persistent Storage	632
34.5. METRICS ANSIBLE ROLE	633
34.5.1. Specifying Metrics Ansible Variables	633
34.5.2. Using Secrets	637
34.5.2.1. Providing Your Own Certificates	637
34.6. DEPLOYING THE METRIC COMPONENTS	637
34.6.1. Metrics Diagnostics	638
34.7. SETTING THE METRICS PUBLIC URL	638
34.8. ACCESSING HAWKULAR METRICS DIRECTLY	639
34.8.1. OpenShift Container Platform Projects and Hawkular Tenants	639
34.8.2. Authorization	640
34.9. SCALING OPENSHIFT CONTAINER PLATFORM CLUSTER METRICS PODS	640
34.10. INTEGRATION WITH AGGREGATED LOGGING	640
34.11. CLEANUP	640
34.12. PROMETHEUS ON OPENSHIFT CONTAINER PLATFORM	641
34.12.1. Setting Prometheus Role Variables	641
34.12.2. Deploying Prometheus Using Ansible Installer	642
34.12.2.1. Additional Methods for Deploying Prometheus	643
34.12.2.2. Accessing the Prometheus Web UI	643
34.12.2.3. Configuring Prometheus for OpenShift Container Platform	643
34.12.3. OpenShift Container Platform Metrics via Prometheus	644
34.12.3.1. Current Metrics	644
34.12.4. Undeploying Prometheus	647
<b>CHAPTER 35. CUSTOMIZING THE WEB CONSOLE .....</b>	<b>648</b>
35.1. OVERVIEW	648
35.2. LOADING EXTENSION SCRIPTS AND STYLESHEETS	648
35.2.1. Setting Extension Properties	649
35.3. EXTENSION OPTION FOR EXTERNAL LOGGING SOLUTIONS	650
35.4. CUSTOMIZING AND DISABLING THE GUIDED TOUR	650
35.5. CUSTOMIZING DOCUMENTATION LINKS	650
35.6. CUSTOMIZING THE LOGO	651
35.7. CHANGING LINKS TO DOCUMENTATION	651
35.8. ADDING OR CHANGING LINKS TO DOWNLOAD THE CLI	651
35.8.1. Customizing the About Page	652
35.9. CONFIGURING NAVIGATION MENUS	652
35.9.1. Top Navigation Dropdown Menus	652
35.9.2. Application Launcher	653
35.9.3. System Status Badge	654
35.9.4. Project Left Navigation	654
35.10. CONFIGURING FEATURED APPLICATIONS	656
35.11. CONFIGURING CATALOG CATEGORIES	657
35.12. CONFIGURING QUOTA NOTIFICATION MESSAGES	658
35.13. CONFIGURING THE CREATE FROM URL NAMESPACE WHITELIST	659
35.14. DISABLING THE COPY LOGIN COMMAND	659
35.14.1. Enabling Wildcard Routes	659
35.15. CUSTOMIZING THE LOGIN PAGE	660
35.15.1. Example Usage	660
35.16. CUSTOMIZING THE OAUTH ERROR PAGE	660
35.17. CHANGING THE LOGOUT URL	661
35.18. CONFIGURING WEB CONSOLE CUSTOMIZATIONS WITH ANSIBLE	661

<b>CHAPTER 36. DEPLOYING EXTERNAL PERSISTENT VOLUME PROVISIONERS</b>	.....	<b>663</b>
36.1. OVERVIEW		663
36.2. BEFORE YOU BEGIN		663
36.2.1. External Provisioners Ansible Role		663
36.2.2. External Provisioners Ansible Variables		663
36.2.3. AWS EFS Provisioner Ansible Variables		663
36.3. DEPLOYING THE PROVISIONERS		665
36.3.1. Deploying the AWS EFS Provisioner		665
36.3.1.1. AWS EFS Object Definition		665
36.4. CLEANUP		666



# CHAPTER 1. OVERVIEW

OpenShift Container Platform Installation and Configuration topics cover the basics of installing and configuring OpenShift Container Platform in your environment. Configuration, management, and logging are also covered. Use these topics for the one-time tasks required to quickly set up your OpenShift Container Platform environment and configure it based on your organizational needs.

For day to day cluster administration tasks, see [Cluster Administration](#).

# CHAPTER 2. INSTALLING A CLUSTER

## 2.1. PLANNING

### 2.1.1. Initial Planning

For production environments, several factors influence installation. Consider the following questions as you read through the documentation:

- *Which installation method do you want to use?* The [Installation Methods](#) section provides some information about the quick and advanced installation methods.
- *How many pods are required in your cluster?* The [Sizing Considerations](#) section provides limits for nodes and pods so you can calculate how large your environment needs to be.
- *How many hosts do you require in the cluster?* The [Environment Scenarios](#) section provides multiple examples of Single Master and Multiple Master configurations.
- *Is high availability required?* High availability is recommended for fault tolerance. In this situation, you might aim to use the [Multiple Masters Using Native HA](#) example as a basis for your environment.
- *Which installation type do you want to use: RPM or containerized?* Both installations provide a working OpenShift Container Platform environment, but you might have a preference for a particular method of installing, managing, and updating your services.
- *Which identity provider do you use for authentication?* If you already use a supported identity provider, it is a best practice to configure OpenShift Container Platform to use that identity provider during [advanced installation](#).
- *Is my installation supported if integrating with other technologies?* See the [OpenShift Container Platform Tested Integrations](#) for a list of tested integrations.

### 2.1.2. Installation Methods



#### IMPORTANT

As of OpenShift Container Platform 3.9, the quick installation method is deprecated. In a future release, it will be removed completely. In addition, using the quick installer to upgrade from version 3.7 to 3.9 is not supported.

Both the quick and advanced installation methods are supported for development and production environments. If you want to quickly get OpenShift Container Platform up and running to try out for the first time, use the quick installer and let the interactive CLI guide you through the configuration options relevant to your environment.

For the most control over your cluster's configuration, you can use the advanced installation method. This method is particularly suited if you are already familiar with Ansible. However, following along with the OpenShift Container Platform documentation should equip you with enough information to reliably deploy your cluster and continue to manage its configuration post-deployment using the provided Ansible playbooks directly.

If you install initially using the quick installer, you can always further tweak your cluster's configuration and adjust the number of hosts in the cluster using the same installer tool. If you wanted to later switch to


using the advanced method, you can create an inventory file for your configuration and carry on that way.

### 2.1.3. Sizing Considerations

Determine how many nodes and pods you require for your OpenShift Container Platform cluster. Cluster scalability correlates to the number of pods in a cluster environment. That number influences the other numbers in your setup. See [Cluster Limits](#) for the latest limits for objects in OpenShift Container Platform.

### 2.1.4. Environment Scenarios

This section outlines different examples of scenarios for your OpenShift Container Platform environment. Use these scenarios as a basis for planning your own OpenShift Container Platform cluster, based on your [sizing](#) needs.



#### NOTE

Moving from a single master cluster to multiple masters after installation is not supported.

For information on updating labels, see [Updating Labels on Nodes](#).

#### 2.1.4.1. Single Master and Node on One System

OpenShift Container Platform can be installed on a single system for a development environment only. An *all-in-one environment* is not considered a production environment.

#### 2.1.4.2. Single Master and Multiple Nodes

The following table describes an example environment for a single [master](#) (with etcd installed on the same host) and two [nodes](#):

Host Name	Infrastructure Component to Install
master.example.com	Master, etcd, and node
node1.example.com	Node
node2.example.com	

#### 2.1.4.3. Single Master, Multiple etcd, and Multiple Nodes

The following table describes an example environment for a single [master](#), three [etcd](#) hosts, and two [nodes](#):

Host Name	Infrastructure Component to Install
master.example.com	Master and node

Host Name	Infrastructure Component to Install
etcd1.example.com	etcd
etcd2.example.com	
etcd3.example.com	
node1.example.com	Node
node2.example.com	

#### 2.1.4.4. Multiple Masters Using Native HA with Co-located Clustered etcd

The following describes an example environment for three [masters](#) with co-located clustered etcd, one HAProxy load balancer, and two [nodes](#) using the [native](#) HA method:

Host Name	Infrastructure Component to Install
master1.example.com	Master (clustered using native HA) and node and clustered etcd
master2.example.com	
master3.example.com	
lb.example.com	HAProxy to load balance API master endpoints
node1.example.com	Node
node2.example.com	

#### 2.1.4.5. Multiple Masters Using Native HA with External Clustered etcd

The following describes an example environment for three [masters](#), one HAProxy load balancer, three external clustered [etcd](#) hosts, and two [nodes](#) using the [native](#) HA method:

Host Name	Infrastructure Component to Install
master1.example.com	Master (clustered using native HA) and node
master2.example.com	
master3.example.com	
lb.example.com	HAProxy to load balance API master endpoints

Host Name	Infrastructure Component to Install
etcd1.example.com	Clustered etcd
etcd2.example.com	
etcd3.example.com	
node1.example.com	Node
node2.example.com	

### 2.1.4.6. Stand-alone Registry

You can also install OpenShift Container Platform to act as a stand-alone registry using the OpenShift Container Platform's integrated registry. See [Installing a Stand-alone Registry](#) for details on this scenario.

### 2.1.5. RPM Versus Containerized

An RPM installation installs all services through package management and configures services to run within the same user space, while a containerized installation installs services using container images and runs separate services in individual containers.

See the [Installing on Containerized Hosts](#) topic for more details on configuring your installation to use containerized services.

## 2.2. PREREQUISITES

### 2.2.1. System Requirements

The following sections identify the hardware specifications and system-level requirements of all hosts within your OpenShift Container Platform environment.

#### 2.2.1.1. Red Hat Subscriptions

You must have an active OpenShift Container Platform subscription on your Red Hat account to proceed. If you do not, contact your sales representative for more information.

#### 2.2.1.2. Minimum Hardware Requirements

The system requirements vary per host type:

Masters	<ul style="list-style-type: none"> <li>Physical or virtual system, or an instance running on a public or private IaaS.</li> <li>Base OS: <a href="#">RHEL 7.3, 7.4, or 7.5</a> with the "Minimal" installation option and the latest packages from the Extras channel, or <a href="#">RHEL Atomic Host</a> 7.4.5 or later.</li> <li>Minimum 4 vCPU (additional are strongly recommended).</li> <li>Minimum 16 GB RAM (additional memory is strongly recommended, especially if etcd is co-located on masters).</li> </ul> <p><b>1</b></p> <ul style="list-style-type: none"> <li>Minimum 40 GB hard disk space for the file system containing <code>/var/</code>.</li> <li>Minimum 1 GB hard disk space for the file system containing <code>/usr/local/bin/</code>.</li> <li>Minimum 1 GB hard disk space for the file system containing the system's temporary directory. <b>2</b></li> <li>Masters with a co-located etcd require a minimum of 4 cores. 2 core systems will not work.</li> </ul>
Nodes	<ul style="list-style-type: none"> <li>Physical or virtual system, or an instance running on a public or private IaaS.</li> <li>Base OS: link:<a href="#">RHEL 7.3, 7.4, or 7.5</a> with "Minimal" installation option, or <a href="#">RHEL Atomic Host</a> 7.4.5 or later.</li> <li>NetworkManager 1.0 or later.</li> <li>1 vCPU.</li> <li>Minimum 8 GB RAM.</li> </ul> <p><b>1</b></p> <ul style="list-style-type: none"> <li>Minimum 15 GB hard disk space for the file system containing <code>/var/</code>.</li> <li>Minimum 1 GB hard disk space for the file system containing <code>/usr/local/bin/</code>.</li> <li>Minimum 1 GB hard disk space for the file system containing the system's temporary directory. <b>2</b></li> <li>An additional minimum 15 GB unallocated space per system running containers for Docker's storage back end; see <a href="#">Configuring Docker Storage</a>. Additional space might be required, depending on the size and number of containers that run on the node.</li> </ul>
External etcd Nodes	<ul style="list-style-type: none"> <li>Minimum 20 GB hard disk space for etcd data.</li> <li>See <a href="#">the Hardware Recommendations section of the CoreOS etcd documentation</a> for information how to properly size your etcd nodes.</li> <li>Currently, OpenShift Container Platform stores image, build, and deployment metadata in etcd. You must periodically <a href="#">prune old resources</a>. If you are planning to leverage a large number of these resources, place etcd on machines with large amounts of memory and fast SSD drives.</li> </ul>

Ansible Controller	The host that you run the Ansible playbook on must have at least 75MiB of free memory per host in the inventory.
--------------------	--

**1** Meeting the `/var` file system sizing requirements in RHEL Atomic Host requires making changes to the default configuration. See [Managing Storage with Docker-formatted Containers](#) for instructions on configuring this during or after installation.

**2** The system’s temporary directory is determined according to the rules defined in the `tempfile` module in Python’s standard library.



### IMPORTANT

OpenShift Container Platform only supports servers with x86\_64 architecture.

You must configure storage for each system that runs a container daemon. For containerized installations, you need storage on masters. Also, by default, the web console is run in containers on masters, and storage is needed on masters to run the web console. Containers are run on nodes, so storage is always required on the nodes. The size of storage depends on workload, number of containers, the size of the containers being run, and the containers’ storage requirements. Containerized etcd also needs container storage configured.

#### 2.2.1.3. Production Level Hardware Requirements

Test or sample environments function with the minimum requirements. For production environments, the following recommendations apply:

##### Master Hosts

In a highly available OpenShift Container Platform cluster with external etcd, a master host should have, in addition to the minimum requirements in the table above, 1 CPU core and 1.5 GB of memory for each 1000 pods. Therefore, the recommended size of a master host in an OpenShift Container Platform cluster of 2000 pods would be the minimum requirements of 2 CPU cores and 16 GB of RAM, plus 2 CPU cores and 3 GB of RAM, totaling 4 CPU cores and 19 GB of RAM.

A minimum of three etcd hosts and a load-balancer between the master hosts are required.

See [Recommended Practices for OpenShift Container Platform Master Hosts](#) for performance guidance.

##### Node Hosts

The size of a node host depends on the expected size of its workload. As an OpenShift Container Platform cluster administrator, you will need to calculate the expected workload, then add about 10 percent for overhead. For production environments, allocate enough resources so that a node host failure does not affect your maximum capacity.

For more information, see [Sizing Considerations](#) and [Cluster Limits](#).



### IMPORTANT

Oversubscribing the physical resources on a node affects resource guarantees the Kubernetes scheduler makes during pod placement. Learn what measures you can take to [avoid memory swapping](#).

#### 2.2.1.4. Red Hat Gluster Storage Hardware Requirements

Any nodes used in a Container-Native Storage or Container-Ready Storage cluster are considered storage nodes. Storage nodes can be grouped into distinct cluster groups, though a single node can not be in multiple groups. For each group of storage nodes:

- A minimum of three storage nodes per group is required.
- Each storage node must have a minimum of 8 GB of RAM. This is to allow running the Red Hat Gluster Storage pods, as well as other applications and the underlying operating system.
  - Each GlusterFS volume also consumes memory on every storage node in its storage cluster, which is about 30 MB. The total amount of RAM should be determined based on how many concurrent volumes are desired or anticipated.
- Each storage node must have at least one raw block device with no present data or metadata. These block devices will be used in their entirety for GlusterFS storage. Make sure the following are not present:
  - Partition tables (GPT or MSDOS)
  - Filesystems or residual filesystem signatures
  - LVM2 signatures of former Volume Groups and Logical Volumes
  - LVM2 metadata of LVM2 physical volumes

If in doubt, `wipefs -a <device>` should clear any of the above.



#### IMPORTANT

It is recommended to plan for two clusters: one dedicated to storage for infrastructure applications (such as an OpenShift Container Registry) and one dedicated to storage for general applications. This would require a total of six storage nodes. This recommendation is made to avoid potential impacts on performance in I/O and volume creation.

#### 2.2.1.5. Optional: Configuring Core Usage

By default, OpenShift Container Platform masters and nodes use all available cores in the system they run on. You can choose the number of cores you want OpenShift Container Platform to use by setting the `GOMAXPROCS` environment variable. See the [Go Language documentation](#) for more information, including how the `GOMAXPROCS` environment variable works.

For example, run the following before starting the server to make OpenShift Container Platform only run on one core:

```
# export GOMAXPROCS=1
```

#### 2.2.1.6. SELinux

Security-Enhanced Linux (SELinux) must be enabled on all of the servers before installing OpenShift Container Platform or the installer will fail. Also, configure `SELINUX=enforcing` and `SELINUXTYPE=targeted` in the `/etc/selinux/config` file:

```
# This file controls the state of SELinux on the system.
# SELINUX= can take one of these three values:
#       enforcing - SELinux security policy is enforced.
#       permissive - SELinux prints warnings instead of enforcing.
#       disabled - No SELinux policy is loaded.
SELINUX=enforcing
# SELINUXTYPE= can take one of these three values:
#       targeted - Targeted processes are protected,
#       minimum - Modification of targeted policy. Only selected processes
are protected.
#       mls - Multi Level Security protection.
SELINUXTYPE=targeted
```

### 2.2.1.7. Red Hat Gluster Storage

To access GlusterFS volumes, the `mount.glusterfs` command must be available on all schedulable nodes. For RPM-based systems, the `glusterfs-fuse` package must be installed:

```
# yum install glusterfs-fuse
```

This package comes installed on every RHEL system. However, it is recommended to update to the latest available version from Red Hat Gluster Storage. To do this, the following RPM repository must be enabled:

```
# subscription-manager repos --enable=rh-gluster-3-client-for-rhel-7-
server-rpms
```

If `glusterfs-fuse` is already installed on the nodes, ensure that the latest version is installed:

```
# yum update glusterfs-fuse
```

#### Optional: Using OverlayFS

OverlayFS is a union file system that allows you to overlay one file system on top of another.

As of Red Hat Enterprise Linux 7.4, you have the option to configure your OpenShift Container Platform environment to use OverlayFS. The `overlay2` graph driver is fully supported in addition to the older `overlay` driver. However, Red Hat recommends using `overlay2` instead of `overlay`, because of its speed and simple implementation.

[Comparing the Overlay Versus Overlay2 Graph Drivers](#) has more information about the `overlay` and `overlay2` drivers.

See the [Overlay Graph Driver](#) section of the Atomic Host documentation for instructions on how to enable the `overlay2` graph driver for the Docker service.

### 2.2.1.8. Security Warning

OpenShift Container Platform runs containers on hosts in the cluster, and in some cases, such as build operations and the registry service, it does so using privileged containers. Furthermore, those containers access the hosts' Docker daemon and perform `docker build` and `docker push` operations. As such, cluster administrators should be aware of the inherent security risks associated with performing `docker run` operations on arbitrary images as they effectively have root access. This is particularly relevant for `docker build` operations.

Exposure to harmful containers can be limited by assigning specific builds to nodes so that any exposure is limited to those nodes. To do this, see the [Assigning Builds to Specific Nodes](#) section of the Developer Guide. For cluster administrators, see the [Configuring Global Build Defaults and Overrides](#) section of the Installation and Configuration Guide.

You can also use [security context constraints](#) to control the actions that a pod can perform and what it has the ability to access. For instructions on how to enable images to run with **USER** in the Dockerfile, see [Managing Security Context Constraints](#) (requires a user with **cluster-admin** privileges).

For more information, see these articles:

- <http://opensource.com/business/14/7/docker-security-selinux>
- <https://docs.docker.com/engine/security/security/>

## 2.2.2. Environment Requirements

The following section defines the requirements of the environment containing your OpenShift Container Platform configuration. This includes networking considerations and access to external services, such as Git repository access, storage, and cloud infrastructure providers.

### 2.2.2.1. DNS

OpenShift Container Platform requires a fully functional DNS server in the environment. This is ideally a separate host running DNS software and can provide name resolution to hosts and containers running on the platform.



#### IMPORTANT

Adding entries into the `/etc/hosts` file on each host is not enough. This file is not copied into containers running on the platform.

Key components of OpenShift Container Platform run themselves inside of containers and use the following process for name resolution:

1. By default, containers receive their DNS configuration file (`/etc/resolv.conf`) from their host.
2. OpenShift Container Platform then inserts one DNS value into the pods (above the node's nameserver values). That value is defined in the `/etc/origin/node/node-config.yaml` file by the **dnsIP** parameter, which by default is set to the address of the host node because the host is using **dnsmasq**.
3. If the **dnsIP** parameter is omitted from the `node-config.yaml` file, then the value defaults to the kubernetes service IP, which is the first nameserver in the pod's `/etc/resolv.conf` file.

As of OpenShift Container Platform 3.2, **dnsmasq** is automatically configured on all masters and nodes. The pods use the nodes as their DNS, and the nodes forward the requests. By default, **dnsmasq** is configured on the nodes to listen on port 53, therefore the nodes cannot run any other type of DNS application.

**NOTE**

**NetworkManager**, a program for providing detection and configuration for systems to automatically connect to the network, is required on the nodes in order to populate **dnsmasq** with the DNS IP addresses.

**NM\_CONTROLLED** is set to **yes** by default. If **NM\_CONTROLLED** is set to **no**, then the NetworkManager dispatch script does not create the relevant **origin-upstream-dns.conf** dnsmasq file, and you would need to configure dnsmasq manually.

Similarly, if the **PEERDNS** parameter is set to **no** in the network script, for example, **/etc/sysconfig/network-scripts/ifcfg-em1**, then the dnsmasq files are not generated, and the Ansible install will fail. Ensure the **PEERDNS** setting is set to **yes**.

The following is an example set of DNS records:

```
master1      A    10.64.33.100
master2      A    10.64.33.103
node1        A    10.64.33.101
node2        A    10.64.33.102
```

If you do not have a properly functioning DNS environment, you could experience failure with:

- Product installation via the reference Ansible-based scripts
- Deployment of the infrastructure containers (registry, routers)
- Access to the OpenShift Container Platform web console, because it is not accessible via IP address alone

#### 2.2.2.1.1. Configuring Hosts to Use DNS

Make sure each host in your environment is configured to resolve hostnames from your DNS server. The configuration for hosts' DNS resolution depend on whether DHCP is enabled. If DHCP is:

- Disabled, then configure your network interface to be static, and add DNS nameservers to NetworkManager.
- Enabled, then the NetworkManager dispatch script automatically configures DNS based on the DHCP configuration. Optionally, you can add a value to **dnsIP** in the **node-config.yaml** file to prepend the pod's **resolv.conf** file. The second nameserver is then defined by the host's first nameserver. By default, this will be the IP address of the node host.

**NOTE**

For most configurations, do not set the **openshift\_dns\_ip** option during the advanced installation of OpenShift Container Platform (using Ansible), because this option overrides the default IP address set by **dnsIP**.

Instead, allow the installer to configure each node to use **dnsmasq** and forward requests to the external DNS provider or SkyDNS, the internal DNS service for cluster-wide DNS resolution of internal hostnames for services and pods. If you do set the **openshift\_dns\_ip** option, then it should be set either with a DNS IP that queries SkyDNS first, or to the SkyDNS service or endpoint IP (the Kubernetes service IP).

To verify that hosts can be resolved by your DNS server:

1. Check the contents of **/etc/resolv.conf**:

```
$ cat /etc/resolv.conf
# Generated by NetworkManager
search example.com
nameserver 10.64.33.1
# nameserver updated by /etc/NetworkManager/dispatcher.d/99-origin-dns.sh
```

In this example, 10.64.33.1 is the address of our DNS server.

2. Test that the DNS servers listed in **/etc/resolv.conf** are able to resolve host names to the IP addresses of all masters and nodes in your OpenShift Container Platform environment:

```
$ dig <node_hostname> @<IP_address> +short
```

For example:

```
$ dig master.example.com @10.64.33.1 +short
10.64.33.100
$ dig node1.example.com @10.64.33.1 +short
10.64.33.101
```

#### 2.2.2.1.2. Configuring a DNS Wildcard

Optionally, configure a wildcard for the router to use, so that you do not need to update your DNS configuration when new routes are added.

A wildcard for a DNS zone must ultimately resolve to the IP address of the OpenShift Container Platform [router](#).

For example, create a wildcard DNS entry for **cloudapps** that has a low time-to-live value (TTL) and points to the public IP address of the host where the router will be deployed:

```
*.cloudapps.example.com. 300 IN A 192.168.133.2
```

In almost all cases, when referencing VMs you must use host names, and the host names that you use must match the output of the **hostname -f** command on each node.



#### WARNING

In your **/etc/resolv.conf** file on each node host, ensure that the DNS server that has the wildcard entry is not listed as a nameserver or that the wildcard domain is not listed in the search list. Otherwise, containers managed by OpenShift Container Platform may fail to resolve host names properly.

#### 2.2.2.2. Network Access

A shared network must exist between the master and node hosts. If you plan to configure [multiple masters for high-availability](#) using the [advanced installation method](#), you must also select an IP to be configured as your [virtual IP](#) (VIP) during the installation process. The IP that you select must be routable between all of your nodes, and if you configure using a FQDN it should resolve on all nodes.

### 2.2.2.2.1. NetworkManager

**NetworkManager**, a program for providing detection and configuration for systems to automatically connect to the network, is required on the nodes in order to populate **dnsmasq** with the DNS IP addresses.

**NM\_CONTROLLED** is set to **yes** by default. If **NM\_CONTROLLED** is set to **no**, then the NetworkManager dispatch script does not create the relevant **origin-upstream-dns.conf** dnsmasq file, and you would need to configure dnsmasq manually.

### 2.2.2.2. Configuring firewalld as the firewall

While iptables is the default firewall, firewalld is recommended for new installations. You can enable firewalld by setting **os\_firewall\_use\_firewalld=true** in [the Ansible inventory file](#).

```
[OSEv3:vars]
os_firewall_use_firewalld=True
```

Setting this variable to **true** opens the required ports and adds rules to the default zone, which ensure that firewalld is configured correctly.



#### NOTE

Using the firewalld default configuration comes with limited configuration options, and cannot be overridden. For example, while you can set up a storage network with interfaces in multiple zones, the interface that nodes communicate on must be in the default zone.

### 2.2.2.2.3. Required Ports

The OpenShift Container Platform installation automatically creates a set of internal firewall rules on each host using [iptables](#). However, if your network configuration uses an external firewall, such as a hardware-based firewall, you must ensure infrastructure components can communicate with each other through specific ports that act as communication endpoints for certain processes or services.

Ensure the following ports required by OpenShift Container Platform are open on your network and configured to allow access between hosts. Some ports are optional depending on your configuration and usage.

**Table 2.1. Node to Node**

4789	UDP	Required for SDN communication between pods on separate hosts.
------	-----	--

**Table 2.2. Nodes to Master**

53 or 8053	TCP/ UDP	Required for DNS resolution of cluster services (SkyDNS). Installations prior to 3.2 or environments upgraded to 3.2 use port 53. New installations will use 8053 by default so that <b>dnsmasq</b> may be configured.
------------	-------------	--

<b>4789</b>	UDP	Required for SDN communication between pods on separate hosts.
<b>443 or 8443</b>	TCP	Required for node hosts to communicate to the master API, for the node hosts to post back status, to receive tasks, and so on.

**Table 2.3. Master to Node**

<b>4789</b>	UDP	Required for SDN communication between pods on separate hosts.
<b>10250</b>	TCP	The master proxies to node hosts via the Kubelet for <b>oc</b> commands.
<b>10010</b>	TCP	If using CRI-O, open this port to allow <b>oc exec</b> and <b>oc rsh</b> operations.

**Table 2.4. Master to Master**

<b>53 or 8053</b>	TCP/ UDP	Required for DNS resolution of cluster services (SkyDNS). Installations prior to 3.2 or environments upgraded to 3.2 use port 53. New installations will use 8053 by default so that <b>dnsmasq</b> may be configured.
<b>2049</b>	TCP/ UDP	Required when provisioning an NFS host as part of the installer.
<b>2379</b>	TCP	Used for standalone etcd (clustered) to accept changes in state.
<b>2380</b>	TCP	etcd requires this port be open between masters for leader election and peering connections when using standalone etcd (clustered).
<b>4789</b>	UDP	Required for SDN communication between pods on separate hosts.

**Table 2.5. External to Load Balancer**

<b>9000</b>	TCP	If you choose the <b>native</b> HA method, optional to allow access to the HAProxy statistics page.
-------------	-----	---

**Table 2.6. External to Master**

<b>443 or 8443</b>	TCP	Required for node hosts to communicate to the master API, for node hosts to post back status, to receive tasks, and so on.
<b>8444</b>	TCP	Port that the <b>atomic-openshift-master-controllers</b> service listens on. Required to be open for the <b>/metrics</b> and <b>/healthz</b> endpoints.

**Table 2.7. IaaS Deployments**

<b>22</b>	TCP	Required for SSH by the installer or system administrator.
-----------	-----	--

<b>53 or 8053</b>	TCP/ UDP	Required for DNS resolution of cluster services (SkyDNS). Installations prior to 3.2 or environments upgraded to 3.2 use port 53. New installations will use 8053 by default so that <b>dnsmasq</b> may be configured. Only required to be internally open on master hosts.
<b>80 or 443</b>	TCP	For HTTP/HTTPS use for the router. Required to be externally open on node hosts, especially on nodes running the router.
<b>1936</b>	TCP	<b>(Optional)</b> Required to be open when running the template router to access statistics. Can be open externally or internally to connections depending on if you want the statistics to be expressed publicly. Can require extra configuration to open. See the Notes section below for more information.
<b>2379 and 2380</b>	TCP	For standalone etcd use. Only required to be internally open on the master host. <b>2379</b> is for server-client connections. <b>2380</b> is for server-server connections, and is only required if you have clustered etcd.
<b>4789</b>	UDP	For VxLAN use (OpenShift SDN). Required only internally on node hosts.
<b>8443</b>	TCP	For use by the OpenShift Container Platform web console, shared with the API server.
<b>10250</b>	TCP	For use by the Kubelet. Required to be externally open on nodes.

## Notes

- In the above examples, port **4789** is used for User Datagram Protocol (UDP).
- When deployments are using the SDN, the pod network is accessed via a service proxy, unless it is accessing the registry from the same node the registry is deployed on.
- OpenShift Container Platform internal DNS cannot be received over SDN. Depending on the detected values of **openshift\_facts**, or if the **openshift\_ip** and **openshift\_public\_ip** values are overridden, it will be the computed value of **openshift\_ip**. For non-cloud deployments, this will default to the IP address associated with the default route on the master host. For cloud deployments, it will default to the IP address associated with the first internal interface as defined by the cloud metadata.
- The master host uses port **10250** to reach the nodes and does not go over SDN. It depends on the target host of the deployment and uses the computed values of **openshift\_hostname** and **openshift\_public\_hostname**.
- Port **1936** can still be inaccessible due to your iptables rules. Use the following to configure iptables to open port **1936**:

```
# iptables -A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m tcp \
--dport 1936 -j ACCEPT
```

**Table 2.8. Aggregated Logging**

9200	TCP	For Elasticsearch API use. Required to be internally open on any infrastructure nodes so Kibana is able to retrieve logs for display. It can be externally opened for direct access to Elasticsearch by means of a route. The route can be created using <code>oc expose</code> .
9300	TCP	For Elasticsearch inter-cluster use. Required to be internally open on any infrastructure node so the members of the Elasticsearch cluster may communicate with each other.

### 2.2.2.3. Persistent Storage

The Kubernetes [persistent volume](#) framework allows you to provision an OpenShift Container Platform cluster with persistent storage using networked storage available in your environment. This can be done after completing the initial OpenShift Container Platform installation depending on your application needs, giving users a way to request those resources without having any knowledge of the underlying infrastructure.

The [Installation and Configuration Guide](#) provides instructions for cluster administrators on provisioning an OpenShift Container Platform cluster with persistent storage using [NFS](#), [GlusterFS](#), [Ceph RBD](#), [OpenStack Cinder](#), [AWS Elastic Block Store \(EBS\)](#), [GCE Persistent Disks](#), and [iSCSI](#).

### 2.2.2.4. Cloud Provider Considerations

There are certain aspects to take into consideration if installing OpenShift Container Platform on a cloud provider.

- For Amazon Web Services, see the [Permissions](#) and the [Configuring a Security Group](#) sections.
- For OpenStack, see the [Permissions](#) and the [Configuring a Security Group](#) sections.

#### 2.2.2.4.1. Overriding Detected IP Addresses and Host Names

Some deployments require that the user override the detected host names and IP addresses for the hosts. To see the default values, run the `openshift_facts` playbook:

```
# ansible-playbook [-i /path/to/inventory] \
    /usr/share/ansible/openshift-ansible/playbooks/byo/openshift_facts.yml
```



#### IMPORTANT

For Amazon Web Services, see the [Overriding Detected IP Addresses and Host Names](#) section.

Now, verify the detected common settings. If they are not what you expect them to be, you can override them.

The [Advanced Installation](#) topic discusses the available Ansible variables in greater detail.

Variable	Usage
<b>hostname</b>	<ul style="list-style-type: none"> <li>Should resolve to the internal IP from the instances themselves.</li> <li><b>openshift_hostname</b> overrides.</li> </ul>
<b>ip</b>	<ul style="list-style-type: none"> <li>Should be the internal IP of the instance.</li> <li><b>openshift_ip</b> will overrides.</li> </ul>
<b>public_hostname</b>	<ul style="list-style-type: none"> <li>Should resolve to the external IP from hosts outside of the cloud.</li> <li>Provider <b>openshift_public_hostname</b> overrides.</li> </ul>
<b>public_ip</b>	<ul style="list-style-type: none"> <li>Should be the externally accessible IP associated with the instance.</li> <li><b>openshift_public_ip</b> overrides.</li> </ul>
<b>use_openshift_sdn</b>	<ul style="list-style-type: none"> <li>Should be true unless the cloud is GCE.</li> <li><b>openshift_use_openshift_sdn</b> overrides.</li> </ul>



### WARNING

If **openshift\_hostname** is set to a value other than the metadata-provided **private-dns-name** value, the native cloud integration for those providers will no longer work.

#### 2.2.2.4.2. Post-Installation Configuration for Cloud Providers

Following the installation process, you can configure OpenShift Container Platform for [AWS](#), [OpenStack](#), or [GCE](#).

## 2.3. HOST PREPARATION

### 2.3.1. Setting PATH

The **PATH** for the root user on each host must contain the following directories:

- **/bin**

- **/sbin**
- **/usr/bin**
- **/usr/sbin**

These should all be included by default in a fresh RHEL 7.x installation.

### 2.3.2. Operating System Requirements

A base installation of 7.3, 7.4, or 7.5 (with the latest packages from the Extras channel) or RHEL Atomic Host 7.4.2 or later is required for master and node hosts. See the following documentation for the respective installation instructions, if required:

- [Red Hat Enterprise Linux 7 Installation Guide](#)
- [Red Hat Enterprise Linux Atomic Host 7 Installation and Configuration Guide](#)

### 2.3.3. Host Registration

Each host must be registered using Red Hat Subscription Manager (RHSM) and have an active OpenShift Container Platform subscription attached to access the required packages.

1. On each host, register with RHSM:

```
# subscription-manager register --username=<user_name> --password=<password>
```

2. Pull the latest subscription data from RHSM:

```
# subscription-manager refresh
```

3. List the available subscriptions:

```
# subscription-manager list --available --matches '*OpenShift*'
```

4. In the output for the previous command, find the pool ID for an OpenShift Container Platform subscription and attach it:

```
# subscription-manager attach --pool=<pool_id>
```

5. Disable all yum repositories:

- a. Disable all the enabled RHSM repositories:

```
# subscription-manager repos --disable="*"
```

- b. List the remaining yum repositories and note their names under **repo id**, if any:

```
# yum repolist
```

- c. Use **yum-config-manager** to disable the remaining yum repositories:

```
# yum-config-manager --disable <repo_id>
```

Alternatively, disable all repositories:

```
yum-config-manager --disable \*
```

Note that this could take a few minutes if you have a large number of available repositories

6. Enable only the repositories required by OpenShift Container Platform 3.9:

```
# subscription-manager repos \
--enable="rhel-7-server-rpms" \
--enable="rhel-7-server-extras-rpms" \
--enable="rhel-7-server-ose-3.9-rpms" \
--enable="rhel-7-fast-datapath-rpms" \
--enable="rhel-7-server-ansible-2.4-rpms"
```

#### NOTE

The addition of the **rhel-7-server-ansible-2.4-rpms** repository is a new requirement as of OpenShift Container Platform 3.9.

### 2.3.4. Installing Base Packages

#### NOTE

Once you have a working inventory file, you can use */usr/share/ansible/openshift-ansible/playbooks/prerequisites.yml* to install container runtimes in their default configuration. If you require customization to the container runtime, follow the guidance in this topic.

For RHEL 7 systems:

1. Install the following base packages:

```
# yum install wget git net-tools bind-utils yum-utils iptables-
services bridge-utils bash-completion kexec-tools sos psacct
```

2. Update the system to the latest packages:

```
# yum update
# systemctl reboot
```

3. If you plan to use the [RPM-based installer](#) to run an advanced installation, you can skip this step. However, if you plan to use the [containerized installer](#):

- a. Install the **atomic** package:

```
# yum install atomic
```

- b. Skip to [Installing Docker](#).

4. Install the following package, which provides RPM-based OpenShift Container Platform installer utilities and pulls in other tools required by the [quick](#) and [advanced installation](#) methods, such as Ansible and related configuration files:

```
# yum install atomic-openshift-utils
```

For RHEL Atomic Host 7 systems:

1. Ensure the host is up to date by upgrading to the latest Atomic tree if one is available:

```
# atomic host upgrade
```

2. After the upgrade is completed and prepared for the next boot, reboot the host:

```
# systemctl reboot
```

### 2.3.5. Installing Docker

At this point, you should install Docker on all master and node hosts. This allows you to configure your [Docker storage options](#) before installing OpenShift Container Platform.

For RHEL 7 systems, install Docker 1.13:



#### NOTE

On RHEL Atomic Host 7 systems, Docker should already be installed, configured, and running by default.

```
# yum install docker-1.13.1
```

After the package installation is complete, verify that version 1.13 was installed:

```
# rpm -V docker-1.13.1
# docker version
```



#### NOTE

The [Advanced Installation](#) method automatically changes `/etc/sysconfig/docker`.

The `--insecure-registry` option instructs the Docker daemon to trust any Docker registry on the indicated subnet, rather than [requiring a certificate](#).



#### IMPORTANT

172.30.0.0/16 is the default value of the `servicesSubnet` variable in the `master-config.yaml` file. If this has changed, then the `--insecure-registry` value in the above step should be adjusted to match, as it is indicating the subnet for the registry to use. Note that the `openshift_portal_net` variable can be set in the Ansible inventory file and used during the [advanced installation](#) method to modify the `servicesSubnet` variable.



#### NOTE

After the initial OpenShift Container Platform installation is complete, you can choose to [secure the integrated Docker registry](#), which involves adjusting the `--insecure-registry` option accordingly.

### 2.3.6. Configuring Docker Storage

Containers and the images they are created from are stored in Docker's storage back end. This storage is ephemeral and separate from any [persistent storage](#) allocated to meet the needs of your applications. With *Ephemeral storage*, container-saved data is lost when the container is removed. With *persistent storage*, container-saved data remains if the container is removed.

You must configure storage for each system that runs a container daemon. For containerized installations, you need storage on masters. Also, by default, the web console is run in containers on masters, and storage is needed on masters to run the web console. Containers are run on nodes, so storage is always required on the nodes. The size of storage depends on workload, number of containers, the size of the containers being run, and the containers' storage requirements. Containerized etcd also needs container storage configured.



#### NOTE

Once you have a working inventory file, you can use `/usr/share/ansible/openshift-ansible/playbooks/prerequisites.yml` to install container runtimes in their default configuration. If you require customization to the container runtime, follow the guidance in this topic.

#### For RHEL Atomic Host

The default storage back end for Docker on RHEL Atomic Host is a thin pool logical volume, which is supported for production environments. You must ensure that enough space is allocated for this volume per the Docker storage requirements mentioned in [System Requirements](#).

If you do not have enough allocated, see [Managing Storage with Docker Formatted Containers](#) for details on using `docker-storage-setup` and basic instructions on storage management in RHEL Atomic Host.

#### For RHEL

The default storage back end for Docker on RHEL 7 is a thin pool on loopback devices, which is not supported for production use and only appropriate for proof of concept environments. For production environments, you must create a thin pool logical volume and re-configure Docker to use that volume.

Docker stores images and containers in a graph driver, which is a pluggable storage technology, such as **DeviceMapper**, **OverlayFS**, and **Btrfs**. Each has advantages and disadvantages. For example, OverlayFS is faster than DeviceMapper at starting and stopping containers, but is not Portable Operating System Interface for Unix (POSIX) compliant because of the architectural limitations of a union file system and is not supported prior to Red Hat Enterprise Linux 7.2. See the [Red Hat Enterprise Linux](#) release notes for information on using OverlayFS with your version of RHEL.

For more information on the benefits and limitations of DeviceMapper and OverlayFS, see [Choosing a Graph Driver](#).

#### 2.3.6.1. Configuring OverlayFS

OverlayFS is a type of union file system. It allows you to overlay one file system on top of another. Changes are recorded in the upper file system, while the lower file system remains unmodified.

[Comparing the Overlay Versus Overlay2 Graph Drivers](#) has more information about the **overlay** and **overlay2** drivers.

For information on enabling the OverlayFS storage driver for the Docker service, see the [Red Hat Enterprise Linux Atomic Host documentation](#).

### 2.3.6.2. Configuring Thin Pool Storage

You can use the **docker-storage-setup** script included with Docker to create a thin pool device and configure Docker's storage driver. This can be done after installing Docker and should be done before creating images or containers. The script reads configuration options from the **/etc/sysconfig/docker-storage-setup** file and supports three options for creating the logical volume:

- **Option A)** Use an additional block device.
- **Option B)** Use an existing, specified volume group.
- **Option C)** Use the remaining free space from the volume group where your root file system is located.

Option A is the most robust option, however it requires adding an additional block device to your host before configuring Docker storage. Options B and C both require leaving free space available when provisioning your host. Option C is known to cause issues with some applications, for example Red Hat Mobile Application Platform (RHMAP).

1. Create the **docker-pool** volume using one of the following three options:

- **Option A)** Use an additional block device.

In **/etc/sysconfig/docker-storage-setup**, set **DEVS** to the path of the block device you wish to use. Set **VG** to the volume group name you wish to create; **docker-vg** is a reasonable choice. For example:

```
# cat <<EOF > /etc/sysconfig/docker-storage-setup
DEVS=/dev/vdc
VG=docker-vg
EOF
```

Then run **docker-storage-setup** and review the output to ensure the **docker-pool** volume was created:

```
# docker-storage-setup
[5/1868]
0
Checking that no-one is using this disk right now ...
OK

Disk /dev/vdc: 31207 cylinders, 16 heads, 63 sectors/track
  sfdisk: /dev/vdc: unrecognized partition table type

Old situation:
  sfdisk: No partitions found

New situation:
```

```

Units: sectors of 512 bytes, counting from 0

      Device Boot   Start     End #sectors Id System
  /dev/vdc1            2048 31457279 31455232 8e Linux LVM
  /dev/vdc2              0       -      0 0 Empty
  /dev/vdc3              0       -      0 0 Empty
  /dev/vdc4              0       -      0 0 Empty
Warning: partition 1 does not start at a cylinder boundary
Warning: partition 1 does not end at a cylinder boundary
Warning: no primary partition is marked bootable (active)
This does not matter for LILO, but the DOS MBR will not boot this
disk.
Successfully wrote the new partition table

Re-reading the partition table ...

If you created or changed a DOS partition, /dev/foo7, say, then
use dd(1)
to zero the first 512 bytes: dd if=/dev/zero of=/dev/foo7 bs=512
count=1
(See fdisk(8).)
Physical volume "/dev/vdc1" successfully created
Volume group "docker-vg" successfully created
Rounding up size to full physical extent 16.00 MiB
Logical volume "docker-poolmeta" created.
Logical volume "docker-pool" created.
WARNING: Converting logical volume docker-vg/docker-pool and
docker-vg/docker-poolmeta to pool's data and metadata volumes.
THIS WILL DESTROY CONTENT OF LOGICAL VOLUME (filesystem etc.)
Converted docker-vg/docker-pool to thin pool.
Logical volume "docker-pool" changed.

```

- **Option B)** Use an existing, specified volume group.

In `/etc/sysconfig/docker-storage-setup`, set **VG** to the desired volume group. For example:

```
# cat <<EOF > /etc/sysconfig/docker-storage-setup
VG=docker-vg
EOF
```

Then run **docker-storage-setup** and review the output to ensure the **docker-pool** volume was created:

```
# docker-storage-setup
Rounding up size to full physical extent 16.00 MiB
Logical volume "docker-poolmeta" created.
Logical volume "docker-pool" created.
WARNING: Converting logical volume docker-vg/docker-pool and
docker-vg/docker-poolmeta to pool's data and metadata volumes.
THIS WILL DESTROY CONTENT OF LOGICAL VOLUME (filesystem etc.)
Converted docker-vg/docker-pool to thin pool.
Logical volume "docker-pool" changed.
```

- **Option C)** Use the remaining free space from the volume group where your root file system is located.

Verify that the volume group where your root file system resides has the desired free space, then run **docker-storage-setup** and review the output to ensure the **docker-pool** volume was created:

```
# docker-storage-setup
  Rounding up size to full physical extent 32.00 MiB
  Logical volume "docker-poolmeta" created.
  Logical volume "docker-pool" created.
  WARNING: Converting logical volume rhel/docker-pool and
  rhel/docker-poolmeta to pool's data and metadata volumes.
  THIS WILL DESTROY CONTENT OF LOGICAL VOLUME (filesystem etc.)
  Converted rhel/docker-pool to thin pool.
  Logical volume "docker-pool" changed.
```

2. Verify your configuration. You should have a **dm.thinpooldev** value in the */etc/sysconfig/docker-storage* file and a **docker-pool** logical volume:

```
# cat /etc/sysconfig/docker-storage
DOCKER_STORAGE_OPTIONS="--storage-driver devicemapper --storage-opt
dm.fs=xfs --storage-opt dm.thinpooldev=/dev/mapper/rhel-docker--pool
--storage-opt dm.use_deferred_removal=true --storage-opt
dm.use_deferred_deletion=true"

# lvs
  LV          VG      Attr      LSize  Pool Origin Data%  Meta%  Move
Log Cpy%Sync Convert
  docker-pool  rhel  twi-a-t---  9.29g            0.00    0.12
```



### IMPORTANT

Before using Docker or OpenShift Container Platform, verify that the **docker-pool** logical volume is large enough to meet your needs. The **docker-pool** volume should be 60% of the available volume group and will grow to fill the volume group via LVM monitoring.

3. If Docker has not yet been started on the host, enable and start the service, then verify it is running:

```
# systemctl enable docker
# systemctl start docker
# systemctl is-active docker
```

If Docker is already running, re-initialize Docker:



### WARNING

This will destroy any containers or images currently on the host.

```
# systemctl stop docker
```

```
# rm -rf /var/lib/docker/*
# systemctl restart docker
```

If there is any content in `/var/lib/docker/`, it must be deleted. Files will be present if Docker has been used prior to the installation of OpenShift Container Platform.

### 2.3.6.3. Reconfiguring Docker Storage

Should you need to reconfigure Docker storage after having created the **docker-pool**, you should first remove the **docker-pool** logical volume. If you are using a dedicated volume group, you should also remove the volume group and any associated physical volumes before reconfiguring **docker-storage-setup** according to the instructions above.

See [Logical Volume Manager Administration](#) for more detailed information on LVM management.

### 2.3.6.4. Enabling Image Signature Support

OpenShift Container Platform is capable of cryptographically verifying images are from trusted sources. The [Container Security Guide](#) provides a high-level description of how image signing works.

You can configure image signature verification using the **atomic** command line interface (CLI), version 1.12.5 or greater. The **atomic** CLI is pre-installed on RHEL Atomic Host systems.



#### NOTE

For more on the **atomic** CLI, see the [Atomic CLI documentation](#).

Install the **atomic** package if it is not installed on the host system:

```
$ yum install atomic
```

The **atomic trust** sub-command manages trust configuration. The default configuration is to whitelist all registries. This means no signature verification is configured.

```
$ atomic trust show
* (default)           accept
```

A reasonable configuration might be to whitelist a particular registry or namespace, blacklist (reject) untrusted registries, and require signature verification on a vendor registry. The following set of commands performs this example configuration:

#### Example Atomic Trust Configuration

```
$ atomic trust add --type insecureAcceptAnything 172.30.1.1:5000

$ atomic trust add --sigstoretype atomic \
--pubkeys pub@example.com \
172.30.1.1:5000/production

$ atomic trust add --sigstoretype atomic \
--pubkeys /etc/pki/example.com.pub \
172.30.1.1:5000/production

$ atomic trust add --sigstoretype web \
```

```
--sigstore https://access.redhat.com/webassets/docker/content/sigstore \
--pubkeys /etc/pki/rpm-gpg/RPM-GPG-KEY-redhat-release \
registry.access.redhat.com

# atomic trust show
* (default) accept
172.30.1.1:5000 accept
172.30.1.1:5000/production signed security@example.com
registry.access.redhat.com signed
security@redhat.com, security@redhat.com
```

When all the signed sources are verified, nodes may be further hardened with a global **reject** default:

```
$ atomic trust default reject

$ atomic trust show
* (default) reject
172.30.1.1:5000 accept
172.30.1.1:5000/production signed security@example.com
registry.access.redhat.com signed
security@redhat.com, security@redhat.com
```

Use the **atomic** man page `man atomic-trust` for additional examples.

The following files and directories comprise the trust configuration of a host:

- ***/etc/containers/registries.d/\****
- ***/etc/containers/policy.json***

The trust configuration may be managed directly on each node or the generated files managed on a separate host and distributed to the appropriate nodes using Ansible, for example. See the [Container Image Signing Integration Guide](#) for an example of automating file distribution with Ansible.

### 2.3.6.5. Managing Container Logs

Sometimes a container's log file (the `/var/lib/docker/containers/<hash>/<hash>-json.log` file on the node where the container is running) can increase to a problematic size. You can manage this by configuring Docker's **json-file** logging driver to restrict the size and number of log files.

Option	Purpose
<code>--log-opt max-size</code>	Sets the size at which a new log file is created.
<code>--log-opt max-file</code>	Sets the maximum number of log files to be kept per host.

For example, to set the maximum file size to 1MB and always keep the last three log files, edit the `/etc/sysconfig/docker` file to configure `max-size=1M` and `max-file=3`:

```
OPTIONS='--insecure-registry=172.30.0.0/16 --selinux-enabled --log-opt
max-size=1M --log-opt max-file=3'
```

Next, restart the Docker service:

```
# systemctl restart docker
```

### 2.3.6.6. Viewing Available Container Logs

Container logs are stored in the `/var/lib/docker/containers/<hash>/` directory on the node where the container is running. For example:

```
# ls -lh
/var/lib/docker/containers/f088349cceac173305d3e2c2e4790051799efe363842fda
b5732f51f5b001fd8/
total 2.6M
-rw-r--r--. 1 root root 5.6K Nov 24 00:12 config.json
-rw-r--r--. 1 root root 649K Nov 24 00:15
f088349cceac173305d3e2c2e4790051799efe363842fdb5732f51f5b001fd8-.json.log
-rw-r--r--. 1 root root 977K Nov 24 00:15
f088349cceac173305d3e2c2e4790051799efe363842fdb5732f51f5b001fd8-
.json.log.1
-rw-r--r--. 1 root root 977K Nov 24 00:15
f088349cceac173305d3e2c2e4790051799efe363842fdb5732f51f5b001fd8-
.json.log.2
-rw-r--r--. 1 root root 1.3K Nov 24 00:12 hostconfig.json
drwx----- 2 root root 6 Nov 24 00:12 secrets
```

See Docker's documentation for additional information on how to [configure logging drivers](#).

### 2.3.6.7. Blocking Local Volume Usage

When a volume is provisioned using the **VOLUME** instruction in a **Dockerfile** or using the **docker run -v <volumename>** command, a host's storage space is used. Using this storage can lead to an unexpected out of space issue and could bring down the host.

In OpenShift Container Platform, users trying to run their own images risk filling the entire storage space on a node host. One solution to this issue is to prevent users from running images with volumes. This way, the only storage a user has access to can be limited, and the cluster administrator can assign storage quota.

Using **docker-novolume-plugin** solves this issue by disallowing starting a container with local volumes defined. In particular, the plug-in blocks **docker run** commands that contain:

- The **--volumes-from** option
- Images that have **VOLUME(s)** defined
- References to existing volumes that were provisioned with the **docker volume** command

The plug-in does not block references to bind mounts.

To enable **docker-novolume-plugin**, perform the following steps on each node host:

1. Install the **docker-novolume-plugin** package:

```
$ yum install docker-novolume-plugin
```

2. Enable and start the **docker-novolume-plugin** service:

```
$ systemctl enable docker-novolume-plugin  
$ systemctl start docker-novolume-plugin
```

3. Edit the **/etc/sysconfig/docker** file and append the following to the **OPTIONS** list:

```
--authorization-plugin=docker-novolume-plugin
```

4. Restart the **docker** service:

```
$ systemctl restart docker
```

After you enable this plug-in, containers with local volumes defined fail to start and show the following error message:

```
runContainer: API error (500): authorization denied by plugin  
docker-novolume-plugin: volumes are not allowed
```

### 2.3.7. Ensuring Host Access

The [quick](#) and [advanced installation](#) methods require a user that has access to all hosts. If you want to run the installer as a non-root user, passwordless **sudo** rights must be configured on each destination host.

For example, you can generate an SSH key on the host where you will invoke the installation process:

```
# ssh-keygen
```

Do **not** use a password.

An easy way to distribute your SSH keys is by using a **bash** loop:

```
# for host in master.example.com \  
#   node1.example.com \  
#   node2.example.com; \  
#   do ssh-copy-id -i ~/.ssh/id_rsa.pub $host; \  
#   done
```

Modify the host names in the above command according to your configuration.

### 2.3.8. Setting Global Proxy Values

The OpenShift Container Platform installer uses the proxy settings in the **\_etc/environment** file.

Ensure the following domain suffixes and IP addresses are in the **/etc/environment** file in the **no\_proxy** parameter:

- Master and node host names (domain suffix).
- Other internal host names (domain suffix).

- Etcd IP addresses (must be IP addresses and not host names, as **etcd** access is done by IP address).
- Docker registry IP address.
- Kubernetes IP address, by default 172.30.0.1. Must be the value set in the **openshift\_portal\_net** parameter in the Ansible inventory file, by default **/etc/ansible/hosts**.
- Kubernetes internal domain suffix: **cluster.local**.
- Kubernetes internal domain suffix: **.svc**.

The following example assumes **http\_proxy** and **https\_proxy** values are set:

```
no_proxy=.internal.example.com,10.0.0.1,10.0.0.2,10.0.0.3,.cluster.local,.
svc,localhost,127.0.0.1,172.30.0.1
```




#### NOTE

Because **noproxy** does not support CIDR, you can use domain suffixes.

### 2.3.9. What's Next?

If you are interested in installing OpenShift Container Platform using the containerized method (optional for RHEL but required for RHEL Atomic Host), see [Installing on Containerized Hosts](#) to prepare your hosts.

When you are ready to proceed, you can install OpenShift Container Platform using the [quick installation](#) or [advanced installation](#) method.



#### IMPORTANT

As of OpenShift Container Platform 3.9, the quick installation method is deprecated. In a future release, it will be removed completely. In addition, using the quick installer to upgrade from version 3.7 to 3.9 is not supported.

If you are installing a stand-alone registry, continue with [Installing a Stand-alone Registry](#).

## 2.4. INSTALLING ON CONTAINERIZED HOSTS

### 2.4.1. RPM Versus Containerized Installation

You can opt to install OpenShift Container Platform using the RPM or containerized package method. Either installation method results in a working environment, but the choice comes from the operating system and how you choose to update your hosts.



#### IMPORTANT

The default method for installing OpenShift Container Platform on Red Hat Enterprise Linux (RHEL) uses RPMs. When targeting a Red Hat Atomic Host system, the containerized method is the only available option, and is automatically selected for you based on the detection of the **/run/ostree-booted** file.

When using RPMs, all services are installed and updated by package management from an outside source. These modify a host's existing configuration within the same user space. Alternatively, with containerized installs, each component of OpenShift Container Platform is shipped as a container (in a self-contained package) and leverages the host's kernel to start and run. Any updated, newer containers replace any existing ones on your host. Choosing one method over the other depends on how you choose to update OpenShift Container Platform in the future.

The following table outlines further differences between the RPM and Containerized methods:

	RPM	Containerized
<b>Installation Method</b>	Packages via <code>yum</code>	Container images via <code>docker</code>
<b>Service Management</b>	<code>systemd</code>	<code>docker</code> and <code>systemd</code> units
<b>Operating System</b>	Red Hat Enterprise Linux	Red Hat Enterprise Linux or Red Hat Atomic Host

## 2.4.2. Install Methods for Containerized Hosts

As with the RPM installation, you can choose between the [quick](#) and [advanced](#) install methods for the containerized install.

For the quick installation method, you can choose between the RPM or containerized method on a per host basis during the interactive installation, or set the values manually in an [installation configuration file](#).

For the advanced installation method, you can set the Ansible variable `containerized=true` in an [inventory file](#) on a cluster-wide or per host basis.

## 2.4.3. Required Images

Containerized installations make use of the following images:

- `openshift3/ose`
- `openshift3/node`
- `openshift3/openvswitch`
- `registry.access.redhat.com/rhel7/etcd`

By default, all of the above images are pulled from the Red Hat Registry at [registry.access.redhat.com](https://registry.access.redhat.com).

If you need to use a private registry to pull these images during the installation, you can specify the registry information ahead of time. For the advanced installation method, you can set the following Ansible variables in your inventory file, as required:

```
openshift_docker_additional_registries=<registry_hostname>
openshift_docker_insecure_registries=<registry_hostname>
openshift_docker_blocked_registries=<registry_hostname>
```

For the quick installation method, you can export the following environment variables on each target host:

```
# export OO_INSTALL_ADDITIONAL_REGISTRIES=<registry_hostname>
# export OO_INSTALL_INSECURE_REGISTRIES=<registry_hostname>
```



### IMPORTANT

Blocked Docker registries cannot currently be specified using the quick installation method.

The configuration of additional, insecure, and blocked Docker registries occurs at the beginning of the installation process to ensure that these settings are applied before attempting to pull any of the required images.

#### 2.4.4. Starting and Stopping Containers

The installation process creates relevant **systemd** units which can be used to start, stop, and poll services using normal **systemctl** commands. For containerized installations, these unit names match those of an RPM installation, with the exception of the **etcd** service which is named **etcd\_container**.

This change is necessary as currently RHEL Atomic Host ships with the **etcd** package installed as part of the operating system, so a containerized version is used for the OpenShift Container Platform installation instead. The installation process disables the default **etcd** service.



### NOTE

The **etcd** package is slated to be removed from RHEL Atomic Host in the future.

#### 2.4.5. File Paths

All OpenShift Container Platform configuration files are placed in the same locations during containerized installation as RPM based installations and will survive **os-tree** upgrades.

However, [the default image stream and template files](#) are installed at [`/etc/origin/examples`](/etc/origin/examples) for containerized installations rather than the standard [`/usr/share/openshift/examples`](/usr/share/openshift/examples), because that directory is read-only on RHEL Atomic Host.

#### 2.4.6. Storage Requirements

RHEL Atomic Host installations normally have a very small root file system. However, the etcd, master, and node containers persist data in the [`/var/lib`](#) directory. Ensure that you have enough space on the root file system before installing OpenShift Container Platform. See the [System Requirements](#) section for details.

#### 2.4.7. Open vSwitch SDN Initialization

OpenShift SDN initialization requires that the Docker bridge be reconfigured and that Docker is restarted. This complicates the situation when the node is running within a container. When using the Open vSwitch (OVS) SDN, you will see the node start, reconfigure Docker, restart Docker (which restarts all containers), and finally start successfully.

In this case, the node service may fail to start and be restarted a few times, because the master services are also restarted along with Docker. The current implementation uses a workaround which relies on setting the **Restart=always** parameter in the Docker based **systemd** units.

## 2.5. QUICK INSTALLATION

### 2.5.1. Overview



#### IMPORTANT

As of OpenShift Container Platform 3.9, the quick installation method is deprecated. In a future release, it will be removed completely. In addition, using the quick installer to upgrade from version 3.7 to 3.9 is not supported. The [advanced installation](#) method will continue to be supported for new installations and cluster upgrades.

The *quick installation* method allows you to use an interactive CLI utility, the **atomic-openshift-installer** command, to install OpenShift Container Platform across a set of hosts. This installer can deploy OpenShift Container Platform components on targeted hosts by either installing RPMs or running containerized services.



#### IMPORTANT

While RHEL Atomic Host is supported for running containerized OpenShift Container Platform services, the installer is provided by an RPM and not available by default in RHEL Atomic Host. Therefore, it must be run from a Red Hat Enterprise Linux 7 system. The host initiating the installation does not need to be intended for inclusion in the OpenShift Container Platform cluster, but it can be.

This installation method is provided to make the installation experience easier by [interactively gathering the data](#) needed to run on each host. The installer is a self-contained wrapper intended for usage on a Red Hat Enterprise Linux (RHEL) 7 system.

In addition to running [interactive installations](#) from scratch, the **atomic-openshift-installer** command can also be run or re-run using a predefined installation configuration file. This file can be used with the installer to:

- run an [unattended installation](#),
- [add nodes](#) to an existing cluster,
- [upgrade your cluster](#), or
- reinstall the OpenShift Container Platform cluster completely.




#### NOTE

To install OpenShift Container Platform as a stand-alone registry, see [Installing a Stand-alone Registry](#).

### 2.5.2. Before You Begin

The installer allows you to install OpenShift Container Platform [master](#) and [node](#) components on a defined set of hosts.



## NOTE

By default, any hosts you designate as masters during the installation process are automatically also configured as nodes so that the masters are configured as part of the [OpenShift Container Platform SDN](#).

See the OpenShift Container Platform 3.9 Release Notes for information on the following related notable technical changes:

- [Masters Marked as Schedulable Nodes by Default](#)
- [Default Node Selector Set By Default and Automatic Node Labeling](#)

Before installing OpenShift Container Platform, you must first [satisfy the prerequisites](#) on your hosts, which includes verifying system and environment requirements and properly installing and configuring Docker. You must also be prepared to provide or validate the following information for each of your targeted hosts during the course of the installation:

- User name on the target host that should run the Ansible-based installation (can be root or non-root)
- Host name
- Whether to install components for master, node, or both
- Whether to use the RPM or containerized method
- Internal and external IP addresses



## IMPORTANT

If you are installing OpenShift Container Platform using the containerized method (optional for RHEL but required for RHEL Atomic Host), see the [Installing on Containerized Hosts](#) topic to ensure that you understand the differences between these methods, then return to this topic to continue.

After following the instructions in the [Prerequisites](#) topic and deciding between the RPM and containerized methods, you can continue to running an [interactive](#) or [unattended](#) installation.

### 2.5.3. Running an Interactive Installation



## NOTE

Ensure you have read through [Before You Begin](#).

You can start the interactive installation by running:

```
$ atomic-openshift-installer install
```

Then follow the on-screen instructions to install a new OpenShift Container Platform cluster.

After it has finished, ensure that you back up the [~/.config/openshift/installer.cfg.yml](#) installation configuration file that is created, as it is required if you later want to re-run the installation, add hosts to the cluster, or [upgrade your cluster](#). Then, [verify the installation](#).

## 2.5.4. Defining an Installation Configuration File

The installer can use a predefined installation configuration file, which contains information about your installation, individual hosts, and cluster. When running an [interactive installation](#), an installation configuration file based on your answers is created for you in `~/.config/openshift/installer.cfg.yml`. The file is created if you are instructed to exit the installation to manually modify the configuration or when the installation completes. You can also create the configuration file manually from scratch to perform an [unattended installation](#).

### Installation Configuration File Specification

```

version: v2 1
variant: openshift-enterprise 2
variant_version: 3.9 3
ansible_log_path: /tmp/ansible.log 4
deployment:
  ansible_ssh_user: root 5
  hosts: 6
    - ip: 10.0.0.1 7
      hostname: master-private.example.com 8
      public_ip: 24.222.0.1 9
      public_hostname: master.example.com 10
      roles: 11
        - master
        - node
      containerized: true 12
      connect_to: 24.222.0.1 13
    - ip: 10.0.0.2
      hostname: node1-private.example.com
      public_ip: 24.222.0.2
      public_hostname: node1.example.com
      node_labels: {'region': 'infra'} 14
      roles:
        - node
      connect_to: 10.0.0.2
    - ip: 10.0.0.3
      hostname: node2-private.example.com
      public_ip: 24.222.0.3
      public_hostname: node2.example.com
      roles:
        - node
      connect_to: 10.0.0.3
  roles: 15
    master:
      <variable_name1>: "<value1>" 16
      <variable_name2>: "<value2>"
    node:
      <variable_name1>: "<value1>" 17

```

**1** The version of this installation configuration file. As of OpenShift Container Platform 3.3, the only valid version here is **v2**.

**2**

The OpenShift Container Platform variant to install. For OpenShift Container Platform, set this to **openshift-enterprise**.

- 3** A valid version of your selected variant: **3.9**, **3.7**, **3.6**, **3.5**, **3.4**, **3.3**, **3.2**, or **3.1**. If not specified, this defaults to the latest version for the specified variant.
- 4** Defines where the Ansible logs are stored. By default, this is the **/tmp/ansible.log** file.
- 5** Defines which user Ansible uses to SSH in to remote systems for gathering facts and for the installation. By default, this is the root user, but you can set it to any user that has **sudo** privileges.
- 6** Defines a list of the hosts onto which you want to install the OpenShift Container Platform master and node components.
- 7** **8** Required. Allows the installer to connect to the system and gather facts before proceeding with the install.
- 9** **10** Required for unattended installations. If these details are not specified, then this information is pulled from the facts gathered by the installer, and you are asked to confirm the details. If undefined for an unattended installation, the installation fails.
- 11** Determines the type of services that are installed. Specified as a list.
- 12** If set to **true**, containerized OpenShift Container Platform services are run on target master and node hosts instead of installed using RPM packages. If set to **false** or unset, the default RPM method is used. RHEL Atomic Host requires the containerized method, and is automatically selected for you based on the detection of the **/run/ostree-booted** file. See [Installing on Containerized Hosts](#) for more details.
- 13** The IP address that Ansible attempts to connect to when installing, upgrading, or uninstalling the systems. If the configuration file was auto-generated, then this is the value you first enter for the host during that interactive install process.
- 14** Node labels can optionally be set per-host.
- 15** Defines a dictionary of roles across the deployment.
- 16** **17** Any ansible variables that should only be applied to hosts assigned a role can be defined. For examples, see [Configuring Ansible](#).

### 2.5.5. Running an Unattended Installation



#### NOTE

Ensure you have read through the [Before You Begin](#).

Unattended installations allow you to define your hosts and cluster configuration in an [installation configuration file](#) before running the installer so that you do not have to go through all of the [interactive installation](#) questions and answers. It also allows you to resume an interactive installation you may have left unfinished, and quickly get back to where you left off.

To run an unattended installation, first define an [installation configuration file](#) at **~/.config/openshift/installer.cfg.yml**. Then, run the installer with the **-u** flag:

```
$ atomic-openshift-installer -u install
```

By default in interactive or unattended mode, the installer uses the configuration file located at `~/.config/openshift/installer.cfg.yml` if the file exists. If it does not exist, attempting to start an unattended installation fails.

Alternatively, you can specify a different location for the configuration file using the `-c` option, but doing so will require you to specify the file location every time you run the installation:

```
$ atomic-openshift-installer -u -c </path/to/file> install
```

After the unattended installation finishes, ensure that you back up the `~/.config/openshift/installer.cfg.yml` file that was used, as it is required if you later want to re-run the installation, add hosts to the cluster, or [upgrade your cluster](#). Then, [verify the installation](#).

## 2.5.6. Verifying the Installation

1. Verify that the master is started and nodes are registered and reporting in **Ready** status. *On the master host*, run the following as root:

```
# oc get nodes
NAME                  STATUS    ROLES     AGE      VERSION
master.example.com   Ready     master    7h
v1.9.1+a0ce1bc657
node1.example.com   Ready     compute   7h
v1.9.1+a0ce1bc657
node2.example.com   Ready     compute   7h
v1.9.1+a0ce1bc657
```

2. To verify that the web console is installed correctly, use the master host name and the web console port number to access the web console with a web browser.

For example, for a master host with a host name of `master.openshift.com` and using the default port of **8443**, the web console would be found at <https://master.openshift.com:8443/console>.

3. Then, see [What's Next](#) for the next steps on configuring your OpenShift Container Platform cluster.

## 2.5.7. Uninstalling OpenShift Container Platform

You can uninstall OpenShift Container Platform from all hosts in your cluster using the installer's `uninstall` command. By default, the installer uses the installation configuration file located at `~/.config/openshift/installer.cfg.yml` if the file exists:

```
$ atomic-openshift-installer uninstall
```

Alternatively, you can specify a different location for the configuration file using the `-c` option:

```
$ atomic-openshift-installer -c </path/to/file> uninstall
```

See the [advanced installation method](#) for more options.

### 2.5.8. What's Next?

Now that you have a working OpenShift Container Platform instance, you can:

- [Configure authentication](#); by default, authentication is set to [Deny All](#).
- Configure the automatically-deployed [integrated Docker registry](#).
- Configure the automatically-deployed [router](#).

## 2.6. ADVANCED INSTALLATION

### 2.6.1. Overview

A reference configuration implemented using [Ansible](#) playbooks is available as the *advanced installation* method for installing a OpenShift Container Platform cluster. Familiarity with Ansible is assumed, however you can use this configuration as a reference to create your own implementation using the configuration management tool of your choosing.



#### IMPORTANT

While RHEL Atomic Host is supported for running containerized OpenShift Container Platform services, the advanced installation method utilizes Ansible, which is not available in RHEL Atomic Host. The RPM-based installer must therefore be run from a RHEL 7 system. The host initiating the installation does not need to be intended for inclusion in the OpenShift Container Platform cluster, but it can be. Alternatively, a [containerized version of the installer](#) is available as a system container, which can be run from a RHEL Atomic Host system.



#### NOTE

To install OpenShift Container Platform as a stand-alone registry, see [Installing a Stand-alone Registry](#).

### 2.6.2. Before You Begin

Before installing OpenShift Container Platform, you must first see the [Prerequisites](#) and [Host Preparation](#) topics to prepare your hosts. This includes verifying system and environment requirements per component type and properly installing and configuring Docker. It also includes installing Ansible version 2.4 or later, as the advanced installation method is based on Ansible playbooks and as such requires directly invoking Ansible.

If you are interested in installing OpenShift Container Platform using the containerized method (optional for RHEL but required for RHEL Atomic Host), see [Installing on Containerized Hosts](#) to ensure that you understand the differences between these methods, then return to this topic to continue.

For large-scale installs, including suggestions for optimizing install time, see the [Scaling and Performance Guide](#).

After following the instructions in the [Prerequisites](#) topic and deciding between the RPM and containerized methods, you can continue in this topic to [Configuring Ansible Inventory Files](#).

### 2.6.3. Configuring Ansible Inventory Files

The `/etc/ansible/hosts` file is Ansible's inventory file for the playbook used to install OpenShift Container Platform. The inventory file describes the configuration for your OpenShift Container Platform cluster. You must replace the default contents of the file with your desired configuration.

The following sections describe commonly-used variables to set in your inventory file during an advanced installation, followed by [example inventory files](#) you can use as a starting point for your installation.

Many of the Ansible variables described are optional. Accepting the default values should suffice for development environments, but for production environments, it is recommended you read through and become familiar with the various options available.

The example inventories describe various environment topographies, including [using multiple masters for high availability](#). You can choose an example that matches your requirements, modify it to match your own environment, and use it as your inventory file when [running the advanced installation](#).

### Image Version Policy

Images require a version number policy in order to maintain updates. See the [Image Version Tag Policy](#) section in the Architecture Guide for more information.

#### 2.6.3.1. Configuring Cluster Variables

To assign environment variables during the Ansible install that apply more globally to your OpenShift Container Platform cluster overall, indicate the desired variables in the `/etc/ansible/hosts` file on separate, single lines within the `[OSEv3:vars]` section. For example:

```
[OSEv3:vars]

openshift_master_identity_providers=[{'name': 'htpasswd_auth',
'login': 'true', 'challenge': 'true',
'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

openshift_master_default_subdomain=apps.test.example.com
```



### IMPORTANT

If a parameter value in the Ansible inventory file contains special characters, such as #, { or }, you must double-escape the value (that is enclose the value in both single and double quotation marks). For example, to use `mypasswordwith###hashsigns` as a value for the variable `openshift_cloudprovider_openstack_password`, declare it as `openshift_cloudprovider_openstack_password='\"mypasswordwith###hash signs\"'` in the Ansible host inventory file.

The following tables describe variables for use with the Ansible installer that can be assigned cluster-wide:

**Table 2.9. General Cluster Variables**

Variable	Purpose
----------	---------

Variable	Purpose
<code>ansible_ssh_user</code>	This variable sets the SSH user for the installer to use and defaults to <code>root</code> . This user should allow SSH-based authentication <a href="#">without requiring a password</a> . If using SSH key-based authentication, then the key should be managed by an SSH agent.
<code>ansible_become</code>	If <code>ansible_ssh_user</code> is not <code>root</code> , this variable must be set to <code>true</code> and the user must be configured for passwordless <code>sudo</code> .
<code>debug_level</code>	<p>This variable sets which INFO messages are logged to the <code>systemd-journald.service</code>. Set one of the following:</p> <ul style="list-style-type: none"> <li>• <b>0</b> to log errors and warnings only</li> <li>• <b>2</b> to log normal information (This is the default level.)</li> <li>• <b>4</b> to log debugging-level information</li> <li>• <b>6</b> to log API-level debugging information (request / response)</li> <li>• <b>8</b> to log body-level API debugging information</li> </ul> <p>For more information on debug log levels, see <a href="#">Configuring Logging Levels</a>.</p>
<code>containerized</code>	If set to <code>true</code> , containerized OpenShift Container Platform services are run on all target master and node hosts in the cluster instead of installed using RPM packages. If set to <code>false</code> or unset, the default RPM method is used. RHEL Atomic Host requires the containerized method, and is automatically selected for you based on the detection of the <code>/run/ostree-booted</code> file. See <a href="#">Installing on Containerized Hosts</a> for more details. Containerized installations are supported starting in OpenShift Container Platform 3.1.1.

Variable	Purpose
<code>openshift_clock_enabled</code>	<p>Whether to enable Network Time Protocol (NTP) on cluster nodes. <code>true</code> by default.</p> <p> <b>IMPORTANT</b></p> <p>To prevent masters and nodes in the cluster from going out of sync, do not change the default value of this parameter.</p>
<code>openshift_master_admission_plugin_config</code>	<p>This variable sets the parameter and arbitrary JSON values as per the requirement in your inventory hosts file. For example:</p> <pre data-bbox="849 774 1420 1089">openshift_master_admission_plugin_config= {"ClusterResourceOverride":  {"configuration":  {"apiVersion": "v1", "kind": "ClusterResourceOverrideConfig", "memoryRequestToLimitPercent": "25", "cpuRequestToLimitPercent": "25", "limitCPUToMemoryPercent": "200"}}}</pre>
<code>openshift_master_audit_config</code>	<p>This variable enables API service auditing. See <a href="#">Audit Configuration</a> for more information.</p>
<code>openshift_master_cluster_hostname</code>	<p>This variable overrides the host name for the cluster, which defaults to the host name of the master.</p>
<code>openshift_master_cluster_public_hostname</code>	<p>This variable overrides the public host name for the cluster, which defaults to the host name of the master.</p>
<code>openshift_master_cluster_method</code>	<p>Optional. This variable defines the HA method when deploying multiple masters. Supports the <code>native</code> method. See <a href="#">Multiple Masters</a> for more information.</p>
<code>openshift_rolling_restart_mode</code>	<p>This variable enables rolling restarts of HA masters (i.e., masters are taken down one at a time) when <a href="#">running the upgrade playbook directly</a>. It defaults to <code>services</code>, which allows rolling restarts of services on the masters. It can instead be set to <code>system</code>, which enables rolling, full system restarts and also works for single master clusters.</p>

Variable	Purpose
<code>openshift_master_identity_providers</code>	This variable sets the <a href="#">identity provider</a> . The default value is <code>Deny All</code> . If you use a supported identity provider, configure OpenShift Container Platform to use it.
<code>openshift_master_named_certificates</code>	These variables are used to configure <a href="#">custom certificates</a> which are deployed as part of the installation. See <a href="#">Configuring Custom Certificates</a> for more information.
<code>openshift_hosted_router_certificate</code>	Provide the location of the <a href="#">custom certificates</a> for the hosted router.
<code>openshift_hosted_registry_cert_expire_days</code>	Validity of the auto-generated registry certificate in days. Defaults to <b>730</b> (2 years).
<code>openshift_ca_cert_expire_days</code>	Validity of the auto-generated CA certificate in days. Defaults to <b>1825</b> (5 years).
<code>openshift_node_cert_expire_days</code>	Validity of the auto-generated node certificate in days. Defaults to <b>730</b> (2 years).
<code>openshift_master_cert_expire_days</code>	Validity of the auto-generated master certificate in days. Defaults to <b>730</b> (2 years).
<code>etcd_ca_default_days</code>	Validity of the auto-generated external etcd certificates in days. Controls validity for etcd CA, peer, server and client certificates. Defaults to <b>1825</b> (5 years).
<code>os_firewall_use_firewalld</code>	Set to <b>true</b> to use firewalld instead of the default iptables. Not available on RHEL Atomic Host. See the <a href="#">Configuring the Firewall</a> section for more information.
<code>openshift_master_session_name</code>	These variables override defaults for <a href="#">session options</a> in the OAuth configuration. See <a href="#">Configuring Session Options</a> for more information.
<code>openshift_master_session_max_seconds</code>	
<code>openshift_master_session_auth_secrets</code>	
<code>openshift_master_session_encryption_secrets</code>	

Variable	Purpose
<code>openshift_set_node_ip</code>	This variable configures <b>nodeIP</b> in the node configuration. This variable is needed in cases where it is desired for node traffic to go over an interface other than the default network interface. The host variable <b>openshift_ip</b> can also be configured on each node to set a specific IP that might not be the IP of the default route.
<code>openshift_master_image_policy_config</code>	Sets <b>imagePolicyConfig</b> in the master configuration. See <a href="#">Image Configuration</a> for details.
<code>openshift_router_selector</code>	Default node selector for automatically deploying router pods. See <a href="#">Configuring Node Host Labels</a> for details.
<code>openshift_registry_selector</code>	Default node selector for automatically deploying registry pods. See <a href="#">Configuring Node Host Labels</a> for details.
<code>openshift_template_service_broker_namespaces</code>	This variable enables the template service broker by specifying one or more namespaces whose templates will be served by the broker.
<code>template_service_broker_selector</code>	Default node selector for automatically deploying template service broker pods, defaults <code>{"region": "infra"}</code> . See <a href="#">Configuring Node Host Labels</a> for details.
<code>osm_default_node_selector</code>	This variable overrides the node selector that projects will use by default when placing pods, which is defined by the <b>projectConfig.defaultNodeSelector</b> field in the master configuration file. Starting in OpenShift Container Platform 3.9, this defaults to <b>node-role.kubernetes.io/compute=true</b> if undefined.

Variable	Purpose
<code>openshift_docker_additional_registries</code>	<p>OpenShift Container Platform adds the specified additional registry or registries to the <code>docker</code> configuration. These are the registries to search. If the registry requires access to a port other than <b>80</b>, include the port number required in the form of <code>&lt;address&gt;:&lt;port&gt;</code>.</p> <p>For example:</p> <pre data-bbox="817 550 1428 628">openshift_docker_additional_registries=example.com:443</pre>
<code>openshift_docker_insecure_registries</code>	<p>OpenShift Container Platform adds the specified additional insecure registry or registries to the <code>docker</code> configuration. For any of these registries, secure sockets layer (SSL) is not verified. Also, add these registries to <code>openshift_docker_additional_registries</code>.</p>
<code>openshift_docker_blocked_registries</code>	<p>OpenShift Container Platform adds the specified blocked registry or registries to the <code>docker</code> configuration. Block the listed registries. Setting this to <b>all</b> blocks everything not in the other variables.</p>
<code>openshift_metrics_hawkular_hostname</code>	<p>This variable sets the host name for integration with the metrics console by overriding <code>metricsPublicURL</code> in the master configuration for cluster metrics. If you alter this variable, ensure the host name is accessible via your router.</p>
<code>openshift_clusterid</code>	<p>This variable is a cluster identifier unique to the AWS Availability Zone. Using this avoids potential issues in Amazon Web Service (AWS) with multiple zones or multiple clusters. See <a href="#">Labeling Clusters for AWS</a> for details.</p>
<code>openshift_image_tag</code>	<p>Use this variable to specify a container image tag to install or configure.</p>
<code>openshift_pkg_version</code>	<p>Use this variable to specify an RPM version to install or configure.</p>

**WARNING**

If you modify the `openshift_image_tag` or the `openshift_pkg_version` variables after the cluster is set up, then an upgrade can be triggered, resulting in downtime.

- If `openshift_image_tag` is set, its value is used for all hosts in containerized environments, even those that have another version installed. If
- `openshift_pkg_version` is set, its value is used for all hosts in RPM-based environments, even those that have another version installed.

**Table 2.10. Networking Variables**

Variable	Purpose
<code>openshift_master_default_subdomain</code>	This variable overrides the default subdomain to use for exposed <a href="#">routes</a> .
<code>os_sdn_network_plugin_name</code>	This variable configures which <a href="#">OpenShift SDN plug-in</a> to use for the pod network, which defaults to <code>redhat/openshift-ovs-subnet</code> for the standard SDN plug-in. Set the variable to <code>redhat/openshift-ovs-multitenant</code> to use the multitenant SDN plug-in.
<code>osm_cluster_network_cidr</code>	This variable overrides the SDN cluster network CIDR block. This is the network from which pod IPs are assigned. This network block should be a private block and must not conflict with existing network blocks in your infrastructure to which pods, nodes, or the master may require access. Defaults to <code>10.128.0.0/14</code> and cannot be arbitrarily re-configured after deployment, although certain changes to it can be made in the <a href="#">SDN master configuration</a> .
<code>openshift_portal_net</code>	This variable configures the subnet in which <a href="#">services</a> will be created within the <a href="#">OpenShift Container Platform SDN</a> . This network block should be private and must not conflict with any existing network blocks in your infrastructure to which pods, nodes, or the master may require access to, or the installation will fail. Defaults to <code>172.30.0.0/16</code> , and cannot be re-configured after deployment. If changing from the default, avoid <code>172.17.0.0/16</code> , which the <code>docker0</code> network bridge uses by default, or modify the <code>docker0</code> network.

Variable	Purpose
<code>osm_host_subnet_length</code>	This variable specifies the size of the per host subnet allocated for pod IPs by <a href="#">OpenShift Container Platform SDN</a> . Defaults to <b>9</b> which means that a subnet of size /23 is allocated to each host; for example, given the default 10.128.0.0/14 cluster network, this will allocate 10.128.0.0/23, 10.128.2.0/23, 10.128.4.0/23, and so on. This cannot be re-configured after deployment.
<code>openshift_node_proxy_mode</code>	This variable specifies the <a href="#">service proxy mode</a> to use: either <b>iptables</b> for the default, <b>pure-iptables</b> implementation, or <b>userspace</b> for the user space proxy.
<code>openshift_use_flannel</code>	This variable enables <b>flannel</b> as an alternative networking layer instead of the default SDN. If enabling <b>flannel</b> , disable the default SDN with the <code>openshift_use_openshift_sdn</code> variable. For more information, see <a href="#">Using Flannel</a> .
<code>openshift_use_openshift_sdn</code>	Set to <b>false</b> to disable the OpenShift SDN plug-in.

### 2.6.3.2. Configuring Deployment Type

Various defaults used throughout the playbooks and roles used by the installer are based on the deployment type configuration (usually defined in an Ansible inventory file).

Ensure the `openshift_deployment_type` parameter in your inventory file's **[OSEv3:vars]** section is set to **openshift-enterprise** to install the OpenShift Container Platform variant:

```
[OSEv3:vars]
openshift_deployment_type=openshift-enterprise
```

### 2.6.3.3. Configuring Host Variables

To assign environment variables to hosts during the Ansible installation, indicate the desired variables in the `/etc/ansible/hosts` file after the host entry in the **[masters]** or **[nodes]** sections. For example:

```
[masters]
ec2-52-6-179-239.compute-1.amazonaws.com openshift_public_hostname=ose3-
master.public.example.com
```

The following table describes variables for use with the Ansible installer that can be assigned to individual host entries:

**Table 2.11. Host Variables**

Variable	Purpose
<code>openshift_hostname</code>	This variable overrides the internal cluster host name for the system. Use this when the system's default IP address does not resolve to the system host name.
<code>openshift_public_hostname</code>	This variable overrides the system's public host name. Use this for cloud installations, or for hosts on networks using a network address translation (NAT).
<code>openshift_ip</code>	This variable overrides the cluster internal IP address for the system. Use this when using an interface that is not configured with the default route. <code>openshift_ip</code> can be used for etcd.
<code>openshift_public_ip</code>	This variable overrides the system's public IP address. Use this for cloud installations, or for hosts on networks using a network address translation (NAT).
<code>containerized</code>	If set to <code>true</code> , containerized OpenShift Container Platform services are run on the target master and node hosts instead of installed using RPM packages. If set to <code>false</code> or unset, the default RPM method is used. RHEL Atomic Host requires the containerized method, and is automatically selected for you based on the detection of the <code>/run/ostree-booted</code> file. See <a href="#">Installing on Containerized Hosts</a> for more details. Containerized installations are supported starting in OpenShift Container Platform 3.1.1.
<code>openshift_node_labels</code>	This variable adds labels to nodes during installation. See <a href="#">Configuring Node Host Labels</a> for more details.
<code>openshift_node_kubelet_args</code>	This variable is used to configure <b>kubeletArguments</b> on nodes, such as arguments used in <a href="#">container and image garbage collection</a> , and to <a href="#">specify resources per node</a> . <b>kubeletArguments</b> are key value pairs that are passed directly to the Kubelet that match the <a href="#">Kubelet's command line arguments</a> . <b>kubeletArguments</b> are not migrated or validated and may become invalid if used. These values override other settings in node configuration which may cause invalid configurations. Example usage: <code>{'image-gc-high-threshold': ['90'], 'image-gc-low-threshold': ['80']}</code> .

Variable	Purpose
<b>openshift_docker_options</b>	<p>This variable configures additional <code>docker</code> options within <code>/etc/sysconfig/docker</code>, such as options used in <a href="#">Managing Container Logs</a>. It is recommended to use <code>json-file</code>.</p> <p>The following example shows the configuration of Docker to use the <code>json-file</code> log driver, where Docker will rotate between three 1 MB log files:</p> <pre>--log-driver json-file --log-opt max-size=1M --log-opt max-file=3"</pre> <p>Do not use when <a href="#">running docker as a system container</a>.</p>
<b>openshift_schedulable</b>	<p>This variable configures whether the host is marked as a schedulable node, meaning that it is available for placement of new pods. See <a href="#">Configuring Schedulability on Masters</a>.</p>

#### 2.6.3.4. Configuring Master API Port

To configure the default ports used by the master API, configure the following variables in the `/etc/ansible/hosts` file:

**Table 2.12. Master API Port**

Variable	Purpose
<b>openshift_master_api_port</b>	<p>This variable sets the port number to access the OpenShift Container Platform API.</p>

For example:

```
openshift_master_api_port=3443
```

The web console port setting (`openshift_master_console_port`) must match the API server port (`openshift_master_api_port`).

#### 2.6.3.5. Configuring Cluster Pre-install Checks

Pre-install checks are a set of diagnostic tasks that run as part of the `openshift_health_checker` Ansible role. They run prior to an Ansible installation of OpenShift Container Platform, ensure that required inventory values are set, and identify potential issues on a host that can prevent or interfere with a successful installation.

The following table describes available pre-install checks that will run before every Ansible installation of OpenShift Container Platform:

**Table 2.13. Pre-install Checks**

Check Name	Purpose
<b>memory_availability</b>	This check ensures that a host has the recommended amount of memory for the specific deployment of OpenShift Container Platform. Default values have been derived from the <a href="#">latest installation documentation</a> . A user-defined value for minimum memory requirements may be set by setting the <b>openshift_check_min_host_memory_gb</b> cluster variable in your inventory file.
<b>disk_availability</b>	This check only runs on etcd, master, and node hosts. It ensures that the mount path for an OpenShift Container Platform installation has sufficient disk space remaining. Recommended disk values are taken from the <a href="#">latest installation documentation</a> . A user-defined value for minimum disk space requirements may be set by setting the <b>openshift_check_min_host_disk_gb</b> cluster variable in your inventory file.
<b>docker_storage</b>	Only runs on hosts that depend on the <b>docker</b> daemon (nodes and containerized installations). Checks that <b>docker</b> 's total usage does not exceed a user-defined limit. If no user-defined limit is set, <b>docker</b> 's maximum usage threshold defaults to 90% of the total size available. The threshold limit for total percent usage can be set with a variable in your inventory file: <b>max_thinpool_data_usage_percent=90</b> . A user-defined limit for maximum thinpool usage may be set by setting the <b>max_thinpool_data_usage_percent</b> cluster variable in your inventory file.
<b>docker_storage_driver</b>	Ensures that the <b>docker</b> daemon is using a storage driver supported by OpenShift Container Platform. If the <b>devicemapper</b> storage driver is being used, the check additionally ensures that a loopback device is not being used. For more information, see <a href="#">Docker's Use the Device Mapper Storage Driver guide</a> .
<b>docker_image_availability</b>	Attempts to ensure that images required by an OpenShift Container Platform installation are available either locally or in at least one of the configured container image registries on the host machine.

Check Name	Purpose
<code>package_version</code>	Runs on <code>yum</code> -based systems determining if multiple releases of a required OpenShift Container Platform package are available. Having multiple releases of a package available during an <code>enterprise</code> installation of OpenShift suggests that there are multiple <code>yum</code> repositories enabled for different releases, which may lead to installation problems. This check is skipped if the <code>openshift_release</code> variable is not defined in the inventory file.
<code>package_availability</code>	Runs prior to non-containerized installations of OpenShift Container Platform. Ensures that RPM packages required for the current installation are available.
<code>package_update</code>	Checks whether a <code>yum</code> update or package installation will succeed, without actually performing it or running <code>yum</code> on the host.

To disable specific pre-install checks, include the variable `openshift_disable_check` with a comma-delimited list of check names in your inventory file. For example:

```
openshift_disable_check=memory_availability,disk_availability
```



#### NOTE

A similar set of health checks meant to run for diagnostics on existing clusters can be found in [Ansible-based Health Checks](#). Another set of checks for checking certificate expiration can be found in [Redeploying Certificates](#).

#### 2.6.3.6. Configuring System Containers

System containers provide a way to containerize services that need to run before the `docker` daemon is running. They are Docker-formatted containers that use:

- [OSTree](#) for storage,
- [runC](#) for the runtime,
- [systemd](#) for service management, and
- [skopeo](#) for searching.

System containers are therefore stored and run outside of the traditional `docker` service. For more details on system container technology, see [Running System Containers](#) in the *Red Hat Enterprise Linux Atomic Host: Managing Containers* documentation.

You can configure your OpenShift Container Platform installation to run certain components as system containers instead of their RPM or standard containerized methods. Currently, the `docker` and `etcd` components can be run as system containers in OpenShift Container Platform.

**WARNING**

System containers are currently OS-specific because they require specific versions of **atomic** and **systemd**. For example, different system containers are created for RHEL, Fedora, or CentOS. Ensure that the system containers you are using match the OS of the host they will run on. OpenShift Container Platform only supports RHEL and RHEL Atomic as the host OS, so by default system containers built for RHEL are used.

#### 2.6.3.6.1. Running Docker as a System Container

The traditional method for using **docker** in an OpenShift Container Platform cluster is an [RPM package installation](#). For Red Hat Enterprise Linux (RHEL) systems, it must be specifically installed; for RHEL Atomic Host systems, it is provided by default.

However, you can configure your OpenShift Container Platform installation to alternatively run **docker** on node hosts as a system container. When using the system container method, the **container-engine** container image and **systemd** service is used on the host instead of the **docker** package and service.

To run **docker** as a system container:

- Because the default storage back end for Docker on RHEL 7 is a thin pool on loopback devices, for any RHEL systems you must still configure a thin pool logical volume for **docker** to use before running the OpenShift Container Platform installation. You can skip these steps for any RHEL Atomic Host systems.

For any RHEL systems, perform the steps described in the following sections:

- [Installing Docker](#)
- [Configuring Docker Storage](#)

After completing the storage configuration steps, you can leave the RPM installed.

- Set the following cluster variable to **True** in your inventory file in the **[OSEv3:vars]** section:

```
openshift_docker_use_system_container=True
```

When using the system container method, the following inventory variables for **docker** are ignored:

- **docker\_version**
- **docker\_upgrade**

Further, the following inventory variable must not be used:

- **openshift\_docker\_options**

You can also force **docker** in the system container to use a specific container registry and repository when pulling the **container-engine** image instead of from the default **registry.access.redhat.com/openshift3/**. To do so, set the following cluster variable in your

inventory file in the **[OSEv3:vars]** section:

```
openshift_docker_systemcontainer_image_override=""
<registry>/<user>/<image>:<tag>"
```

#### 2.6.3.6.2. Running etcd as a System Container

When using the RPM-based installation method for OpenShift Container Platform, etcd is installed using RPM packages on any RHEL systems. When using the containerized installation method, the **rhel7/etcd** image is used instead for RHEL or RHEL Atomic Hosts.

However, you can configure your OpenShift Container Platform installation to alternatively run etcd as a system container. Whereas the standard containerized method uses a systemd service named **etcd\_container**, the system container method uses the service name etcd, same as the RPM-based method. The data directory for etcd using this method is **/var/lib/etcd**.

To run etcd as a system container, set the following cluster variable in your inventory file in the **[OSEv3:vars]** section:

```
openshift_use_etcd_system_container=True
```

#### 2.6.3.7. Configuring a Registry Location

If you are using an image registry other than the default at **registry.access.redhat.com**, specify the desired registry within the **/etc/ansible/hosts** file.

```
oreg_url=example.com/openshift3/ose-${component}:${version}
openshift_examples_modify_imagestreams=true
```

**Table 2.14. Registry Variables**

Variable	Purpose
<b>oreg_url</b>	Set to the alternate image location. Necessary if you are not using the default registry at <b>registry.access.redhat.com</b> .
<b>openshift_examples_modify_imagestreams</b>	Set to <b>true</b> if pointing to a registry other than the default. Modifies the image stream location to the value of <b>oreg_url</b> .
<b>openshift_docker_additional_registries</b>	Specify the additional registry or registries. If the registry required to access the registry is other than <b>80</b> include the port number required in the form of <b>&lt;address&gt;:&lt;port&gt;</b>
<b>openshift_cockpit_deployer_prefix</b>	Specify the URL and path to namespace where the registry-console image is located. Note that the value for this must end in <b>/openshift3</b> rather than <b>ose-</b> , which is the standard for other images.

Variable	Purpose
<code>openshift_web_console_prefix</code>	Specify the prefix for the web console images.
<code>openshift_service_catalog_image_prefix</code>	Specify the prefix for the service catalog component image.
<code>ansible_service_broker_image_prefix</code>	Specify the prefix for the ansible service broker component image.
<code>template_service_broker_prefix</code>	Specify the prefix for the template service broker component image.
<code>openshift_crio_systemcontainer_image_override</code>	A setting for if you are using CRI-O and if you are using an alternative CRI-O system container image from another registry.

For example:

```
oreg_url=example.com/openshift3/ose-${component}:${version}
openshift_examples_modify_imagestreams=true
openshift_docker_additional_registries=example.com:443
+openshift_crio_systemcontainer_image_override=<registry>/<repo>/<image>:<tag>
openshift_cockpit_deployer_prefix='registry.example.com/openshift3/'
openshift_web_console_prefix='registry.example.com/openshift3/ose-
openshift_service_catalog_image_prefix='registry.example.com/openshift3/ose-
ansible_service_broker_image_prefix='registry.example.com/openshift3/ose-
template_service_broker_prefix='registry.example.com/openshift3/ose-'
```

### 2.6.3.8. Configuring a Registry Route

To allow users to push and pull images to the internal Docker registry from outside of the OpenShift Container Platform cluster, configure the registry route in the `/etc/ansible/hosts` file. By default, the registry route is `docker-registry-default.router.default.svc.cluster.local`.

**Table 2.15. Registry Route Variables**

Variable	Purpose
----------	---------

Variable	Purpose
<code>openshift_hosted_registry_routehost</code>	Set to the value of the desired registry route. The route contains either a name that resolves to an infrastructure node where a router manages communication or the subdomain that you set as the default application subdomain wildcard value. For example, if you set the <code>openshift_master_default_subdomain</code> parameter to <code>apps.example.com</code> and <code>*.apps.example.com</code> resolves to infrastructure nodes or a load balancer, you might use <code>registry.apps.example.com</code> as the registry route.
<code>openshift_hosted_registry_routecertificates</code>	Set the paths to the registry certificates. If you do not provide values for the certificate locations, certificates are generated. You can define locations for the following certificates: <ul style="list-style-type: none"> <li>• <code>certfile</code></li> <li>• <code>keyfile</code></li> <li>• <code>cafile</code></li> </ul>
<code>openshift_hosted_registry_routetermination</code>	Set to one of the following values: <ul style="list-style-type: none"> <li>• Set to <code>reencrypt</code> to terminate encryption at the edge router and re-encrypt it with a new certificate supplied by the destination.</li> <li>• Set to <code>passthrough</code> to terminate encryption at the destination. The destination is responsible for decrypting traffic.</li> </ul>

For example:

```
openshift_hosted_registry_routehost=<path>
openshift_hosted_registry_routetermination=reencrypt
openshift_hosted_registry_routecertificates= "{\"certfile\": '<path>/org-cert.pem', \"keyfile\": '<path>/org-privkey.pem', \"cafile\": '<path>/org-chain.pem'}"
```

### 2.6.3.9. Configuring the Registry Console

If you are using a Cockpit registry console image other than the default or require a specific version of the console, specify the desired registry within the `/etc/ansible/hosts` file:

```
openshift_cockpit_deployer_prefix=<registry_name>/<namespace>/
openshift_cockpit_deployer_version=<cockpit_image_tag>
```

**Table 2.16. Registry Variables**

Variable	Purpose
<b>openshift_cockpit_deployer_prefix</b>	Specify the URL and path to the directory where the image is located.
<b>openshift_cockpit_deployer_version</b>	Specify the Cockpit image version.

For example: If your image is at `registry.example.com/openshift3/registry-console` and you require version 3.9.3, enter:

```
openshift_cockpit_deployer_prefix='registry.example.com/openshift3/'
openshift_cockpit_deployer_version='3.9.3'
```

### 2.6.3.10. Configuring Red Hat Gluster Storage Persistent Storage

Red Hat Gluster Storage can be configured to provide persistent storage and dynamic provisioning for OpenShift Container Platform. It can be used both containerized within OpenShift Container Platform (**Container-Native Storage**) and non-containerized on its own nodes (**Container-Ready Storage**).

Additional information and examples, including the ones below, can be found at [Persistent Storage Using Red Hat Gluster Storage](#).

#### 2.6.3.10.1. Configuring Container-Native Storage



##### IMPORTANT

See [Container-Native Storage Considerations](#) for specific host preparations and prerequisites.

1. In your inventory file, add **glusterfs** in the **[OSEv3:children]** section to enable the **[glusterfs]** group:

```
[OSEv3:children]
masters
nodes
glusterfs
```

2. Add a **[glusterfs]** section with entries for each storage node that will host the GlusterFS storage. For each node, set **glusterfs\_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_devices='[ "</path/to/device1/>", "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs]
node11.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node12.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node13.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

- Add the hosts listed under **[glusterfs]** to the **[nodes]** group:

```
[nodes]
...
node11.example.com openshift_schedulable=True
node12.example.com openshift_schedulable=True
node13.example.com openshift_schedulable=True
```

### 2.6.3.10.2. Configuring Container-Ready Storage

- In your inventory file, add **glusterfs** in the **[OSEv3:children]** section to enable the **[glusterfs]** group:

```
[OSEv3:children]
masters
nodes
glusterfs
```

- Include the following variables in the **[OSEv3:vars]** section, adjusting them as needed for your configuration:

```
[OSEv3:vars]
...
openshift_storage_glusterfs_is_native=false
openshift_storage_glusterfs_storageclass=true
openshift_storage_glusterfs_heketi_is_native=true
openshift_storage_glusterfs_heketi_executor=ssh
openshift_storage_glusterfs_heketi_ssh_port=22
openshift_storage_glusterfs_heketi_ssh_user=root
openshift_storage_glusterfs_heketi_ssh_sudo=false
openshift_storage_glusterfs_heketi_ssh_keyfile="/root/.ssh/id_rsa"
```

- Add a **[glusterfs]** section with entries for each storage node that will host the GlusterFS storage. For each node, set **glusterfs\_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Also, set **glusterfs\_ip** to the IP address of the node. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_ip=<ip_address> glusterfs_devices='[ "</path/to/device1/>", "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs]
gluster1.example.com glusterfs_ip=192.168.10.11 glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

```
gluster2.example.com glusterfs_ip=192.168.10.12 glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
gluster3.example.com glusterfs_ip=192.168.10.13 glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

### 2.6.3.11. Configuring an OpenShift Container Registry

An integrated [OpenShift Container Registry](#) can be deployed using the advanced installer.

#### 2.6.3.11.1. Configuring Registry Storage

If no registry storage options are used, the default OpenShift Container Registry is ephemeral and all data will be lost when the pod no longer exists. There are several options for enabling registry storage when using the advanced installer:

##### Option A: NFS Host Group



##### NOTE

The use of NFS for registry storage is not recommended in OpenShift Container Platform.

When the following variables are set, an NFS volume is created during an advanced install with the path **<nfs\_directory>/<volume\_name>** on the host within the **[nfs]** host group. For example, the volume path using these options would be **/exports/registry**:

```
[OSEv3:vars]
```

```
openshift_hosted_registry_storage_kind=nfs
openshift_hosted_registry_storage_access_modes=['ReadWriteMany']
openshift_hosted_registry_storage_nfs_directory=/exports
openshift_hosted_registry_storage_nfs_options='*(rw,root_squash)'
openshift_hosted_registry_storage_volume_name=registry
openshift_hosted_registry_storage_volume_size=10Gi
```

##### Option B: External NFS Host



##### NOTE

The use of NFS for registry storage is not recommended in OpenShift Container Platform.

To use an external NFS volume, one must already exist with a path of **<nfs\_directory>/<volume\_name>** on the storage host. The remote volume path using the following options would be **nfs.example.com:/exports/registry**.

```
[OSEv3:vars]
```

```
openshift_hosted_registry_storage_kind=nfs
openshift_hosted_registry_storage_access_modes=['ReadWriteMany']
openshift_hosted_registry_storage_host=nfs.example.com
openshift_hosted_registry_storage_nfs_directory=/exports
openshift_hosted_registry_storage_volume_name=registry
openshift_hosted_registry_storage_volume_size=10Gi
```

## Upgrading or Installing OpenShift Container Platform with NFS

The use of NFS for the core OpenShift Container Platform components is not recommended, as NFS (and the NFS Protocol) does not provide the proper consistency needed for the applications that make up the OpenShift Container Platform infrastructure.

As a result, the installer and update playbooks require an option to enable the use of NFS with core infrastructure components.

```
# Enable unsupported configurations, things that will yield a partially
# functioning cluster but would not be supported for production use
#openshift_enable_unsupported_configurations=false
```

If you see the following messages when upgrading or installing an OpenShift Container Platform 3.9.z cluster, then an additional step is required.

```
TASK [Run variable sanity checks]
*****
fatal: [host.example.com]: FAILED! => {"failed": true, "msg":
"last_checked_host: host.example.com, last_checked_var:
openshift_hosted_registry_storage_kind;nfs is an unsupported type for
openshift_hosted_registry_storage_kind.
openshift_enable_unsupported_configurations=True mustbe specified to
continue with this configuration."}
```

In your Ansible inventory file, specify the following parameter:

```
[OSEv3:vars]
openshift_enable_unsupported_configurations=True
```

## Option C: OpenStack Platform

An OpenStack storage configuration must already exist.

```
[OSEv3:vars]

openshift_hosted_registry_storage_kind=openstack
openshift_hosted_registry_storage_access_modes=['ReadWriteOnce']
openshift_hosted_registry_storage_openstack_filesystem=ext4
openshift_hosted_registry_storage_openstack_volumeID=3a650b4f-c8c5-4e0a-
8ca5-eaee11f16c57
openshift_hosted_registry_storage_volume_size=10Gi
```

## Option D: AWS or Another S3 Storage Solution

The simple storage solution (S3) bucket must already exist.

```
[OSEv3:vars]

#openshift_hosted_registry_storage_kind=object
#openshift_hosted_registry_storage_provider=s3
#openshift_hosted_registry_storage_s3_accesskey=access_key_id
#openshift_hosted_registry_storage_s3_secretkey=secret_access_key
#openshift_hosted_registry_storage_s3_bucket=bucket_name
#openshift_hosted_registry_storage_s3_region=bucket_region
#openshift_hosted_registry_storage_s3_chunksize=26214400
#openshift_hosted_registry_storage_s3_rootdirectory=/registry
```


```
#openshift_hosted_registry_pullthrough=true
#openshift_hosted_registry_acceptsschema2=true
#openshift_hosted_registry_enforcequota=true
```

If you are using a different S3 service, such as Minio or ExoScale, also add the region endpoint parameter:

```
openshift_hosted_registry_storage_s3_regionendpoint=https://myendpoint.example.com/
```

#### Option E: Container-Native Storage

Similar to [configuring Container-Native Storage](#), Red Hat Gluster Storage can be configured to provide storage for an OpenShift Container Registry during the initial installation of the cluster to offer redundant and reliable storage for the registry.



#### IMPORTANT

See [Container-Native Storage Considerations](#) for specific host preparations and prerequisites.

1. In your inventory file, set the following variable under **[OSEv3:vars]**:

```
[OSEv3:vars]
...
openshift_hosted_registry_storage_kind=glusterfs
```

2. Add **glusterfs\_registry** in the **[OSEv3:children]** section to enable the **[glusterfs\_registry]** group:

```
[OSEv3:children]
masters
nodes
glusterfs_registry
```

3. Add a **[glusterfs\_registry]** section with entries for each storage node that will host the GlusterFS storage. For each node, set **glusterfs\_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_devices='[ "</path/to/device1/>", "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs_registry]
node11.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node12.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node13.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

4. Add the hosts listed under **[glusterfs\_registry]** to the **[nodes]** group:

```
[nodes]
```

```

...
node11.example.com openshift_schedulable=True
node12.example.com openshift_schedulable=True
node13.example.com openshift_schedulable=True

```

#### Option F: Google Cloud Storage (GCS) bucket on Google Compute Engine (GCE)

A GCS bucket must already exist.

[OSEv3:vars]

```

openshift_hosted_registry_storage_provider=gcs
openshift_hosted_registry_storage_gcs_bucket=bucket01
openshift_hosted_registry_storage_gcs_keyfile=test.key
openshift_hosted_registry_storage_gcs_rootdirectory=/registry

```

#### 2.6.3.12. Configuring Global Proxy Options

If your hosts require use of a HTTP or HTTPS proxy in order to connect to external hosts, there are many components that must be configured to use the proxy, including masters, Docker, and builds. Node services only connect to the master API requiring no external access and therefore do not need to be configured to use a proxy.

In order to simplify this configuration, the following Ansible variables can be specified at a cluster or host level to apply these settings uniformly across your environment.



#### NOTE

See [Configuring Global Build Defaults and Overrides](#) for more information on how the proxy environment is defined for builds.

**Table 2.17. Cluster Proxy Variables**

Variable	Purpose
<code>openshift_http_proxy</code>	This variable specifies the <b>HTTP_PROXY</b> environment variable for masters and the Docker daemon.
<code>openshift_https_proxy</code>	This variable specifies the <b>HTTPS_PROXY</b> environment variable for masters and the Docker daemon.
<code>openshift_no_proxy</code>	This variable is used to set the <b>NO_PROXY</b> environment variable for masters and the Docker daemon. Provide a comma-separated list of host names, domain names, or wildcard host names that do not use the defined proxy. By default, this list is augmented with the list of all defined OpenShift Container Platform host names.

Variable	Purpose
<code>openshift_generate_no_proxy_hosts</code>	This boolean variable specifies whether or not the names of all defined OpenShift hosts and <code>*.cluster.local</code> should be automatically appended to the <code>NO_PROXY</code> list. Defaults to <code>true</code> ; set it to <code>false</code> to override this option.
<code>openshift_builddefaults_http_proxy</code>	This variable defines the <code>HTTP_PROXY</code> environment variable inserted into builds using the <code>BuildDefaults</code> admission controller. If <code>openshift_http_proxy</code> is set, this variable will inherit that value; you only need to set this if you want your builds to use a different value.
<code>openshift_builddefaults_https_proxy</code>	This variable defines the <code>HTTPS_PROXY</code> environment variable inserted into builds using the <code>BuildDefaults</code> admission controller. If <code>openshift_https_proxy</code> is set, this variable will inherit that value; you only need to set this if you want your builds to use a different value.
<code>openshift_builddefaults_no_proxy</code>	This variable defines the <code>NO_PROXY</code> environment variable inserted into builds using the <code>BuildDefaults</code> admission controller. If <code>openshift_no_proxy</code> is set, this variable will inherit that value; you only need to set this if you want your builds to use a different value.
<code>openshift_builddefaults_git_http_proxy</code>	This variable defines the HTTP proxy used by <code>git clone</code> operations during a build, defined using the <code>BuildDefaults</code> admission controller. If <code>openshift_builddefaults_http_proxy</code> is set, this variable will inherit that value; you only need to set this if you want your <code>git clone</code> operations to use a different value.
<code>openshift_builddefaults_git_https_proxy</code>	This variable defines the HTTPS proxy used by <code>git clone</code> operations during a build, defined using the <code>BuildDefaults</code> admission controller. If <code>openshift_builddefaults_https_proxy</code> is set, this variable will inherit that value; you only need to set this if you want your <code>git clone</code> operations to use a different value.

### 2.6.3.13. Configuring the Firewall



#### IMPORTANT

If you are changing the default firewall, ensure that each host in your cluster is using the same firewall type to prevent inconsistencies.

**NOTE**

While iptables is the default firewall, firewalld is recommended for new installations.

OpenShift Container Platform uses iptables as the default firewall, but you can configure your cluster to use firewalld during the install process.

Because iptables is the default firewall, OpenShift Container Platform is designed to have it configured automatically. However, iptables rules can break OpenShift Container Platform if not configured correctly. The advantages of firewalld include allowing multiple objects to safely share the firewall rules.

To use firewalld as the firewall for an OpenShift Container Platform installation, add the `os_firewall_use_firewalld` variable to the list of configuration variables in the Ansible host file at install:

```
[OSEv3:vars]
os_firewall_use_firewalld=True
```

Setting this variable to `true` opens the required ports and adds rules to the default zone, ensuring that firewalld is configured correctly.

**NOTE**

Using the firewalld default configuration comes with limited configuration options, and cannot be overridden. For example, while you can set up a storage network with interfaces in multiple zones, the interface that nodes communicate on must be in the default zone.

#### 2.6.3.14. Configuring Schedulability on Masters

Any hosts you designate as masters during the installation process should also be configured as nodes so that the masters are configured as part of the [OpenShift SDN](#). You must do so by adding entries for these hosts to the `[nodes]` section:

```
[nodes]
master.example.com
```

In previous versions of OpenShift Container Platform, master hosts were marked as unschedulable nodes by default by the installer, meaning that new pods could not be placed on the hosts. Starting with OpenShift Container Platform 3.9, however, masters are marked schedulable automatically during installation. This change is mainly so that the web console, which used to run as part of the master itself, can instead be run as a pod deployed to the master.

If you want to change the schedulability of a host post-installation, see [Marking Nodes as Unschedulable or Schedulable](#).

#### 2.6.3.15. Configuring Node Host Labels

You can assign [labels](#) to node hosts during the Ansible install by configuring the `/etc/ansible/hosts` file. Labels are useful for determining the placement of pods onto nodes using the [scheduler](#). Other than `region=infra` (referred to as *dedicated infrastructure nodes* and discussed further in [Configuring Dedicated Infrastructure Nodes](#)), the actual label names and values are arbitrary and can be assigned however you see fit per your cluster's requirements.

To assign labels to a node host during an Ansible install, use the `openshift_node_labels` variable with the desired labels added to the desired node host entry in the `[nodes]` section. In the following example, labels are set for a region called `primary` and a zone called `east`:

```
[nodes]
node1.example.com openshift_node_labels="{'region': 'primary', 'zone': 'east'}"
```

Starting in OpenShift Container Platform 3.9, masters are now marked as schedulable nodes by default. As a result, the default node selector (defined in the master configuration file's `projectConfig.defaultNodeSelector` field to determine which node that projects will use by default when placing pods, and previously left blank by default) is now set by default during cluster installations. It is set to `node-role.kubernetes.io/compute=true` unless overridden using the `osm_default_node_selector` Ansible variable.

In addition, whether `osm_default_node_selector` is set or not, the following automatic labeling occurs for hosts defined in your inventory file during installation:

- non-master, non-dedicated infrastructure nodes hosts (for example, the `node1.example.com` host shown above) are labeled with `node-role.kubernetes.io/compute=true`
- master nodes are labeled `node-role.kubernetes.io/master=true`

This ensures that the default node selector has available nodes to choose from when determining pod placement.



## IMPORTANT

If you accept the default node selector of `node-role.kubernetes.io/compute=true` during installation, ensure that you do not only have dedicated infrastructure nodes as the non-master nodes defined in your cluster. In that scenario, application pods would fail to deploy because no nodes with the `node-role.kubernetes.io/compute=true` label would be available to match the default node selector when scheduling pods for projects.

See [Setting the Cluster-wide Default Node Selector](#) for steps on adjusting this setting post-installation if needed.

### 2.6.3.15.1. Configuring Dedicated Infrastructure Nodes

It is recommended for production environments that you maintain dedicated infrastructure nodes where the registry and router pods can run separately from pods used for user applications.

The `openshift_router_selector` and `openshift_registry_selector` Ansible settings determine the label selectors used when placing registry and router pods. They are set to `region=infra` by default:

```
# default selectors for router and registry services
# openshift_router_selector='region=infra'
# openshift_registry_selector='region=infra'
```

The registry and router are only able to run on node hosts with the `region=infra` label, which are then considered dedicated infrastructure nodes. Ensure that at least one node host in your OpenShift Container Platform environment has the `region=infra` label. For example:

```
[nodes]
infra-node1.example.com openshift_node_labels="{'region': 'infra', 'zone': 'default'}"
```



## IMPORTANT

If there is not a node in the **[nodes]** section that matches the selector settings, the default router and registry will be deployed as failed with **Pending** status.

If you do not intend to use OpenShift Container Platform to manage the registry and router, configure the following Ansible settings:

```
openshift_hosted_manage_registry=false
openshift_hosted_manage_router=false
```

If you are using an image registry other than the default **registry.access.redhat.com**, you need to [specify the desired registry](#) in the **/etc/ansible/hosts** file.

As described in [Configuring Schedulability on Masters](#), master hosts are marked schedulable by default. If you label a master host with **region=infra** and have no other dedicated infrastructure nodes, the master hosts must also be marked as schedulable. Otherwise, the registry and router pods cannot be placed anywhere:

```
[nodes]
master.example.com openshift_node_labels="{'region': 'infra', 'zone': 'default'}" openshift_schedulable=true
```

### 2.6.3.16. Configuring Session Options

[Session options](#) in the OAuth configuration are configurable in the inventory file. By default, Ansible populates a **sessionSecretsFile** with generated authentication and encryption secrets so that sessions generated by one master can be decoded by the others. The default location is **/etc/origin/master/session-secrets.yaml**, and this file will only be re-created if deleted on all masters.

You can set the session name and maximum number of seconds with **openshift\_master\_session\_name** and **openshift\_master\_session\_max\_seconds**:

```
openshift_master_session_name=ssn
openshift_master_session_max_seconds=3600
```

If provided, **openshift\_master\_session\_auth\_secrets** and **openshift\_master\_encryption\_secrets** must be equal length.

For **openshift\_master\_session\_auth\_secrets**, used to authenticate sessions using HMAC, it is recommended to use secrets with 32 or 64 bytes:

```
openshift_master_session_auth_secrets=['DONT+USE+THIS+SECRET+b4NV+pmZNSO']
```

For **openshift\_master\_encryption\_secrets**, used to encrypt sessions, secrets must be 16, 24, or 32 characters long, to select AES-128, AES-192, or AES-256:

```
openshift_master_session_encryption_secrets=
['DONT+USE+THIS+SECRET+b4NV+pmZNSO']
```

### 2.6.3.17. Configuring Custom Certificates

Custom serving certificates for the public host names of the OpenShift Container Platform API and [web console](#) can be deployed during an advanced installation and are configurable in the inventory file.



#### NOTE

Custom certificates should only be configured for the host name associated with the **publicMasterURL** which can be set using **openshift\_master\_cluster\_public\_hostname**. Using a custom serving certificate for the host name associated with the **masterURL** (**openshift\_master\_cluster\_hostname**) will result in TLS errors as infrastructure components will attempt to contact the master API using the internal **masterURL** host.

Certificate and key file paths can be configured using the **openshift\_master\_named\_certificates** cluster variable:

```
openshift_master_named_certificates=[{"certfile": "/path/to/custom1.crt",
"keyfile": "/path/to/custom1.key", "cafile": "/path/to/custom-ca1.crt"}]
```

File paths must be local to the system where Ansible will be run. Certificates are copied to master hosts and are deployed within the */etc/origin/master/named\_certificates*/directory.

Ansible detects a certificate's **Common Name** and **Subject Alternative Names**. Detected names can be overridden by providing the "**names**" key when setting **openshift\_master\_named\_certificates**:

```
openshift_master_named_certificates=[{"certfile": "/path/to/custom1.crt",
"keyfile": "/path/to/custom1.key", "names": ["public-master-host.com"],
"cafile": "/path/to/custom-ca1.crt"}]
```

Certificates configured using **openshift\_master\_named\_certificates** are cached on masters, meaning that each additional Ansible run with a different set of certificates results in all previously deployed certificates remaining in place on master hosts and within the master configuration file.

If you would like **openshift\_master\_named\_certificates** to be overwritten with the provided value (or no value), specify the **openshift\_master\_overwrite\_named\_certificates** cluster variable:

```
openshift_master_overwrite_named_certificates=true
```

For a more complete example, consider the following cluster variables in an inventory file:

```
openshift_master_cluster_method=native
openshift_master_cluster_hostname=lb-internal.openshift.com
openshift_master_cluster_public_hostname=custom.openshift.com
```

To overwrite the certificates on a subsequent Ansible run, you could set the following:

```
openshift_master_named_certificates=[{"certfile": "/root/STAR.openshift.com.crt", "keyfile": "/root/STAR.openshift.com.key", "names": ["custom.openshift.com"]}]  
openshift_master_overwrite_named_certificates=true
```

### 2.6.3.18. Configuring Certificate Validity

By default, the certificates used to govern the etcd, master, and kubelet expire after two to five years. The validity (length in days until they expire) for the auto-generated registry, CA, node, and master certificates can be configured during installation using the following variables (default values shown):

```
[OSEv3:vars]  
  
openshift_hosted_registry_cert_expire_days=730  
openshift_ca_cert_expire_days=1825  
openshift_node_cert_expire_days=730  
openshift_master_cert_expire_days=730  
etcd_ca_default_days=1825
```

These values are also used when [redeploying certificates](#) via Ansible post-installation.

### 2.6.3.19. Configuring Cluster Metrics

Cluster metrics are not set to automatically deploy. Set the following to enable cluster metrics when using the advanced installation method:

```
[OSEv3:vars]  
  
openshift_metrics_install_metrics=true
```

The metrics public URL can be set during cluster installation using the `openshift_metrics_hawkular_hostname` Ansible variable, which defaults to:

```
https://hawkular-metrics.  
{{openshift\_master\_default\_subdomain}}/hawkular/metrics
```

If you alter this variable, ensure the host name is accessible via your router.

```
openshift_metrics_hawkular_hostname=hawkular-metrics.  
{{openshift_master_default_subdomain}}
```



#### IMPORTANT

In accordance with upstream Kubernetes rules, metrics can be collected only on the default interface of `eth0`.



#### NOTE

You must set an `openshift_master_default_subdomain` value to deploy metrics.

#### 2.6.3.19.1. Configuring Metrics Storage

The `openshift_metrics_cassandra_storage_type` variable must be set in order to use

persistent storage for metrics. If `openshift_metrics_cassandra_storage_type` is not set, then cluster metrics data is stored in an `emptyDir` volume, which will be deleted when the Cassandra pod terminates.

There are three options for enabling cluster metrics storage when using the advanced install:

#### Option A: Dynamic

If your OpenShift Container Platform environment supports [dynamic volume provisioning](#) for your cloud provider, use the following variable:

```
[OSEv3:vars]  
openshift_metrics_cassandra_storage_type=dynamic
```

If there are multiple default dynamically provisioned volume types, such as gluster-storage and glusterfs-storage-block, you can specify the provisioned volume type by variable. For example,  
`openshift_logging_es_pvc_storage_class_name=glusterfs-storage-block`  
`openshift_metrics_cassandra_pvc_storage_class_name=glusterfs-storage-block`.

Check [Volume Configuration](#) for more information on using `DynamicProvisioningEnabled` to enable or disable dynamic provisioning.

#### Option B: NFS Host Group



#### IMPORTANT

The use of NFS for metrics storage is not recommended in OpenShift Container Platform.

When the following variables are set, an NFS volume is created during an advanced install with path `<nfs_directory>/<volume_name>` on the host within the `[nfs]` host group. For example, the volume path using these options would be `/exports/metrics`:

```
[OSEv3:vars]  
openshift_metrics_storage_kind=nfs  
openshift_metrics_storage_access_modes=['ReadWriteOnce']  
openshift_metrics_storage_nfs_directory=/exports  
openshift_metrics_storage_nfs_options='*(rw,root_squash)'  
openshift_metrics_storage_volume_name=metrics  
openshift_metrics_storage_volume_size=10Gi
```

#### Option C: External NFS Host



#### IMPORTANT

The use of NFS for metrics storage is not recommended in OpenShift Container Platform.

To use an external NFS volume, one must already exist with a path of `<nfs_directory>/<volume_name>` on the storage host.

```
[OSEv3:vars]  
openshift_metrics_storage_kind=nfs
```

```
openshift_metrics_storage_access_modes=['ReadWriteOnce']
openshift_metrics_storage_host=nfs.example.com
openshift_metrics_storage_nfs_directory=/exports
openshift_metrics_storage_volume_name=metrics
openshift_metrics_storage_volume_size=10Gi
```

The remote volume path using the following options would be ***nfs.example.com:/exports/metrics***.

### Upgrading or Installing OpenShift Container Platform with NFS

The use of NFS for the core OpenShift Container Platform components is not recommended, as NFS (and the NFS Protocol) does not provide the proper consistency needed for the applications that make up the OpenShift Container Platform infrastructure.

As a result, the installer and update playbooks require an option to enable the use of NFS with core infrastructure components.

```
# Enable unsupported configurations, things that will yield a partially
# functioning cluster but would not be supported for production use
#openshift_enable_unsupported_configurations=false
```

If you see the following messages when upgrading or installing an OpenShift Container Platform 3.9.z cluster, then an additional step is required.

```
TASK [Run variable sanity checks]
*****
fatal: [host.example.com]: FAILED! => {"failed": true, "msg":
"last_checked_host: host.example.com, last_checked_var:
openshift_hosted_registry_storage_kind;nfs is an unsupported type for
openshift_hosted_registry_storage_kind.
openshift_enable_unsupported_configurations=True mustbe specified to
continue with this configuration."}
```

In your Ansible inventory file, specify the following parameter:

```
[OSEv3:vars]
openshift_enable_unsupported_configurations=True
```

#### 2.6.3.20. Configuring Cluster Logging

Cluster logging is not set to automatically deploy by default. Set the following to enable cluster logging when using the advanced installation method:

```
[OSEv3:vars]
openshift_logging_install_logging=true
```

##### 2.6.3.20.1. Configuring Logging Storage

The **openshift\_logging\_es\_pvc\_dynamic** variable must be set in order to use persistent storage for logging. If **openshift\_logging\_es\_pvc\_dynamic** is not set, then cluster logging data is stored in an **emptyDir** volume, which will be deleted when the Elasticsearch pod terminates.

There are three options for enabling cluster logging storage when using the advanced install:

## Option A: Dynamic

If your OpenShift Container Platform environment supports [dynamic volume provisioning](#) for your cloud provider, use the following variable:

```
[OSEv3:vars]  
openshift_logging_es_pvc_dynamic=true
```

If there are multiple default dynamically provisioned volume types, such as gluster-storage and glusterfs-storage-block, you can specify the provisioned volume type by variable. For example,

**openshift\_logging\_es\_pvc\_storage\_class\_name=glusterfs-storage-block**  
**openshift\_metrics\_cassandra\_pvc\_storage\_class\_name=glusterfs-storage-block.**

Check [Volume Configuration](#) for more information on using **DynamicProvisioningEnabled** to enable or disable dynamic provisioning.

## Option B: NFS Host Group




### IMPORTANT

The use of NFS for logging storage is not recommended in OpenShift Container Platform.

When the following variables are set, an NFS volume is created during an advanced install with path **<nfs\_directory>/<volume\_name>** on the host within the **[nfs]** host group. For example, the volume path using these options would be **/exports/logging**:

```
[OSEv3:vars]  
openshift_logging_storage_kind=nfs  
openshift_logging_storage_access_modes=['ReadWriteOnce']  
openshift_logging_storage_nfs_directory=/exports  
openshift_logging_storage_nfs_options='*(rw,root_squash)'  
openshift_logging_storage_volume_name=logging  
openshift_logging_storage_volume_size=10Gi
```

## Option C: External NFS Host



### IMPORTANT

The use of NFS for logging storage is not recommended in OpenShift Container Platform.

To use an external NFS volume, one must already exist with a path of **<nfs\_directory>/<volume\_name>** on the storage host.

```
[OSEv3:vars]  
openshift_logging_storage_kind=nfs  
openshift_logging_storage_access_modes=['ReadWriteOnce']  
openshift_logging_storage_host=nfs.example.com  
openshift_logging_storage_nfs_directory=/exports  
openshift_logging_storage_volume_name=logging  
openshift_logging_storage_volume_size=10Gi
```

The remote volume path using the following options would be `nfs.example.com:/exports/logging`.

### Upgrading or Installing OpenShift Container Platform with NFS

The use of NFS for the core OpenShift Container Platform components is not recommended, as NFS (and the NFS Protocol) does not provide the proper consistency needed for the applications that make up the OpenShift Container Platform infrastructure.

As a result, the installer and update playbooks require an option to enable the use of NFS with core infrastructure components.

```
# Enable unsupported configurations, things that will yield a partially
# functioning cluster but would not be supported for production use
#openshift_enable_unsupported_configurations=false
```

If you see the following messages when upgrading or installing an OpenShift Container Platform 3.9.z cluster, then an additional step is required.

```
TASK [Run variable sanity checks]
*****
fatal: [host.example.com]: FAILED! => {"failed": true, "msg":
"last_checked_host: host.example.com, last_checked_var:
openshift_hosted_registry_storage_kind;nfs is an unsupported type for
openshift_hosted_registry_storage_kind.
openshift_enable_unsupported_configurations=True mustbe specified to
continue with this configuration."}
```

In your Ansible inventory file, specify the following parameter:

```
[OSEv3:vars]
openshift_enable_unsupported_configurations=True
```

#### 2.6.3.21. Configuring the Service Catalog

The [service catalog](#) is enabled by default during installation. Enabling the service broker allows service brokers to be registered with the catalog.



#### NOTE

To disable automatic deployment, set the following cluster variables in your inventory file:

```
openshift_enable_service_catalog=false
```

When the service catalog is enabled, the OpenShift Ansible broker and template service broker are both enabled as well; see [Configuring the OpenShift Ansible Broker](#) and [Configuring the Template Service Broker](#) for more information.

#### 2.6.3.22. Configuring the OpenShift Ansible Broker

The [OpenShift Ansible broker](#) (OAB) is enabled by default during installation. However, further configuration may be required for use.


##### 2.6.3.22.1. Configuring Persistent Storage for the OpenShift Ansible Broker

The OAB deploys its own etcd instance separate from the etcd used by the rest of the OpenShift Container Platform cluster. The OAB's etcd instance requires separate storage using persistent volumes (PVs) to function. If no PV is available, etcd will wait until the PV can be satisfied. The OAB application will enter a **CrashLoop** state until its etcd instance is available.

Some Ansible playbook bundles (APBs) also require a PV for their own usage in order to deploy. For example, each of the database APBs have two plans: the Development plan uses ephemeral storage and does not require a PV, while the Production plan is persisted and does require a PV.

APB	PV Required?
<b>postgresql-apb</b>	Yes, but only for the Production plan
<b>mysql-apb</b>	Yes, but only for the Production plan
<b>mariadb-apb</b>	Yes, but only for the Production plan
<b>mediawiki-apb</b>	Yes

To configure persistent storage for the OAB:



### NOTE

The following example shows usage of an NFS host to provide the required PVs, but [other persistent storage providers](#) can be used instead.

1. In your inventory file, add **nfs** to the **[OSEv3:children]** section to enable the **[nfs]** group:

```
[OSEv3:children]
masters
nodes
nfs
```

2. Add a **[nfs]** group section and add the host name for the system that will be the NFS host:

```
[nfs]
master1.example.com
```

3. Add the following in the **[OSEv3:vars]** section:

```
openshift_hosted_etcd_storage_kind=nfs
openshift_hosted_etcd_storage_nfs_options="*"
(rw,root_squash,sync,no_wdelay)
openshift_hosted_etcd_storage_nfs_directory=/opt/osev3-etcd ①
openshift_hosted_etcd_storage_volume_name=etcd-vol2 ②
openshift_hosted_etcd_storage_access_modes=[ "ReadWriteOnce" ]
openshift_hosted_etcd_storage_volume_size=1G
openshift_hosted_etcd_storage_labels={'storage': 'etcd'}
```

- 1 2** An NFS volume will be created with path <nfs\_directory>/<volume\_name> on the host within the [nfs] group. For example, the volume path using these options would be /opt/osev3-etcd/etc-d-vol2.

These settings create a persistent volume that is attached to the OAB's etcd instance during cluster installation.

### 2.6.3.22.2. Configuring the OpenShift Ansible Broker for Local APB Development

In order to do [APB development](#) with the OpenShift Container Registry in conjunction with the OAB, a whitelist of images the OAB can access must be defined. If a whitelist is not defined, the broker will ignore APBs and users will not see any APBs available.

By default, the whitelist is empty so that a user cannot add APB images to the broker without a cluster administrator configuring the broker. To whitelist all images that end in `-apb`:

1. In your inventory file, add the following to the [OSEv3:vars] section:

```
ansible_service_broker_local_registry_whitelist=['.*-apb$']
```

### 2.6.3.23. Configuring the Template Service Broker

The [template service broker](#) (TSB) is enabled by default during installation.

To configure the TSB, one or more projects must be defined as the broker's source namespace(s) for loading templates and image streams into the service catalog. Set the desired projects by modifying the following in your inventory file's [OSEv3:vars] section:

```
openshift_template_service_broker_namespaces=['openshift','myproject']
```

By default, the TSB will use the nodeselector `{"region": "infra"}` for deploying its pods. You can modify this by setting the desired nodeselector in your inventory file's [OSEv3:vars] section:

```
template_service_broker_selector={"region": "infra"}
```

### 2.6.3.24. Configuring Web Console Customization

The following Ansible variables set master configuration options for customizing the web console. See [Customizing the Web Console](#) for more details on these customization options.

**Table 2.18. Web Console Customization Variables**

Variable	Purpose
<code>openshift_web_console_install</code>	Determines whether to install the web console. Can be set to <code>true</code> or <code>false</code> . Defaults to <code>true</code> .
<code>openshift_web_console_prefix</code>	The prefix for the component images. For example, with <code>openshift3/ose-web-console:v3.9</code> , set prefix <code>openshift3/ose-</code> .

Variable	Purpose
<code>openshift_web_console_version</code>	The version for the component images. For example, with <code>openshift3/ose-web-console:v3.9</code> , set prefix <code>openshift3/ose-</code> . <code>openshift3/ose-web-console:v3.9.11</code> , set version as <code>v3.9.11</code> , or to always get the latest 3.9 image, set <code>v3.9</code> .
<code>openshift_master_logout_url</code>	Sets <code>clusterInfo.logoutPublicURL</code> in the web console configuration. See <a href="#">Changing the Logout URL</a> for details. Example value: <code>https://example.com/logout</code>
<code>openshift_web_console_extension_script_urls</code>	Sets <code>extensions.scriptURLs</code> in the web console configuration. See <a href="#">Loading Extension Scripts and Stylesheets</a> for details. Example value: <code>['https://example.com/scripts/menu-customization.js', 'https://example.com/scripts/nav-customization.js']</code>
<code>openshift_web_console_extension_stylesheet_urls</code>	Sets <code>extensions.stylesheetURLs</code> in the web console configuration. See <a href="#">Loading Extension Scripts and Stylesheets</a> for details. Example value: <code>['https://example.com/styles/logo.css', 'https://example.com/styles/custom-styles.css']</code>
<code>openshift_master_oauth_template</code>	Sets the OAuth template in the master configuration. See <a href="#">Customizing the Login Page</a> for details. Example value: <code>['/path/to/login-template.html']</code>
<code>openshift_master_metrics_public_url</code>	Sets <code>metricsPublicURL</code> in the master configuration. See <a href="#">Setting the Metrics Public URL</a> for details. Example value: <code>https://hawkular-metrics.example.com/hawkular/metrics</code>
<code>openshift_master_logging_public_url</code>	Sets <code>loggingPublicURL</code> in the master configuration. See <a href="#">Kibana</a> for details. Example value: <code>https://kibana.example.com</code>
<code>openshift_web_console_inactivity_timeout_minutes</code>	Configure the web console to log the user out automatically after a period of inactivity. Must be a whole number greater than or equal to 5, or 0 to disable the feature. Defaults to 0 (disabled).

Variable	Purpose
<code>openshift_web_console_cluster_resource_overrides_enabled</code>	Boolean value indicating if the cluster is configured for overcommit. When <code>true</code> , the web console will hide fields for CPU request, CPU limit, and memory request when editing resource limits since these values should be set by the cluster resource override configuration.

## 2.6.4. Example Inventory Files

### 2.6.4.1. Single Master Examples

You can configure an environment with a single master and multiple nodes, and either a single or multiple number of external etcd hosts.



#### NOTE

Moving from a single master cluster to multiple masters after installation is not supported.

#### Single Master, Single etcd, and Multiple Nodes

The following table describes an example environment for a single `master` (with a single `etcd` on the same host), two `nodes` for hosting user applications, and two nodes with the `region=infra` label for hosting `dedicated infrastructure`:

Host Name	Infrastructure Component to Install
<code>master.example.com</code>	Master, etcd, and node
<code>node1.example.com</code>	Node
<code>node2.example.com</code>	
<code>infra-node1.example.com</code>	Node (with <code>region=infra</code> label)
<code>infra-node2.example.com</code>	

You can see these example hosts present in the `[masters]`, `[etcd]`, and `[nodes]` sections of the following example inventory file:

#### Single Master, Single etcd, and Multiple Nodes Inventory File

```
# Create an OSEv3 group that contains the masters, nodes, and etcd groups
[OSEv3:children]
masters
nodes
etcd

# Set variables common for all OSEv3 hosts
```

```
[OSEv3:vars]
# SSH user, this user should allow ssh based auth without requiring a
password
ansible_ssh_user=root

# If ansible_ssh_user is not root, ansible_become must be set to true
#ansible_become=true

openshift_deployment_type=openshift-enterprise
oreg_url=example.com/openshift3/ose-${component}:${version}
openshift_examples_modify_imagestreams=true

# uncomment the following to enable htpasswd authentication; defaults to
DenyAllPasswordIdentityProvider
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

# host group for masters
[masters]
master.example.com

# host group for etcd
[etcd]
master.example.com

# host group for nodes, includes region info
[nodes]
master.example.com
node1.example.com openshift_node_labels="{'region': 'primary', 'zone':
'east'}"
node2.example.com openshift_node_labels="{'region': 'primary', 'zone':
'west'}"
infra-node1.example.com openshift_node_labels="{'region': 'infra', 'zone':
'default'}"
infra-node2.example.com openshift_node_labels="{'region': 'infra', 'zone':
'default'}"
```



## IMPORTANT

See [Configuring Node Host Labels](#) to ensure you understand the default node selector requirements and node label considerations beginning in OpenShift Container Platform 3.9.

To use this example, modify the file to match your environment and specifications, and save it as `/etc/ansible/hosts`.

### Single Master, Multiple etcd, and Multiple Nodes

The following table describes an example environment for a single `master`, three `etcd` hosts, two `nodes` for hosting user applications, and two nodes with the `region=infra` label for hosting `dedicated infrastructure`:

Host Name	Infrastructure Component to Install
master.example.com	Master and node
etcd1.example.com	etcd
etcd2.example.com	
etcd3.example.com	
node1.example.com	Node
node2.example.com	
infra-node1.example.com	Node (with <b>region=infra</b> label)
infra-node2.example.com	

You can see these example hosts present in the **[masters]**, **[nodes]**, and **[etcd]** sections of the following example inventory file:

### Single Master, Multiple etcd, and Multiple Nodes Inventory File

```
# Create an OSEv3 group that contains the masters, nodes, and etcd groups
[OSEv3:children]
masters
nodes
etcd


# Set variables common for all OSEv3 hosts
[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise
oreg_url=example.com/openshift3/ose-${component}:${version}
openshift_examples_modify_imagestreams=true

# uncomment the following to enable htpasswd authentication; defaults to
DenyAllPasswordIdentityProvider
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login': 'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider', 'filename': '/etc/origin/master/htpasswd'}]

# host group for masters
[masters]
master.example.com

# host group for etcd
[etcd]
etcd1.example.com
etcd2.example.com
etcd3.example.com
```

```
# host group for nodes, includes region info
[nodes]
master.example.com
node1.example.com openshift_node_labels="{'region': 'primary', 'zone': 'east'}"
node2.example.com openshift_node_labels="{'region': 'primary', 'zone': 'west'}"
infra-node1.example.com openshift_node_labels="{'region': 'infra', 'zone': 'default'}"
infra-node2.example.com openshift_node_labels="{'region': 'infra', 'zone': 'default'}"
```



## IMPORTANT

See [Configuring Node Host Labels](#) to ensure you understand the default node selector requirements and node label considerations beginning in OpenShift Container Platform 3.9.

To use this example, modify the file to match your environment and specifications, and save it as ***/etc/ansible/hosts***.

### 2.6.4.2. Multiple Masters Examples

You can configure an environment with multiple masters, multiple etcd hosts, and multiple nodes. Configuring [multiple masters for high availability](#) (HA) ensures that the cluster has no single point of failure.



## NOTE

Moving from a single master cluster to multiple masters after installation is not supported.

When configuring multiple masters, the advanced installation supports the **native** high availability (HA) method. This method leverages the native HA master capabilities built into OpenShift Container Platform and can be combined with any load balancing solution.

If a host is defined in the **[lb]** section of the inventory file, Ansible installs and configures HAProxy automatically as the load balancing solution. If no host is defined, it is assumed you have pre-configured an external load balancing solution of your choice to balance the master API (port 8443) on all master hosts.



## NOTE

This HAProxy load balancer is intended to demonstrate the API server's HA mode and is not recommended for production environments. If you are deploying to a cloud provider, Red Hat recommends deploying a cloud-native TCP-based load balancer or take other steps to provide a highly available load balancer.

For an external load balancing solution, you must have:

- A pre-created load balancer virtual IP (VIP) configured for SSL passthrough.
- A VIP listening on the port specified by the **openshift\_master\_api\_port** value (8443 by default) and proxying back to all master hosts on that port.

- A domain name for VIP registered in DNS.
  - The domain name will become the value of both `openshift_master_cluster_public_hostname` and `openshift_master_cluster_hostname` in the OpenShift Container Platform installer.

See [the External Load Balancer Integrations example in Github](#) for more information. For more on the high availability master architecture, see [Kubernetes Infrastructure](#).



## NOTE

The advanced installation method does not currently support multiple HAProxy load balancers in an active-passive setup. See the [Load Balancer Administration documentation](#) for post-installation amendments.

To configure multiple masters, refer to [Multiple Masters with Multiple etcd](#)

### Multiple Masters Using Native HA with External Clustered etcd

The following describes an example environment for three `masters` using the `native` HA method; one HAProxy load balancer, three `etcd` hosts, two `nodes` for hosting user applications, and two nodes with the `region=infra` label for hosting `dedicated infrastructure`:

Host Name	Infrastructure Component to Install
<code>master1.example.com</code>	Master (clustered using native HA) and node
<code>master2.example.com</code>	
<code>master3.example.com</code>	
<code>lb.example.com</code>	HAProxy to load balance API master endpoints
<code>etcd1.example.com</code>	<code>etcd</code>
<code>etcd2.example.com</code>	
<code>etcd3.example.com</code>	
<code>node1.example.com</code>	Node
<code>node2.example.com</code>	
<code>infra-node1.example.com</code>	Node (with <code>region=infra</code> label)
<code>infra-node2.example.com</code>	

You can see these example hosts present in the `[masters]`, `[etcd]`, `[lb]`, and `[nodes]` sections of the following example inventory file:

### Multiple Masters Using HAProxy Inventory File

```
# Create an OSEv3 group that contains the master, nodes, etcd, and lb
groups.
# The lb group lets Ansible configure HAProxy as the load balancing
solution.
# Comment lb out if your load balancer is pre-configured.
[OSEv3:children]
masters
nodes
etcd
lb

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise
oreg_url=https://example.com/openshift3/ose-$component:$version
openshift_examples_modify_imagestreams=true

# Uncomment the following to enable htpasswd authentication; defaults to
# DenyAllPasswordIdentityProvider.
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

# Native high availability cluster method with optional load balancer.
# If no lb group is defined installer assumes that a load balancer has
# been preconfigured. For installation the value of
# openshift_master_cluster_hostname must resolve to the load balancer
# or to one or all of the masters defined in the inventory if no load
# balancer is present.
openshift_master_cluster_method=native
openshift_master_cluster_hostname=https://openshift-internal.example.com
openshift_master_cluster_public_hostname=https://openshift-cluster.example.com

# apply updated node defaults
openshift_node_kubelet_args={'pods-per-core': ['10'], 'max-pods': ['250'],
'image-gc-high-threshold': ['90'], 'image-gc-low-threshold': ['80']}

# enable ntp on masters to ensure proper failover
openshift_clock_enabled=true

# host group for masters
[masters]
master1.example.com
master2.example.com
master3.example.com

# host group for etcd
[etcd]
etcd1.example.com
etcd2.example.com
etcd3.example.com

# Specify load balancer host
[lb]
lb.example.com
```

```
# host group for nodes, includes region info
[nodes]
master[1:3].example.com
node1.example.com openshift_node_labels="{'region': 'primary', 'zone': 'east'}"
node2.example.com openshift_node_labels="{'region': 'primary', 'zone': 'west'}"
infra-node1.example.com openshift_node_labels="{'region': 'infra', 'zone': 'default'}"
infra-node2.example.com openshift_node_labels="{'region': 'infra', 'zone': 'default'}"
```



## IMPORTANT

See [Configuring Node Host Labels](#) to ensure you understand the default node selector requirements and node label considerations beginning in OpenShift Container Platform 3.9.

To use this example, modify the file to match your environment and specifications, and save it as `/etc/ansible/hosts`.

### Multiple Masters Using Native HA with Co-located Clustered etcd

The following describes an example environment for three `masters` using the **native** HA method (with `etcd` on each host), one HAProxy load balancer, two `nodes` for hosting user applications, and two nodes with the `region=infra` label for hosting `dedicated infrastructure`:

Host Name	Infrastructure Component to Install
<code>master1.example.com</code>	Master (clustered using native HA) and node with etcd on each host
<code>master2.example.com</code>	
<code>master3.example.com</code>	
<code>lb.example.com</code>	HAProxy to load balance API master endpoints
<code>node1.example.com</code>	Node
<code>node2.example.com</code>	
<code>infra-node1.example.com</code>	Node (with <code>region=infra</code> label)
<code>infra-node2.example.com</code>	

You can see these example hosts present in the `[masters]`, `[etcd]`, `[lb]`, and `[nodes]` sections of the following example inventory file:

```
# Create an OSEv3 group that contains the master, nodes, etcd, and lb
groups.
```

```
# The lb group lets Ansible configure HAProxy as the load balancing
solution.
# Comment lb out if your load balancer is pre-configured.
[OSEv3:children]
masters
nodes
etcd
lb

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise
oreg_url=example.com/openshift3/ose-${component}:${version}
openshift_examples_modify_imagestreams=true

# Uncomment the following to enable htpasswd authentication; defaults to
# DenyAllPasswordIdentityProvider.
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

# Native high availability cluster method with optional load balancer.
# If no lb group is defined installer assumes that a load balancer has
# been preconfigured. For installation the value of
# openshift_master_cluster_hostname must resolve to the load balancer
# or to one or all of the masters defined in the inventory if no load
# balancer is present.
openshift_master_cluster_method=native
openshift_master_cluster_hostname=openshift-internal.example.com
openshift_master_cluster_public_hostname=openshift-cluster.example.com

# host group for masters
[masters]
master1.example.com
master2.example.com
master3.example.com

# host group for etcd
[etcd]
master1.example.com
master2.example.com
master3.example.com

# Specify load balancer host
[lb]
lb.example.com

# host group for nodes, includes region info
[nodes]
master[1:3].example.com
node1.example.com openshift_node_labels="{'region': 'primary', 'zone':
'east'}"
node2.example.com openshift_node_labels="{'region': 'primary', 'zone':
'west'}"
infra-node1.example.com openshift_node_labels="{'region': 'infra', 'zone':
```

```
'default'}"
infra-node2.example.com openshift_node_labels="{'region': 'infra', 'zone':
'default'}"
```



### IMPORTANT


See [Configuring Node Host Labels](#) to ensure you understand the default node selector requirements and node label considerations beginning in OpenShift Container Platform 3.9.

To use this example, modify the file to match your environment and specifications, and save it as `/etc/ansible/hosts`.

## 2.6.5. Running the Advanced Installation

After you have [configured Ansible](#) by defining an inventory file in `/etc/ansible/hosts`, you run the advanced installation playbook via Ansible.

The installer uses modularized playbooks allowing administrators to install specific components as needed. By breaking up the roles and playbooks, there is better targeting of ad hoc administration tasks. This results in an increased level of control during installations and results in time savings.



### NOTE

The playbooks and their ordering are detailed below in [Running Individual Component Playbooks](#).

### 2.6.5.1. Running the RPM-based Installer

The RPM-based installer uses Ansible installed via RPM packages to run playbooks and configuration files available on the local host.



### IMPORTANT

Do not run OpenShift Ansible playbooks under `nohup`. Using `nohup` with the playbooks causes file descriptors to be created and not closed. Therefore, the system can run out of files to open and the playbook will fail.

To run the RPM-based installer:

- Run the `prerequisites.yml` playbook. This playbook installs required software packages, if any, and modifies the container runtimes. Unless you need to configure the container runtimes, run this playbook only once, before you deploy a cluster the first time:

```
# ansible-playbook [-i /path/to/inventory] \
/usr/share/ansible/openshift-ansible/playbooks/prerequisites.yml
```

- If your inventory file is not in the `/etc/ansible/hosts` directory, specify `-i` and the path to the inventory file.

- Run the `deploy_cluster.yml` playbook to initiate the cluster installation:

```
# ansible-playbook [-i /path/to/inventory] \
    /usr/share/ansible/openshift-
    ansible/playbooks/deploy_cluster.yml
```

If for any reason the installation fails, before re-running the installer, see [Known Issues](#) to check for any specific instructions or workarounds.



### WARNING

The installer caches playbook configuration values for 10 minutes, by default. If you change any system, network, or inventory configuration, and then re-run the installer within that 10 minute period, the new values are not used, and the previous values are used instead. You can delete the contents of the cache, which is defined by the **fact\_caching\_connection** value in the **/etc/ansible/ansible.cfg** file. An example of this file is shown in [Recommended Installation Practices](#).

## 2.6.5.2. Running the Containerized Installer

The **openshift3/ose-ansible** image is a containerized version of the OpenShift Container Platform installer. This installer image provides the same functionality as the RPM-based installer, but it runs in a containerized environment that provides all of its dependencies rather than being installed directly on the host. The only requirement to use it is the ability to run a container.

### 2.6.5.2.1. Running the Installer as a System Container

The installer image can be used as a [system container](#). System containers are stored and run outside of the traditional **docker** service. This enables running the installer image from one of the target hosts without concern for the install restarting **docker** on the host.

To use the Atomic CLI to run the installer as a run-once system container, perform the following steps as the **root** user:

1. Run the **prerequisites.yml** playbook:

```
# atomic install --system \
    --storage=ostree \
    --set INVENTORY_FILE=/path/to/inventory \ ①
    --set PLAYBOOK_FILE=/usr/share/ansible/openshift-
    ansible/playbooks/prerequisites.yml \
    --set OPTS="-v" \
    registry.access.redhat.com/openshift3/ose-ansible:v3.9
```

- 1 Specify the location on the local host for your inventory file.

This command runs a set of prerequisite tasks by using the inventory file specified and the **root** user's SSH configuration.

2. Run the **deploy\_cluster.yml** playbook:

```
# atomic install --system \
--storage=ostree \
--set INVENTORY_FILE=/path/to/inventory \ ①
--set PLAYBOOK_FILE=/usr/share/ansible/openshift-
ansible/playbooks/deploy_cluster.yml \
--set OPTS="-v" \
registry.access.redhat.com/openshift3/ose-ansible:v3.9
```

- 1 Specify the location on the local host for your inventory file.

This command initiates the cluster installation by using the inventory file specified and the **root** user's SSH configuration. It logs the output on the terminal and also saves it in the **/var/log/ansible.log** file. The first time this command is run, the image is imported into **OSTree** storage (system containers use this rather than **docker** daemon storage). On subsequent runs, it reuses the stored image.

If for any reason the installation fails, before re-running the installer, see [Known Issues](#) to check for any specific instructions or workarounds.

#### 2.6.5.2.2. Running Other Playbooks

You can use the **PLAYBOOK\_FILE** environment variable to specify other playbooks you want to run by using the containerized installer. The default value of the **PLAYBOOK\_FILE** is **/usr/share/ansible/openshift-ansible/playbooks/deploy\_cluster.yml**, which is the main cluster installation playbook, but you can set it to the path of another playbook inside the container.

For example, to run the [pre-install checks](#) playbook before installation, use the following command:

```
# atomic install --system \
--storage=ostree \
--set INVENTORY_FILE=/path/to/inventory \
--set PLAYBOOK_FILE=/usr/share/ansible/openshift-
ansible/playbooks/openshift-checks/pre-install.yml \ ①
--set OPTS="-v" \ ②
registry.access.redhat.com/openshift3/ose-ansible:v3.9
```

- 1 Set **PLAYBOOK\_FILE** to the full path of the playbook starting at the **playbooks**/directory. Playbooks are located in the same locations as with the RPM-based installer.
- 2 Set **OPTS** to add command line options to **ansible-playbook**.

#### 2.6.5.2.3. Running the Installer as a Docker Container

The installer image can also run as a **docker** container anywhere that **docker** can run.

**WARNING**

This method must not be used to run the installer on one of the hosts being configured, as the install may restart **docker** on the host, disrupting the installer container execution.

**NOTE**

Although this method and the system container method above use the same image, they run with different entry points and contexts, so runtime parameters are not the same.

At a minimum, when running the installer as a **docker** container you must provide:

- SSH key(s), so that Ansible can reach your hosts.
- An Ansible inventory file.
- The location of the Ansible playbook to run against that inventory.

Here is an example of how to run an install via **docker**, which must be run by a non-**root** user with access to **docker**:

1. First, run the *prerequisites.yml* playbook:

```
$ docker run -t -u `id -u` \ ①
  -v $HOME/.ssh/id_rsa:/opt/app-root/src/.ssh/id_rsa:Z \ ②
  -v $HOME/ansible/hosts:/tmp/inventory:Z \ ③
  -e INVENTORY_FILE=/tmp/inventory \ ④
  -e PLAYBOOK_FILE=playbooks/prerequisites.yml \ ⑤
  -e OPTS="-v" \ ⑥
  registry.access.redhat.com/openshift3/ose-ansible:v3.9
```

- 1 **-u `id -u`** makes the container run with the same UID as the current user, which allows that user to use the SSH key inside the container (SSH private keys are expected to be readable only by their owner).
- 2 **-v \$HOME/.ssh/id\_rsa:/opt/app-root/src/.ssh/id\_rsa:Z** mounts your SSH key (**\$HOME/.ssh/id\_rsa**) under the container user's **\$HOME/.ssh** (**/opt/app-root/src** is the **\$HOME** of the user in the container). If you mount the SSH key into a non-standard location you can add an environment variable with **-e ANSIBLE\_PRIVATE\_KEY\_FILE=/the/mount/point** or set **ansible\_ssh\_private\_key\_file=/the/mount/point** as a variable in the inventory to point Ansible at it. Note that the SSH key is mounted with the **:Z** flag. This is required so that the container can read the SSH key under its restricted SELinux context. This also means that your original SSH key file will be re-labeled to something like **system\_u:object\_r:container\_file\_t:s0:c113,c247**. For more details about **:Z**, check the **docker-run(1)** man page. Keep this in mind when providing these volume mount specifications because this might have unexpected consequences: for example, if you mount (and therefore re-label) your whole **\$HOME/.ssh** directory it will block the host's

**sshd** from accessing your public keys to login. For this reason you may want to use a separate copy of the SSH key (or directory), so that the original file labels remain untouched.

**3 4** -v \$HOME/ansible/hosts:/tmp/inventory:Z and -e

**INVENTORY\_FILE=/tmp/inventory** mount a static Ansible inventory file into the container as **/tmp/inventory** and set the corresponding environment variable to point at it. As with the SSH key, the inventory file SELinux labels may need to be relabeled by using the :Z flag to allow reading in the container, depending on the existing label (for files in a user **\$HOME** directory this is likely to be needed). So again you may prefer to copy the inventory to a dedicated location before mounting it. The inventory file can also be downloaded from a web server if you specify the **INVENTORY\_URL** environment variable, or generated dynamically using **DYNAMIC\_SCRIPT\_URL** to specify an executable script that provides a dynamic inventory.

- 5** -e **PLAYBOOK\_FILE=playbooks/prerequisites.yml** specifies the playbook to run (in this example, the prerequisites playbook) as a relative path from the top level directory of **openshift-ansible** content. The full path from the RPM can also be used, as well as the path to any other playbook file in the container.
- 6** -e **OPTS="-v"** supplies arbitrary command line options (in this case, -v to increase verbosity) to the **ansible-playbook** command that runs inside the container.

2. Next, run the **deploy\_cluster.yml** playbook to initiate the cluster installation:

```
$ docker run -t -u `id -u` \
-v $HOME/.ssh/id_rsa:/opt/app-root/src/.ssh/id_rsa:Z \
-v $HOME/ansible/hosts:/tmp/inventory:Z \
-e INVENTORY_FILE=/tmp/inventory \
-e PLAYBOOK_FILE=playbooks/deploy_cluster.yml \
-e OPTS="-v" \
registry.access.redhat.com/openshift3/ose-ansible:v3.9
```

### 2.6.5.3. Running Individual Component Playbooks

The main installation playbook **/usr/share/ansible/openshift-ansible/playbooks/deploy\_cluster.yml** runs a set of individual component playbooks in a specific order, and the installer reports back at the end what phases you have gone through. If the installation fails, you are notified which phase failed along with the errors from the Ansible run.

After you resolve the errors, you can continue installation:

- You can run the remaining individual installation playbooks.
- If you are installing in a new environment, you can run the **deploy\_cluster.yml** playbook again.

If you want to run only the remaining playbooks, start by running the playbook for the phase that failed and then run each of the remaining playbooks in order:

```
# ansible-playbook [-i /path/to/inventory] <playbook_file_location>
```

The following table lists the playbooks in the order that they must run:

**Table 2.19. Individual Component Playbook Run Order**

Playbook Name	File Location
Health Check	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-checks/pre-install.yml</code>
etcd Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-etcd/config.yml</code>
NFS Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-nfs/config.yml</code>
Load Balancer Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-loadbalancer/config.yml</code>
Master Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-master/config.yml</code>
Master Additional Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-master/additional_config.yml</code>
Node Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-node/config.yml</code>
GlusterFS Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-glusterfs/config.yml</code>
Hosted Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-hosted/config.yml</code>
Web Console Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-web-console/config.yml</code>
Metrics Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-metrics/config.yml</code>
Logging Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-logging/config.yml</code>
Prometheus Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-prometheus/config.yml</code>
Service Catalog Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-service-catalog/config.yml</code>
Management Install	<code>/usr/share/ansible/openshift-ansible/playbooks/openshift-management/config.yml</code>

## 2.6.6. Verifying the Installation

After the installation completes:

1. Verify that the master is started and nodes are registered and reporting in **Ready** status. *On the master host*, run the following as root:

```
# oc get nodes
NAME           STATUS    ROLES     AGE      VERSION

```

master.example.com v1.9.1+a0ce1bc657	Ready	master	7h
node1.example.com v1.9.1+a0ce1bc657	Ready	compute	7h
node2.example.com v1.9.1+a0ce1bc657	Ready	compute	7h

- To verify that the web console is installed correctly, use the master host name and the web console port number to access the web console with a web browser.

For example, for a master host with a host name of `master.openshift.com` and using the default port of **8443**, the web console would be found at `https://master.openshift.com:8443/console`.

### Verifying Multiple etcd Hosts

If you installed multiple etcd hosts:

- First, verify that the `etcd` package, which provides the `etcdctl` command, is installed:

```
# yum install etcd
```

- On a master host, verify the etcd cluster health, substituting for the FQDNs of your etcd hosts in the following:

```
# etcdctl -c \
https://etcd1.example.com:2379,https://etcd2.example.com:2379,https://
//etcd3.example.com:2379 \
--ca-file=/etc/origin/master/master.etcd-ca.crt \
--cert-file=/etc/origin/master/master.etcd-client.crt \
--key-file=/etc/origin/master/master.etcd-client.key cluster-
health
```

- Also verify the member list is correct:

```
# etcdctl -c \
https://etcd1.example.com:2379,https://etcd2.example.com:2379,https://
//etcd3.example.com:2379 \
--ca-file=/etc/origin/master/master.etcd-ca.crt \
--cert-file=/etc/origin/master/master.etcd-client.crt \
--key-file=/etc/origin/master/master.etcd-client.key member list
```

### Verifying Multiple Masters Using HAProxy

If you installed multiple masters using HAProxy as a load balancer, browse to the following URL according to your [lb] section definition and check HAProxy's status:

```
http://<lb_hostname>:9000
```

You can verify your installation by consulting the [HAProxy Configuration documentation](#).

### 2.6.7. Optionally Securing Builds

Running `docker build` is a privileged process, so the container has more access to the node than might be considered acceptable in some multi-tenant environments. If you do not trust your users, you

can use a more secure option at the time of installation. Disable Docker builds on the cluster and require that users build images outside of the cluster. See [Securing Builds by Strategy](#) for more information on this optional process.

## 2.6.8. Uninstalling OpenShift Container Platform

You can uninstall OpenShift Container Platform hosts in your cluster by running the [\*uninstall.yml\*](#) playbook. This playbook deletes OpenShift Container Platform content installed by Ansible, including:

- Configuration
- Containers
- Default templates and image streams
- Images
- RPM packages

The playbook will delete content for any hosts defined in the inventory file that you specify when running the playbook. If you want to uninstall OpenShift Container Platform across all hosts in your cluster, run the playbook using the inventory file you used when installing OpenShift Container Platform initially or ran most recently:

```
# ansible-playbook [-i /path/to/file] \
/usr/share/ansible/openshift-ansible/playbooks/adhoc/uninstall.yml
```

### 2.6.8.1. Uninstalling Nodes

You can also uninstall node components from specific hosts using the [\*uninstall.yml\*](#) playbook while leaving the remaining hosts and cluster alone:



#### WARNING

This method should only be used when attempting to uninstall specific node hosts and not for specific masters or etcd hosts, which would require further configuration changes within the cluster.

1. First follow the steps in [Deleting Nodes](#) to remove the node object from the cluster, then continue with the remaining steps in this procedure.
2. Create a different inventory file that only references those hosts. For example, to only delete content from one node:

```
[OSEv3:children]
nodes ①

[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise
```

```
[nodes]
node3.example.com openshift_node_labels="{'region': 'primary',
'zone': 'west'}" ②
```

- ① Only include the sections that pertain to the hosts you are interested in uninstalling.
- ② Only include hosts that you want to uninstall.

3. Specify that new inventory file using the `-i` option when running the `uninstall.yml` playbook:

```
# ansible-playbook -i /path/to/new/file \
    /usr/share/ansible/openshift-
    ansible/playbooks/adhoc/uninstall.yml
```

When the playbook completes, all OpenShift Container Platform content should be removed from any specified hosts.

### 2.6.9. Known Issues

- On failover in multiple master clusters, it is possible for the controller manager to overcorrect, which causes the system to run more pods than what was intended. However, this is a transient event and the system does correct itself over time. See <https://github.com/kubernetes/kubernetes/issues/10030> for details.
- If the Ansible installer fails, you can still install OpenShift Container Platform:
  - If you did not modify the SDN configuration or generate new certificates, run the `deploy_cluster.yml` playbook again.
  - If you modified the SDN configuration, generated new certificates, or the installer fails again, you must either start over with a clean operating system installation or `uninstall` and install again.
  - If you use virtual machines, start from a fresh image or `uninstall` and install again.
  - If you use bare metal machines, `uninstall` and install again.
- There is a known issue in the initial GA release of OpenShift Container Platform 3.9 that causes the installation and upgrade playbooks to consume more memory than previous releases. The node scale-up and installation Ansible playbooks may have consumed more memory on the control host (the system where you run the playbooks from) than expected due to the use of `include_tasks` in several places. This issue has been addressed with the release of [RHBA-2018:0600](#); the majority of these instances have now been converted to `import_tasks` calls, which do not consume as much memory. After this change, memory consumption on the control host should be below 100MiB per host; for large environments (100+ hosts), a control host with at least 16GiB of memory is recommended. ([BZ#1558672](#))

### 2.6.10. What's Next?

Now that you have a working OpenShift Container Platform instance, you can:

- Deploy an [integrated Docker registry](#).
- Deploy a [router](#).

## 2.7. DISCONNECTED INSTALLATION

### 2.7.1. Overview

Frequently, portions of a datacenter may not have access to the Internet, even via proxy servers. Installing OpenShift Container Platform in these environments is considered a disconnected installation.

An OpenShift Container Platform disconnected installation differs from a regular installation in two primary ways:

- The OpenShift Container Platform software channels and repositories are not available via Red Hat's content distribution network.
- OpenShift Container Platform uses several containerized components. Normally, these images are pulled directly from Red Hat's Docker registry. In a disconnected environment, this is not possible.

A disconnected installation ensures the OpenShift Container Platform software is made available to the relevant servers, then follows the same installation process as a standard connected installation. This topic additionally details how to manually download the container images and transport them onto the relevant servers.

Once installed, in order to use OpenShift Container Platform, you will need source code in a source control repository (for example, Git). This topic assumes that an internal Git repository is available that can host source code and this repository is accessible from the OpenShift Container Platform nodes. Installing the source control repository is outside the scope of this document.

Also, when building applications in OpenShift Container Platform, your build may have some external dependencies, such as a Maven Repository or Gem files for Ruby applications. For this reason, and because they might require certain tags, many of the Quickstart templates offered by OpenShift Container Platform may not work on a disconnected environment. However, while Red Hat container images try to reach out to external repositories by default, you can configure OpenShift Container Platform to use your own internal repositories. For the purposes of this document, we assume that such internal repositories already exist and are accessible from the OpenShift Container Platform nodes hosts. Installing such repositories is outside the scope of this document.



#### NOTE

You can also have a [Red Hat Satellite](#) server that provides access to Red Hat content via an intranet or LAN. For environments with Satellite, you can synchronize the OpenShift Container Platform software onto the Satellite for use with the OpenShift Container Platform servers.

[Red Hat Satellite 6.1](#) also introduces the ability to act as a Docker registry, and it can be used to host the OpenShift Container Platform containerized components. Doing so is outside of the scope of this document.

### 2.7.2. Prerequisites

This document assumes that you understand [OpenShift Container Platform's overall architecture](#) and that you have already planned out what the topology of your environment will look like.

### 2.7.3. Required Software and Components

In order to pull down the required software repositories and container images, you will need a Red Hat Enterprise Linux (RHEL) 7 server with access to the Internet and at least 100GB of additional free space. All steps in this section should be performed on the Internet-connected server as the root system user.

### 2.7.3.1. Syncing Repositories

Before you sync with the required repositories, you may need to import the appropriate GPG key:

```
$ rpm --import /etc/pki/rpm-gpg/RPM-GPG-KEY-redhat-release
```

If the key is not imported, the indicated package is deleted after syncing the repository.

To sync the required repositories:

1. Register the server with the Red Hat Customer Portal. You must use the login and password associated with the account that has access to the OpenShift Container Platform subscriptions:

```
$ subscription-manager register
```

2. Pull the latest subscription data from RHSM:

```
$ subscription-manager refresh
```

3. Attach to a subscription that provides OpenShift Container Platform channels. You can find the list of available subscriptions using:

```
$ subscription-manager list --available --matches '*OpenShift*'
```

Then, find the pool ID for the subscription that provides OpenShift Container Platform, and attach it:

```
$ subscription-manager attach --pool=<pool_id>
$ subscription-manager repos --disable="*"
$ subscription-manager repos \
    --enable="rhel-7-server-rpms" \
    --enable="rhel-7-server-extras-rpms" \
    --enable="rhel-7-fast-datapath-rpms" \
    --enable="rhel-7-server-ansible-2.4-rpms" \
    --enable="rhel-7-server-ose-3.9-rpms"
```

4. The **yum-utils** command provides the **reposync** utility, which lets you mirror yum repositories, and **createrepo** can create a usable **yum** repository from a directory:

```
$ sudo yum -y install yum-utils createrepo docker git
```

You will need up to 110GB of free space in order to sync the software. Depending on how restrictive your organization's policies are, you could re-connect this server to the disconnected LAN and use it as the repository server. You could use USB-connected storage and transport the software to another server that will act as the repository server. This topic covers these options.

5. Make a path to where you want to sync the software (either locally or on your USB or other device):

```
$ mkdir -p </path/to/repos>
```

- Sync the packages and create the repository for each of them. You will need to modify the command for the appropriate path you created above:

```
$ for repo in \
rhel-7-server-rpms \
rhel-7-server-extras-rpms \
rhel-7-fast-datapath-rpms \
rhel-7-server-ansible-2.4-rpms \
rhel-7-server-ose-3.9-rpms
do
    reposync --gpgcheck -lM --repoid=${repo} --
download_path=/path/to/repos
    createrepo -v </path/to/repos/>${repo} -o </path/to/repos/>${repo}
done
```

### 2.7.3.2. Syncing Images

To sync the container images:

- Start the Docker daemon:

```
$ systemctl start docker
```

- If you are performing a [containerized install](#), pull all of the required OpenShift Container Platform host component images. Replace `<tag>` with **v3.9.33** for the latest version.

```
# docker pull registry.access.redhat.com/rhel7/etcd
# docker pull registry.access.redhat.com/openshift3/ose:<tag>
# docker pull registry.access.redhat.com/openshift3/node:<tag>
# docker pull registry.access.redhat.com/openshift3/openvswitch:
<tag>
```

- Pull all of the required OpenShift Container Platform infrastructure component images. Replace `<tag>` with **v3.9.33** for the latest version.

```
$ docker pull registry.access.redhat.com/openshift3/ose-ansible:
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-cluster-
capacity:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-deployer:
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-docker-
builder:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-docker-
registry:<tag>
$ docker pull registry.access.redhat.com/openshift3/registry-
console:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-egress-http-
proxy:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-egress-
router:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-f5-router:
```

```
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-haproxy-
router:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-keepalived-
ipfailover:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-pod:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-sti-builder:
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-template-
service-broker:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-web-console:
<tag>
$ docker pull registry.access.redhat.com/openshift3/ose:<tag>
$ docker pull registry.access.redhat.com/openshift3/container-
engine:<tag>
$ docker pull registry.access.redhat.com/openshift3/node:<tag>
$ docker pull registry.access.redhat.com/openshift3/openvswitch:
<tag>
$ docker pull registry.access.redhat.com/rhel7/etcd
```



### NOTE

If you use NFS, you need the **ose-recycler** image. Otherwise, the volumes will not recycle, potentially causing errors.

The recycle reclaim policy is deprecated in favor of dynamic provisioning, and it will be removed in future releases.

- Pull all of the required OpenShift Container Platform component images for the additional centralized log aggregation and metrics aggregation components. Replace **<tag>** with **v3.9.33** for the latest version.

```
$ docker pull registry.access.redhat.com/openshift3/logging-auth-
proxy:<tag>
$ docker pull registry.access.redhat.com/openshift3/logging-curator:
<tag>
$ docker pull registry.access.redhat.com/openshift3/logging-
elasticsearch:<tag>
$ docker pull registry.access.redhat.com/openshift3/logging-fluentd:
<tag>
$ docker pull registry.access.redhat.com/openshift3/logging-kibana:
<tag>
$ docker pull registry.access.redhat.com/openshift3/oauth-proxy:
<tag>
$ docker pull registry.access.redhat.com/openshift3/metrics-
cassandra:<tag>
$ docker pull registry.access.redhat.com/openshift3/metrics-
hawkular-metrics:<tag>
$ docker pull registry.access.redhat.com/openshift3/metrics-
hawkular-openshift-agent:<tag>
$ docker pull registry.access.redhat.com/openshift3/metrics-
heapster:<tag>
$ docker pull registry.access.redhat.com/openshift3/prometheus:<tag>
$ docker pull registry.access.redhat.com/openshift3/prometheus-
alert-buffer:<tag>
```

```
$ docker pull registry.access.redhat.com/openshift3/prometheus-
alertmanager:<tag>
$ docker pull registry.access.redhat.com/openshift3/prometheus-node-
exporter:<tag>
$ docker pull registry.access.redhat.com/cloudforms46/cfme-
openshift-postgresql
$ docker pull registry.access.redhat.com/cloudforms46/cfme-
openshift-memcached
$ docker pull registry.access.redhat.com/cloudforms46/cfme-
openshift-app-ui
$ docker pull registry.access.redhat.com/cloudforms46/cfme-
openshift-app
$ docker pull registry.access.redhat.com/cloudforms46/cfme-
openshift-embedded-ansible
$ docker pull registry.access.redhat.com/cloudforms46/cfme-
openshift-httpd
$ docker pull registry.access.redhat.com/cloudforms46/cfme-httpd-
configmap-generator
$ docker pull registry.access.redhat.com/rhgs3/rhgs-server-rhel7
$ docker pull registry.access.redhat.com/rhgs3/rhgs-volmanager-rhel7
$ docker pull registry.access.redhat.com/rhgs3/rhgs-gluster-block-
prov-rhel7
$ docker pull registry.access.redhat.com/rhgs3/rhgs-s3-server-rhel7
```



## IMPORTANT

For Red Hat support, a Container-Native Storage (CNS) subscription is required for **rhgs3/** images.



## IMPORTANT

Prometheus on OpenShift Container Platform is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offeringstechpreview/>.

5. For the service catalog, OpenShift Ansible broker, and template service broker features (as described in [Advanced Installation](#)), pull the following images. Replace **<tag>** with **v3.9.33** for the latest version.

```
$ docker pull registry.access.redhat.com/openshift3/ose-service-
catalog:<tag>
$ docker pull registry.access.redhat.com/openshift3/ose-ansible-
service-broker:<tag>
$ docker pull registry.access.redhat.com/openshift3/mediawiki-apb:
<tag>
$ docker pull registry.access.redhat.com/openshift3/postgresql-apb:
<tag>
```

6. Pull the Red Hat-certified [Source-to-Image \(S2I\)](#) builder images that you intend to use in your OpenShift environment. You can pull the following images:

```
$ docker pull registry.access.redhat.com/jboss-amq-6/amq63-openshift
$ docker pull registry.access.redhat.com/jboss-datagrid-
7/datagrid71-openshift
$ docker pull registry.access.redhat.com/jboss-datagrid-
7/datagrid71-client-openshift
$ docker pull registry.access.redhat.com/jboss-datavirt-
6/datavirt63-openshift
$ docker pull registry.access.redhat.com/jboss-datavirt-
6/datavirt63-driver-openshift
$ docker pull registry.access.redhat.com/jboss-decisionserver-
6/decisionserver64-openshift
$ docker pull registry.access.redhat.com/jboss-processserver-
6/processserver64-openshift
$ docker pull registry.access.redhat.com/jboss-eap-6/eap64-openshift
$ docker pull registry.access.redhat.com/jboss-eap-7/eap70-openshift
$ docker pull registry.access.redhat.com/jboss-webserver-
3/webserver31-tomcat7-openshift
$ docker pull registry.access.redhat.com/jboss-webserver-
3/webserver31-tomcat8-openshift
$ docker pull registry.access.redhat.com/openshift3/jenkins-1-rhel7
$ docker pull registry.access.redhat.com/openshift3/jenkins-2-rhel7
$ docker pull registry.access.redhat.com/openshift3/jenkins-slave-
base-rhel7
$ docker pull registry.access.redhat.com/openshift3/jenkins-slave-
maven-rhel7
$ docker pull registry.access.redhat.com/openshift3/jenkins-slave-
nodejs-rhel7
$ docker pull registry.access.redhat.com/rhscl/mongodb-32-rhel7
$ docker pull registry.access.redhat.com/rhscl/mysql-57-rhel7
$ docker pull registry.access.redhat.com/rhscl/perl-524-rhel7
$ docker pull registry.access.redhat.com/rhscl/php-56-rhel7
$ docker pull registry.access.redhat.com/rhscl/postgresql-95-rhel7
$ docker pull registry.access.redhat.com/rhscl/python-35-rhel7
$ docker pull registry.access.redhat.com/redhat-sso-7/sso70-
openshift
$ docker pull registry.access.redhat.com/rhscl/ruby-24-rhel7
$ docker pull registry.access.redhat.com/redhat-openjdk-
18/openjdk18-openshift
$ docker pull registry.access.redhat.com/redhat-sso-7/sso71-
openshift
$ docker pull registry.access.redhat.com/rhscl/nodejs-6-rhel7
$ docker pull registry.access.redhat.com/rhscl/mariadb-101-rhel7
```

Make sure to indicate the correct tag specifying the desired version number. For example, to pull both the previous and latest version of the Tomcat image:

```
$ docker pull \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:latest
$ docker pull \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:1.1
```

### 2.7.3.3. Preparing Images for Export

Container images can be exported from a system by first saving them to a tarball and then transporting them:

1. Make and change into a repository home directory:

```
$ mkdir </path/to/repos/images>
$ cd </path/to/repos/images>
```

2. If you are performing a [containerized install](#), export the OpenShift Container Platform host component images:

```
# docker save -o ose3-host-images.tar \
  registry.access.redhat.com/rhel7/etcd \
  registry.access.redhat.com/openshift3/ose \
  registry.access.redhat.com/openshift3/node \
  registry.access.redhat.com/openshift3/openvswitch
```

3. Export the OpenShift Container Platform infrastructure component images:

```
$ docker save -o ose3-images.tar \
  registry.access.redhat.com/openshift3/ose-ansible \
  registry.access.redhat.com/openshift3/ose-ansible-service-broker \
  registry.access.redhat.com/openshift3/ose-cluster-capacity \
  registry.access.redhat.com/openshift3/ose-deployer \
  registry.access.redhat.com/openshift3/ose-docker-builder \
  registry.access.redhat.com/openshift3/ose-docker-registry \
  registry.access.redhat.com/openshift3/registry-console \
  registry.access.redhat.com/openshift3/ose-egress-http-proxy \
  registry.access.redhat.com/openshift3/ose-egress-router \
  registry.access.redhat.com/openshift3/ose-f5-router \
  registry.access.redhat.com/openshift3/ose-haproxy-router \
  registry.access.redhat.com/openshift3/ose-keepalived-ipfailover \
  registry.access.redhat.com/openshift3/ose-pod \
  registry.access.redhat.com/openshift3/ose-sti-builder \
  registry.access.redhat.com/openshift3/ose-template-service-
  broker \
  registry.access.redhat.com/openshift3/ose-web-console \
  registry.access.redhat.com/openshift3/ose \
  registry.access.redhat.com/openshift3/container-engine \
  registry.access.redhat.com/openshift3/node \
  registry.access.redhat.com/openshift3/openvswitch \
  registry.access.redhat.com/openshift3/prometheus \
  registry.access.redhat.com/openshift3/prometheus-alert-buffer \
  registry.access.redhat.com/openshift3/prometheus-alertmanager \
  registry.access.redhat.com/openshift3/prometheus-node-exporter \
  registry.access.redhat.com/cloudforms46/cfme-openshift-
  postgresql \
  registry.access.redhat.com/cloudforms46/cfme-openshift-memcached \
  registry.access.redhat.com/cloudforms46/cfme-openshift-app-ui \
  registry.access.redhat.com/cloudforms46/cfme-openshift-app \
  registry.access.redhat.com/cloudforms46/cfme-openshift-embedded-
```

```
ansible \
    registry.access.redhat.com/cloudforms46/cfme-openshift-httpd \
    registry.access.redhat.com/cloudforms46/cfme-httpd-configmap-
generator \
    registry.access.redhat.com/rhgs3/rhgs-server-rhel7 \
    registry.access.redhat.com/rhgs3/rhgs-volmanager-rhel7 \
    registry.access.redhat.com/rhgs3/rhgs-gluster-block-prov-rhel7 \
    registry.access.redhat.com/rhgs3/rhgs-s3-server-rhel7
```



## IMPORTANT

For Red Hat support, a CNS subscription is required for **rhgs3/** images.

4. If you synchronized the metrics and log aggregation images, export them:

```
$ docker save -o ose3-logging-metrics-images.tar \
    registry.access.redhat.com/openshift3/logging-auth-proxy \
    registry.access.redhat.com/openshift3/logging-curator \
    registry.access.redhat.com/openshift3/logging-elasticsearch \
    registry.access.redhat.com/openshift3/logging-fluentd \
    registry.access.redhat.com/openshift3/logging-kibana \
    registry.access.redhat.com/openshift3/metrics-cassandra \
    registry.access.redhat.com/openshift3/metrics-hawkular-metrics \
    registry.access.redhat.com/openshift3/metrics-hawkular-
    openshift-agent \
    registry.access.redhat.com/openshift3/metrics-heapster
```

5. Export the S2I builder images that you synced in the previous section. For example, if you synced only the Jenkins and Tomcat images:

```
$ docker save -o ose3-builder-images.tar \
    registry.access.redhat.com/jboss-webserver-3/webserver30-
    tomcat7-openshift:latest \
    registry.access.redhat.com/jboss-webserver-3/webserver30-
    tomcat7-openshift:1.1 \
    registry.access.redhat.com/openshift3/jenkins-1-rhel7 \
    registry.access.redhat.com/openshift3/jenkins-2-rhel7 \
    registry.access.redhat.com/openshift3/jenkins-slave-base-rhel7 \
    registry.access.redhat.com/openshift3/jenkins-slave-maven-rhel7 \
    \
    registry.access.redhat.com/openshift3/jenkins-slave-nodejs-rhel7
```

### 2.7.4. Repository Server

During the installation (and for later updates, should you so choose), you will need a webserver to host the repositories. RHEL 7 can provide the Apache webserver.

#### Option 1: Re-configuring as a Web server

If you can re-connect the server where you synchronized the software and images to your LAN, then you can simply install Apache on the server:

```
$ sudo yum install httpd
```

Skip to [Placing the Software](#).

### Option 2: Building a Repository Server

If you need to build a separate server to act as the repository server, install a new RHEL 7 system with at least 110GB of space. On this repository server during the installation, make sure you select the **Basic Web Server** option.

#### 2.7.4.1. Placing the Software

1. If necessary, attach the external storage, and then copy the repository files into Apache's root folder. Note that the below copy step (`cp -a`) should be substituted with move (`mv`) if you are repurposing the server you used to sync:

```
$ cp -a /path/to/repos /var/www/html/
$ chmod -R +r /var/www/html/repos
$ restorecon -vR /var/www/html
```

2. Add the firewall rules:

```
$ sudo firewall-cmd --permanent --add-service=http
$ sudo firewall-cmd --reload
```

3. Enable and start Apache for the changes to take effect:

```
$ systemctl enable httpd
$ systemctl start httpd
```

### 2.7.5. OpenShift Container Platform Systems

#### 2.7.5.1. Building Your Hosts

At this point you can perform the initial creation of the hosts that will be part of the OpenShift Container Platform environment. It is recommended to use the latest version of RHEL 7 and to perform a minimal installation. You will also want to pay attention to the other [OpenShift Container Platform-specific prerequisites](#).

Once the hosts are initially built, the repositories can be set up.

#### 2.7.5.2. Connecting the Repositories

On all of the relevant systems that will need OpenShift Container Platform software components, create the required repository definitions. Place the following text in the `/etc/yum.repos.d/ose.repo` file, replacing `<server_IP>` with the IP or host name of the Apache server hosting the software repositories:

```
[rhel-7-server-rpms]
name=rhel-7-server-rpms
baseurl=http://<server_IP>/repos/rhel-7-server-rpms
enabled=1
gpgcheck=0
[rhel-7-server-extras-rpms]
name=rhel-7-server-extras-rpms
```

```

baseurl=http://<server_IP>/repos/rhel-7-server-extras-rpms
enabled=1
gpgcheck=0
[rhel-7-fast-datapath-rpms]
name=rhel-7-fast-datapath-rpms
baseurl=http://<server_IP>/repos/rhel-7-fast-datapath-rpms
enabled=1
gpgcheck=0
[rhel-7-server-ansible-2.4-rpms]
name=rhel-7-server-ansible-2.4-rpms
baseurl=http://<server_IP>/repos/rhel-7-server-ansible-2.4-rpms
enabled=1
gpgcheck=0
[rhel-7-server-ose-3.9-rpms]
name=rhel-7-server-ose-3.9-rpms
baseurl=http://<server_IP>/repos/rhel-7-server-ose-3.9-rpms
enabled=1
gpgcheck=0

```

### 2.7.5.3. Host Preparation

At this point, the systems are ready to continue to be prepared [following the OpenShift Container Platform documentation](#).

Skip the section titled **Host Registration** and start with **Installing Base Packages**.

## 2.7.6. Installing OpenShift Container Platform

### 2.7.6.1. Importing OpenShift Container Platform Component Images

To import the relevant components, securely copy the images from the connected host to the individual OpenShift Container Platform hosts:

```

$ scp /var/www/html/repos/images/ose3-images.tar
root@<openshift_host_name>:
$ ssh root@<openshift_host_name> "docker load -i ose3-images.tar"
$ scp /var/www/html/images/ose3-builder-images.tar
root@<openshift_master_host_name>:
$ ssh root@<openshift_master_host_name> "docker load -i ose3-builder-
images.tar"

```

Perform the same steps for the host components if your install will be containerized. Perform the same steps for the metrics and logging images, if your cluster will use them.

If you prefer, you could use **wget** on each OpenShift Container Platform host to fetch the tar file, and then perform the Docker import command locally.

### 2.7.6.2. Running the OpenShift Container Platform Installer

You can now choose to follow the [quick](#) or [advanced](#) OpenShift Container Platform installation instructions in the documentation.

**NOTE**

For [containerized installations](#), to install the etcd container, you can set the Ansible variable `osm_etcd_image` to be the fully qualified name of the etcd image on your local registry, for example, `registry.example.com/rhel7/etcd`.

### 2.7.6.3. Creating the Internal Docker Registry

You now need to [create the internal Docker registry](#).

If you want to [install a stand-alone registry](#), you must [pull the registry-console container image](#) and set `deployment_subtype=registry` in the inventory file.

### 2.7.7. Post-Installation Changes

In one of the previous steps, the S2I images were imported into the Docker daemon running on one of the OpenShift Container Platform master hosts. In a connected installation, these images would be pulled from Red Hat's registry on demand. Since the Internet is not available to do this, the images must be made available in another Docker registry.

OpenShift Container Platform provides an internal registry for storing the images that are built as a result of the S2I process, but it can also be used to hold the S2I builder images. The following steps assume you did not customize the service IP subnet (172.30.0.0/16) or the Docker registry port (5000).

#### 2.7.7.1. Re-tagging S2I Builder Images

1. On the master host where you imported the S2I builder images, obtain the service address of your Docker registry that you installed on the master:

```
$ export REGISTRY=$(oc get service -n default \
    docker-registry --output=go-template='{{.spec.clusterIP}} \
    {{"\n"}}{}')
```

2. Next, tag all of the builder images that you synced and exported before pushing them into the OpenShift Container Platform Docker registry. For example, if you synced and exported only the Tomcat image:

```
$ docker tag \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:1.1 \
$REGISTRY:5000/openshift/webserver30-tomcat7-openshift:1.1
$ docker tag \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:latest \
$REGISTRY:5000/openshift/webserver30-tomcat7-openshift:1.2
$ docker tag \
registry.access.redhat.com/jboss-webserver-3/webserver30-tomcat7-
openshift:latest \
$REGISTRY:5000/openshift/webserver30-tomcat7-openshift:latest
```

#### 2.7.7.2. Configuring a Registry Location

If you are using an image registry other than the default at `registry.access.redhat.com`, specify the desired registry within the `/etc/ansible/hosts` file.

```
oreg_url=example.com/openshift3/ose-${component}:${version}
openshift_examples_modify_imagestreams=true
```

Depending on your registry, you may need to configure:

```
openshift_docker_additional_registries=example.com
openshift_docker_insecure_registries=example.com
```



### NOTE

You can also set the `openshift_docker_insecure_registries` variable to the IP address of the host. `0.0.0.0/0` is not a valid setting.

**Table 2.20. Registry Variables**

Variable	Purpose
<code>oreg_url</code>	Set to the alternate image location. Necessary if you are not using the default registry at <code>registry.access.redhat.com</code> .
<code>openshift_examples_modify_imagestreams</code>	Set to <code>true</code> if pointing to a registry other than the default. Modifies the image stream location to the value of <code>oreg_url</code> .
<code>openshift_docker_additional_registries</code>	Set <code>openshift_docker_additional_registries</code> to add its value in the <code>add_registry</code> line in <code>/etc/sysconfig/docker</code> . With <code>add_registry</code> , you can add your own registry to be used for Docker search and Docker pull. Use the <code>add_registry</code> option to list a set of registries, each prepended with <code>--add-registry</code> flag. The first registry added will be the first registry searched. For example, <code>add_registry=--add-registry registry.access.redhat.com --add-registry example.com</code> .
<code>openshift_docker_insecure_registries</code>	Set <code>openshift_docker_insecure_registries</code> to add its value in the <code>insecure_registry</code> line in <code>/etc/sysconfig/docker</code> . If you have a registry secured with HTTPS but do not have proper certificates distributed, you can tell Docker not to look for full authorization by adding the registry to the <code>insecure_registry</code> line and uncommenting it. For example, <code>insecure_registry-insecure-registry example.com</code> . Can be set to the host name or IP address of the host. <code>0.0.0.0/0</code> is not a valid setting for the IP address.

### 2.7.7.3. Creating an Administrative User

Pushing the container images into OpenShift Container Platform's Docker registry requires a user with **cluster-admin** privileges. Because the default OpenShift Container Platform system administrator does not have a standard authorization token, they cannot be used to log in to the Docker registry.

To create an administrative user:

1. Create a new user account in the authentication system you are using with OpenShift Container Platform. For example, if you are using local **htpasswd**-based authentication:

```
$ htpasswd -b /etc/openshift/openshift-passwd <admin_username>  
<password>
```

2. The external authentication system now has a user account, but a user must log in to OpenShift Container Platform before an account is created in the internal database. Log in to OpenShift Container Platform for this account to be created. This assumes you are using the self-signed certificates generated by OpenShift Container Platform during the installation:

```
$ oc login --certificate-authority=/etc/origin/master/ca.crt \  
-u <admin_username> https://<openshift_master_host>:8443
```

3. Get the user's authentication token:

```
$ MYTOKEN=$(oc whoami -t)  
$ echo $MYTOKEN  
iwo7hc4Xi1D2KOLL4V1055ExH2V1PmLD-W2-J0d6Fko
```

### 2.7.7.4. Modifying the Security Policies

1. Using **oc login** switches to the new user. Switch back to the OpenShift Container Platform system administrator in order to make policy changes:

```
$ oc login -u system:admin
```

2. In order to push images into the OpenShift Container Platform Docker registry, an account must have the **image-builder** security role. Add this to your OpenShift Container Platform administrative user:

```
$ oc adm policy add-role-to-user system:image-builder  
<admin_username>
```

3. Next, add the administrative role to the user in the **openshift** project. This allows the administrative user to edit the **openshift** project, and, in this case, push the container images:

```
$ oc adm policy add-role-to-user admin <admin_username> -n openshift
```

### 2.7.7.5. Editing the Image Stream Definitions

The **openshift** project is where all of the image streams for builder images are created by the installer. They are loaded by the installer from the **/usr/share/openshift/examples** directory. Change all of the definitions by deleting the image streams which had been loaded into OpenShift Container Platform's database, then re-create them:

1. Delete the existing image streams:

```
$ oc delete is -n openshift --all
```

2. Make a backup of the files in **/usr/share/openshift/examples** if you desire. Next, edit the file **image-streams-rhel7.json** in the **/usr/share/openshift/examples/image-streams** folder. You will find an image stream section for each of the builder images. Edit the **spec** stanza to point to your internal Docker registry.

For example, change:

```
"from": {
  "kind": "DockerImage",
  "name": "registry.access.redhat.com/rhscl/httpd-24-rhel7"
}
```

to:

```
"from": {
  "kind": "DockerImage",
  "name": "172.30.69.44:5000/openshift/httpd-24-rhel7"
}
```

In the above, the repository name was changed from **rhscl** to **openshift**. You will need to ensure the change, regardless of whether the repository is **rhscl**, **openshift3**, or another directory. Every definition should have the following format:

```
<registry_ip>:5000/openshift/<image_name>
```

Repeat this change for every image stream in the file. Ensure you use the correct IP address that you determined earlier. When you are finished, save and exit. Repeat the same process for the JBoss image streams in the **/usr/share/openshift/examples/xpaas-streams/jboss-image-streams.json** file.

### 2.7.7.6. Loading the Container Images

At this point the system is ready to load the container images.

1. Log in to the Docker registry using the token and registry service IP obtained earlier:

```
$ docker login -u adminuser -e mailto:adminuser@abc.com \
-p $MYTOKEN $REGISTRY:5000
```

2. Push the Docker images:

```
$ docker push $REGISTRY:5000/openshift/webserver30-tomcat7-
openshift:1.1
$ docker push $REGISTRY:5000/openshift/webserver30-tomcat7-
openshift:1.2
$ docker push $REGISTRY:5000/openshift/webserver30-tomcat7-
openshift:latest
```

3. Load the updated image stream definitions:

```
$ oc create -f /usr/share/openshift/examples/image-streams/image-streams-rhel7.json -n openshift  
$ oc create -f /usr/share/openshift/examples/xpaas-streams/jboss-image-streams.json -n openshift
```

4. Verify that all the image streams now have the tags populated:

```
$ oc get imagestreams -n openshift  
NAME                                     DOCKER REPO  
TAGS                                     UPDATED  
jboss-webserver30-tomcat7-openshift      $REGISTRY/jboss-webserver-  
3/webserver30-jboss-tomcat7-openshift    1.1,1.1-2,1.1-6 + 2 more...  
2 weeks ago  
...
```

## 2.7.8. Installing a Router

At this point, the OpenShift Container Platform environment is almost ready for use. It is likely that you will want to [install and configure a router](#).

# 2.8. INSTALLING A STAND-ALONE DEPLOYMENT OF OPENSHIFT CONTAINER REGISTRY

## 2.8.1. About OpenShift Container Registry

OpenShift Container Platform is a fully-featured enterprise solution that includes an integrated container registry called [OpenShift Container Registry](#) (OCR). Alternatively, instead of deploying OpenShift Container Platform as a full PaaS environment for developers, you can install OCR as a stand-alone container registry to run on-premise or in the cloud.

When installing a stand-alone deployment of OCR, a cluster of masters and nodes is still installed, similar to a typical OpenShift Container Platform installation. Then, the container registry is deployed to run on the cluster. This stand-alone deployment option is useful for administrators that want a container registry, but do not require the full OpenShift Container Platform environment that includes the developer-focused web console and application build and deployment tools.

OCR provides the following capabilities:

- A user-focused [registry web console](#), Cockpit.
- [Secured traffic](#) by default, served via TLS.
- [Global identity provider authentication](#).
- A [project namespace](#) model to enable teams to collaborate through [role-based access control \(RBAC\)](#) authorization.
- A [Kubernetes-based cluster](#) to manage services.
- An image abstraction called [image streams](#) to enhance image management.

Administrators may want to deploy a stand-alone OCR to manage a registry separately that supports multiple OpenShift Container Platform clusters. A stand-alone OCR also enables administrators to separate their registry to satisfy their own security or compliance requirements.

## 2.8.2. Minimum Hardware Requirements

Installing a stand-alone OCR has the following hardware requirements:

- Physical or virtual system, or an instance running on a public or private IaaS.
- Base OS: RHEL 7.3, 7.4, or 7.5 with the "Minimal" installation option and the latest packages from the RHEL 7 Extras channel, or RHEL Atomic Host 7.4.5 or later.
- NetworkManager 1.0 or later
- 2 vCPU.
- Minimum 16 GB RAM.
- Minimum 15 GB hard disk space for the file system containing `/var/`.
- An additional minimum 15 GB unallocated space to be used for Docker's storage back end; see [Configuring Docker Storage](#) for details.



### IMPORTANT

OpenShift Container Platform only supports servers with x86\_64 architecture.



### NOTE

Meeting the `/var/` file system sizing requirements in RHEL Atomic Host requires making changes to the default configuration. See [Managing Storage in Red Hat Enterprise Linux Atomic Host](#) for instructions on configuring this during or after installation.

## 2.8.3. Supported System Topologies

The following system topologies are supported for stand-alone OCR:

All-in-one	A single host that includes the master, node, etcd, and registry components.
Multiple Masters (Highly-Available)	Three hosts with all components included on each (master, node, etcd, and registry), with the masters configured for native high-availability.

## 2.8.4. Host Preparation

Before installing stand-alone OCR, all of the same steps detailed in the [Host Preparation](#) topic for installing a full OpenShift Container Platform PaaS must be performed. This includes registering and subscribing the host(s) to the proper repositories, installing or updating certain packages, and setting up Docker and its storage requirements.

Follow the steps in the [Host Preparation](#) topic, then continue to [Stand-alone Registry Installation Methods](#).

## 2.8.5. Stand-alone Registry Installation Methods

To install a stand-alone registry, use either of the standard installation methods (quick or advanced) used to install any variant of OpenShift Container Platform.

### 2.8.5.1. Quick Installation for Stand-alone OpenShift Container Registry



#### IMPORTANT

As of OpenShift Container Platform 3.9, the quick installation method is deprecated. In a future release, it will be removed completely. In addition, using the quick installer to upgrade from version 3.7 to 3.9 is not supported.

The following shows the step-by-step process for running the quick install tool to install an OpenShift Container Registry, instead of the full OpenShift Container Platform install.

1. Start the interactive installation:

```
$ atomic-openshift-installer install
```

2. Follow the on-screen instructions to install a new registry. The installation questions will be largely the same as if you were installing a full OpenShift Container Platform PaaS. When you reach the following screen, choose **2** to follow the registry installation path:

```
Which variant would you like to install?
```

- ```
(1) OpenShift Container Platform  
(2) Registry
```

3. Specify the hosts that make up your cluster:

```
Enter hostname or IP address:
```

```
Will this host be an OpenShift master? [y/N]:
```

```
Will this host be RPM or Container based (rpm/container)? [rpm]:
```

See the [Installing on Containerized Hosts](#) topic for information about RPM versus containerized hosts.

4. Change the cluster host name, if desired:

```
Enter hostname or IP address [None]:
```

5. Choose the host to act as the storage host (the master host by default):

```
Enter hostname or IP address [master.host.example.com]:
```

6. Change the default subdomain, if desired:

```
New default subdomain (ENTER for none) []:
```


**NOTE**

All certificates and routes are created with this subdomain. Ensure this is set to the correct desired subdomain to avoid having to change the configuration after installation.

7. Specify a HTTP or HTTPS proxy, if needed:

```
Specify your http proxy ? (ENTER for none) []:
Specify your https proxy ? (ENTER for none) []:
```

After the previous has been entered, the next page summarizes your install and starts to gather the host information.

**NOTE**

For further usage details on the quick installer in general, including next steps, see the full topic at [Quick Installation](#).

### 2.8.5.2. Advanced Installation for Stand-alone OpenShift Container Registry

When using the advanced installation method to install stand-alone OCR, use the same steps for installing a full OpenShift Container Platform PaaS using Ansible described in the full [Advanced Installation](#) topic. The main difference is that you must set **deployment\_subtype=registry** in the inventory file within the **[OSEv3:vars]** section for the playbooks to follow the registry installation path.

See the following example inventory files for the different supported system topologies:

#### All-in-one Stand-alone OpenShift Container Registry Inventory File

```
# Create an OSEv3 group that contains the masters and nodes groups
[OSEv3:children]
masters
nodes
etcd

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
# SSH user, this user should allow ssh based auth without requiring a
password
ansible_ssh_user=root

openshift_master_default_subdomain=apps.test.example.com

# If ansible_ssh_user is not root, ansible_become must be set to true
#ansible_become=true

openshift_deployment_type=openshift-enterprise
deployment_subtype=registry ①
openshift_hosted_infra_selector="" ②

# uncomment the following to enable htpasswd authentication; defaults to
DenyAllPasswordIdentityProvider
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
```

```
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

# host group for masters
[masters]
registry.example.com

# host group for etcd
[etcd]
registry.example.com

# host group for nodes
[nodes]
registry.example.com
```

- 1 Set **deployment\_subtype=registry** to ensure installation of stand-alone OCR and not a full OpenShift Container Platform environment.
- 2 Allows the registry and its web console to be scheduled on the single host.

## Multiple Masters (Highly-Available) Stand-alone OpenShift Container Registry Inventory File

```
# Create an OSEv3 group that contains the master, nodes, etcd, and lb
groups.
# The lb group lets Ansible configure HAProxy as the load balancing
solution.
# Comment lb out if your load balancer is pre-configured.
[OSEv3:children]
masters
nodes
etcd
lb

# Set variables common for all OSEv3 hosts
[OSEv3:vars]
ansible_ssh_user=root
openshift_deployment_type=openshift-enterprise
deployment_subtype=registry ①

openshift_master_default_subdomain=apps.test.example.com

# Uncomment the following to enable htpasswd authentication; defaults to
# DenyAllPasswordIdentityProvider.
#openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login':
'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider',
'filename': '/etc/origin/master/htpasswd'}]

# Native high availability cluster method with optional load balancer.
# If no lb group is defined installer assumes that a load balancer has
# been preconfigured. For installation the value of
# openshift_master_cluster_hostname must resolve to the load balancer
# or to one or all of the masters defined in the inventory if no load
# balancer is present.
openshift_master_cluster_method=native
```

```

openshift_master_cluster_hostname=openshift-internal.example.com
openshift_master_cluster_public_hostname=openshift-cluster.example.com

# apply updated node defaults
openshift_node_kubelet_args={'pods-per-core': ['10'], 'max-pods': ['250'],
'image-gc-high-threshold': ['90'], 'image-gc-low-threshold': ['80']}

# enable ntp on masters to ensure proper failover
openshift_clock_enabled=true

# host group for masters
[masters]
master1.example.com
master2.example.com
master3.example.com

# host group for etcd
[etcd]
etcd1.example.com
etcd2.example.com
etcd3.example.com

# Specify load balancer host
[lb]
lb.example.com

# host group for nodes, includes region info
[nodes]
master[1:3].example.com openshift_node_labels="{'region': 'infra', 'zone': 'default'}"
node1.example.com openshift_node_labels="{'region': 'primary', 'zone': 'east'}"
node2.example.com openshift_node_labels="{'region': 'primary', 'zone': 'west'}"

```

- 1** Set **deployment\_subtype=registry** to ensure installation of stand-alone OCR and not a full OpenShift Container Platform environment.

After you have configured Ansible by defining an inventory file in **/etc/ansible/hosts**:

1. Run the **prerequisites.yml** playbook to configure base packages and Docker. This must be run only once before deploying a new cluster. Use the following command, specifying **-i** if your inventory file located somewhere other than **/etc/ansible/hosts**:



### IMPORTANT

The host that you run the Ansible playbook on must have at least 75MiB of free memory per host in the inventory.

```

# ansible-playbook [-i /path/to/inventory] \
/usr/share/ansible/openshift-ansible/playbooks/prerequisites.yml

```

2. Run the **deploy\_cluster.yml** playbook to initiate the installation:

```
# ansible-playbook [-i /path/to/inventory] \
    /usr/share/ansible/openshift-
    ansible/playbooks/deploy_cluster.yml
```



### NOTE

For more detailed usage information on the advanced installation method, including a comprehensive list of available Ansible variables, see the full topic at [Advanced Installation](#).

# CHAPTER 3. SETTING UP THE REGISTRY

## 3.1. REGISTRY OVERVIEW

### 3.1.1. About the Registry

OpenShift Container Platform can build [container images](#) from your source code, deploy them, and manage their lifecycle. To enable this, OpenShift Container Platform provides an internal, [integrated Docker registry](#) that can be deployed in your OpenShift Container Platform environment to locally manage images.

### 3.1.2. Integrated or Stand-alone Registries

During an initial installation of a full OpenShift Container Platform cluster, it is likely that the registry was deployed automatically during the installation process. If it was not, or if you want to further customize the configuration of your registry, see [Deploying a Registry on Existing Clusters](#).


While it can be deployed to run as an integrated part of your full OpenShift Container Platform cluster, the OpenShift Container Platform registry can alternatively be installed separately as a stand-alone container image registry.

To install a stand-alone registry, follow [Installing a Stand-alone Registry](#). This installation path deploys an all-in-one cluster running a registry and specialized web console.

## 3.2. DEPLOYING A REGISTRY ON EXISTING CLUSTERS

### 3.2.1. Overview

If the integrated registry was not previously deployed automatically during the initial installation of your OpenShift Container Platform cluster, or if it is no longer running successfully and you need to redeploy it on your existing cluster, see the following sections for options on deploying a new registry.



#### NOTE

This topic is not required if you installed a [stand-alone registry](#).

### 3.2.2. Deploying the Registry

To deploy the integrated Docker registry, use the `oc adm registry` command as a user with cluster administrator privileges. For example:

```
$ oc adm registry --config=/etc/origin/master/admin.kubeconfig \❶
  --service-account=registry \❷
  --images='registry.access.redhat.com/openshift3/ose-
${component}:${version}' \❸
```

❶ `--config` is the path to the [CLI configuration file](#) for the [cluster administrator](#).

❷ `--service-account` is the service account used to run the registry's pod.

❸ Required to pull the correct image for OpenShift Container Platform.

This creates a service and a deployment configuration, both called **docker-registry**. Once deployed successfully, a pod is created with a name similar to **docker-registry-1-cpty9**.

To see a full list of options that you can specify when creating the registry:

```
$ oc adm registry --help
```

The value for **--fs-group** must be [permitted by the SCC](#) used by the registry (typically, the restricted SCC).

### 3.2.3. Deploying the Registry as a DaemonSet

Use the **oc adm registry** command to deploy the registry as a **DaemonSet** with the **--daemonset** option.

Daemonsets ensure that when nodes are created, they contain copies of a specified pod. When the nodes are removed, the pods are garbage collected.

For more information on **DaemonSets**, see [Using Daemonsets](#).

### 3.2.4. Registry Compute Resources

By default, the registry is created with no settings for [compute resource requests or limits](#). For production, it is highly recommended that the deployment configuration for the registry be updated to set resource requests and limits for the registry pod. Otherwise, the registry pod will be considered a [BestEffort pod](#).

See [Compute Resources](#) for more information on configuring requests and limits.

### 3.2.5. Storage for the Registry

The registry stores container images and metadata. If you simply deploy a pod with the registry, it uses an ephemeral volume that is destroyed if the pod exits. Any images anyone has built or pushed into the registry would disappear.

This section lists the supported registry storage drivers. See the Docker registry documentation for [more information](#).

The following list includes storage drivers that need to be configured in the registry's configuration file:

- [Filesystem](#). Filesystem is the default and does not need to be configured.
- [S3](#). See the [CloudFront configuration](#) documentation for more information.
- [OpenStack Swift](#)
- [Google Cloud Storage \(GCS\)](#)
- [Microsoft Azure](#)
- [Aliyun OSS](#)

General registry storage configuration options are supported. See the Docker registry documentation for [more information](#).

The following storage options need to be configured through the [filesystem driver](#):

- GlusterFS Storage
- Ceph Rados Block Device



### NOTE

For more information on supported persistent storage drivers, see [Configuring Persistent Storage](#) and [Persistent Storage Examples](#).

#### 3.2.5.1. Production Use

For production use, attach a remote volume or [define and use the persistent storage method of your choice](#).

For example, to use an existing persistent volume claim:

```
$ oc volume deploymentconfigs/docker-registry --add --name=registry-storage -t pvc \
--claim-name=<pvc_name> --overwrite
```



### NOTE

See [Known Issues](#) if using a scaled registry with a shared NFS volume.

##### 3.2.5.1.1. Use Amazon S3 as a Storage Back-end

There is also an option to use Amazon Simple Storage Service storage with the internal Docker registry. It is a secure cloud storage manageable through [AWS Management Console](#). To use it, the registry's configuration file must be manually edited and mounted to the registry pod. However, before you start with the configuration, look at upstream's [recommended steps](#).

Take a [default YAML configuration file](#) as a base and replace the **filesystem** entry in the **storage** section with **s3** entry such as below. The resulting storage section may look like this:

```
storage:
  cache:
    layerinfo: inmemory
  delete:
    enabled: true
  s3:
    accesskey: awsaccesskey ①
    secretkey: awssecretkey ②
    region: us-west-1
    regionendpoint: http://myobjects.local
    bucket: bucketname
    encrypt: true
    keyid: mykeyid
    secure: true
    v4auth: false
    chunkszie: 5242880
    rootdirectory: /s3/object/name/prefix
```

- 1 Replace with your Amazon access key.
- 2 Replace with your Amazon secret key.

All of the **s3** configuration options are documented in upstream's [driver reference documentation](#).

[Overriding the registry configuration](#) will take you through the additional steps on mounting the configuration file into pod.




#### WARNING

When the registry runs on the S3 storage back-end, there are [reported issues](#).

### 3.2.5.2. Non-Production Use

For non-production use, you can use the **--mount-host=<path>** option to specify a directory for the registry to use for persistent storage. The registry volume is then created as a host-mount at the specified **<path>**.



#### IMPORTANT

The **--mount-host** option mounts a directory from the node on which the registry container lives. If you scale up the **docker-registry** deployment configuration, it is possible that your registry pods and containers will run on different nodes, which can result in two or more registry containers, each with its own local storage. This will lead to unpredictable behavior, as subsequent requests to pull the same image repeatedly may not always succeed, depending on which container the request ultimately goes to.

The **--mount-host** option requires that the registry container run in privileged mode. This is automatically enabled when you specify **--mount-host**. However, not all pods are allowed to run **privileged containers** by default. If you still want to use this option, create the registry and specify that it use the **registry** service account that was created during installation:

```
$ oc adm registry --service-account=registry \
  --config=/etc/origin/master/admin.kubeconfig \
  --images='registry.access.redhat.com/openshift3/ose-
${component}:${version}' \
  --mount-host=<path>
```



#### IMPORTANT

The Docker registry pod runs as user **1001**. This user must be able to write to the host directory. You may need to change directory ownership to user ID **1001** with this command:

```
$ sudo chown 1001:root <path>
```

### 3.2.6. Enabling the Registry Console

OpenShift Container Platform provides a web-based interface to the integrated registry. This registry console is an optional component for browsing and managing images. It is deployed as a stateless service running as a pod.



#### NOTE

If you installed OpenShift Container Platform as a [stand-alone registry](#), the registry console is already deployed and secured automatically during installation.



#### IMPORTANT

If Cockpit is already running, you'll need to shut it down before proceeding in order to avoid a port conflict (9090 by default) with the registry console.

#### 3.2.6.1. Deploying the Registry Console



#### IMPORTANT

You must first have [exposed the registry](#).

1. Create a passthrough route in the **default** project. You will need this when creating the registry console application in the next step.

```
$ oc create route passthrough --service registry-console \
--port registry-console \
-n default
```

2. Deploy the registry console application. Replace `<openshift_oauth_url>` with the URL of the OpenShift Container Platform OAuth provider, which is typically the master.

```
$ oc new-app -n default --template=registry-console \
-p
OPENSHIFT_OAUTH_PROVIDER_URL="https://<openshift_oauth_url>:8443" \
-p REGISTRY_HOST=$(oc get route docker-registry -n default -- \
template='{{ .spec.host }}') \
-p COCKPIT_KUBE_URL=$(oc get route registry-console -n default - \
-template='https://{{ .spec.host }}')
```



#### NOTE

If the redirection URL is wrong when you are trying to log in to the registry console, check your OAuth client with `oc get oauthclients`.

3. Finally, use a web browser to view the console using the route URI.

#### 3.2.6.2. Securing the Registry Console

By default, the registry console generates self-signed TLS certificates if deployed manually per the steps in [Deploying the Registry Console](#). See [Troubleshooting the Registry Console](#) for more information.

Use the following steps to add your organization's signed certificates as a secret volume. This assumes your certificates are available on the **oc** client host.

1. Create a **.cert** file containing the certificate and key. Format the file with:

- One or more **BEGIN CERTIFICATE** blocks for the server certificate and the intermediate certificate authorities
  - A block containing a **BEGIN PRIVATE KEY** or similar for the key. The key must not be encrypted
- For example:

```
-----BEGIN CERTIFICATE-----
MIIDUzCCAjugAwIBAgIJAPXW+CuNYS6QMA0GCSqGSIb3DQEBCwUAMD8xKTAnBgNV
BAoMIGI0OGE2NGNkNmMwNTQ1YThhZTgxOTEzZDE5YmJjMmRjMRIwEAYDVQQDDAls
...
-----END CERTIFICATE-----
-----BEGIN CERTIFICATE-----
MIIDUzCCAjugAwIBAgIJAPXW+CuNYS6QMA0GCSqGSIb3DQEBCwUAMD8xKTAnBgNV
BAoMIGI0OGE2NGNkNmMwNTQ1YThhZTgxOTEzZDE5YmJjMmRjMRIwEAYDVQQDDAls
...
-----END CERTIFICATE-----
-----BEGIN PRIVATE KEY-----
MIIEvgIBADANBgkqhkiG9w0BAQEFAASCBKgwggSkAgEAAoIBAQCyOJ5gar0Yw0sm
8TBCDSqQ/H1awGMzDYdB11xuHHsxYS2VepPMzMzryHR137I4dGFLhvdTvJUH8lUS
...
-----END PRIVATE KEY-----
```

- The secured registry should contain the following Subject Alternative Names (SAN) list:
  - Two service hostnames.  
For example:

```
docker-registry.default.svc.cluster.local
docker-registry.default.svc
```

- Service IP address.  
For example:

```
172.30.124.220
```

Use the following command to get the Docker registry service IP address:

```
oc get service docker-registry --template='{{.spec.clusterIP}}'
```

- Public hostname.  
For example:

```
docker-registry-default.apps.example.com
```

Use the following command to get the Docker registry public hostname:

```
oc get route docker-registry --template '{{.spec.host}}'
```

For example, the server certificate should contain SAN details similar to the following:

```
X509v3 Subject Alternative Name:  
DNS:docker-registry-public.openshift.com,  
DNS:docker-registry.default.svc, DNS:docker-  
registry.default.svc.cluster.local, DNS:172.30.2.98, IP  
Address:172.30.2.98
```

The registry console loads a certificate from the `/etc/cockpit/ws-certs.d` directory. It uses the last file with a `.cert` extension in alphabetical order. Therefore, the `.cert` file should contain at least two PEM blocks formatted in the OpenSSL style.

If no certificate is found, a self-signed certificate is created using the `openssl` command and stored in the `0-self-signed.cert` file.

## 2. Create the secret:

```
$ oc create secret generic console-secret \  
--from-file=/path/to/console.cert
```

## 3. Add the secrets to the `registry-console` deployment configuration:

```
$ oc volume dc/registry-console --add --type=secret \  
--secret-name=console-secret -m /etc/cockpit/ws-certs.d
```

This triggers a new deployment of the registry console to include your signed certificates.

### 3.2.6.3. Troubleshooting the Registry Console

#### 3.2.6.3.1. Debug Mode

The registry console debug mode is enabled using an environment variable. The following command redeploys the registry console in debug mode:

```
$ oc set env dc registry-console G_MESSAGES_DEBUG=cockpit-ws,cockpit-  
wrapper
```

Enabling debug mode allows more verbose logging to appear in the registry console's pod logs.

#### 3.2.6.3.2. Display SSL Certificate Path

To check which certificate the registry console is using, a command can be run from inside the console pod.

## 1. List the pods in the `default` project and find the registry console's pod name:

```
$ oc get pods -n default  
NAME                      READY     STATUS    RESTARTS   AGE  
registry-console-1-rssrw   1/1      Running   0          1d
```

## 2. Using the pod name from the previous command, get the certificate path that the `cockpit-ws` process is using. This example shows the console using the auto-generated certificate:

```
$ oc exec registry-console-1-rssrw remotectl certificate
certificate: /etc/cockpit/ws-certs.d/0-self-signed.cert
```

## 3.3. ACCESSING THE REGISTRY

### 3.3.1. Viewing Logs

To view the logs for the Docker registry, use the **oc logs** command with the deployment configuration:

```
$ oc logs dc/docker-registry
2015-05-01T19:48:36.300593110Z time="2015-05-01T19:48:36Z" level=info
msg="version=v2.0.0+unknown"
2015-05-01T19:48:36.303294724Z time="2015-05-01T19:48:36Z" level=info
msg="redis not configured" instance.id=9ed6c43d-23ee-453f-9a4b-
031fea646002
2015-05-01T19:48:36.303422845Z time="2015-05-01T19:48:36Z" level=info
msg="using inmemory layerinfo cache" instance.id=9ed6c43d-23ee-453f-9a4b-
031fea646002
2015-05-01T19:48:36.303433991Z time="2015-05-01T19:48:36Z" level=info
msg="Using OpenShift Auth handler"
2015-05-01T19:48:36.303439084Z time="2015-05-01T19:48:36Z" level=info
msg="listening on :5000" instance.id=9ed6c43d-23ee-453f-9a4b-031fea646002
```

### 3.3.2. File Storage

Tag and image metadata is stored in OpenShift Container Platform, but the registry stores layer and signature data in a volume that is mounted into the registry container at `/registry`. As **oc exec** does not work on privileged containers, to view a registry's contents you must manually SSH into the node housing the registry pod's container, then run **docker exec** on the container itself:

1. List the current pods to find the pod name of your Docker registry:

```
# oc get pods
```

Then, use **oc describe** to find the host name for the node running the container:

```
# oc describe pod <pod_name>
```

2. Log into the desired node:

```
# ssh node.example.com
```

3. List the running containers from the default project on the node host and identify the container ID for the Docker registry:

```
# docker ps --filter=name=registry_docker-registry.*_default_
```

4. List the registry contents using the **oc rsh** command:

```
# oc rsh dc/docker-registry find /registry
/registry/docker
```

```

/registry/docker/registry
/registry/docker/registry/v2
/registry/docker/registry/v2/blobs 1
/registry/docker/registry/v2/blobs/sha256
/registry/docker/registry/v2/blobs/sha256/ed
/registry/docker/registry/v2/blobs/sha256/ed/ede17b139a271d6b1331ca3
d83c648c24f92cece5f89d95ac6c34ce751111810
/registry/docker/registry/v2/blobs/sha256/ed/ede17b139a271d6b1331ca3
d83c648c24f92cece5f89d95ac6c34ce751111810/data 2
/registry/docker/registry/v2/blobs/sha256/a3
/registry/docker/registry/v2/blobs/sha256/a3/a3ed95caeb02ffe68cdd9fd
84406680ae93d633cb16422d00e8a7c22955b46d4
/registry/docker/registry/v2/blobs/sha256/a3/a3ed95caeb02ffe68cdd9fd
84406680ae93d633cb16422d00e8a7c22955b46d4/data
/registry/docker/registry/v2/blobs/sha256/f7
/registry/docker/registry/v2/blobs/sha256/f7/f72a00a23f01987b42cb26f
259582bb33502bdb0fcf5011e03c60577c4284845
/registry/docker/registry/v2/blobs/sha256/f7/f72a00a23f01987b42cb26f
259582bb33502bdb0fcf5011e03c60577c4284845/data
/registry/docker/registry/v2/repositories 3
/registry/docker/registry/v2/repositories/p1
/registry/docker/registry/v2/repositories/p1/pause 4
/registry/docker/registry/v2/repositories/p1/pause/_manifests
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisions
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisions/sha256
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisions/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisions/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf/signatures 5
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisions/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf/signatures/sha256
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisions/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf/signatures/sha256/ede17b139a271d6b1331ca3d83c648c24f92cece5f
89d95ac6c34ce751111810
/registry/docker/registry/v2/repositories/p1/pause/_manifests/revisions/sha256/e9a2ac6418981897b399d3709f1b4a6d2723cd38a4909215ce2752a5c
068b1cf/signatures/sha256/ede17b139a271d6b1331ca3d83c648c24f92cece5f
89d95ac6c34ce751111810/link 6
/registry/docker/registry/v2/repositories/p1/pause/_uploads 7
/registry/docker/registry/v2/repositories/p1/pause/_layers 8
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256/a3
ed95caeb02ffe68cdd9fd84406680ae93d633cb16422d00e8a7c22955b46d4
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256/a3
ed95caeb02ffe68cdd9fd84406680ae93d633cb16422d00e8a7c22955b46d4/link
9
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256/f7

```

```
2a00a23f01987b42cb26f259582bb33502bdb0fcf5011e03c60577c4284845  
/registry/docker/registry/v2/repositories/p1/pause/_layers/sha256/f7  
2a00a23f01987b42cb26f259582bb33502bdb0fcf5011e03c60577c4284845/link
```

- 1 This directory stores all layers and signatures as blobs.
- 2 This file contains the blob's contents.
- 3 This directory stores all the image repositories.
- 4 This directory is for a single image repository **p1/pause**.
- 5 This directory contains signatures for a particular image manifest revision.
- 6 This file contains a reference back to a blob (which contains the signature data).
- 7 This directory contains any layers that are currently being uploaded and staged for the given repository.
- 8 This directory contains links to all the layers this repository references.
- 9 This file contains a reference to a specific layer that has been linked into this repository via an image.

### 3.3.3. Accessing the Registry Directly

For advanced usage, you can access the registry directly to invoke **docker** commands. This allows you to push images to or pull them from the integrated registry directly using operations like **docker push** or **docker pull**. To do so, you must be logged in to the registry using the **docker login** command. The operations you can perform depend on your user permissions, as described in the following sections.

#### 3.3.3.1. User Prerequisites

To access the registry directly, the user that you use must satisfy the following, depending on your intended usage:

- For any direct access, you must have a [regular user](#) for your preferred [identity provider](#). A regular user can generate an access token required for logging in to the registry. [System users](#), such as **system:admin**, cannot obtain access tokens and, therefore, cannot access the registry directly.

For example, if you are using **HTPASSWD** authentication, you can create one using the following command:

```
# htpasswd /etc/origin/openshift-htpasswd <user_name>
```

- For pulling images, for example when using the **docker pull** command, the user must have the **registry-viewer** role. To add this role:

```
$ oc policy add-role-to-user registry-viewer <user_name>
```

- For writing or pushing images, for example when using the **docker push** command, the user must have the **registry-editor** role. To add this role:

```
$ oc policy add-role-to-user registry-editor <user_name>
```

For more information on user permissions, see [Managing Role Bindings](#).

### 3.3.3.2. Logging in to the Registry



#### NOTE

Ensure your user satisfies the [prerequisites](#) for accessing the registry directly.

To log in to the registry directly:

1. Ensure you are logged in to OpenShift Container Platform as a **regular user**:

```
$ oc login
```

2. Log in to the Docker registry by using your access token:

```
docker login -u openshift -p $(oc whoami -t) <registry_ip>:<port>
```



#### NOTE

You can pass any value for the username, the token contains all necessary information. Passing a username that contains colons will result in a login failure.

### 3.3.3.3. Pushing and Pulling Images

After [logging in to the registry](#), you can perform **docker pull** and **docker push** operations against your registry.



#### IMPORTANT

You can pull arbitrary images, but if you have the **system:registry** role added, you can only push images to the registry in your project.

In the following examples, we use:

| Component     | Value                                |
|---------------|--------------------------------------|
| <registry_ip> | <b>172.30.124.220</b>                |
| <port>        | <b>5000</b>                          |
| <project>     | <b>openshift</b>                     |
| <image>       | <b>busybox</b>                       |
| <tag>         | omitted (defaults to <b>latest</b> ) |

- Pull an arbitrary image:

```
$ docker pull docker.io/busybox
```

- Tag the new image with the form <registry\_ip>:<port>/<project>/<image>. The project name **must** appear in this [pull specification](#) for OpenShift Container Platform to correctly place and later access the image in the registry.

```
$ docker tag docker.io/busybox 172.30.124.220:5000/openshift/busybox
```



#### NOTE

Your regular user must have the **system:image-builder** role for the specified project, which allows the user to write or push an image. Otherwise, the **docker push** in the next step will fail. To test, you can [create a new project](#) to push the **busybox** image.

- Push the newly-tagged image to your registry:

```
$ docker push 172.30.124.220:5000/openshift/busybox
...
cf2616975b4a: Image successfully pushed
Digest:
sha256:3662dd821983bc4326bee12caec61367e7fb6f6a3ee547cbaff98f77403ca
b55
```

### 3.3.4. Accessing Registry Metrics

The OpenShift Container Registry provides an endpoint for [Prometheus metrics](#). Prometheus is a stand-alone, open source systems monitoring and alerting toolkit.

The metrics are exposed at the `/extensions/v2/metrics` path of the registry endpoint. However, this route must first be enabled; see [Extended Registry Configuration](#) for instructions.

The following is a simple example of a metrics query:

```
$ curl -s -u <user>:<secret> \ ①
    http://172.30.30:5000/extensions/v2/metrics | grep openshift | head
    -n 10

# HELP openshift_build_info A metric with a constant '1' value labeled by
major, minor, git commit & git version from which OpenShift was built.
# TYPE openshift_build_info gauge
openshift_build_info{gitCommit="67275e1",gitVersion="v3.6.0-
alpha.1+67275e1-803",major="3",minor="6+"} 1
# HELP openshift_registry_request_duration_seconds Request latency summary
in microseconds for each operation
# TYPE openshift_registry_request_duration_seconds summary
openshift_registry_request_duration_seconds{name="test/origin-
pod",operation="blobstore.create",quantile="0.5"} 0
openshift_registry_request_duration_seconds{name="test/origin-
pod",operation="blobstore.create",quantile="0.9"} 0
openshift_registry_request_duration_seconds{name="test/origin-
```

```
pod", operation="blobstore.create", quantile="0.99"} 0
openshift_registry_request_duration_seconds_sum{name="test/origin-pod", operation="blobstore.create"} 0
openshift_registry_request_duration_seconds_count{name="test/origin-pod", operation="blobstore.create"} 5
```

- 1** <user> can be arbitrary, but <secret> must match the value specified in the [registry configuration](#).

See the [upstream Prometheus documentation](#) for more advanced queries and recommended visualizers.

## 3.4. SECURING AND EXPOSING THE REGISTRY

### 3.4.1. Overview

By default, the OpenShift Container Platform registry is secured during cluster installation so that it serves traffic via TLS. A passthrough route is also created by default to expose the service externally.

If for any reason your registry has not been secured or exposed, see the following sections for steps on how to manually do so.

### 3.4.2. Manually Securing the Registry

To manually secure the registry to serve traffic via TLS:

1. [Deploy the registry](#).
2. Fetch the service IP and port of the registry:

```
$ oc get svc/docker-registry
NAME           LABELS
SELECTOR
docker-registry   docker-registry=default
                  docker-
                  registry=default   172.30.124.220   5000/TCP
```

3. You can use an existing server certificate, or create a key and server certificate valid for specified IPs and host names, signed by a specified CA. To create a server certificate for the registry service IP and the **docker-registry.default.svc.cluster.local** host name, run the following command from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**:

```
$ oc adm ca create-server-cert \
  --signer-cert=/etc/origin/master/ca.crt \
  --signer-key=/etc/origin/master/ca.key \
  --signer-serial=/etc/origin/master/ca.serial.txt \
  --hostnames='docker-registry.default.svc.cluster.local,docker-registry.default.svc,172.30.124.220' \
  --cert=/etc/secrets/registry.crt \
  --key=/etc/secrets/registry.key
```

If the router will be [exposed externally](#), add the public route host name in the **--hostnames** flag:

```
--hostnames='mydocker-registry.example.com, docker-
registry.default.svc.cluster.local, 172.30.124.220 \
```

See [Redeploying Registry and Router Certificates](#) for additional details on updating the default certificate so that the route is externally accessible.



### NOTE

The `oc adm ca create-server-cert` command generates a certificate that is valid for two years. This can be altered with the `--expire-days` option, but for security reasons, it is recommended to not make it greater than this value.

4. Create the secret for the registry certificates:

```
$ oc create secret generic registry-certificates \
--from-file=/etc/secrets/registry.crt \
--from-file=/etc/secrets/registry.key
```

5. Add the secret to the registry pod's service accounts (including the `default` service account):

```
$ oc secrets link registry registry-certificates
$ oc secrets link default registry-certificates
```



### NOTE

Limiting secrets to only the service accounts that reference them is disabled by default. This means that if `serviceAccountConfig.limitSecretReferences` is set to `false` (the default setting) in the master configuration file, linking secrets to a service is not required.

6. Pause the `docker-registry` service:

```
$ oc rollout pause dc/docker-registry
```

7. Add the secret volume to the registry deployment configuration:

```
$ oc volume dc/docker-registry --add --type=secret \
--secret-name=registry-certificates -m /etc/secrets
```

8. Enable TLS by adding the following environment variables to the registry deployment configuration:

```
$ oc set env dc/docker-registry \
REGISTRY_HTTP_TLS_CERTIFICATE=/etc/secrets/registry.crt \
REGISTRY_HTTP_TLS_KEY=/etc/secrets/registry.key
```

See the [Configuring a registry section of the Docker documentation](#) for more information.

9. Update the scheme used for the registry's liveness probe from HTTP to HTTPS:

```
$ oc patch dc/docker-registry -p '{"spec": {"template": {"spec":
```

```
{"containers": [{"name": "registry", "livenessProbe": {"httpGet": {"scheme": "HTTPS"}}}]} ]}'
```

- If your registry was initially deployed on OpenShift Container Platform 3.2 or later, update the scheme used for the registry's readiness probe from HTTP to HTTPS:

```
$ oc patch dc/docker-registry -p '{"spec": {"template": {"spec": {"containers": [{"name": "registry", "readinessProbe": {"httpGet": {"scheme": "HTTPS"}}}]} }}}'
```

- Resume the **docker-registry** service:

```
$ oc rollout resume dc/docker-registry
```

- Validate the registry is running in TLS mode. Wait until the latest **docker-registry** deployment completes and verify the Docker logs for the registry container. You should find an entry for **listening on :5000, tls**.

```
$ oc logs dc/docker-registry | grep tls
time="2015-05-27T05:05:53Z" level=info msg="listening on :5000, tls"
instance.id=deeba528-c478-41f5-b751-dc48e4935fc2
```

- Copy the CA certificate to the Docker certificates directory. This must be done on all nodes in the cluster:

```
$ dcertsdir=/etc/docker/certs.d
$ destdir_addr=$dcertsdir/172.30.124.220:5000
$ destdir_name=$dcertsdir/docker-
registry.default.svc.cluster.local:5000

$ sudo mkdir -p $destdir_addr $destdir_name
$ sudo cp ca.crt $destdir_addr ①
$ sudo cp ca.crt $destdir_name
```

① The **ca.crt** file is a copy of **/etc/origin/master/ca.crt** on the master.

- When using authentication, some versions of **docker** also require you to configure your cluster to trust the certificate at the OS level.

- Copy the certificate:

```
$ cp /etc/origin/master/ca.crt /etc/pki/ca-
trust/source/anchors/myregistrydomain.com.crt
```

- Run:

```
$ update-ca-trust enable
```

- Remove the **--insecure-registry** option only for this particular registry in the

**/etc/sysconfig/docker** file. Then, reload the daemon and restart the **docker** service to reflect this configuration change:

```
$ sudo systemctl daemon-reload
$ sudo systemctl restart docker
```

16. Validate the **docker** client connection. Running **docker push** to the registry or **docker pull** from the registry should succeed. Make sure you have [logged into the registry](#).

```
$ docker tag|push <registry/image> <internal_registry/project/image>
```

For example:

```
$ docker pull busybox
$ docker tag docker.io/busybox 172.30.124.220:5000/openshift/busybox
$ docker push 172.30.124.220:5000/openshift/busybox
...
cf2616975b4a: Image successfully pushed
Digest:
sha256:3662dd821983bc4326bee12caec61367e7fb6f6a3ee547cbaff98f77403ca
b55
```

### 3.4.3. Manually Exposing a Secure Registry

Instead of logging in to the OpenShift Container Platform registry from within the OpenShift Container Platform cluster, you can gain external access to it by first securing the registry and then exposing it with a route. This allows you to log in to the registry from outside the cluster using the route address, and to tag and push images using the route host.

1. Each of the following prerequisite steps are performed by default during a typical cluster installation. If they have not been, perform them manually:
  - a. [Manually deploy the registry](#).
  - b. [Manually secure the registry](#).
  - c. [Manually deploy a router](#).
2. A [passthrough](#) route should have been created by default for the registry during the initial cluster installation:
  - a. Verify whether the route exists:

```
$ oc get route/docker-registry -o yaml
apiVersion: v1
kind: Route
metadata:
  name: docker-registry
spec:
  host: <host> ①
  to:
    kind: Service
    name: docker-registry ②
  tls:
    termination: passthrough ③
```

- - 1 The host for your route. You must be able to resolve this name externally via DNS to the router's IP address.
  - 2 The service name for your registry.
  - 3 Specifies this route as a passthrough route.



### NOTE

Re-encrypt routes are also supported for exposing the secure registry.

- b. If it does not exist, create the route via the **oc create route passthrough** command, specifying the registry as the route's service. By default, the name of the created route is the same as the service name:

- i. Get the **docker-registry** service details:

```
$ oc get svc
NAME           CLUSTER_IP      EXTERNAL_IP    PORT(S)
SELECTOR
docker-registry   172.30.69.167 <none>        5000/TCP
docker-registry=default   4h
kubernetes       172.30.0.1     <none>
443/TCP, 53/UDP, 53/TCP <none>                4h
router          172.30.172.132 <none>        80/TCP
router=router      4h
```

- ii. Create the route:

```
$ oc create route passthrough \
--service=docker-registry \
--hostname=<host>
route "docker-registry" created
```

- 1 Specifies the registry as the route's service.
  - 2 The route name is identical to the service name.
3. Next, you must trust the certificates being used for the registry on your host system to allow the host to push and pull images. The certificates referenced were created when you secured your registry.

```
$ sudo mkdir -p /etc/docker/certs.d/<host>
$ sudo cp <ca_certificate_file> /etc/docker/certs.d/<host>
$ sudo systemctl restart docker
```

4. Log in to the registry using the information from securing the registry. However, this time point to the host name used in the route rather than your service IP. When logging in to a secured and exposed registry, make sure you specify the registry in the **docker login** command:

```
# docker login -e user@company.com \
```

```
-u f83j5h6 \
-p Ju1PeM47R0B92Lk3AZp-bWJSck2F7aGCiZ66aFGZrs2 \
<host>
```

5. You can now tag and push images using the route host. For example, to tag and push a **busybox** image in a project called **test**:

```
$ oc get imagestreams -n test
NAME      DOCKER REPO      TAGS      UPDATED

$ docker pull busybox
$ docker tag busybox <host>/test/busybox
$ docker push <host>/test/busybox
The push refers to a repository [<host>/test/busybox] (len: 1)
8c2e06607696: Image already exists
6ce2e90b0bc7: Image successfully pushed
cf2616975b4a: Image successfully pushed
Digest:
sha256:6c7e676d76921031532d7d9c0394d0da7c2906f4cb4c049904c4031147d8c
a31

$ docker pull <host>/test/busybox
latest: Pulling from <host>/test/busybox
cf2616975b4a: Already exists
6ce2e90b0bc7: Already exists
8c2e06607696: Already exists
Digest:
sha256:6c7e676d76921031532d7d9c0394d0da7c2906f4cb4c049904c4031147d8c
a31
Status: Image is up to date for <host>/test/busybox:latest

$ oc get imagestreams -n test
NAME      DOCKER REPO      TAGS      UPDATED
busybox   172.30.11.215:5000/test/busybox   latest    2 seconds ago
```



#### NOTE

Your image streams will have the IP address and port of the registry service, not the route name and port. See **oc get imagestreams** for details.

#### 3.4.4. Manually Exposing a Non-Secure Registry

Instead of securing the registry in order to expose the registry, you can simply expose a non-secure registry for non-production OpenShift Container Platform environments. This allows you to have an external route to the registry without using SSL certificates.



#### WARNING

Only non-production environments should expose a non-secure registry to external access.

To expose a non-secure registry:

1. Expose the registry:

```
# oc expose service docker-registry --hostname=<hostname> -n default
```

This creates the following JSON file:

```
apiVersion: v1
kind: Route
metadata:
  creationTimestamp: null
  labels:
    docker-registry: default
  name: docker-registry
spec:
  host: registry.example.com
  port:
    targetPort: "5000"
  to:
    kind: Service
    name: docker-registry
status: {}
```

2. Verify that the route has been created successfully:

```
# oc get route
NAME           HOST/PORT      PATH      SERVICE
LABELS          INSECURE POLICY   TLS TERMINATION
docker-registry  registry.example.com   docker-registry
docker-registry=default
```

3. Check the health of the registry:

```
$ curl -v http://registry.example.com/healthz
```

Expect an HTTP 200/OK message.

After exposing the registry, update your `/etc/sysconfig/docker` file by adding the port number to the **OPTIONS** entry. For example:

```
OPTIONS='--selinux-enabled --insecure-registry=172.30.0.0/16 --
insecure-registry registry.example.com:80'
```



### IMPORTANT

The above options should be added on the client from which you are trying to log in.

Also, ensure that Docker is running on the client.

When [logging in](#) to the non-secured and exposed registry, make sure you specify the registry in the `docker login` command. For example:

```
# docker login -e user@company.com \
-u f83j5h6 \
-p Ju1PeM47R0B92Lk3AZp-bWJSck2F7aGCiZ66aFGZrs2 \
<host>
```

## 3.5. EXTENDED REGISTRY CONFIGURATION

### 3.5.1. Maintaining the Registry IP Address

OpenShift Container Platform refers to the integrated registry by its service IP address, so if you decide to delete and recreate the **docker-registry** service, you can ensure a completely transparent transition by arranging to re-use the old IP address in the new service. If a new IP address cannot be avoided, you can minimize cluster disruption by rebooting only the masters.

#### Re-using the Address

To re-use the IP address, you must save the IP address of the old **docker-registry** service prior to deleting it, and arrange to replace the newly assigned IP address with the saved one in the new **docker-registry** service.

1. Make a note of the **clusterIP** for the service:

```
$ oc get svc/docker-registry -o yaml | grep clusterIP:
```

2. Delete the service:

```
$ oc delete svc/docker-registry dc/docker-registry
```

3. Create the registry definition in **registry.yaml**, replacing <options> with, for example, those used in step 3 of the instructions in the [Non-Production Use](#) section:

```
$ oc adm registry <options> -o yaml > registry.yaml
```

4. Edit **registry.yaml**, find the **Service** there, and change its **clusterIP** to the address noted in step 1.

5. Create the registry using the modified **registry.yaml**:

```
$ oc create -f registry.yaml
```

#### Rebooting the Masters

If you are unable to re-use the IP address, any operation that uses a [pull specification](#) that includes the old IP address will fail. To minimize cluster disruption, you must reboot the masters:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
```

This ensures that the old registry URL, which includes the old IP address, is cleared from the cache.

**NOTE**

We recommend against rebooting the entire cluster because that incurs unnecessary downtime for pods and does not actually clear the cache.

### 3.5.2. Whitelisting Docker Registries

You can specify a whitelist of docker registries, allowing you to curate a set of images and templates that are available for download by OpenShift Container Platform users. This curated set can be placed in one or more docker registries, and then added to the whitelist. When using a whitelist, only the specified registries are accessible within OpenShift Container Platform, and all other registries are denied access by default.

To configure a whitelist:

1. Edit the `/etc/sysconfig/docker` file to block all registries:

```
BLOCK_REGISTRY='--block-registry=all'
```

You may need to uncomment the `BLOCK_REGISTRY` line.

2. In the same file, add registries to which you want to allow access:

```
ADD_REGISTRY='--add-registry=<registry1> --add-registry=<registry2>'
```

#### Allowing Access to Registries

```
ADD_REGISTRY='--add-registry=registry.access.redhat.com'
```

This example would restrict access to images available on the [Red Hat Customer Portal](#).

Once the whitelist is configured, if a user tries to pull from a docker registry that is not on the whitelist, they will receive an error message stating that this registry is not allowed.

### 3.5.3. Setting the Registry Hostname

You can configure the hostname and port the registry is known by for both internal and external references. By doing this, image streams will provide hostname based push and pull specifications for images, allowing consumers of the images to be isolated from changes to the registry service ip and potentially allowing image streams and their references to be portable between clusters.

To set the hostname used to reference the registry from within the cluster, set the `internalRegistryHostname` in the `imagePolicyConfig` section of the master configuration file. The external hostname is controlled by setting the `externalRegistryHostname` value in the same location.

#### Image Policy Configuration

```
imagePolicyConfig:
  internalRegistryHostname: docker-registry.default.svc.cluster.local:5000
  externalRegistryHostname: docker-registry.mycompany.com
```

The registry itself must be configured with the same internal hostname value. This can be accomplished by setting the **REGISTRY\_OPENSHIFT\_SERVER\_ADDR** environment variable on the registry deployment configuration, or by setting the value in the [OpenShift section](#) of the registry configuration.



#### NOTE

If you have enabled TLS for your registry the server certificate must include the hostnames by which you expect the registry to be referenced. See [securing the registry](#) for instructions on adding hostnames to the server certificate.

### 3.5.4. Overriding the Registry Configuration

You can override the integrated registry's default configuration, found by default at `/config.yml` in a running registry's container, with your own [custom configuration](#).



#### NOTE

Upstream configuration options in this file may also be overridden using environment variables. The [middleware section](#) is an exception as there are just a few options that can be overridden using environment variables. [Learn how to override specific configuration options.](#)

To enable management of the registry configuration file directly and deploy an updated configuration using a [ConfigMap](#):

1. [Deploy the registry](#).
2. Edit the registry configuration file locally as needed. The initial YAML file deployed on the registry is provided below. [Review supported options](#).

#### Registry Configuration File

```
version: 0.1
log:
  level: debug
http:
  addr: :5000
storage:
  cache:
    blobdescriptor: inmemory
  filesystem:
    rootdirectory: /registry
  delete:
    enabled: true
auth:
  openshift:
    realm: openshift
middleware:
  registry:
    - name: openshift
repository:
  - name: openshift
    options:
      acceptschema2: true
      pullthrough: true
```

```

    enforcequota: false
    projectcachettl: 1m
    blobrepositorycachettl: 10m
  storage:
    - name: openshift
  openshift:
    version: 1.0
  metrics:
    enabled: false
    secret: <secret>

```

3. Create a **ConfigMap** holding the content of each file in this directory:

```
$ oc create configmap registry-config \
--from-file=</path/to/custom/registry/config.yml>/
```

4. Add the **registry-config** ConfigMap as a volume to the registry's deployment configuration to mount the custom configuration file at **/etc/docker/registry/**:

```
$ oc volume dc/docker-registry --add --type=configmap \
--configmap-name=registry-config -m /etc/docker/registry/
```

5. Update the registry to reference the configuration path from the previous step by adding the following environment variable to the registry's deployment configuration:

```
$ oc set env dc/docker-registry \
REGISTRY_CONFIGURATION_PATH=/etc/docker/registry/config.yml
```

This may be performed as an iterative process to achieve the desired configuration. For example, during troubleshooting, the configuration may be temporarily updated to put it in **debug** mode.

To update an existing configuration:



### WARNING

This procedure will overwrite the currently deployed registry configuration.

1. Edit the local registry configuration file, **config.yml**.

2. Delete the **registry-config** configmap:

```
$ oc delete configmap registry-config
```

3. Recreate the configmap to reference the updated configuration file:

```
$ oc create configmap registry-config \
--from-file=</path/to/custom/registry/config.yml>/
```

4. Redeploy the registry to read the updated configuration:

```
$ oc rollout latest docker-registry
```

**TIP**

Maintain configuration files in a source control repository.

### 3.5.5. Registry Configuration Reference

There are many configuration options available in the upstream [docker distribution](#) library. Not all [configuration options](#) are supported or enabled. Use this section as a reference when [overriding the registry configuration](#).

**NOTE**

Upstream configuration options in this file may also be overridden using environment variables. However, the [middleware section](#) may **not** be overridden using environment variables. [Learn how to override specific configuration options](#).

#### 3.5.5.1. Log

[Upstream options](#) are supported.

Example:

```
log:  
  level: debug  
  formatter: text  
  fields:  
    service: registry  
    environment: staging
```

#### 3.5.5.2. Hooks

Mail hooks are not supported.

#### 3.5.5.3. Storage

This section lists the supported registry storage drivers. See the [Docker registry documentation](#) for more information.

The following list includes storage drivers that need to be configured in the registry's configuration file:

- [Filesystem](#). Filesystem is the default and does not need to be configured.
- [S3](#). See the [CloudFront configuration](#) documentation for more information.
- [OpenStack Swift](#)
- [Google Cloud Storage \(GCS\)](#)
- [Microsoft Azure](#)

- Aliyun OSS

General registry storage configuration options are supported. See [the Docker registry documentation for more information](#).

The following storage options need to be configured through the [filesystem driver](#):

- GlusterFS Storage
- Ceph Rados Block Device



#### NOTE

For more information on supported persistent storage drivers, see [Configuring Persistent Storage](#) and [Persistent Storage Examples](#).

### General Storage Configuration Options

```
storage:
  delete:
    enabled: true ①
  redirect:
    disable: false
  cache:
    blobdescriptor: inmemory
  maintenance:
    uploadpurging:
      enabled: true
      age: 168h
      interval: 24h
      dryrun: false
    readonly:
      enabled: false
```

- ① This entry is **mandatory** for image pruning to work properly.

#### 3.5.5.4. Auth

Auth options should not be altered. The **openshift** extension is the only supported option.

```
auth:
  openshift:
    realm: openshift
```

#### 3.5.5.5. Middleware

The **repository** middleware extension allows to configure OpenShift Container Platform middleware responsible for interaction with OpenShift Container Platform and image proxying.

```
middleware:
  registry:
    - name: openshift ①
```

```

repository:
  - name: openshift 2
    options:
      acceptschema2: true 3
      pullthrough: true 4
      mirrorpullthrough: true 5
      enforcequota: false 6
      projectcachettl: 1m 7
      blobrepositorycachettl: 10m 8
  storage:
    - name: openshift 9

```

**1 2 9** These entries are mandatory. Their presence ensures required components are loaded. These values should not be changed.

- 3** Allows you to store [manifest schema v2](#) during a push to the registry. See [below](#) for more details.
- 4** Allows the registry to act as a proxy for remote blobs. See [below](#) for more details.
- 5** Allows the registry cache blobs to be served from remote registries for fast access later. The mirroring starts when the blob is accessed for the first time. The option has no effect if the [pullthrough](#) is disabled.
- 6** Prevents blob uploads exceeding the size limit, which are defined in the targeted project.
- 7** An expiration timeout for limits cached in the registry. The lower the value, the less time it takes for the limit changes to propagate to the registry. However, the registry will query limits from the server more frequently and, as a consequence, pushes will be slower.
- 8** An expiration timeout for remembered associations between blob and repository. The higher the value, the higher probability of fast lookup and more efficient registry operation. On the other hand, memory usage will raise as well as a risk of serving image layer to user, who is no longer authorized to access it.

### 3.5.5.5.1. CloudFront Middleware

The [CloudFront middleware extension](#) can be added to support AWS, CloudFront CDN storage provider. CloudFront middleware speeds up distribution of image content internationally. The blobs are distributed to several edge locations around the world. The client is always directed to the edge with the lowest latency.



#### NOTE

The [CloudFront middleware extension](#) can be only used with [S3](#) storage. It is utilized only during blob serving. Therefore, only blob downloads can be speeded up, not uploads.

The following is an example of minimal configuration of S3 storage driver with a CloudFront middleware:

```

version: 0.1
log:
  level: debug
http:

```

```

addr: :5000
storage:
  cache:
    blobdescriptor: inmemory
delete:
  enabled: true
s3: ①
  accesskey: BJKMSZBRESWJQXRWMAEQ
  secretkey: 5ah5I91SNXbeoUXXDasFtadRq0dy62Jzln0W1goS
  region: us-east-1
  bucket: docker.myregistry.com
auth:
  openshift:
    realm: openshift
middleware:
  registry:
    - name: openshift
repository:
  - name: openshift
storage:
  - name: cloudfront ②
    options:
      baseurl: https://jrpbyn0k5k88bi.cloudfront.net/ ③
      privatekey: /etc/docker/cloudfront-ABCDEFGHIJKLMNOPQRSTUVWXYZ.pem ④
      keypairid: ABCDEFGHIJKLMNOPQRSTUVWXYZ ⑤
  - name: openshift

```

- ① The S3 storage must be configured the same way regardless of CloudFront middleware.
- ② The CloudFront storage middleware needs to be listed before OpenShift middleware.
- ③ The CloudFront base URL. In the AWS management console, this is listed as **Domain Name** of CloudFront distribution.
- ④ The location of your AWS private key on the filesystem. This must be not confused with Amazon EC2 key pair. See the [AWS documentation](#) on creating CloudFront key pairs for your trusted signers. The file needs to be mounted as a **secret** into the registry pod.
- ⑤ The ID of your Cloudfront key pair.

### 3.5.5.2. Overriding Middleware Configuration Options

The **middleware** section cannot be overridden using environment variables. There are a few exceptions, however. For example:

```

middleware:
  repository:
    - name: openshift
      options:
        acceptschema2: true ①
        pullthrough: true ②
        mirrorpullthrough: true ③

```

```

enforcequota: false 4
projectcachettl: 1m 5
blobrepositorycachettl: 10m 6

```

- 1** A configuration option that can be overridden by the boolean environment variable **REGISTRY\_MIDDLEWARE\_REPOSITORY\_OPENSHIFT\_ACCEPTSCHEMA2**, which allows for the ability to accept manifest schema v2 on manifest put requests. Recognized values are **true** and **false** (which applies to all the other boolean variables below).
- 2** A configuration option that can be overridden by the boolean environment variable **REGISTRY\_MIDDLEWARE\_REPOSITORY\_OPENSHIFT\_PULLTHROUGH**, which enables a proxy mode for remote repositories.
- 3** A configuration option that can be overridden by the boolean environment variable **REGISTRY\_MIDDLEWARE\_REPOSITORY\_OPENSHIFT\_MIRRORPULLTHROUGH**, which instructs registry to mirror blobs locally if serving remote blobs.
- 4** A configuration option that can be overridden by the boolean environment variable **REGISTRY\_MIDDLEWARE\_REPOSITORY\_OPENSHIFT\_ENFORCEQUOTA**, which allows the ability to turn quota enforcement on or off. By default, quota enforcement is off.
- 5** A configuration option that can be overridden by the environment variable **REGISTRY\_MIDDLEWARE\_REPOSITORY\_OPENSHIFT\_PROJECTCACHETTL**, specifying an eviction timeout for project quota objects. It takes a valid time duration string (for example, **2m**). If empty, you get the default timeout. If zero (**0m**), caching is disabled.
- 6** A configuration option that can be overridden by the environment variable **REGISTRY\_MIDDLEWARE\_REPOSITORY\_OPENSHIFT\_BLOBREPOSITORYCACHETTL**, specifying an eviction timeout for associations between blob and containing repository. The format of the value is the same as in **projectcachettl** case.

### 3.5.5.3. Image Pullthrough

If enabled, the registry will attempt to fetch requested blob from a remote registry unless the blob exists locally. The remote candidates are calculated from **DockerImage** entries stored in status of the **image stream**, a client pulls from. All the unique remote registry references in such entries will be tried in turn until the blob is found.

Pullthrough will only occur if an image stream tag exists for the image being pulled. For example, if the image being pulled is **docker-registry.default.svc:5000/yourproject/yourimage:prod** then the registry will look for an image stream tag named **yourimage:prod** in the project **yourproject**. If it finds one, it will attempt to pull the image using the **dockerImageReference** associated with that image stream tag.

When performing pullthrough, the registry will use pull credentials found in the project associated with the image stream tag that is being referenced. This capability also makes it possible for you to pull images that reside on a registry they do not have credentials to access, as long as you have access to the image stream tag that references the image.

You must ensure that your registry has appropriate certificates to trust any external registries you do a pullthrough against. The certificates need to be placed in the **/etc/pki/tls/certs** directory on the pod. You can mount the certificates using a **configuration map** or **secret**. Note that the entire **/etc/pki/tls/certs** directory must be replaced. You must include the new certificates and replace the system certificates in your secret or configuration map that you mount.

Note that by default image stream tags use a reference policy type of **Source** which means that when the image stream reference is resolved to an image pull specification, the specification used will point to the source of the image. For images hosted on external registries, this will be the external registry and as a result the resource will reference and pull the image by the external registry. For example, `registry.access.redhat.com/openshift3/jenkins-2-rhel7` and pullthrough will not apply. To ensure that resources referencing image streams use a pull specification that points to the internal registry, the image stream tag should use a reference policy type of **Local**. More information is available on [Reference Policy](#).

This feature is on by default. However, it can be disabled using a [configuration option](#).

By default, all the remote blobs served this way are stored locally for subsequent faster access unless `mirrorpullthrough` is disabled. The downside of this mirroring feature is an increased storage usage.



### NOTE

The mirroring starts when a client tries to fetch at least a single byte of the blob. To pre-fetch a particular image into integrated registry before it is actually needed, you can run the following command:

```
$ oc get imagestreamtag/${IS}:${TAG} -o jsonpath='{.image.dockerImageLayers[*].name}' | \
xargs -n1 -I {} curl -H "Range: bytes=0-1" -u user:${TOKEN} \
http://${REGISTRY_IP}:${PORT}/v2/default/mysql/blobs/{}
```



### NOTE

This OpenShift Container Platform mirroring feature should not be confused with the upstream [registry pull through cache feature](#), which is a similar but distinct capability.

#### 3.5.5.4. Manifest Schema v2 Support

Each image has a manifest describing its blobs, instructions for running it and additional metadata. The manifest is versioned, with each version having different structure and fields as it evolves over time. The same image can be represented by multiple manifest versions. Each version will have different digest though.

The registry currently supports [manifest v2 schema 1 \(schema1\)](#) and [manifest v2 schema 2 \(schema2\)](#). The former is being obsoleted but will be supported for an extended amount of time.

You should be wary of compatibility issues with various Docker clients:

- Docker clients of version 1.9 or older support only **schema1**. Any manifest this client pulls or pushes will be of this legacy schema.
- Docker clients of version 1.10 support both **schema1** and **schema2**. And by default, it will push the latter to the registry if it supports newer schema.

The registry, storing an image with **schema1** will always return it unchanged to the client. **Schema2** will be transferred unchanged only to newer Docker client. For the older one, it will be converted on-the-fly to **schema1**.

This has significant consequences. For example an image pushed to the registry by a newer Docker client cannot be pulled by the older Docker by its digest. That's because the stored image's manifest is of **schema2** and its digest can be used to pull only this version of manifest.

For this reason, the registry is configured by default not to store **schema2**. This ensures that any docker client will be able to pull from the registry any image pushed there regardless of client's version.

Once you're confident that all the registry clients support **schema2**, you'll be safe to enable its support in the registry. See the [middleware configuration reference](#) above for particular option.

### 3.5.5.6. OpenShift

This section reviews the configuration of global settings for features specific to OpenShift Container Platform. In a future release, **openshift**-related settings in the [Middleware](#) section will be obsoleted.

Currently, this section allows you to configure registry metrics collection:

```
openshift:
  version: 1.0 1
  server:
    addr: docker-registry.default.svc 2
  metrics:
    enabled: false 3
    secret: <secret> 4
  requests:
    read:
      maxrunning: 10 5
      maxinqueue: 10 6
      maxwaitinqueue 2m 7
    write:
      maxrunning: 10 8
      maxinqueue: 10 9
      maxwaitinqueue 2m 10
```

- 1** A mandatory entry specifying configuration version of this section. The only supported value is **1.0**.
- 2** The hostname of the registry. Should be set to the same value configured on the master. It can be overridden by the environment variable **REGISTRY\_OPENShift\_SERVER\_ADDR**.
- 3** Can be set to **true** to enable metrics collection. It can be overridden by the boolean environment variable **REGISTRY\_OPENSIFT\_METRICS\_ENABLED**.
- 4** A secret used to authorize client requests. Metrics clients must use it as a bearer token in **Authorization** header. It can be overridden by the environment variable **REGISTRY\_OPENSIFT\_METRICS\_SECRET**.
- 5** Maximum number of simultaneous pull requests. It can be overridden by the environment variable **REGISTRY\_OPENSIFT\_REQUESTS\_READ\_MAXRUNNING**. Zero indicates no limit.
- 6** Maximum number of queued pull requests. It can be overridden by the environment variable **REGISTRY\_OPENSIFT\_REQUESTS\_READ\_MAXINQUEUE**. Zero indicates no limit.
- 7** Maximum time a pull request can wait in the queue before being rejected. It can be overridden by the environment variable **REGISTRY\_OPENSIFT\_REQUESTS\_READ\_MAXWAITINQUEUE**. Zero indicates no limit.
- 8** Maximum number of simultaneous push requests. It can be overridden by the environment variable **REGISTRY\_OPENSIFT\_REQUESTS\_WRITE\_MAXRUNNING**. Zero indicates no limit.

- 9 Maximum number of queued push requests. It can be overridden by the environment variable **REGISTRY\_OPENSIFT\_REQUESTS\_WRITE\_MAXINQUEUE**. Zero indicates no limit.
- 10 Maximum time a push request can wait in the queue before being rejected. It can be overridden by the environment variable **REGISTRY\_OPENSIFT\_REQUESTS\_WRITE\_MAXWAITINQUEUE**. Zero indicates no limit.

See [Accessing Registry Metrics](#) for usage information.

### 3.5.5.7. Reporting

Reporting is unsupported.

### 3.5.5.8. HTTP

[Upstream options](#) are supported. [Learn how to alter these settings via environment variables](#). Only the **tls** section should be altered. For example:

```
http:
  addr: :5000
  tls:
    certificate: /etc/secrets/registry.crt
    key: /etc/secrets/registry.key
```

### 3.5.5.9. Notifications

[Upstream options](#) are supported. The [REST API Reference](#) provides more comprehensive integration options.

Example:

```
notifications:
  endpoints:
    - name: registry
      disabled: false
      url: https://url:port/path
      headers:
        Accept:
          - text/plain
      timeout: 500
      threshold: 5
      backoff: 1000
```

### 3.5.5.10. Redis

Redis is not supported.

### 3.5.5.11. Health

[Upstream options](#) are supported. The registry deployment configuration provides an integrated health check at [/healthz](#).

### 3.5.5.12. Proxy

Proxy configuration should not be enabled. This functionality is provided by the [OpenShift Container Platform repository middleware extension](#), `pullthrough: true`.

### 3.5.5.13. Cache

The integrated registry actively caches data to reduce the number of calls to slow external resources. There are two caches:

1. The storage cache that is used to cache blobs metadata. This cache does not have an expiration time and the data is there until it is explicitly deleted.
2. The application cache contains association between blobs and repositories. The data in this cache has an expiration time.

In order to completely turn off the cache, you need to change the configuration:

```
version: 0.1
log:
  level: debug
http:
  addr: :5000
storage:
  cache: {} 1
openshift:
  version: 1.0
  cache:
    disabled: true 2
    blobrepositoryttl: 10m
```

- 1** Disables cache of metadata accessed in the storage backend. Without this cache, the registry server will constantly access the backend for metadata.
- 2** Disables the cache in which contains the blob and repository associations. Without this cache, the registry server will continually re-query the data from the master API and recompute the associations.

## 3.6. KNOWN ISSUES

### 3.6.1. Overview

The following are the known issues when deploying or using the integrated registry.

### 3.6.2. Image Push Errors with Scaled Registry Using Shared NFS Volume

When using a scaled registry with a shared NFS volume, you may see one of the following errors during the push of an image:

- `digest invalid: provided digest did not match uploaded content`
- `blob upload unknown`

- **blob upload invalid**

These errors are returned by an internal registry service when Docker attempts to push the image. Its cause originates in the synchronization of file attributes across nodes. Factors such as NFS client side caching, network latency, and layer size can all contribute to potential errors that might occur when pushing an image using the default round-robin load balancing configuration.

You can perform the following steps to minimize the probability of such a failure:

1. Ensure that the **sessionAffinity** of your **docker-registry** service is set to **ClientIP**:

```
$ oc get svc/docker-registry --template='{{.spec.sessionAffinity}}'
```

This should return **ClientIP**, which is the default in recent OpenShift Container Platform versions. If not, change it:

```
$ oc patch svc/docker-registry -p '{"spec":{"sessionAffinity": "ClientIP"}}'
```

2. Ensure that the NFS export line of your registry volume on your NFS server has the **no\_wdelay** options listed. The **no\_wdelay** option prevents the server from delaying writes, which greatly improves read-after-write consistency, a requirement of the registry.



#### NOTE

The guidelines for NFS are recommended to help you get started. You may switch off from NFS when moving to production.

### 3.6.3. Pull of Internally Managed Image Fails with "not found" Error

This error occurs when the pulled image is pushed to an image stream different from the one it is being pulled from. This is caused by re-tagging a built image into an arbitrary image stream:

```
$ oc tag srcimagestream:latest anyproject/pullimagestream:latest
```

And subsequently pulling from it, using an image reference such as:

```
internal.registry.url:5000/anyproject/pullimagestream:latest
```

During a manual Docker pull, this will produce a similar error:

```
Error: image anyproject/pullimagestream:latest not found
```

To prevent this, avoid the tagging of internally managed images completely, or re-push the built image to the desired namespace [manually](#).

### 3.6.4. Image Push Fails with "500 Internal Server Error" on S3 Storage

There are problems reported happening when the registry runs on S3 storage back-end. Pushing to a Docker registry occasionally fails with the following error:

```
Received unexpected HTTP status: 500 Internal Server Error
```

To debug this, you need to [view the registry logs](#). In there, look for similar error messages occurring at the time of the failed push:

```
time="2016-03-30T15:01:21.22287816-04:00" level=error msg="unknown error completing upload: driver.Error{DriverName:\"s3\", Enclosed:(*url.Error)(0xc20901cea0)}" http.request.method=PUT
...
time="2016-03-30T15:01:21.493067808-04:00" level=error msg="response completed with error" err.code=UNKNOWN err.detail="s3: Put https://s3.amazonaws.com/oso-tsi-docker/registry/docker/registry/v2/blobs/sha256/ab/abe5af443833d60cf672e2ac57589410dddec060ed725d3e676f1865af63d2e2/data: EOF" err.message="unknown error" http.request.method=PUT
...
time="2016-04-02T07:01:46.056520049-04:00" level=error msg="error putting into main store: s3: The request signature we calculated does not match the signature you provided. Check your key and signing method."
http.request.method=PUT
atest
```

If you see such errors, contact your Amazon S3 support. There may be a problem in your region or with your particular bucket.

### 3.6.5. Image Pruning Fails

If you encounter the following error when pruning images:

```
BL0B
sha256:49638d540b2b62f3b01c388e9d8134c55493b1fa659ed84e97cb59b87a6b8e6c
error deleting blob
```

And your [registry log](#) contains the following information:

```
error deleting blob
\"sha256:49638d540b2b62f3b01c388e9d8134c55493b1fa659ed84e97cb59b87a6b8e6c\"
": operation unsupported
```

It means that your [custom configuration file](#) lacks mandatory entries in the [storage section](#), namely **storage:delete:enabled** set to **true**. Add them, re-deploy the registry, and repeat your image pruning operation.

# CHAPTER 4. SETTING UP A ROUTER

## 4.1. ROUTER OVERVIEW

### 4.1.1. About Routers

There are many ways to [get traffic into the cluster](#). The most common approach is to use the OpenShift Container Platform [router](#) as the ingress point for external traffic destined for [services](#) in your OpenShift Container Platform installation.

OpenShift Container Platform provides and supports the following router plug-ins:

- The [HAProxy template router](#) is the default plug-in. It uses the [openshift3/ose-haproxy-router](#) image to run an HAProxy instance alongside the template router plug-in inside a container on OpenShift Container Platform. It currently supports HTTP(S) traffic and TLS-enabled traffic via SNI. The router's container listens on the host network interface, unlike most containers that listen only on private IPs. The router proxies external requests for route names to the IPs of actual pods identified by the service associated with the route.
- The [F5 router](#) integrates with an existing **F5 BIG-IP®** system in your environment to synchronize routes. **F5 BIG-IP®** version 11.4 or newer is required in order to have the F5 iControl REST API.



#### NOTE

The F5 router plug-in is available starting in OpenShift Container Platform 3.0.2.

- [Deploying a Default HAProxy Router](#)
- [Deploying a Custom HAProxy Router](#)
- [Deploying a F5 BIG-IP® Router](#)
- [Configuring the HAProxy Router to Use PROXY Protocol](#)
- [Configuring Route Timeouts](#)

### 4.1.2. Router Service Account

Before deploying an OpenShift Container Platform cluster, you must have a service account for the router. Starting in OpenShift Container Platform 3.1, a router [service account](#) is automatically created during a quick or advanced installation (previously, this required manual creation). This service account has permissions to a [security context constraint](#) (SCC) that allows it to specify host ports.

#### 4.1.2.1. Permission to Access Labels

When [namespace labels](#) are used, for example in creating [router shards](#), the service account for the router must have **cluster-reader** permission.

```
$ oc adm policy add-cluster-role-to-user \
  cluster-reader \
  system:serviceaccount:default:router
```

With a service account in place, you can proceed to installing [a default HAProxy Router](#), [a customized HAProxy Router](#) or [F5 Router](#).

## 4.2. USING THE DEFAULT HAProxy ROUTER

### 4.2.1. Overview

The `oc adm router` command is provided with the administrator CLI to simplify the tasks of setting up routers in a new installation. If you followed the [quick installation](#), then a default router was automatically created for you. The `oc adm router` command creates the service and deployment configuration objects. Use the `--service-account` option to specify the service account the router will use to contact the master.

The [router service account](#) can be created in advance or created by the `oc adm router --service-account` command.

Every form of communication between OpenShift Container Platform components is secured by TLS and uses various certificates and authentication methods. The `--default-certificate`.pem format file can be supplied or one is created by the `oc adm router` command. When [routes](#) are created, the user can provide route certificates that the router will use when handling the route.



#### IMPORTANT

When deleting a router, ensure the deployment configuration, service, and secret are deleted as well.

Routers are deployed on specific nodes. This makes it easier for the cluster administrator and external network manager to coordinate which IP address will run a router and which traffic the router will handle. The routers are deployed on specific nodes by using [node selectors](#).



#### IMPORTANT

Routers use host networking by default, and they directly attach to port 80 and 443 on all interfaces on a host. Restrict routers to hosts where ports 80/443 are available and not being consumed by another service, and set this using [node selectors](#) and the [scheduler configuration](#). As an example, you can achieve this by dedicating infrastructure nodes to run services such as routers.



#### IMPORTANT

It is recommended to use separate distinct `openshift-router` service account with your router. This can be provided using the `--service-account` flag to the `oc adm router` command.

```
$ oc adm router --dry-run --service-account=router ①
```

① `--service-account` is the name of a [service account](#) for the `openshift-router`.



## IMPORTANT

Router pods created using `oc adm router` have default resource requests that a node must satisfy for the router pod to be deployed. In an effort to increase the reliability of infrastructure components, the default resource requests are used to increase the QoS tier of the router pods above pods without resource requests. The default values represent the observed minimum resources required for a basic router to be deployed and can be edited in the routers deployment configuration and you may want to increase them based on the load of the router.

### 4.2.2. Creating a Router

The [quick installation](#) process automatically creates a default router. If the router does not exist, run the following to create a router:

```
$ oc adm router <router_name> --replicas=<number> --service-account=router
```

`--replicas` is usually **1** unless a [high availability](#) configuration is being created.

To find the host IP address of the router:

```
$ oc get po <router-pod> --template={{.status.hostIP}}
```

You can also [use router shards](#) to ensure that the router is filtered to specific namespaces or routes, or [set any environment variables](#) after router creation. In this case create a router for each shard.

### 4.2.3. Other Basic Router Commands

#### Checking the Default Router

The default router service account, named **router**, is automatically created during quick and advanced installations. To verify that this account already exists:

```
$ oc adm router --dry-run --service-account=router
```

#### Viewing the Default Router

To see what the default router would look like if created:

```
$ oc adm router --dry-run -o yaml --service-account=router
```

#### Deploying the Router to a Labeled Node

To deploy the router to any node(s) that match a specified [node label](#):

```
$ oc adm router <router_name> --replicas=<number> --selector=<label> \
--service-account=router
```

For example, if you want to create a router named **router** and have it placed on a node labeled with **region=infra**:

```
$ oc adm router router --replicas=1 --selector='region=infra' \
--service-account=router
```

During [advanced installation](#), the **openshift\_router\_selector** and

**openshift\_registry\_selector** Ansible settings are set to **region=infra** by default. The default router and registry will only be automatically deployed if a node exists that matches the **region=infra** label.

For information on updating labels, see [Updating Labels on Nodes](#).

Multiple instances are created on different hosts according to the [scheduler policy](#).

### Using a Different Router Image

To use a different router image and view the router configuration that would be used:

```
$ oc adm router <router_name> -o <format> --images=<image> \
--service-account=router
```

For example:

```
$ oc adm router region-west -o yaml --images=myrepo/somerouter:mytag \
--service-account=router
```

### 4.2.4. Filtering Routes to Specific Routers

Using the **ROUTE\_LABELS** environment variable, you can filter routes so that they are used only by specific routers.

For example, if you have multiple routers, and 100 routes, you can attach labels to the routes so that a portion of them are handled by one router, whereas the rest are handled by another.

1. After [creating a router](#), use the **ROUTE\_LABELS** environment variable to tag the router:

```
$ oc env dc/<router=name> ROUTE_LABELS="key=value"
```

2. Add the label to the desired routes:

```
oc label route <route=name> key=value
```

3. To verify that the label has been attached to the route, check the route configuration:

```
$ oc describe route/<route_name>
```

### Setting the Maximum Number of Concurrent Connections

The router can handle a maximum number of 20000 connections by default. You can change that limit depending on your needs. Having too few connections prevents the health check from working, which causes unnecessary restarts. You need to configure the system to support the maximum number of connections. The limits shown in '**sysctl fs.nr\_open**' and '**sysctl fs.file-max**' must be large enough. Otherwise, HAProxy will not start.

When the router is created, the **--max-connections=** option sets the desired limit:

```
$ oc adm router --max-connections=10000 . . .
```

Edit the **ROUTER\_MAX\_CONNECTIONS** environment variable in the router's deployment configuration to change the value. The router pods are restarted with the new value. If **ROUTER\_MAX\_CONNECTIONS** is not present, the default value of 20000, is used.



#### NOTE

A connection includes the frontend and internal backend. This counts as two connections. Be sure to set **ROUTER\_MAX\_CONNECTIONS** to double than the number of connections you intend to create.

#### 4.2.5. HAProxy Strict SNI

The **HAProxy strict-sni** can be controlled through the **ROUTER\_STRICT\_SNI** environment variable in the router's deployment configuration. It can also be set when the router is created by using the **--strict-sni** command line option.

```
$ oc adm router --strict-sni
```

#### 4.2.6. TLS Cipher Suites

Set the router **cipher suite** using the **--ciphers** option when creating a router:

```
$ oc adm router --ciphers=modern . . .
```

The values are: **modern**, **intermediate**, or **old**, with **intermediate** as the default. Alternatively, a set of ":" separated ciphers can be provided. The ciphers must be from the set displayed by:

```
$ openssl ciphers
```

Alternatively, use the **ROUTER\_CIPHERS** environment variable for an existing router.

#### 4.2.7. Highly-Available Routers

You can [set up a highly-available router](#) on your OpenShift Container Platform cluster using IP failover. This setup has multiple replicas on different nodes so the failover software can switch to another replica if the current one fails.

#### 4.2.8. Customizing the Router Service Ports

You can customize the service ports that a template router binds to by setting the environment variables **ROUTER\_SERVICE\_HTTP\_PORT** and **ROUTER\_SERVICE\_HTTPS\_PORT**. This can be done by creating a template router, then editing its deployment configuration.

The following example creates a router deployment with **0** replicas and customizes the router service HTTP and HTTPS ports, then scales it appropriately (to **1** replica).

```
$ oc adm router --replicas=0 --ports='10080:10080,10443:10443' 1
$ oc set env dc/router ROUTER_SERVICE_HTTP_PORT=10080 \
    ROUTER_SERVICE_HTTPS_PORT=10443
$ oc scale dc/router --replicas=1
```

- 1** Ensures exposed ports are appropriately set for routers that use the container networking mode --host-network=false.



## IMPORTANT

If you do customize the template router service ports, you will also need to ensure that the nodes where the router pods run have those custom ports opened in the firewall (either via Ansible or **iptables**, or any other custom method that you use via **firewall-cmd**).

The following is an example using **iptables** to open the custom router service ports.

```
$ iptables -A INPUT -p tcp --dport 10080 -j ACCEPT
$ iptables -A INPUT -p tcp --dport 10443 -j ACCEPT
```

### 4.2.9. Working With Multiple Routers

An administrator can create multiple routers with the same definition to serve the same set of routes. Each router will be on a different **node** and will have a different IP address. The network administrator will need to get the desired traffic to each node.

Multiple routers can be grouped to distribute routing load in the cluster and separate tenants to different routers or **shards**. Each router or shard in the group admits routes based on the selectors in the router. An administrator can create shards over the whole cluster using **ROUTE\_LABELS**. A user can create shards over a namespace (project) by using **NAMESPACE\_LABELS**.

### 4.2.10. Adding a Node Selector to a Deployment Configuration

Making specific routers deploy on specific nodes requires two steps:

1. Add a **label** to the desired node:

```
$ oc label node 10.254.254.28 "router=first"
```

2. Add a node selector to the router deployment configuration:

```
$ oc edit dc <deploymentConfigName>
```

Add the **template.spec.nodeSelector** field with a key and value corresponding to the label:

```
...
  template:
    metadata:
      creationTimestamp: null
      labels:
        router: router1
    spec:
      nodeSelector: 1
        router: "first"
...

```

- 1 The key and value are **router** and **first**, respectively, corresponding to the **router=first** label.

## 4.2.11. Using Router Shards

*Router sharding* uses **NAMESPACE\_LABELS** and **ROUTE\_LABELS**, to filter router namespaces and routes. This enables you to distribute subsets of routes over multiple router deployments. By using non-overlapping subsets, you can effectively partition the set of routes. Alternatively, you can define shards comprising overlapping subsets of routes.

By default, a router selects all routes from all [projects \(namespaces\)](#). Sharding involves adding labels to routes or namespaces and label selectors to routers. Each router shard comprises the routes that are selected by a specific set of label selectors or belong to the namespaces that are selected by a specific set of label selectors.



### NOTE

The router service account must have the **[cluster reader]** permission set to allow access to labels in other namespaces.

### Router Sharding and DNS

Because an external DNS server is needed to route requests to the desired shard, the administrator is responsible for making a separate DNS entry for each router in a project. A router will not forward unknown routes to another router.

Consider the following example:


- Router A lives on host 192.168.0.5 and has routes with **\*.foo.com**.
- Router B lives on host 192.168.1.9 and has routes with **\*.example.com**.

Separate DNS entries must resolve **\*.foo.com** to the node hosting Router A and **\*.example.com** to the node hosting Router B:

- **\*.foo.com A IN 192.168.0.5**
- **\*.example.com A IN 192.168.1.9**

### Router Sharding Examples

This section describes router sharding using namespace and route labels.

**Figure 4.1. Router Sharding Based on Namespace Labels**

OPENSFIFT\_415490\_0217

1. Configure a router with a namespace label selector:

```
$ oc set env dc/router NAMESPACE_LABELS="router=r1"
```

2. Because the router has a selector on the namespace, the router will handle routes only for matching namespaces. In order to make this selector match a namespace, label the namespace accordingly:

```
$ oc label namespace default "router=r1"
```

3. Now, if you create a route in the default namespace, the route is available in the default router:

```
$ oc create -f route1.yaml
```

4. Create a new project (namespace) and create a route, **route2**:

```
$ oc new-project p1
$ oc create -f route2.yaml
```

Notice the route is not available in your router.

5. Label namespace **p1** with **router=r1**

```
$ oc label namespace p1 "router=r1"
```

Adding this label makes the route available in the router.

### Example

A router deployment **finops-router** is configured with the label selector **NAMESPACE\_LABELS="name in (finance, ops)"**, and a router deployment **dev-router** is configured with the label selector **NAMESPACE\_LABELS="name=dev"**.

If all routes are in namespaces labeled **name=finance**, **name=ops**, and **name=dev**, then this configuration effectively distributes your routes between the two router deployments.

In the above scenario, sharding becomes a special case of partitioning, with no overlapping subsets. Routes are divided between router shards.

The criteria for route selection govern how the routes are distributed. It is possible to have overlapping subsets of routes across router deployments.

### Example

In addition to **finops-router** and **dev-router** in the example above, you also have **devops-router**, which is configured with a label selector **NAMESPACE\_LABELS="name in (dev, ops)"**. The routes in namespaces labeled **name=dev** or **name=ops** now are serviced by two different router deployments. This becomes a case in which you have defined overlapping subsets of routes, as illustrated in the procedure in [Router Sharding Based on Namespace Labels](#).

In addition, this enables you to create more complex routing rules, allowing the diversion of higher priority traffic to the dedicated **finops-router** while sending lower priority traffic to **devops-router**.

## Router Sharding Based on Route Labels

**NAMESPACE\_LABELS** allows filtering of the projects to service and selecting all the routes from those projects, but you may want to partition routes based on other criteria associated with the routes themselves. The **ROUTE\_LABELS** selector allows you to slice-and-dice the routes themselves.

### Example

A router deployment **prod-router** is configured with the label selector **ROUTE\_LABELS="mydeployment=prod"**, and a router deployment **devtest-router** is configured with the label selector **ROUTE\_LABELS="mydeployment in (dev, test)"**. This configuration partitions routes between the two router deployments according to the routes' labels, irrespective of their namespaces.

The example assumes you have all the routes you want to be serviced tagged with a label **"mydeployment=<tag>"**.

### 4.2.11.1. Creating Router Shards

This section describes an advanced example of router sharding. Suppose there are 26 routes, named **a** — **z**, with various labels:

#### Possible labels on routes

|            |          |           |              |
|------------|----------|-----------|--------------|
| sla=high   | geo=east | hw=modest | dept=finance |
| sla=medium | geo=west | hw=strong | dept=dev     |
| sla=low    |          |           | dept=ops     |

These labels express the concepts including service level agreement, geographical location, hardware requirements, and department. The routes can have at most one label from each column. Some routes may have other labels or no labels at all.

| Name(s) | SLA    | Geo  | HW     | Dept    | Other Labels |
|---------|--------|------|--------|---------|--------------|
| a       | high   | east | modest | finance | type=static  |
| b       |        | west | strong |         | type=dynamic |
| c, d, e | low    |      | modest |         | type=static  |
| g—k     | medium |      | strong | dev     |              |
| l—s     | high   |      | modest | ops     |              |
| t—z     |        | west |        |         | type=dynamic |

Here is a convenience script **mkshard** that illustrates how **oc adm router**, **oc set env**, and **oc scale** can be used together to make a router shard.

```
#!/bin/bash
# Usage: mkshard ID SELECTION-EXPRESSION
id=$1
sel="$2"
router=router-shard-$id
oc adm router $router --replicas=0
dc=dc/router-shard-$id
oc set env $dc ROUTE_LABELS="$sel"
oc scale $dc --replicas=3
```

- 1 The created router has name **router-shard-<id>**.
- 2 Specify no scaling for now.
- 3 The deployment configuration for the router.
- 4 Set the selection expression using **oc set env**. The selection expression is the value of the **ROUTE\_LABELS** environment variable.
- 5 Scale it up.

Running **mkshard** several times creates several routers:

| Router         | Selection Expression | Routes |
|----------------|----------------------|--------|
| router-shard-1 | sla=high             | a, l—s |
| router-shard-2 | geo=west             | b, t—z |
| router-shard-3 | dept=dev             | g—k    |

#### 4.2.11.2. Modifying Router Shards

Because a router shard is a construct [based on labels](#), you can modify either the labels (via [oc label](#)) or the selection expression (via [oc set env](#)).

This section extends the example started in the [Creating Router Shards](#) section, demonstrating how to change the selection expression.

Here is a convenience script **modshard** that modifies an existing router to use a new selection expression:

```
#!/bin/bash
# Usage: modshard ID SELECTION-EXPRESSION...
id=$1
shift
router=router-shard-$id
dc=dc/$router
oc scale $dc --replicas=0
oc set env $dc "$@"
oc scale $dc --replicas=3
```

- 1
- 2
- 3
- 4
- 5

- 1 The modified router has name **router-shard-<id>**.
- 2 The deployment configuration where the modifications occur.
- 3 Scale it down.
- 4 Set the new selection expression using **oc set env**. Unlike **mkshard** from the [Creating Router Shards](#) section, the selection expression specified as the non-ID arguments to **modshard** must include the environment variable name as well as its value.
- 5 Scale it back up.



#### NOTE

In **modshard**, the **oc scale** commands are not necessary if the [deployment strategy](#) for **router-shard-<id>** is **Rolling**.

For example, to expand the department for **router-shard-3** to include **ops** as well as **dev**:

```
$ modshard 3 ROUTE_LABELS='dept in (dev, ops)'
```

The result is that **router-shard-3** now selects routes **g—s** (the combined sets of **g—k** and **l—s**).

This example takes into account that there are only three departments in this example scenario, and specifies a department to leave out of the shard, thus achieving the same result as the preceding example:

```
$ modshard 3 ROUTE_LABELS='dept != finance'
```

This example specifies three comma-separated qualities, and results in only route **b** being selected:

```
$ modshard 3 ROUTE_LABELS='hw=strong, type=dynamic, geo=west'
```

Similarly to **ROUTE\_LABELS**, which involves a route's labels, you can select routes based on the labels of the route's namespace using the **NAMESPACE\_LABELS** environment variable. This example modifies **router-shard-3** to serve routes whose namespace has the label **frequency=weekly**:

```
$ modshard 3 NAMESPACE_LABELS='frequency=weekly'
```

The last example combines **ROUTE\_LABELS** and **NAMESPACE\_LABELS** to select routes with label **sla=low** and whose namespace has the label **frequency=weekly**:

```
$ modshard 3 \
  NAMESPACE_LABELS='frequency=weekly' \
  ROUTE_LABELS='sla=low'
```

#### 4.2.12. Finding the Host Name of the Router

When exposing a service, a user can use the same route from the DNS name that external users use to access the application. The network administrator of the external network must make sure the host name resolves to the name of a router that has admitted the route. The user can set up their DNS with a CNAME that points to this host name. However, the user may not know the host name of the router. When it is not known, the cluster administrator can provide it.

The cluster administrator can use the **--router-canonical-hostname** option with the router's canonical host name when creating the router. For example:

```
# oc adm router myrouter --router-canonical-hostname="rtr.example.com"
```

This creates the **ROUTER\_CANONICAL\_HOSTNAME** environment variable in the router's deployment configuration containing the host name of the router.

For routers that already exist, the cluster administrator can edit the router's deployment configuration and add the **ROUTER\_CANONICAL\_HOSTNAME** environment variable:

```
spec:
  template:
    spec:
      containers:
        - env:
          - name: ROUTER_CANONICAL_HOSTNAME
            value: rtr.example.com
```

The **ROUTER\_CANONICAL\_HOSTNAME** value is displayed in the route status for all routers that have

admitted the route. The route status is refreshed every time the router is reloaded.

When a user creates a route, all of the active routers evaluate the route and, if conditions are met, admit it. When a router that defines the `ROUTER_CANONICAL_HOSTNAME` environment variable admits the route, the router places the value in the `routerCanonicalHostname` field in the route status. The user can examine the route status to determine which, if any, routers have admitted the route, select a router from the list, and find the host name of the router to pass along to the network administrator.

```
status:
  ingress:
    conditions:
      lastTransitionTime: 2016-12-07T15:20:57Z
      status: "True"
      type: Admitted
      host: hello.in.mycloud.com
      routerCanonicalHostname: rtr.example.com
      routerName: myrouter
      wildcardPolicy: None
```

`oc describe` includes the host name when available:

```
$ oc describe route/hello-route3
...
Requested Host: hello.in.mycloud.com exposed on router myroute (host
rtr.example.com) 12 minutes ago
```

Using the above information, the user can ask the DNS administrator to set up a CNAME from the route's host, `hello.in.mycloud.com`, to the router's canonical hostname, `rtr.example.com`. This results in any traffic to `hello.in.mycloud.com` reaching the user's application.

### 4.2.13. Customizing the Default Routing Subdomain

You can customize the suffix used as the default routing subdomain for your environment by modifying the [master configuration file](#) (the `/etc/origin/master/master-config.yaml` file by default). Routes that do not specify a host name would have one generated using this default routing subdomain.

The following example shows how you can set the configured suffix to `v3.openshift.test`:

```
routingConfig:
  subdomain: v3.openshift.test
```



#### NOTE

This change requires a restart of the master if it is running.

With the OpenShift Container Platform master(s) running the above configuration, the [generated host name](#) for the example of a route named `no-route-hostname` without a host name added to a namespace `mynamespace` would be:

```
no-route-hostname-mynamespace.v3.openshift.test
```

### 4.2.14. Forcing Route Host Names to a Custom Routing Subdomain

If an administrator wants to restrict all routes to a specific routing subdomain, they can pass the **--force-subdomain** option to the **oc adm router** command. This forces the router to override any host names specified in a route and generate one based on the template provided to the **--force-subdomain** option.

The following example runs a router, which overrides the route host names using a custom subdomain template  **\${name} - \${namespace}.apps.example.com**.

```
$ oc adm router --force-subdomain='${name}-${namespace}.apps.example.com'
```

#### 4.2.15. Using Wildcard Certificates

A TLS-enabled route that does not include a certificate uses the router's default certificate instead. In most cases, this certificate should be provided by a trusted certificate authority, but for convenience you can use the OpenShift Container Platform CA to create the certificate. For example:

```
$ CA=/etc/origin/master
$ oc adm ca create-server-cert --signer-cert=$CA/ca.crt \
    --signer-key=$CA/ca.key --signer-serial=$CA/ca.serial.txt \
    --hostnames='*.cloudapps.example.com' \
    --cert=cloudapps.crt --key=cloudapps.key
```



##### NOTE

The **oc adm ca create-server-cert** command generates a certificate that is valid for two years. This can be altered with the **--expire-days** option, but for security reasons, it is recommended to not make it greater than this value.

Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

The router expects the certificate and key to be in PEM format in a single file:

```
$ cat cloudapps.crt cloudapps.key $CA/ca.crt > cloudapps.router.pem
```

From there you can use the **--default-cert** flag:

```
$ oc adm router --default-cert=cloudapps.router.pem --service-account=router
```



##### NOTE

Browsers only consider wildcards valid for subdomains one level deep. So in this example, the certificate would be valid for *a.cloudapps.example.com* but not for *a.b.cloudapps.example.com*.

#### 4.2.16. Manually Redeploy Certificates

To manually redeploy the router certificates:

1. Check to see if a secret containing the default router certificate was added to the router:

```
$ oc volumes dc/router
  deploymentconfigs/router
    secret/router-certs as server-certificate
      mounted at /etc/pki/tls/private
```

If the certificate is added, skip the following step and overwrite the secret.

2. Make sure that you have a default certificate directory set for the following variable **DEFAULT\_CERTIFICATE\_DIR**:

```
$ oc env dc/router --list
  DEFAULT_CERTIFICATE_DIR=/etc/pki/tls/private
```

If not, create the directory using the following command:

```
$ oc env dc/router DEFAULT_CERTIFICATE_DIR=/etc/pki/tls/private
```

3. Export the certificate to PEM format:

```
$ cat custom-router.key custom-router.crt custom-ca.crt > custom-router.crt
```

4. Overwrite or create a router certificate secret:

If the certificate secret was added to the router, overwrite the secret. If not, create a new secret.

To overwrite the secret, run the following command:

```
$ oc create secret generic router-certs --from-file=tls.crt=custom-router.crt --from-file=tls.key=custom-router.key --type=kubernetes.io/tls -o json | oc replace -f -
```

To create a new secret, run the following commands:

```
$ oc create secret generic router-certs --from-file=tls.crt=custom-router.crt --from-file=tls.key=custom-router.key --type=kubernetes.io/tls

$ oc volume dc/router --add --mount-path=/etc/pki/tls/private --secret-name='router-certs' --name router-certs
```

5. Deploy the router.

```
$ oc rollout latest dc/router
```

#### 4.2.17. Using Secured Routes

Currently, password protected key files are not supported. HAProxy prompts for a password upon starting and does not have a way to automate this process. To remove a passphrase from a keyfile, you can run:

```
# openssl rsa -in <passwordProtectedKey.key> -out <new.key>
```

Here is an example of how to use a secure edge terminated route with TLS termination occurring on the router before traffic is proxied to the destination. The secure edge terminated route specifies the TLS certificate and key information. The TLS certificate is served by the router front end.

First, start up a router instance:

```
# oc adm router --replicas=1 --service-account=router
```

Next, create a private key, csr and certificate for our edge secured route. The instructions on how to do that would be specific to your certificate authority and provider. For a simple self-signed certificate for a domain named **www.example.test**, see the example shown below:

```
# sudo openssl genrsa -out example-test.key 2048
#
# sudo openssl req -new -key example-test.key -out example-test.csr \
-subj "/C=US/ST=CA/L=Mountain View/O=OS3/OU=Eng/CN=www.example.test"
#
# sudo openssl x509 -req -days 366 -in example-test.csr \
-signkey example-test.key -out example-test.crt
```

Generate a route using the above certificate and key.

```
$ oc create route edge --service=my-service \
--hostname=www.example.test \
--key=example-test.key --cert=example-test.crt
route "my-service" created
```

Look at its definition.

```
$ oc get route/my-service -o yaml
apiVersion: v1
kind: Route
metadata:
  name: my-service
spec:
  host: www.example.test
  to:
    kind: Service
    name: my-service
  tls:
    termination: edge
    key: |
      -----BEGIN PRIVATE KEY-----
      [...]
      -----END PRIVATE KEY-----
    certificate: |
      -----BEGIN CERTIFICATE-----
      [...]
      -----END CERTIFICATE-----
```

Make sure your DNS entry for **www.example.test** points to your router instance(s) and the route to your domain should be available. The example below uses curl along with a local resolver to simulate the DNS lookup:

```
# routerip="4.1.1.1" # replace with IP address of one of your router instances.
# curl -k --resolve www.example.test:443:$routerip
https://www.example.test/
```

## 4.2.18. Using Wildcard Routes (for a Subdomain)

The HAProxy router has support for wildcard routes, which are enabled by setting the **ROUTER\_ALLOW\_WILDCARD\_ROUTES** environment variable to **true**. Any routes with a wildcard policy of **Subdomain** that pass the router admission checks will be serviced by the HAProxy router. Then, the HAProxy router exposes the associated service (for the route) per the route's wildcard policy.



### IMPORTANT

To change a route's wildcard policy, you must remove the route and recreate it with the updated wildcard policy. Editing only the route's wildcard policy in a route's **.yaml** file does not work.

```
$ oc adm router --replicas=0 ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true
$ oc scale dc/router --replicas=1
```

[Learn how to configure the web console for wildcard routes.](#)

### Using a SecureWildcard Edge Terminated Route

This example reflects TLS termination occurring on the router before traffic is proxied to the destination. Traffic sent to any hosts in the subdomain **example.org** (**\*.example.org**) is proxied to the exposed service.

The secure edge terminated route specifies the TLS certificate and key information. The TLS certificate is served by the router front end for all hosts that match the subdomain (**\*.example.org**).

1. Start up a router instance:

```
$ oc adm router --replicas=0 --service-account=router
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true
$ oc scale dc/router --replicas=1
```

2. Create a private key, certificate signing request (CSR), and certificate for the edge secured route.

The instructions on how to do this are specific to your certificate authority and provider. For a simple self-signed certificate for a domain named **\*.example.test**, see this example:

```
# sudo openssl genrsa -out example-test.key 2048
#
# sudo openssl req -new -key example-test.key -out example-test.csr \
#   -subj "/C=US/ST=CA/L=Mountain View/O=OS3/OU=Eng/CN=*.example.test"
#
# sudo openssl x509 -req -days 366 -in example-test.csr \
#   -signkey example-test.key -out example-test.crt
```

3. Generate a wildcard route using the above certificate and key:

```
$ cat > route.yaml <<REOF
apiVersion: v1
kind: Route
metadata:
  name: my-service
spec:
  host: www.example.test
  wildcardPolicy: Subdomain
  to:
    kind: Service
    name: my-service
  tls:
    termination: edge
    key: "$(perl -pe 's/\n/\n/' example-test.key)"
    certificate: "$(perl -pe 's/\n/\n/' example-test.cert)"
REOF
$ oc create -f route.yaml
```

Ensure your DNS entry for `*.example.test` points to your router instance(s) and the route to your domain is available.

This example uses `curl` with a local resolver to simulate the DNS lookup:

```
# routerip="4.1.1.1" # replace with IP address of one of your
router instances.
# curl -k --resolve www.example.test:443:$routerip
https://www.example.test/
# curl -k --resolve abc.example.test:443:$routerip
https://abc.example.test/
# curl -k --resolve anyname.example.test:443:$routerip
https://anyname.example.test/
```

For routers that allow wildcard routes (`ROUTER_ALLOW_WILDCARD_ROUTES` set to `true`), there are some caveats to the ownership of a subdomain associated with a wildcard route.

Prior to wildcard routes, ownership was based on the claims made for a host name with the namespace with the oldest route winning against any other claimants. For example, route `r1` in namespace `ns1` with a claim for `one.example.test` would win over another route `r2` in namespace `ns2` for the same host name `one.example.test` if route `r1` was older than route `r2`.

In addition, routes in other namespaces were allowed to claim non-overlapping hostnames. For example, route `rone` in namespace `ns1` could claim `www.example.test` and another route `rtwo` in namespace `d2` could claim `c3po.example.test`.

This is still the case if there are *no* wildcard routes claiming that same subdomain (`example.test` in the above example).

However, a wildcard route needs to claim all of the host names within a subdomain (host names of the form `\*.example.test`). A wildcard route's claim is allowed or denied based on whether or not the oldest route for that subdomain (`example.test`) is in the same namespace as the wildcard route. The oldest route can be either a regular route or a wildcard route.

For example, if there is already a route `eldest` that exists in the `ns1` namespace that claimed a host

named **owner.example.test** and, if at a later point in time, a new wildcard route **wildthing** requesting for routes in that subdomain (**example.test**) is added, the claim by the wildcard route will *only* be allowed if it is the same namespace (**ns1**) as the owning route.

The following examples illustrate various scenarios in which claims for wildcard routes will succeed or fail.

In the example below, a router that allows wildcard routes will allow non-overlapping claims for hosts in the subdomain **example.test** as long as a wildcard route has not claimed a subdomain.

```
$ oc adm router ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test
$ oc expose service myservice --hostname=aname.example.test
$ oc expose service myservice --hostname=bname.example.test

$ oc project ns2
$ oc expose service anotherservice --hostname=second.example.test
$ oc expose service anotherservice --hostname=cname.example.test

$ oc project otherns
$ oc expose service thirdservice --hostname=emmy.example.test
$ oc expose service thirdservice --hostname=webby.example.test
```

In the example below, a router that allows wildcard routes will not allow the claim for **owner.example.test** or **aname.example.test** to succeed since the owning namespace is **ns1**.

```
$ oc adm router ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test
$ oc expose service myservice --hostname=aname.example.test

$ oc project ns2
$ oc expose service secondservice --hostname=bname.example.test
$ oc expose service secondservice --hostname=cname.example.test

$ # Router will not allow this claim with a different path name `/p1` as
$ # namespace `ns1` has an older route claiming host `aname.example.test`.
$ oc expose service secondservice --hostname=aname.example.test --
path="/p1"

$ # Router will not allow this claim as namespace `ns1` has an older route
$ # claiming host name `owner.example.test`.
$ oc expose service secondservice --hostname=owner.example.test

$ oc project otherns

$ # Router will not allow this claim as namespace `ns1` has an older route
$ # claiming host name `aname.example.test`.
$ oc expose service thirdservice --hostname=aname.example.test
```

In the example below, a router that allows wildcard routes will allow the claim for `\*.example.test` to succeed since the owning namespace is **ns1** and the wildcard route belongs to that same namespace.

```
$ oc adm router ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test

$ # Reusing the route.yaml from the previous example.
$ # spec:
$ #   host: www.example.test
$ #   wildcardPolicy: Subdomain

$ oc create -f route.yaml  # router will allow this claim.
```

In the example below, a router that allows wildcard routes will not allow the claim for `\*.example.test` to succeed since the owning namespace is **ns1** and the wildcard route belongs to another namespace **cyclone**.

```
$ oc adm router ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test

$ # Switch to a different namespace/project.
$ oc project cyclone

$ # Reusing the route.yaml from a prior example.
$ # spec:
$ #   host: www.example.test
$ #   wildcardPolicy: Subdomain

$ oc create -f route.yaml  # router will deny (_NOT_ allow) this claim.
```

Similarly, once a namespace with a wildcard route claims a subdomain, only routes within that namespace can claim any hosts in that same subdomain.

In the example below, once a route in namespace **ns1** with a wildcard route claims subdomain **example.test**, only routes in the namespace **ns1** are allowed to claim any hosts in that same subdomain.

```
$ oc adm router ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=owner.example.test

$ oc project othersns

$ # namespace `othersns` is allowed to claim for other.example.test
$ oc expose service otherservice --hostname=other.example.test
```

```
$ oc project ns1

$ # Reusing the route.yaml from the previous example.
$ # spec:
$ #   host: www.example.test
$ #   wildcardPolicy: Subdomain

$ oc create -f route.yaml    # Router will allow this claim.

$ # In addition, route in namespace otherns will lose its claim to host
$ # `other.example.test` due to the wildcard route claiming the
subdomain.

$ # namespace `ns1` is allowed to claim for deux.example.test
$ oc expose service mysecondservice --hostname=deux.example.test

$ # namespace `ns1` is allowed to claim for deux.example.test with path
/p1
$ oc expose service mythirdservice --hostname=deux.example.test --
path="/p1"

$ oc project otherns

$ # namespace `otherns` is not allowed to claim for deux.example.test
$ # with a different path '/otherpath'
$ oc expose service otherservice --hostname=deux.example.test --
path="/otherpath"

$ # namespace `otherns` is not allowed to claim for owner.example.test
$ oc expose service yetanotherservice --hostname=owner.example.test

$ # namespace `otherns` is not allowed to claim for unclaimed.example.test
$ oc expose service yetanotherservice --hostname=unclaimed.example.test
```

In the example below, different scenarios are shown, in which the owner routes are deleted and ownership is passed within and across namespaces. While a route claiming host **eldest.example.test** in the namespace **ns1** exists, wildcard routes in that namespace can claim subdomain **example.test**. When the route for host **eldest.example.test** is deleted, the next oldest route **senior.example.test** would become the oldest route and would not affect any other routes. Once the route for host **senior.example.test** is deleted, the next oldest route **junior.example.test** becomes the oldest route and block the wildcard route claimant.

```
$ oc adm router ...
$ oc set env dc/router ROUTER_ALLOW_WILDCARD_ROUTES=true

$ oc project ns1
$ oc expose service myservice --hostname=eldest.example.test
$ oc expose service seniorbservice --hostname=senior.example.test

$ oc project otherns

$ # namespace `otherns` is allowed to claim for other.example.test
$ oc expose service juniorbservice --hostname=junior.example.test

$ oc project ns1
```

```
$ # Reusing the route.yaml from the previous example.
$ # spec:
$ #   host: www.example.test
$ #   wildcardPolicy: Subdomain

$ oc create -f route.yaml    # Router will allow this claim.

$ # In addition, route in namespace otherns will lose its claim to host
$ # `junior.example.test` due to the wildcard route claiming the
subdomain.

$ # namespace `ns1` is allowed to claim for dos.example.test
$ oc expose service mysecondservice --hostname=dos.example.test

$ # Delete route for host `eldest.example.test`, the next oldest route is
$ # the one claiming `senior.example.test`, so route claims are
unaffected.
$ oc delete route myservice

$ # Delete route for host `senior.example.test`, the next oldest route is
$ # the one claiming `junior.example.test` in another namespace, so claims
$ # for a wildcard route would be affected. The route for the host
$ # `dos.example.test` would be unaffected as there are no other wildcard
$ # claimants blocking it.
$ oc delete route seniorservice
```

#### 4.2.19. Using the Container Network Stack

The OpenShift Container Platform router runs inside a container and the default behavior is to use the network stack of the host (i.e., the node where the router container runs). This default behavior benefits performance because network traffic from remote clients does not need to take multiple hops through user space to reach the target service and container.

Additionally, this default behavior enables the router to get the actual source IP address of the remote connection rather than getting the node's IP address. This is useful for defining ingress rules based on the originating IP, supporting sticky sessions, and monitoring traffic, among other uses.

This host network behavior is controlled by the `--host-network` router command line option, and the default behaviour is the equivalent of using `--host-network=true`. If you wish to run the router with the container network stack, use the `--host-network=false` option when creating the router. For example:

```
$ oc adm router --service-account=router --host-network=false
```

Internally, this means the router container must publish the 80 and 443 ports in order for the external network to communicate with the router.



#### NOTE

Running with the container network stack means that the router sees the source IP address of a connection to be the NATed IP address of the node, rather than the actual remote IP address.



## NOTE

On OpenShift Container Platform clusters using [multi-tenant network isolation](#), routers on a non-default namespace with the `--host-network=false` option will load all routes in the cluster, but routes across the namespaces will not be reachable due to network isolation. With the `--host-network=true` option, routes bypass the container network and it can access any pod in the cluster. If isolation is needed in this case, then do not add routes across the namespaces.

### 4.2.20. Exposing Router Metrics

The [HAProxy router metrics](#) are, by default, exposed or published in [Prometheus format](#) for consumption by external metrics collection and aggregation systems (e.g. Prometheus, statsd). Metrics are also available directly from the [HAProxy router](#) in its own CSV format.

When you create a router, as below,

```
$ oc adm router --service-account=router
```

metrics are automatically available in Prometheus format on the stats-port, default 1936. To suppress metrics collection,

```
$ oc adm router --service-account=router --stats-port=0
```

To switch to the HAProxy CSV format metrics, edit the [environment variables](#) for the router dc and delete the following lines:

- name: ROUTER\_LISTEN\_ADDR  
value: 0.0.0.0:1936
- name: ROUTER\_METRICS\_TYPE  
value: haproxy

Where 1936 is the STATS\_PORT value.



## NOTE

The `--expose-metrics` and `--metrics-image` options are deprecated. The haproxy-exporter side car is now integrated into the router controller so you can delete the sidecar container from existing router deployment configs. You can continue to use the side car in existing routers. New routers use the integrated metrics.

You can extract the raw statistics in Prometheus format by using the following.

Information needed to access the metrics is found the router service annotations:

```
metadata:  
  annotations:  
    prometheus.io/port: "1936"  
    prometheus.io/scrape: "true"  
    prometheus.openshift.io/password: IIMoDqON02  
    prometheus.openshift.io/username: admin
```

The metrics port is set from the STATS\_PORT, default 1936. You may need to confiugre your firewall to permit access. Use the above username and password to access the metrics. The path is "/metrics".

```
$ curl <user>:<password>@<router_IP>:<STATS_PORT>/metrics
for example:
$ curl admin:sLzdR6SgDJ@10.254.254.35:1936/metrics
...
# HELP haproxy_backend_connections_total Total number of connections.
# TYPE haproxy_backend_connections_total gauge
haproxy_backend_connections_total{backend="http",namespace="default",route
="hello-route"} 0
haproxy_backend_connections_total{backend="http",namespace="default",route
="hello-route-alt"} 0
haproxy_backend_connections_total{backend="http",namespace="default",route
="hello-route01"} 0
...
# HELP haproxy_exporter_server_threshold Number of servers tracked and the
current threshold value.
# TYPE haproxy_exporter_server_threshold gauge
haproxy_exporter_server_threshold{type="current"} 11
haproxy_exporter_server_threshold{type="limit"} 500
...
# HELP haproxy_frontend_bytes_in_total Current total of incoming bytes.
# TYPE haproxy_frontend_bytes_in_total gauge
haproxy_frontend_bytes_in_total{frontend="fe_no_sni"} 0
haproxy_frontend_bytes_in_total{frontend="fe_sni"} 0
haproxy_frontend_bytes_in_total{frontend="public"} 119070
...
# HELP haproxy_server_bytes_in_total Current total of incoming bytes.
# TYPE haproxy_server_bytes_in_total gauge
haproxy_server_bytes_in_total{namespace="",pod="",route="",server="fe_no_s
ni",service=""} 0
haproxy_server_bytes_in_total{namespace="",pod="",route="",server="fe_sni"
,service=""} 0
haproxy_server_bytes_in_total{namespace="default",pod="docker-registry-5-
nk5fz",route="docker-registry",server="10.130.0.89:5000",service="docke
r-registry"} 0
haproxy_server_bytes_in_total{namespace="default",pod="hello-rc-
vkjqx",route="hello-route",server="10.130.0.90:8080",service="hello-svc-
1"} 0
...
...
```

#### 4.2.21. Preventing Connection Failures During Restarts

If you connect to the router while the proxy is reloading, there is a small chance that your connection will end up in the wrong network queue and be dropped. The issue is being addressed. In the meantime, it is possible to work around the problem by installing **iptables** rules to prevent connections during the reload window. However, doing so means that the router needs to run with elevated privilege so that it can manipulate **iptables** on the host. It also means that connections that happen during the reload are temporarily ignored and must retransmit their connection start, lengthening the time it takes to connect, but preventing connection failure.

To prevent this, configure the router to use **iptables** by changing the service account, and setting an environment variable on the router.

## Use a Privileged SCC

When creating the router, allow it to use the privileged SCC. This gives the router user the ability to create containers with root privileges on the nodes:

```
$ oc adm policy add-scc-to-user privileged -z router
```

## Patch the Router Deployment Configuration to Create a Privileged Container

You can now create privileged containers. Next, configure the router deployment configuration to use the privilege so that the router can set the iptables rules it needs. This patch changes the router deployment configuration so that the container that is created runs as privileged (and therefore gets correct capabilities) and run as root:

```
$ oc patch dc router -p '{"spec":{"template":{"spec":{"containers":[{"name":"router","securityContext":{"privileged":true}}],"securityContext":{"runAsUser": 0}}}}'
```

## Configure the Router to Use iptables

Set the option on the router deployment configuration:

```
$ oc set env dc/router -c router DROP_SYN_DURING_RESTART=true
```

If you used a non-default name for the router, you must change ***dc/router*** accordingly.

### 4.2.22. ARP Cache Tuning for Large-scale Clusters

In OpenShift Container Platform clusters with large numbers of routes (greater than the value of **net.ipv4.neigh.default.gc\_thresh3**, which is **65536** by default), you must increase the default values of sysctl variables on each node in the cluster running the router pod to allow more entries in the ARP cache.

When the problem is occurring, the kernel messages would be similar to the following:

```
[ 1738.811139] net_ratelimit: 1045 callbacks suppressed
[ 1743.823136] net_ratelimit: 293 callbacks suppressed
```

When this issue occurs, the **oc** commands might start to fail with the following error:

```
Unable to connect to the server: dial tcp: lookup <hostname> on <ip>:<port>: write udp <ip>:<port>-><ip>:<port>: write: invalid argument
```

To verify the actual amount of ARP entries for IPv4, run the following:

```
# ip -4 neigh show nud all | wc -l
```

If the number begins to approach the **net.ipv4.neigh.default.gc\_thresh3** threshold, increase the values. Get the current value by running:

```
# sysctl net.ipv4.neigh.default.gc_thresh1
net.ipv4.neigh.default.gc_thresh1 = 128
# sysctl net.ipv4.neigh.default.gc_thresh2
```

```

net.ipv4.neigh.default.gc_thresh2 = 512
# sysctl net.ipv4.neigh.default.gc_thresh3
net.ipv4.neigh.default.gc_thresh3 = 1024

```

The following sysctl sets the variables to the OpenShift Container Platform current default values.

```

# sysctl net.ipv4.neigh.default.gc_thresh1=8192
# sysctl net.ipv4.neigh.default.gc_thresh2=32768
# sysctl net.ipv4.neigh.default.gc_thresh3=65536

```

To make these settings permanent, [see this document](#).

#### 4.2.23. Protecting Against DDoS Attacks

Add **timeout http-request** to the default HAProxy router image to protect the deployment against distributed denial-of-service (DDoS) attacks (for example, slowloris):

```

# and the haproxy stats socket is available at /var/run/haproxy.stats
global
    stats socket ./haproxy.stats level admin

defaults
    option http-server-close
    mode http
    timeout http-request 5s
    timeout connect 5s ①
    timeout server 10s
    timeout client 30s

```

① **timeout http-request** is set up to 5 seconds. HAProxy gives a client 5 seconds \*to send its whole HTTP request. Otherwise, HAProxy shuts the connection with \*an error.

Also, when the environment variable **ROUTER\_SLOWLORIS\_TIMEOUT** is set, it limits the amount of time a client has to send the whole HTTP request. Otherwise, HAProxy will shut down the connection.

Setting the environment variable allows information to be captured as part of the router's deployment configuration and does not require manual modification of the template, whereas manually adding the HAProxy setting requires you to rebuild the router pod and maintain your router template file.

Using annotations implements basic DDoS protections in the HAProxy template router, including the ability to limit the:

- number of concurrent TCP connections
- rate at which a client can request TCP connections
- rate at which HTTP requests can be made

These are enabled on a per route basis because applications can have extremely different traffic patterns.

**Table 4.1. HAProxy Template Router Settings**

| Setting                                                                        | Description                                                                                     |
|--------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------|
| <code>haproxy.router.openshift.io/rate-limit-connections</code>                | Enables the settings be configured (when set to <code>true</code> , for example).               |
| <code>haproxy.router.openshift.io/rate-limit-connections.concurrent-tcp</code> | The number of concurrent TCP connections that can be made by the same IP address on this route. |
| <code>haproxy.router.openshift.io/rate-limit-connections.rate-tcp</code>       | The number of TCP connections that can be opened by a client IP.                                |
| <code>haproxy.router.openshift.io/rate-limit-connections.rate-http</code>      | The number of HTTP requests that a client IP can make in a 3-second period.                     |

## 4.3. DEPLOYING A CUSTOMIZED HAProxy ROUTER

### 4.3.1. Overview

The default HAProxy router is intended to satisfy the needs of most users. However, it does not expose all of the capability of HAProxy. Therefore, users may need to modify the router for their own needs.

You may need to implement new features within the application back-ends, or modify the current operation. The router plug-in provides all the facilities necessary to make this customization.

The router pod uses a template file to create the needed HAProxy configuration file. The template file is a [golang template](#). When processing the template, the router has access to OpenShift Container Platform information, including the router's deployment configuration, the set of admitted routes, and some helper functions.

When the router pod starts, and every time it reloads, it creates an HAProxy configuration file, and then it starts HAProxy. The [HAProxy configuration manual](#) describes all of the features of HAProxy and how to construct a valid configuration file.

A [configMap](#) can be used to add the new template to the router pod. With this approach, the router deployment configuration is modified to mount the [configMap](#) as a volume in the router pod. The [TEMPLATE\\_FILE](#) environment variable is set to the full path name of the template file in the router pod.

Alternatively, you can build a custom router image and use it when deploying some or all of your routers. There is no need for all routers to run the same image. To do this, modify the [haproxy-template.config](#) file, and [rebuild](#) the router image. The new image is pushed to the cluster's Docker repository, and the router's deployment configuration [image:](#) field is updated with the new name. When the cluster is updated, the image needs to be rebuilt and pushed.

In either case, the router pod starts with the template file.

### 4.3.2. Obtaining the Router Configuration Template

The HAProxy template file is fairly large and complex. For some changes, it may be easier to modify the existing template rather than writing a complete replacement. You can obtain a [haproxy-config.template](#) file from a running router by running this on master, referencing the router pod:

```
# oc get po
```

```

NAME          READY   STATUS    RESTARTS   AGE
router-2-40fc3   1/1     Running   0          11d
# oc rsh router-2-40fc3 cat haproxy-config.template > haproxy-
config.template
# oc rsh router-2-40fc3 cat haproxy.config > haproxy.config

```

Alternatively, you can log onto the node that is running the router:

```

# docker run --rm --interactive=true --tty --entrypoint=cat \
  registry.access.redhat.com/openshift3/ose-haproxy-router:v3.7 haproxy-
config.template

```

The image name is from **docker images**.

Save this content to a file for use as the basis of your customized template. The saved **haproxy.config** shows what is actually running.

### 4.3.3. Modifying the Router Configuration Template

#### 4.3.3.1. Background

The template is based on the [golang template](#). It can reference any of the environment variables in the router's deployment configuration, any configuration information that is described below, and router provided helper functions.

The structure of the template file mirrors the resulting HAProxy configuration file. As the template is processed, anything not surrounded by `{{ " something " }}` is directly copied to the configuration file. Passages that are surrounded by `{{ " something " }}` are evaluated. The resulting text, if any, is copied to the configuration file.

#### 4.3.3.2. Go Template Actions

The **define** action names the file that will contain the processed template.

```

{{define "/var/lib/haproxy/conf/haproxy.config"}}pipeline{{end}}

```

**Table 4.2. Template Router Functions**

| Function                                                                             | Meaning                                                                                                                           |
|--------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------|
| <code>endpointsForAlias(alias ServiceAliasConfig, svc ServiceUnit) []Endpoint</code> | Returns the list of valid endpoints.                                                                                              |
| <code>env(variable, default string) string</code>                                    | Tries to get the named environment variable from the pod. Returns the second argument if the variable cannot be read or is empty. |

| Function                                                                              | Meaning                                                                                                                                                                                                                                                                |
|---------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>matchPattern(pattern, s string) bool</code>                                     | The first argument is a string that contains the regular expression, the second argument is the variable to test. Returns a Boolean value indicating whether the regular expression provided as the first argument matches the string provided as the second argument. |
| <code>isInteger(s string) bool</code>                                                 | Determines if a given variable is an integer.                                                                                                                                                                                                                          |
| <code>matchValues(s string, allowedValues ...string) bool</code>                      | Compares a given string to a list of allowed strings.                                                                                                                                                                                                                  |
| <code>genSubdomainWildcardRegexp(hostname, path string, exactPath bool) string</code> | Generates a regular expression matching the subdomain for hosts (and paths) with a wildcard policy.                                                                                                                                                                    |
| <code>generateRouteRegexp(hostname, path string, wildcard bool) string</code>         | Generates a regular expression matching the route hosts (and paths). The first argument is the host name, the second is the path, and the third is a wildcard Boolean.                                                                                                 |
| <code>genCertificateHostName(hostname string, wildcard bool) string</code>            | Generates host name to use for serving/matching certificates. First argument is the host name and the second is the wildcard Boolean.                                                                                                                                  |

These functions are provided by the HAProxy template router plug-in.

#### 4.3.3.3. Router Provided Information

This section reviews the OpenShift Container Platform information that the router makes available to the template. The router configuration parameters are the set of data that the HAProxy router plug-in is given. The fields are accessed by **(dot) .Fieldname**.

The tables below the Router Configuration Parameters expand on the definitions of the various fields. In particular, **.State** has the set of admitted routes.

**Table 4.3. Router Configuration Parameters**

| Field                     | Type                                           | Description                                                                                      |
|---------------------------|------------------------------------------------|--------------------------------------------------------------------------------------------------|
| <code>WorkingDir</code>   | string                                         | The directory that files will be written to, defaults to <code>/var/lib/containers/router</code> |
| <code>State</code>        | <code>map[string] (ServiceAliasConfig)`</code> | The routes.                                                                                      |
| <code>ServiceUnits</code> | <code>map[string]ServiceUnit</code>            | The service lookup.                                                                              |

| Field                     | Type        | Description                                                   |
|---------------------------|-------------|---------------------------------------------------------------|
| <b>DefaultCertificate</b> | string      | Full path name to the default certificate in pem format.      |
| <b>PeerEndpoints</b>      | `[]Endpoint | Peers.                                                        |
| <b>StatsUser</b>          | string      | User name to expose stats with (if the template supports it). |
| <b>StatsPassword</b>      | string      | Password to expose stats with (if the template supports it).  |
| <b>StatsPort</b>          | int         | Port to expose stats with (if the template supports it).      |
| <b>BindPorts</b>          | bool        | Whether the router should bind the default ports.             |

**Table 4.4. Router ServiceAliasConfig (A Route)**

| Field                 | Type                                     | Description                                                                                                  |
|-----------------------|------------------------------------------|--------------------------------------------------------------------------------------------------------------|
| <b>Name</b>           | string                                   | The user-specified name of the route.                                                                        |
| <b>Namespace</b>      | string                                   | The namespace of the route.                                                                                  |
| <b>Host</b>           | string                                   | The host name. For example, <code>www.example.com</code> .                                                   |
| <b>Path</b>           | string                                   | Optional path. For example, <code>www.example.com/myservice</code> where <code>myservice</code> is the path. |
| <b>TLSTermination</b> | <code>routeapi.TLSTerminationType</code> | The termination policy for this back-end; drives the mapping files and router configuration.                 |
| <b>Certificates</b>   | <code>map[string]Certificate</code>      | Certificates used for securing this back-end. Keyed by the certificate ID.                                   |
| <b>Status</b>         | <code>ServiceAliasConfigStatus</code>    | Indicates the status of configuration that needs to be persisted.                                            |

| Field                                | Type                                                    | Description                                                                                                                                             |
|--------------------------------------|---------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>PreferPort</b>                    | string                                                  | Indicates the port the user wants to expose. If empty, a port will be selected for the service.                                                         |
| <b>InsecureEdgeTerminationPolicy</b> | <code>routeapi.InsecureEdgeTerminationPolicyType</code> | Indicates desired behavior for insecure connections to an edge-terminated route: <b>none</b> (or <b>disable</b> ), <b>allow</b> , or <b>redirect</b> .  |
| <b>RoutingKeyName</b>                | string                                                  | Hash of the route + namespace name used to obscure the cookie ID.                                                                                       |
| <b>IsWildcard</b>                    | bool                                                    | Indicates this service unit needing wildcard support.                                                                                                   |
| <b>Annotations</b>                   | <code>map[string]string</code>                          | Annotations attached to this route.                                                                                                                     |
| <b>ServiceUnitNames</b>              | <code>map[string]int32</code>                           | Collection of services that support this route, keyed by service name and valued on the weight attached to it with respect to other entries in the map. |
| <b>ActiveServiceUnits</b>            | int                                                     | Count of the <b>ServiceUnitNames</b> with a non-zero weight.                                                                                            |

The **ServiceAliasConfig** is a route for a service. Uniquely identified by host + path. The default template iterates over routes using `{{range $cfgIdx, $cfg := .State}}`. Within such a `{{range}}` block, the template can refer to any field of the current **ServiceAliasConfig** using `$cfg.Field`.

**Table 4.5. Router ServiceUnit**

| Field                | Type                    | Description                                                                                       |
|----------------------|-------------------------|---------------------------------------------------------------------------------------------------|
| <b>Name</b>          | string                  | Name corresponds to a service name + namespace. Uniquely identifies the <b>ServiceUnit</b> .      |
| <b>EndpointTable</b> | <code>[]Endpoint</code> | Endpoints that back the service. This translates into a final backend implementation for routers. |

**ServiceUnit** is an encapsulation of a service, the endpoints that back that service, and the routes that point to the service. This is the data that drives the creation of the router configuration files

**Table 4.6. Router Endpoint**

| Field                | Type   |
|----------------------|--------|
| <b>ID</b>            | string |
| <b>IP</b>            | string |
| <b>Port</b>          | string |
| <b>TargetName</b>    | string |
| <b>PortName</b>      | string |
| <b>IdHash</b>        | string |
| <b>NoHealthCheck</b> | bool   |

**Endpoint** is an internal representation of a Kubernetes endpoint.

**Table 4.7. Router Certificate, ServiceAliasConfigStatus**

| Field                           | Type   | Description                                                                                                                                               |
|---------------------------------|--------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Certificate</b>              | string | Represents a public/private key pair. It is identified by an ID, which will become the file name. A CA certificate will not have a <b>PrivateKey</b> set. |
| <b>ServiceAliasConfigStatus</b> | string | Indicates that the necessary files for this configuration have been persisted to disk. Valid values: "saved", "".                                         |

**Table 4.8. Router Certificate Type**

| Field      | Type   | Description      |
|------------|--------|------------------|
| ID         | string |                  |
| Contents   | string | The certificate. |
| PrivateKey | string | The private key. |

**Table 4.9. Router TLSTerminationType**

| Field                                    | Type   | Description                                                                                                                                                          |
|------------------------------------------|--------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>TLSTerminationType</b>                | string | Dictates where the secure communication will stop.                                                                                                                   |
| <b>InsecureEdgeTerminationPolicyType</b> | string | Indicates the desired behavior for insecure connections to a route. While each router may make its own decisions on which ports to expose, this is normally port 80. |

**TLSTerminationType** and **InsecureEdgeTerminationPolicyType** dictate where the secure communication will stop.

**Table 4.10. Router TLSTerminationType Values**

| Constant                         | Value              | Meaning                                                                                                       |
|----------------------------------|--------------------|---------------------------------------------------------------------------------------------------------------|
| <b>TLSTerminationEdge</b>        | <b>edge</b>        | Terminate encryption at the edge router.                                                                      |
| <b>TLSTerminationPassthrough</b> | <b>passthrough</b> | Terminate encryption at the destination, the destination is responsible for decrypting traffic.               |
| <b>TLSTerminationReencrypt</b>   | <b>reencrypt</b>   | Terminate encryption at the edge router and re-encrypt it with a new certificate supplied by the destination. |

**Table 4.11. Router InsecureEdgeTerminationPolicyType Values**

| Type            | Meaning                                                       |
|-----------------|---------------------------------------------------------------|
| <b>Allow</b>    | Traffic is sent to the server on the insecure port (default). |
| <b>Disable</b>  | No traffic is allowed on the insecure port.                   |
| <b>Redirect</b> | Clients are redirected to the secure port.                    |

None ("") is the same as **Disable**.

#### 4.3.3.4. Annotations

Each route can have annotations attached. Each annotation is just a name and a value.

```
apiVersion: v1
kind: Route
```

```

metadata:
  annotations:
    haproxy.router.openshift.io/timeout: 5500ms
[...]

```

The name can be anything that does not conflict with existing Annotations. The value is any string. The string can have multiple tokens separated by a space. For example, **aa bb cc**. The template uses **{{index}}** to extract the value of an annotation. For example:

```

{{$balanceAlgo := index $cfg.Annotations
"haproxy.router.openshift.io/balance"}}

```

This is an example of how this could be used for mutual client authorization.

```

{{ with $cnList := index $cfg.Annotations "whiteListCertCommonName" }}
{{ if ne $cnList "" }}
  acl test ssl_c_s_dn(CN) -m str {{ $cnList }}
  http-request deny if !test
{{ end }}
{{ end }}

```

Then, you can handle the white-listed CNs with this command.

```
$ oc annotate route <route-name> --overwrite whiteListCertCommonName="CN1
CN2 CN3"
```

See [Route-specific Annotations](#) for more information.

#### 4.3.3.5. Environment Variables

The template can use any environment variables that exist in the router pod. The environment variables can be set in the deployment configuration. New environment variables can be added.

They are referenced by the **env** function:

```

{{env "ROUTER_MAX_CONNECTIONS" "20000"}}

```

The first string is the variable, and the second string is the default when the variable is missing or **nil**. When **ROUTER\_MAX\_CONNECTIONS** is not set or is **nil**, 20000 is used. Environment variables are a map where the key is the environment variable name and the content is the value of the variable.

See [Route-specific Environment variables](#) for more information.

#### 4.3.3.6. Example Usage

Here is a simple template based on the HAProxy template file.

Start with a comment:

```

{{/*
  Here is a small example of how to work with templates
  taken from the HAProxy template file.
*/}}

```

The template can create any number of output files. Use a **define** construct to create an output file. The file name is specified as an argument to define, and everything inside the **define** block up to the matching end is written as the contents of that file.

```
 {{ define "/var/lib/haproxy/conf/haproxy.config" }}
global
{{ end }}
```

The above will copy **global** to the **/var/lib/haproxy/conf/haproxy.config** file, and then close the file.

Set up logging based on environment variables.

```
 {{ with (env "ROUTER_SYSLOG_ADDRESS" "") }}}
log {{.}} {{env "ROUTER_LOGFacility" "local1"}} {{env
"ROUTER_LOG_LEVEL" "warning"}}
{{ end }}
```

The **env** function extracts the value for the environment variable. If the environment variable is not defined or **nil**, the second argument is returned.

The **with** construct sets the value of **.** (dot) within the **with** block to whatever value is provided as an argument to **with**. The **with** action tests Dot for **nil**. If not **nil**, the clause is processed up to the **end**. In the above, assume **ROUTER\_SYSLOG\_ADDRESS** contains **/var/log/msg**, **ROUTER\_LOG\_FACILITY** is not defined, and **ROUTER\_LOG\_LEVEL** contains **info**. The following will be copied to the output file:

```
 log /var/log/msg local1 info
```

Each admitted route ends up generating lines in the configuration file. Use **range** to go through the admitted routes:

```
 {{ range $cfgIdx, $cfg := .State }}
  backend be_http_{{$cfgIdx}}
{{end}}
```

**.State** is a map of **ServiceAliasConfig**, where the key is the route name. **range** steps through the map and, for each pass, it sets **\$cfgIdx** with the **key**, and sets **`\$cfg`** to point to the **ServiceAliasConfig** that describes the route. If there are two routes named **myroute** and **hisroute**, the above will copy the following to the output file:

```
 backend be_http_myroute
backend be_http_hisroute
```

Route Annotations, **\$cfg.Annotations**, is also a map with the annotation name as the key and the content string as the value. The route can have as many annotations as desired and the use is defined by the template author. The user codes the annotation into the route and the template author customized the HAProxy template to handle the annotation.

The common usage is to index the annotation to get the value.

```
 {{$balanceAlgo := index $cfg.Annotations
"haproxy.router.openshift.io/balance"}}
```

The index extracts the value for the given annotation, if any. Therefore, `{\$balanceAlgo` will contain the string associated with the annotation or **nil**. As above, you can test for a non-**nil** string and act on it with the **with** construct.

```
 {{ with $balanceAlgo }}  
   balance $balanceAlgo  
 {{ end }}
```

Here when **\$balanceAlgo** is not **nil**, **balance \$balanceAlgo** is copied to the output file.

In a second example, you want to set a server timeout based on a timeout value set in an annotation.

```
 $value := index $cfg.Annotations "haproxy.router.openshift.io/timeout"
```

The **\$value** can now be evaluated to make sure it contains a properly constructed string. The **matchPattern** function accepts a regular expression and returns **true** if the argument satisfies the expression.

```
 matchPattern "[1-9][0-9]*(us\|ms\|s\|m\|h\|d)?" $value
```

This would accept **5000ms** but not **7y**. The results can be used in a test.

```
 {{if (matchPattern "[1-9][0-9]*(us\|ms\|s\|m\|h\|d)?" $value) }}  
   timeout server {{$value}}  
 {{end}}
```

It can also be used to match tokens:

```
 matchPattern "roundrobin|leastconn|source" $balanceAlgo
```

Alternatively **matchValues** can be used to match tokens:

```
 matchValues $balanceAlgo "roundrobin" "leastconn" "source"
```

#### 4.3.4. Using a ConfigMap to Replace the Router Configuration Template

You can use a [ConfigMap](#) to customize the router instance without rebuilding the router image. The **haproxy-config.template**, **reload-haproxy**, and other scripts can be modified as well as creating and modifying router environment variables.

1. Copy the **haproxy-config.template** that you want to modify as [described above](#). Modify it as desired.
2. Create a ConfigMap:

```
 $ oc create configmap customrouter --from-file=haproxy-  
 config.template
```

The **customrouter** ConfigMap now contains a copy of the modified **haproxy-config.template** file.

3. Modify the router deployment configuration to mount the ConfigMap as a file and point the **TEMPLATE\_FILE** environment variable to it. This can be done via **oc set env** and **oc volume** commands, or alternatively by editing the router deployment configuration.

### Using oc commands

```
$ oc volume dc/router --add --overwrite \
    --name=config-volume \
    --mount-path=/var/lib/haproxy/conf/custom \
    --source='{"configMap": { "name": "customrouter"} }'
$ oc set env dc/router \
    TEMPLATE_FILE=/var/lib/haproxy/conf/custom/haproxy-
config.template
```

### Editing the Router Deployment Configuration

Use **oc edit dc router** to edit the router deployment configuration with a text editor.

```
...
  - name: STATS_USERNAME
    value: admin
  - name: TEMPLATE_FILE ①
    value: /var/lib/haproxy/conf/custom/haproxy-
config.template
    image: openshift/origin-haproxy-routerp
...
  terminationMessagePath: /dev/termination-log
  volumeMounts: ②
    - mountPath: /var/lib/haproxy/conf/custom
      name: config-volume
  dnsPolicy: ClusterFirst
...
  terminationGracePeriodSeconds: 30
  volumes: ③
    - configMap:
        name: customrouter
        name: config-volume
...

```

- 1 In the **spec.container.env** field, add the **TEMPLATE\_FILE** environment variable to point to the mounted **haproxy-config.template** file.
- 2 Add the **spec.container.volumeMounts** field to create the mount point.
- 3 Add a new **spec.volumes** field to mention the ConfigMap.

Save the changes and exit the editor. This restarts the router.

#### 4.3.5. Using Stick Tables

The following example customization can be used in a [highly-available routing setup](#) to use stick-tables that synchronize between peers.

## Adding a Peer Section

In order to synchronize stick-tables amongst peers you must define a peers section in your HAProxy configuration. This section determines how HAProxy will identify and connect to peers. The plug-in provides data to the template under the **.PeerEndpoints** variable to allow you to easily identify members of the router service. You may add a peer section to the **haproxy-config.template** file inside the router image by adding:

```
    {{ if (len .PeerEndpoints) gt 0 }}
    peers openshift_peers
        {{ range $endpointID, $endpoint := .PeerEndpoints }}
            peer {{$endpoint.TargetName}} {{$endpoint.IP}}:1937
        {{ end }}
    {{ end }}
```

## Changing the Reload Script

When using stick-tables, you have the option of telling HAProxy what it should consider the name of the local host in the peer section. When creating endpoints, the plug-in attempts to set the **TargetName** to the value of the endpoint's **TargetRef.Name**. If **TargetRef** is not set, it will set the **TargetName** to the IP address. The **TargetRef.Name** corresponds with the Kubernetes host name, therefore you can add the **-L** option to the **reload-haproxy** script to identify the local host in the peer section.

```
peer_name=$HOSTNAME ①

if [ -n "$old_pid" ]; then
    /usr/sbin/haproxy -f $config_file -p $pid_file -L $peer_name -sf
$old_pid
else
    /usr/sbin/haproxy -f $config_file -p $pid_file -L $peer_name
fi
```

- ① Must match an endpoint target name that is used in the peer section.

## Modifying Back Ends

Finally, to use the stick-tables within back ends, you can modify the HAProxy configuration to use the stick-tables and peer set. The following is an example of changing the existing back end for TCP connections to use stick-tables:

```
    {{ if eq $cfg.TLSTermination "passthrough" }}
backend be_tcp_{{$cfgIdx}}
    balance leastconn
    timeout check 5000ms
    stick-table type ip size 1m expire 5m{{ if (len $.PeerEndpoints) gt 0 }}
    peers openshift_peers {{ end }}
    stick on src
        {{ range $endpointID, $endpoint :=
$serviceUnit.EndpointTable }}
            server {{$endpointID}} {{$endpoint.IP}}:{{$endpoint.Port}} check inter
5000ms
        {{ end }}
    {{ end }}
```

After this modification, you can [rebuild your router](#).

### 4.3.6. Rebuilding Your Router

In order to rebuild the router, you need copies of several files that are present on a running router. Make a work directory and copy the files from the router:

```
# mkdir - myrouter/conf
# cd myrouter
# oc get po
NAME                  READY   STATUS    RESTARTS   AGE
router-2-40fc3        1/1     Running   0          11d
# oc rsh router-2-40fc3 cat haproxy-config.template > conf/haproxy-
config.template
# oc rsh router-2-40fc3 cat error-page-503.http > conf/error-page-503.http
# oc rsh router-2-40fc3 cat default_pub_keys.pem >
conf/default_pub_keys.pem
# oc rsh router-2-40fc3 cat ../Dockerfile > Dockerfile
# oc rsh router-2-40fc3 cat ../reload-haproxy > reload-haproxy
```

You can edit or replace any of these files. However, ***conf/haproxy-config.template*** and ***reload-haproxy*** are the most likely to be modified.

After updating the files:

```
# docker build -t openshift/origin-haproxy-router-myversion .
# docker tag openshift/origin-haproxy-router-myversion
172.30.243.98:5000/openshift/haproxy-router-myversion ①
# docker push 172.30.243.98:5000/openshift/origin-haproxy-router-pc:latest
②
```

- ① Tag the version with the repository. In this case the repository is **172.30.243.98:5000**.
- ② Push the tagged version to the repository. It may be necessary to **docker login** to the repository first.

To use the new router, edit the router deployment configuration either by changing the **image:** string or by adding the **--images=<repo>/<image>:<tag>** flag to the **oc adm router** command.

When debugging the changes, it is helpful to set **imagePullPolicy: Always** in the deployment configuration to force an image pull on each pod creation. When debugging is complete, you can change it back to **imagePullPolicy: IfNotPresent** to avoid the pull on each pod start.

## 4.4. CONFIGURING THE HAProxy ROUTER TO USE THE PROXY PROTOCOL

### 4.4.1. Overview

By default, the HAProxy router expects incoming connections to unsecure, edge, and re-encrypt routes to use HTTP. However, you can configure the router to expect incoming requests by using [the PROXY protocol](#) instead. This topic describes how to configure the HAProxy router and an external load balancer to use the PROXY protocol.

#### 4.4.2. Why Use the PROXY Protocol?

When an intermediary service such as a proxy server or load balancer forwards an HTTP request, it appends the source address of the connection to the request's "Forwarded" header in order to provide this information to subsequent intermediaries and to the back-end service to which the request is ultimately forwarded. However, if the connection is encrypted, intermediaries cannot modify the "Forwarded" header. In this case, the HTTP header will not accurately communicate the original source address when the request is forwarded.

To solve this problem, some load balancers encapsulate HTTP requests using the PROXY protocol as an alternative to simply forwarding HTTP. Encapsulation enables the load balancer to add information to the request without modifying the forwarded request itself. In particular, this means that the load balancer can communicate the source address even when forwarding an encrypted connection.

The HAProxy router can be configured to accept the PROXY protocol and decapsulate the HTTP request. Because the router terminates encryption for edge and re-encrypt routes, the router can then update the "Forwarded" HTTP header (and related HTTP headers) in the request, appending any source address that is communicated using the PROXY protocol.



#### WARNING

The PROXY protocol and HTTP are incompatible and cannot be mixed. If you use a load balancer in front of the router, both must use either the PROXY protocol or HTTP. Configuring one to use one protocol and the other to use the other protocol will cause routing to fail.

#### 4.4.3. Using the PROXY Protocol

By default, the HAProxy router does not use the PROXY protocol. The router can be configured using the `ROUTER_USE_PROXY_PROTOCOL` environment variable to expect the PROXY protocol for incoming connections:

##### Enable the PROXY Protocol

```
$ oc env dc/router ROUTER_USE_PROXY_PROTOCOL=true
```

Set the variable to any value other than `true` or `TRUE` to disable the PROXY protocol:

##### Disable the PROXY Protocol

```
$ oc env dc/router ROUTER_USE_PROXY_PROTOCOL=false
```

If you enable the PROXY protocol in the router, you must configure your load balancer in front of the router to use the PROXY protocol as well. Following is an example of configuring Amazon's Elastic Load Balancer (ELB) service to use the PROXY protocol. This example assumes that ELB is forwarding ports 80 (HTTP), 443 (HTTPS), and 5000 (for the image registry) to the router running on one or more EC2 instances.

##### Configure Amazon ELB to Use the PROXY Protocol

- To simplify subsequent steps, first set some shell variables:

```
$ lb='infra-lb' 1
$ instances=( 'i-079b4096c654f563c' ) 2
$ secgroups=( 'sg-e1760186' ) 3
$ subnets=( 'subnet-cf57c596' ) 4
```

- 1** The name of your ELB.
- 2** The instance or instances on which the router is running.
- 3** The security group or groups for this ELB.
- 4** The subnet or subnets for this ELB.

- Next, create the ELB with the appropriate listeners, security groups, and subnets.



### NOTE

You must configure all listeners to use the TCP protocol, not the HTTP protocol.

```
$ aws elb create-load-balancer --load-balancer-name "$lb" \
--listeners \
'Protocol=TCP,LoadBalancerPort=80,InstanceProtocol=TCP,InstancePort=
80' \
'Protocol=TCP,LoadBalancerPort=443,InstanceProtocol=TCP,InstancePort=
443' \
'Protocol=TCP,LoadBalancerPort=5000,InstanceProtocol=TCP,InstancePor
t=5000' \
--security-groups $secgroups \
--subnets $subnets
{
    "DNSName": "infra-lb-2006263232.us-east-1.elb.amazonaws.com"
}
```

- Register your router instance or instances with the ELB:

```
$ aws elb register-instances-with-load-balancer --load-balancer-name
"$lb" \
--instances $instances
{
    "Instances": [
        {
            "InstanceId": "i-079b4096c654f563c"
        }
    ]
}
```

- Configure the ELB's health check:

```
$ aws elb configure-health-check --load-balancer-name "$lb" \
    --health-check
'Target=HTTP:1936/healthz,Interval=30,UnhealthyThreshold=2,HealthyThreshold=2,Timeout=5'
{
    "HealthCheck": {
        "HealthyThreshold": 2,
        "Interval": 30,
        "Target": "HTTP:1936/healthz",
        "Timeout": 5,
        "UnhealthyThreshold": 2
    }
}
```

- Finally, create a load-balancer policy with the **ProxyProtocol** attribute enabled, and configure it on the ELB's TCP ports 80 and 443:

```
$ aws elb create-load-balancer-policy --load-balancer-name "$lb" \
    --policy-name "${lb}-ProxyProtocol-policy" \
    --policy-type-name 'ProxyProtocolPolicyType' \
    --policy-attributes
'AttributeName=ProxyProtocol,AttributeValue=true'
$ for port in 80 443
do
    aws elb set-load-balancer-policies-for-backend-server \
        --load-balancer-name "$lb" \
        --instance-port "$port" \
        --policy-names "${lb}-ProxyProtocol-policy"
done
```

## Verify the Configuration

You can examine the load balancer as follows to verify that the configuration is correct:

```
$ aws elb describe-load-balancers --load-balancer-name "$lb" | \
    jq '.LoadBalancerDescriptions| [ .[] ].ListenerDescriptions' [
    [
        {
            "Listener": {
                "InstancePort": 80,
                "LoadBalancerPort": 80,
                "Protocol": "TCP",
                "InstanceProtocol": "TCP"
            },
            "PolicyNames": ["infra-lb-ProxyProtocol-policy"] ①
        },
        {
            "Listener": {
                "InstancePort": 443,
                "LoadBalancerPort": 443,
                "Protocol": "TCP",
                "InstanceProtocol": "TCP"
            },
            "PolicyNames": ["infra-lb-ProxyProtocol-policy"] ②
        }
    ]
]
```

```

},
{
  "Listener": {
    "InstancePort": 5000,
    "LoadBalancerPort": 5000,
    "Protocol": "TCP",
    "InstanceProtocol": "TCP"
  },
  "PolicyNames": []
}
]
]
]

```

- 1 The listener for TCP port 80 should have the policy for using the PROXY protocol.
- 2 The listener for TCP port 443 should have the same policy.
- 3 The listener for TCP port 5000 should **not** have the policy.

Alternatively, if you already have an ELB configured, but it is not configured to use the PROXY protocol, you will need to change the existing listener for TCP port 80 to use the TCP protocol instead of HTTP (TCP port 443 should already be using the TCP protocol):

```

$ aws elb delete-load-balancer-listeners --load-balancer-name "$lb" \
--load-balancer-ports 80
$ aws elb create-load-balancer-listeners --load-balancer-name "$lb" \
--listeners
'Protocol=TCP,LoadBalancerPort=80,InstanceProtocol=TCP,InstancePort=80'

```

## Verify the Protocol Updates

Verify that the protocol has been updated as follows:

```

$ aws elb describe-load-balancers --load-balancer-name "$lb" |
  jq '[.LoadBalancerDescriptions[]].ListenerDescriptions'
[
  [
    {
      "Listener": {
        "InstancePort": 443,
        "LoadBalancerPort": 443,
        "Protocol": "TCP",
        "InstanceProtocol": "TCP"
      },
      "PolicyNames": []
    },
    {
      "Listener": {
        "InstancePort": 5000,
        "LoadBalancerPort": 5000,
        "Protocol": "TCP",
        "InstanceProtocol": "TCP"
      },
      "PolicyNames": []
    }
  ]
]
```

```
{
  "Listener": {
    "InstancePort": 80,
    "LoadBalancerPort": 80,
    "Protocol": "TCP", ①
    "InstanceProtocol": "TCP"
  },
  "PolicyNames": []
}
]
```

- ①** All listeners, including the listener for TCP port 80, should be using the TCP protocol.

Then, create a load-balancer policy and add it to the ELB as described in Step 5 above.

## 4.5. USING THE F5 ROUTER PLUG-IN

### 4.5.1. Overview



#### NOTE

The F5 router plug-in is available starting in OpenShift Container Platform 3.0.2.

The F5 router plug-in is provided as a container image and run as a pod, just like the [default HAProxy router](#).



#### IMPORTANT

Support relationships between F5 and Red Hat provide a full scope of support for F5 integration. F5 provides support for the **F5 BIG-IP®** product. Both F5 and Red Hat jointly support the integration with Red Hat OpenShift. While Red Hat helps with bug fixes and feature enhancements, all get communicated to F5 Networks where they are managed as part of their development cycles.

### 4.5.2. Prerequisites and Supportability

When deploying the F5 router plug-in, ensure you meet the following requirements:

- A F5 host IP with:
  - Credentials for API access
  - SSH access via a private key
- An F5 user with Advanced Shell access
- A virtual server for HTTP routes:
  - *HTTP profile* must be *http*.
- A virtual server with HTTP profile routes:

- *HTTP profile* must be *http*
- *SSL Profile (client)* must be *clientssl*
- *SSL Profile (server)* must be *serverssl*
- For edge integration (not recommended):
  - A working ramp node
  - A working tunnel to the ramp node
- For native integration:
  - A host-internal IP capable of communicating with all nodes on the port 4789/UDP
  - The sdn-services add-on license installed on the F5 host.

OpenShift Container Platform supports only the following **F5 BIG-IP®** versions:

- 11.x
- 12.x

## IMPORTANT

The following features are not supported with **F5 BIG-IP®**:

- Wildcard routes together with re-encrypt routes - you must supply a certificate and a key in the route. If you provide a certificate, a key, and a certificate authority (CA), the CA is never used.
- A pool is created for all services, even for the ones with no associated route.
- [Idling applications](#)
- Unencrypted HTTP traffic in *redirect* mode, with edge TLS termination. (**insecureEdgeTerminationPolicy: Redirect**)
- Sharding, that is, having multiple **vservers** on the F5.
- SSL cipher (**ROUTER\_CIPHERS=modern/old**)
- Customizing the endpoint health checks for time-intervals and the type of checks.
- Serving F5 metrics by using a metrics server.
- Specifying a different target port (**PreferPort/TargetPort**) rather than the ones specified in the service.
- Customizing the source IP whitelists, that is, allowing traffic for a route only from specific IP addresses.
- Customizing timeout values, such as **max connect time**, or **tcp FIN timeout**.
- HA mode for the **F5 BIG-IP®**.

#### 4.5.2.1. Configuring the Virtual Servers

As a prerequisite to working with the **openshift-F5** integrated router, two virtual servers (one virtual server each for HTTP and HTTPS profiles, respectively) need to be set up in the **F5 BIG-IP®** appliance.

To set up a virtual server in the **F5 BIG-IP®** appliance, follow the [instructions from F5](#).

While creating the virtual server, ensure the following settings are in place:

- For the HTTP server, set the **ServicePort** to '**http' /80**'.
- For the HTTPS server, set the **ServicePort** to '**https' /443**'.
- In the basic configuration, set the HTTP profile to **/Common/http** for both of the virtual servers.
- For the HTTPS server, create a default **client-ssl** profile and select it for the **SSL Profile (Client)**.
  - To create the default client SSL profile, follow the [instructions from F5](#), especially the **Configuring the fallback (default) client SSL profile** section, which discusses that the certificate/key pair is the default that will be served in the case that custom certificates are not provided for a route or server name.

#### 4.5.3. Deploying the F5 Router



##### IMPORTANT

The F5 router must be run in privileged mode, because route certificates are copied using the **scp** command:

```
$ oc adm policy remove-scc-from-user hostnetwork -z router
$ oc adm policy add-scc-to-user privileged -z router
```

Deploy the F5 router with the **oc adm router** command, but provide additional flags (or environment variables) specifying the following parameters for the **F5 BIG-IP®** host:

| Flag                            | Description                                                                                                                                                                   |
|---------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>--type=f5-router</b>         | Specifies that an F5 router should be launched (the default <b>--type</b> is <b>haproxy-router</b> ).                                                                         |
| <b>--external-host</b>          | Specifies the <b>F5 BIG-IP®</b> host's management interface's host name or IP address.                                                                                        |
| <b>--external-host-username</b> | Specifies the <b>F5 BIG-IP®</b> user name (typically <b>admin</b> ). The <b>F5 BIG-IP</b> user account must have access to the Advanced Shell (Bash) on the F5 BIG-IP system. |
| <b>--external-host-password</b> | Specifies the <b>F5 BIG-IP®</b> password.                                                                                                                                     |

| Flag                           | Description                                                                                                                                        |
|--------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| --external-host-http-vserver   | Specifies the name of the F5 virtual server for HTTP connections. This must be configured by the user prior to launching the router pod.           |
| --external-host-https-vserver  | Specifies the name of the F5 virtual server for HTTPS connections. This must be configured by the user prior to launching the router pod.          |
| --external-host-private-key    | Specifies the path to the SSH private key file for the <b>F5 BIG-IP®</b> host. Required to upload and delete key and certificate files for routes. |
| --external-host-insecure       | A Boolean flag that indicates that the F5 router should skip strict certificate verification with the <b>F5 BIG-IP®</b> host.                      |
| --external-host-partition-path | Specifies the <b>F5 BIG-IP®</b> partition path (the default is <b>/Common</b> ).                                                                   |

For example:

```
$ oc adm router \
  --type=f5-router \
  --external-host=10.0.0.2 \
  --external-host-username=admin \
  --external-host-password=mypassword \
  --external-host-http-vserver=ose-vserver \
  --external-host-https-vserver=https-ose-vserver \
  --external-host-private-key=/path/to/key \
  --host-network=false \
  --service-account=router
```

As with the HAProxy router, the **oc adm router** command creates the service and deployment configuration objects, and thus the replication controllers and pod(s) in which the F5 router itself runs. The replication controller restarts the F5 router in case of crashes. Because the F5 router is watching routes, endpoints, and nodes and configuring **F5 BIG-IP®** accordingly, running the F5 router in this way, along with an appropriately configured **F5 BIG-IP®** deployment, should satisfy high-availability requirements.

#### 4.5.4. F5 Router Partition Paths

Partition paths allow you to store your OpenShift Container Platform routing configuration in a custom **F5 BIG-IP®** administrative partition, instead of the default **/Common** partition. You can use custom administrative partitions to secure **F5 BIG-IP®** environments. This means that an OpenShift Container Platform-specific configuration stored in **F5 BIG-IP®** system objects reside within a logical container, allowing administrators to define access control policies on that specific administrative partition.

See the [F5 BIG-IP® documentation](#) for more information about administrative partitions.

To configure your OpenShift Container Platform for partition paths:

1. Optionally, perform some cleaning steps:
  - a. Ensure F5 is configured to be able to switch to the **/Common** and **/Custom** paths.
  - b. Delete the static FDB of **vxlan5000**. See the [F5 BIG-IP® documentation](#) for more information.
2. [Configure a virtual server](#) for the custom partition.
3. Deploy the F5 router using the **--external-host-partition-path** flag to specify a partition path:

```
$ oc adm router --external-host-partition-path=/OpenShift/zone1 ...
```

#### 4.5.5. Setting Up F5 Native Integration



##### NOTE

This section reviews how to set up F5 native integration with OpenShift Container Platform. The concepts of F5 appliance and OpenShift Container Platform connection and data flow of F5 native integration are discussed in the [F5 Native Integration](#) section of the Routes topic.



##### NOTE

Only **F5 BIG-IP®** appliance version 12.x and above works with the native integration presented in this section. You also need sdn-services add-on license for the integration to work properly. For version 11.x, follow the instructions to set up a *ramp node*.

As of OpenShift Container Platform version 3.4, using native integration of F5 with OpenShift Container Platform does not require configuring a ramp node for F5 to be able to reach the pods on the overlay network as created by OpenShift SDN.

The F5 controller pod needs to be launched with enough information so that it can successfully directly connect to pods.

1. Create a ghost **hostsubnet** on the OpenShift Container Platform cluster:

```
$ cat > f5-hostsubnet.yaml << EOF
{
  "kind": "HostSubnet",
  "apiVersion": "v1",
  "metadata": {
    "name": "openshift-f5-node",
    "annotations": {
      "pod.network.openshift.io/assign-subnet": "true",
      "pod.network.openshift.io/fixed-vnid-host": "0" ①
    }
  },
  "host": "openshift-f5-node",
```

```

    "hostIP": "10.3.89.213" 2
} EOF
$ oc create -f f5-hostsubnet.yaml

```

- 1** Make F5 global.
- 2** The internal IP of the F5 appliance.

2. Determine the subnet allocated for the ghost **hostsubnet** just created:

```

$ oc get hostsubnets
NAME          HOST          HOST IP
SUBNET
openshift-f5-node  openshift-f5-node  10.3.89.213
10.131.0.0/23
openshift-master-node  openshift-master-node  172.17.0.2
10.129.0.0/23
openshift-node-1  openshift-node-1  172.17.0.3
10.128.0.0/23
openshift-node-2  openshift-node-2  172.17.0.4
10.130.0.0/23

```

3. Check the **SUBNET** for the newly created **hostsubnet**. In this example, **10.131.0.0/23**.

4. Get the entire pod network's CIDR:

```
$ oc get clusternetwork
```

This value will be something like **10.128.0.0/14**, noting the mask (**14** in this example).

5. To construct the gateway address, pick any IP address from the **hostsubnet** (for example, **10.131.0.5**). Use the mask of the pod network (**14**). The gateway address becomes: **10.131.0.5/14**.
6. Launch the F5 controller pod, following [these instructions](#). Additionally, allow the access to 'node' cluster resource for the service account and use the two new additional options for VXLAN native integration.

```

$ # Add policy to allow router to access nodes using the sdn-reader
role
$ oc adm policy add-cluster-role-to-user system:sdn-reader
system:serviceaccount:default:router
$ # Launch the router pod with vxlan-gw and F5's internal IP as
extra arguments
$ --external-host-internal-ip=10.3.89.213
$ --external-host-vxlan-gw=10.131.0.5/14
$ oc adm router \
  --type=f5-router \
  --external-host=10.3.89.90 \
  --external-host-username=admin \
  --external-host-password=mypassword \
  --external-host-http-vserver=ose-vserver \
  --external-host-https-vserver=https-ose-vserver \
  --external-host-private-key=/path/to/key \

```

```
--service-account=router \
--host-network=false \
--external-host-internal-ip=10.3.89.213 \
--external-host-vxlan-gw=10.131.0.5/14
```



### NOTE

The **external-host-username** is a **F5 BIG-IP** user account with access to the Advanced Shell (Bash) on the F5 BIG-IP system.


The F5 setup is now ready, without the need to set up the ramp node.

# CHAPTER 5. DEPLOYING RED HAT CLOUDFORMS

## 5.1. DEPLOYING {MGMT-APP} ON OPENSIFT CONTAINER PLATFORM

### 5.1.1. Introduction

The OpenShift Container Platform installer includes the Ansible role **openshift-management** and playbooks for deploying Red Hat CloudForms 4.6 (CloudForms Management Engine 5.9, or CFME) on OpenShift Container Platform.



When deploying Red Hat CloudForms on OpenShift Container Platform, there are two major decisions to make:

1. Do you want an external or a containerized (also referred to as *podified*) PostgreSQL database?
2. Which storage class will back your persistent volumes (PVs)?

For the first decision, you can deploy Red Hat CloudForms in one of two ways, depending on the location of the PostgreSQL database to be used by Red Hat CloudForms:

| Deployment Variant  | Description                                                                                                                                         |
|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| Fully containerized | All application services and the PostgreSQL database are run as pods on OpenShift Container Platform.                                               |
| External database   | The application utilizes an externally-hosted PostgreSQL database server, while all other services are ran as pods on OpenShift Container Platform. |

For the second decision, the **openshift-management** role provides customization options for overriding many default deployment parameters. This includes the following storage class options to back your PVs:


| Storage Class | Description                                  |
|---------------|----------------------------------------------|
| NFS (default) | Local, on cluster                            |
| NFS External  | NFS somewhere else, like a storage appliance |

| Storage Class            | Description                                                              |
|--------------------------|--------------------------------------------------------------------------|
| Cloud Provider           | Use automatic storage provisioning from your cloud provider (GCE or AWS) |
| Preconfigured (advanced) | Assumes you created everything ahead of time                             |

Topics in this guide include the requirements for running Red Hat CloudForms on OpenShift Container Platform, descriptions of the available configuration variables, and instructions on running the installer either during your initial OpenShift Container Platform installation or after your cluster has been provisioned.

## 5.2. REQUIREMENTS FOR RED HAT CLOUDFORMS ON OPENSHIFT CONTAINER PLATFORM

The default requirements are listed in the table below. These can be overridden by [customizing template parameters](#).



### IMPORTANT

The application performance will suffer, or possibly even fail to deploy, if these requirements are not satisfied.

**Table 5.1. Default Requirements**

| Item                | Requirement            | Description                                  | Customization Parameter            |
|---------------------|------------------------|----------------------------------------------|------------------------------------|
| Application Memory  | $\geq 4.0 \text{ Gi}$  | Minimum required memory for the application  | <b>APPLICATION_MEM_REQ</b>         |
| Application Storage | $\geq 5.0 \text{ Gi}$  | Minimum PV size required for the application | <b>APPLICATION_VOLUME_CAPACITY</b> |
| PostgreSQL Memory   | $\geq 6.0 \text{ Gi}$  | Minimum required memory for the database     | <b>POSTGRESQL_MEM REQ</b>          |
| PostgreSQL Storage  | $\geq 15.0 \text{ Gi}$ | Minimum PV size required for the database    | <b>DATABASE_VOLUME_CAPACITY</b>    |
| Cluster Hosts       | $\geq 3$               | Number of hosts in your cluster              | N/A                                |

To sum up these requirements:

- You must have several cluster nodes.
- Your cluster nodes must have lots of memory available.
- You must have several GiB's of storage available, either locally or on your cloud provider.
- PV sizes can be changed by providing override values to template parameters.

## 5.3. CONFIGURING ROLE VARIABLES

### 5.3.1. Overview

The following sections describe role variables that may be used in your [Ansible inventory file](#), which is used to control the behavior of the Red Hat CloudForms installation when [running the installer](#).

### 5.3.2. General Variables

| Variable                                              | Required | Default                                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|-------------------------------------------------------|----------|-------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_management_install_management</code>  | No       | <code>false</code>                        | Boolean, set to <code>true</code> to install the application.                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <code>openshift_management_install_beta</code>        | Yes      | <code>false</code>                        | CFME 4.6 is currently available (not in beta), however this variable must be set to <code>true</code> to begin the installation. This requirement will be removed in an upcoming release. ( <a href="#">BZ#1557909</a> )                                                                                                                                                                                                                                                      |
| <code>openshift_management_app_template</code>        | Yes      | <code>miq-template</code>                 | The deployment variant of Red Hat CloudForms to install. Currently, you must change it from the default <code>miq-template</code> , otherwise the upstream ManageIQ application will be installed instead of Red Hat CloudForms. This default will be changed to <code>cfme-template</code> in an upcoming release. ( <a href="#">BZ#1557909</a> ) Set <code>cfme-template</code> for a containerized database or <code>cfme-template-ext-db</code> for an external database. |
| <code>openshift_management_project</code>             | No       | <code>openshift-management</code>         | Namespace (project) for the Red Hat CloudForms installation.                                                                                                                                                                                                                                                                                                                                                                                                                  |
| <code>openshift_management_project_description</code> | No       | <code>CloudForms Management Engine</code> | Namespace (project) description.                                                                                                                                                                                                                                                                                                                                                                                                                                              |

| Variable                                    | Required | Default              | Description                                                                                                                                                                                                                                          |
|---------------------------------------------|----------|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_management_use_rname</code> | No       | <code>admin</code>   | Default management user name. Changing this value does not change the user name; only change this value if you have changed the name already and are running integration scripts (such as the script to <a href="#">add container providers</a> ).   |
| <code>openshift_management_password</code>  | No       | <code>smartvm</code> | Default management password. Changing this value does not change the password; only change this value if you have changed the password already and are running integration scripts (such as the script to <a href="#">add container providers</a> ). |

### 5.3.3. Customizing Template Parameters

You can use the `openshift_management_template_parameters` Ansible role variable to specify any template parameters you want to override in the application or PV templates.

For example, if you wanted to reduce the memory requirement of the PostgreSQL pod, then you could set the following:

```
openshift_management_template_parameters={'POSTGRESQL_MEM_REQ': '1Gi'}
```

When the Red Hat CloudForms template is processed, **1Gi** will be used for the value of the `POSTGRESQL_MEM_REQ` template parameter.

Not all template parameters are present in *both* template variants (containerized or external database). For example, while the podified database template has a `POSTGRESQL_MEM_REQ` parameter, no such parameter is present in the external db template, as there is no need for this information due to there being no databases that require pods.

Therefore, be very careful if you are overriding template parameters. Including parameters not defined in a template will cause errors. If you do receive an error during the **Ensure the Management App is created** task, run the [uninstall scripts](#) first before running the installer again.

### 5.3.4. Database Variables

#### 5.3.4.1. Containerized (Podified) Database

Any `POSTGRES_*` or `DATABASE_*` template parameters in the `cfme-template.yaml` file may be customized through the `openshift_management_template_parameters` hash in your inventory file..

#### 5.3.4.2. External Database

Any `POSTGRES_*` or `DATABASE_*` template parameters in the `cfme-template-ext-db.yaml` file may be customized through the `openshift_management_template_parameters` hash in your inventory file..

External PostgreSQL databases require you to provide database connection parameters. You must set the required connection keys in the `openshift_management_template_parameters` parameter in your inventory. The following keys are required:

- **DATABASE\_USER**
- **DATABASE\_PASSWORD**
- **DATABASE\_IP**
- **DATABASE\_PORT** (Most PostgreSQL servers run on port **5432**)
- **DATABASE\_NAME**

**NOTE**

Ensure your external database is running PostgreSQL 9.5 or you may not be able to deploy the CloudForms application successfully.

Your inventory would contain a line similar to:

```
[OSEv3:vars]
openshift_management_app_template=cfme-template-ext-db 1
openshift_management_template_parameters={'DATABASE_USER': 'root',
'DATABASE_PASSWORD': 'mypassword', 'DATABASE_IP': '10.10.10.10',
'DATABASE_PORT': '5432', 'DATABASE_NAME': 'cfme'}
```

- 1** Set **openshift\_management\_app\_template** parameter to **cfme-template-ext-db**.

### 5.3.5. Storage Class Variables

| Variable                                                  | Required | Default      | Description                                                                                                                                                                                                                                                                                                         |
|-----------------------------------------------------------|----------|--------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>openshift_management_storage_classes</b>               | No       | <b>nfs</b>   | Storage type to use. Options are <b>nfs</b> , <b>nfs_external</b> , <b>preconfigured</b> , or <b>cloudprovider</b> .                                                                                                                                                                                                |
| <b>openshift_management_storage_nfs_external_hostname</b> | No       | <b>false</b> | If you are using an external NFS server, such as a NetApp appliance, then you must set the host name here. Leave the value as <b>false</b> if you are not using external NFS. Additionally, external NFS requires that you create the NFS exports that will back the application PV and optionally the database PV. |

| Variable                                                     | Required | Default                | Description                                                                                                                                                                                                                                                                      |
|--------------------------------------------------------------|----------|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_management_storage_nfs_base_dir</code>       | No       | <code>/exports/</code> | If you are using external NFS, then you can set the base path to the exports location here. For local NFS, you can also change this value if you want to change the default path used for local NFS exports.                                                                     |
| <code>openshift_management_storage_nfs_local_hostname</code> | No       | <code>false</code>     | If you do not have an <code>[nfs]</code> group in your inventory, or want to simply manually define the local NFS host in your cluster, set this parameter to the host name of the preferred NFS server. The server must be a part of your OpenShift Container Platform cluster. |

### 5.3.5.1. NFS (Default)

The NFS storage class is best suited for proof-of-concept and test deployments. It is also the default storage class for deployments. No additional configuration is required for this choice.

This storage class configures NFS on a cluster host (by default, the first master in the inventory file) to back the required PVs. The application requires a PV, and the database (which may be hosted externally) may require a second. PV minimum required sizes are 5GiB for the Red Hat CloudForms application, and 15GiB for the PostgreSQL database (20GiB minimum available space on a volume or partition if used specifically for NFS purposes).

Customization is provided through the following role variables:

- `openshift_management_storage_nfs_base_dir`
- `openshift_management_storage_nfs_local_hostname`

### 5.3.5.2. NFS External

External NFS leans on pre-configured NFS servers to provide exports for the required PVs. For external NFS you must have a `cfme-app` and optionally a `cfme-db` (for containerized database) exports.

Configuration is provided through the following role variables:

- `openshift_management_storage_nfs_external_hostname`
- `openshift_management_storage_nfs_base_dir`

The `openshift_management_storage_nfs_external_hostname` parameter must be set to the host name or IP of your external NFS server.

If `/exports` is not the parent directory to your exports then you must set the base directory via the `openshift_management_storage_nfs_base_dir` parameter.

For example, if your server export is `/exports/hosted/prod/cfme-app`, then you must set `openshift_management_storage_nfs_base_dir=/exports/hosted/prod`.

### 5.3.5.3. Cloud Provider

If you are using OpenShift Container Platform cloud provider integration for your storage class, Red Hat CloudForms can also use the cloud provider storage to back its required PVs. For this functionality to work, you must have configured the `openshift_cloudprovider_kind` variable (for AWS or GCE) and all associated parameters specific to your chosen cloud provider.

When the application is created using this storage class, the required PVs are automatically provisioned using the configured cloud provider storage integration.

There are no additional variables to configure the behavior of this storage class.

### 5.3.5.4. Preconfigured (Advanced)

The `preconfigured` storage class implies that you know exactly what you are doing and that all storage requirements have been taken care ahead of time. Typically this means that you have already created the correctly sized PVs. The installer will do nothing to modify any storage settings.

There are no additional variables to configure the behavior of this storage class.

## 5.4. RUNNING THE INSTALLER

### 5.4.1. Deploying Red Hat CloudForms During or After OpenShift Container Platform Installation

You can choose to deploy Red Hat CloudForms either during initial OpenShift Container Platform installation or after the cluster has been provisioned:

1. Ensure the following are set in your inventory file under the `[OSEv3:vars]` section:

```
[OSEv3:vars]
openshift_management_install_management=true
openshift_management_install_beta=true ①
```

- ① CFME 4.6 is currently available (not in beta), however this variable must be set to `true` to begin the installation. This requirement will be removed in an upcoming release.  
[\(BZ#1557909\)](#)

2. Set any other Red Hat CloudForms role variables in your inventory file as described in [Configuring Role Variables](#). Resources to assist in this are provided in [Example Inventory Files](#).
3. Choose which playbook to run depending on whether OpenShift Container Platform is already provisioned:

- a. If you want to install Red Hat CloudForms at the same time you install your OpenShift Container Platform cluster, call the standard ***config.yml*** playbook as described in [Running the Advanced Installation](#) to begin the OpenShift Container Platform cluster and Red Hat CloudForms installation.
- b. If you want to install Red Hat CloudForms on an already provisioned OpenShift Container Platform cluster, call the Red Hat CloudForms playbook directly to begin the installation:

```
# ansible-playbook -v [-i /path/to/inventory] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    management/config.yml
```

## 5.4.2. Example Inventory Files

The following sections show example snippets of inventory files showing various configurations of Red Hat CloudForms on OpenShift Container Platform that can help you get started.



### NOTE

See [Configuring Role Variables](#) for complete variable descriptions.

### 5.4.2.1. All Defaults

This example is the simplest, using all of the default values and choices. This results in a fully-containerized (podified) Red Hat CloudForms installation. All application components, as well as the PostgreSQL database, are created as pods in OpenShift Container Platform:

```
[OSEv3:vars]
openshift_management_app_template=cfme-template
```

### 5.4.2.2. External NFS Storage

This is as the previous example, except that instead of using local NFS services in the cluster, it uses an existing, external NFS server (such as a storage appliance). Note the two new parameters:

```
[OSEv3:vars]
openshift_management_app_template=cfme-template
openshift_management_storage_class=nfs_external ①
openshift_management_storage_nfs_external_hostname=nfs.example.com ②
```

① Set to **nfs\_external**.

② Set to the host name of the NFS server.

If the external NFS host exports directories under a different parent directory, such as **/exports/hosted/prod**, add the following additional variable:

```
openshift_management_storage_nfs_base_dir=/exports/hosted/prod
```

### 5.4.2.3. Override PV Sizes

This example overrides the persistent volume (PV) sizes. PV sizes must be set via `openshift_management_template_parameters`, which ensures that the application and database are able to make claims on created PVs without interfering with each other:

```
[OSEv3:vars]
openshift_management_app_template=cfme-template
openshift_management_template_parameters={'APPLICATION_VOLUME_CAPACITY': '10Gi', 'DATABASE_VOLUME_CAPACITY': '25Gi'}
```

#### 5.4.2.4. Override Memory Requirements

In a test or proof-of-concept installation, you may need to reduce the application and database memory requirements to fit within your capacity. Note that reducing memory limits can result in reduced performance or a complete failure to initialize the application:

```
[OSEv3:vars]
openshift_management_app_template=cfme-template
openshift_management_template_parameters={'APPLICATION_MEM_REQ': '3000Mi', 'POSTGRESQL_MEM_REQ': '1Gi', 'ANSIBLE_MEM_REQ': '512Mi'}
```

This example instructs the installer to process the application template with the parameter `APPLICATION_MEM_REQ` set to **3000Mi**, `POSTGRESQL_MEM_REQ` set to **1Gi**, and `ANSIBLE_MEM_REQ` set to **512Mi**.

These parameters can be combined with the parameters displayed in the previous example [Override PV Sizes](#).

#### 5.4.2.5. External PostgreSQL Database

To use an external database, you must change the `openshift_management_app_template` parameter value to `cfme-template-ext-db`.

Additionally, database connection information must be supplied using the `openshift_management_template_parameters` variable. See [Configuring Role Variables](#) for more details.

```
[OSEv3:vars]
openshift_management_app_template=cfme-template-ext-db
openshift_management_template_parameters={'DATABASE_USER': 'root', 'DATABASE_PASSWORD': 'mypassword', 'DATABASE_IP': '10.10.10.10', 'DATABASE_PORT': '5432', 'DATABASE_NAME': 'cfme'}
```



#### IMPORTANT

Ensure you are running PostgreSQL 9.5 or you may not be able to deploy the application successfully.

## 5.5. ENABLING CONTAINER PROVIDER INTEGRATION

### 5.5.1. Adding a Single Container Provider

After deploying Red Hat CloudForms on OpenShift Container Platform as described in [Running the](#)

[Installer](#), there are two methods for enabling container provider integration. You can manually add OpenShift Container Platform as a container provider, or you can try the playbooks included with this role.

### 5.5.1.1. Adding Manually

See the following Red Hat CloudForms documentation for steps on manually adding your OpenShift Container Platform cluster as a container provider:

- [Integration with OpenShift Container Platform](#)

### 5.5.1.2. Adding Automatically

Automated container provider integration can be accomplished using the playbooks included with this role.

This playbook:

1. Gathers the necessary authentication secrets.
2. Finds the public routes to the Red Hat CloudForms application and the cluster API.
3. Makes a REST call to add the OpenShift Container Platform cluster as a container provider.

To run the container provider playbook:

```
# ansible-playbook -v [-i /path/to/inventory] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    management/add_container_provider.yml
```

## 5.5.2. Multiple Container Providers

As well as providing playbooks to integrate your current OpenShift Container Platform cluster into your Red Hat CloudForms deployment, this role includes a script which allows you to add multiple container platforms as container providers in any arbitrary Red Hat CloudForms server. The container platforms can be OpenShift Container Platform or OpenShift Origin.

Using the multiple provider script requires manual configuration and setting an **EXTRA\_VARS** parameter on the CLI when running the playbook.

### 5.5.2.1. Preparing the Script

To prepare the multiple provider script, complete the following manual configuration:

1. Copy the **/usr/share/ansible/openshift-ansible/roles/openshift\_management/files/examples/container\_providers.yml** example somewhere, such as **/tmp/cp.yml**. You will be modifying this file.
2. If you changed your Red Hat CloudForms name or password, update the **hostname**, **user**, and **password** parameters in the **management\_server** key in the **container\_providers.yml** file that you copied.
3. Fill in an entry under the **container\_providers** key for each container platform cluster you want to add as container providers.

- The following parameters must be configured:

- **auth\_key** - This is the token of a service account that has **cluster-admin** privileges.
- **hostname** - This is the host name that points to the cluster API. Each container provider must have a unique host name.
- **name** - This is the name of the cluster to be displayed in the Red Hat CloudForms server container providers overview page. This must be unique.

## TIP

To obtain the **auth\_key** bearer token from your clusters:

```
$ oc serviceaccounts get-token -n management-infra management-admin
```

- The following parameters may be optionally configured:

- **port** - Update this key if your container platform cluster runs the API on a port other than **8443**.
- **endpoint** - You may enable SSL verification (**verify\_ssl**) or change the validation setting to **ssl-with-validation**. Support for custom trusted CA certificates is not currently available.

### 5.5.2.1.1. Example

As an example, consider the following scenario:

- You copied the **container\_providers.yml** file to **/tmp/cp.yml**.
- You want to add two OpenShift Container Platform clusters.
- Your Red Hat CloudForms server runs on **mgmt.example.com**

For this scenario, you would customize **/tmp/cp.yml** as follows:

```
container_providers:
  - connection_configurations:
      - authentication: {auth_key: "<token>", authtype: bearer, type: AuthToken} ①
        endpoint: {role: default, security_protocol: ssl-without-validation, verify_ssl: 0}
        hostname: "<provider_hostname1>"
        name: <display_name1>
        port: 8443
        type: "ManageIQ::Providers::Openshift::ContainerManager"
  - connection_configurations:
      - authentication: {auth_key: "<token>", authtype: bearer, type: AuthToken} ②
        endpoint: {role: default, security_protocol: ssl-without-validation, verify_ssl: 0}
        hostname: "<provider_hostname2>"
```

```

name: <display_name2>
port: 8443
type: "ManageIQ::Providers::Openshift::ContainerManager"
management_server:
  hostname: "<hostname>"
  user: <user_name>
  password: <password>

```

- 1** **2** Replace <token> with the management token for this cluster.

### 5.5.2.2. Running the Playbook

To run the multiple-providers integration script, you must provide the path to the container providers configuration file as an **EXTRA\_VARS** parameter to the **ansible-playbook** command. Use the **-e** (or **--extra-vars**) parameter to set **container\_providers\_config** to the configuration file path:

```

# ansible-playbook -v [-i /path/to/inventory] \
-e container_providers_config=/tmp/cp.yml \
/usr/share/ansible/openshift-ansible/playbooks/openshift-
management/add_many_container_providers.yml

```

After the playbook completes, you should find two new container providers in your Red Hat CloudForms service. Navigate to the **Compute** → **Containers** → **Providers** page to see an overview.

### 5.5.3. Refreshing Providers

After adding either a single or multiple container providers, the new provider(s) must be refreshed in Red Hat CloudForms to get all the latest data about the container provider and the containers being managed. This involves navigating to each provider in the Red Hat CloudForms web console and clicking a refresh button for each.

See the following Red Hat CloudForms documentation for steps:

- [Managing Providers](#)

## 5.6. UNINSTALLING RED HAT CLOUDFORMS

### 5.6.1. Running the Uninstall Playbook

To uninstall and erase a deployed Red Hat CloudForms installation from OpenShift Container Platform, run the following playbook:

```

# ansible-playbook -v [-i /path/to/inventory] \
/usr/share/ansible/openshift-ansible/playbooks/openshift-
management/uninstall.yml

```



#### IMPORTANT

NFS export definitions and data stored on NFS exports are not automatically removed. You are urged to manually erase any data from old application or database deployments before attempting to initialize a new deployment.

## 5.6.2. Troubleshooting

Failure to erase old PostgreSQL data can result in cascading errors, causing the **postgresql** pod to enter a **crashloopbackoff** state. This blocks the **cfme** pod from ever starting. The cause of the **crashloopbackoff** is due to incorrect file permissions on the database NFS export created during a previous deployment.

To continue, erase all data from the PostgreSQL export and delete the pod (not the deployer pod). For example, if you had the following pods:

```
$ oc get pods
NAME          READY   STATUS    RESTARTS   AGE
httpd-1-cx7fk 1/1     Running   1          21h
cfme-0         0/1     Running   1          21h
memcached-1-vkc7p 1/1     Running   1          21h
postgresql-1-deploy 1/1     Running   1          21h
postgresql-1-6w2t4 0/1     CrashLoopBackOff 1          21h
```

Then you would:

1. Erase the data from the database NFS export.
2. Run:

```
$ oc delete postgresql-1-6w2t4
```

The PostgreSQL deployer pod will try to scale up a new **postgresql** pod to replace the one you deleted. After the **postgresql** pod is running, the **cfme** pod will stop blocking and begin application initialization.

# CHAPTER 6. MASTER AND NODE CONFIGURATION

The `openshift start` command and its subcommands (`master` to launch a `master server` and `node` to launch a `node server`) take a limited set of arguments that are sufficient for launching servers in a development or experimental environment.

However, these arguments are insufficient to describe and control the full set of configuration and security options that are necessary in a production environment. To provide those options, it is necessary to use the master and node configuration files:

- Master host files at [`/etc/origin/master/master-config.yaml`](#)
- Node host files at [`/etc/origin/node/node-config.yaml`](#)

These files define options including overriding the default plug-ins, connecting to etcd, automatically creating service accounts, building image names, customizing project requests, configuring volume plug-ins, and much more.

This topic covers the available options for customizing your OpenShift Container Platform master and node hosts, and shows you how to make changes to the configuration after installation.

These files are fully specified with no default values. Therefore, an empty value indicates that you want to start up with an empty value for that parameter. This makes it easy to reason about exactly what your configuration is, but it also makes it difficult to remember all of the options to specify. To make this easier, the configuration files can be created with the `--write-config` option and then used with the `--config` option.

## 6.1. INSTALLATION DEPENDENCIES

For testing environments deployed via the [quick install](#) tool, one master should be sufficient. The quick installation method should not be used for production environments.

Production environments should be installed using the [advanced install](#). In production environments, it is a good idea to use [multiple masters](#) for the purposes of [high availability](#) (HA). A cluster architecture of three masters is recommended, and [HAproxy](#) is the recommended solution for this.

### CAUTION

If etcd is installed on the *master hosts*, you must configure your cluster to use at least three masters, because etcd would not be able to decide which one is authoritative. The only way to successfully run only two masters is if you install etcd on hosts other than the masters.

## 6.2. CONFIGURING MASTERS AND NODES

The method you use to configure your master and node configuration files must match the method that was used to install your OpenShift Container Platform cluster. If you followed the:

- [Advanced installation](#) method using Ansible, then make your configuration changes in the Ansible playbook.
- [Quick installation](#) method, then make your changes [manually in the configuration files](#) themselves.

## 6.3. MAKING CONFIGURATION CHANGES USING ANSIBLE

For this section, familiarity with Ansible is assumed.

Only a portion of the available host configuration options are [exposed to Ansible](#). After an OpenShift Container Platform install, Ansible creates an inventory file with some substituted values. Modifying this inventory file and re-running the Ansible installer playbook is how you customize your OpenShift Container Platform cluster.

While OpenShift Container Platform supports using Ansible as the advanced install method, using an Ansible playbook and inventory file, you can also use other management tools, such as [Puppet](#), [Chef](#), [Salt](#).

### Use Case: Configuring the cluster to use HTPasswd authentication



#### NOTE

- This use case assumes you have already set up [SSH keys](#) to all the nodes referenced in the playbook.
- The **htpasswd** utility is in the **httpd-tools** package:

```
# yum install httpd-tools
```

To modify the Ansible inventory and make configuration changes:

1. Open the **./hosts** inventory file:

#### Example 6.1. Sample inventory file:

```
[OSEv3:children]
masters
nodes

[OSEv3:vars]
ansible_ssh_user=cloud-user
ansible_become=true
openshift_deployment_type=openshift-enterprise

[masters]
ec2-52-6-179-239.compute-1.amazonaws.com  openshift_ip=172.17.3.88
openshift_public_ip=52-6-179-239
openshift_hostname=master.example.com
openshift_public_hostname=ose3-master.public.example.com
containerized=True

[nodes]
ec2-52-6-179-239.compute-1.amazonaws.com  openshift_ip=172.17.3.88
openshift_public_ip=52-6-179-239
openshift_hostname=master.example.com
openshift_public_hostname=ose3-master.public.example.com
containerized=True  openshift_schedulable=False
ec2-52-95-5-36.compute-1.amazonaws.com  openshift_ip=172.17.3.89
openshift_public_ip=52.3.5.36  openshift_hostname=node.example.com
openshift_public_hostname=ose3-node.public.example.com
containerized=True
```

2. Add the following new variables to the **[OSEv3:vars]** section of the file:

```
# htpasswd auth
openshift_master_identity_providers=[{'name': 'htpasswd_auth',
'login': 'true', 'challenge': 'true', 'kind':
'HTPasswdPasswordIdentityProvider', 'filename':
'/etc/origin/master/htpasswd'}]
# Defining htpasswd users
openshift_master_htpasswd_users={'<name>': '<hashed-password>',
'<name>': '<hashed-password>'}
# or
#openshift_master_htpasswd_file=<path/to/local/pre-
generated/htpasswdfile>
```

For HTPasswd authentication, you can use either the **openshift\_master\_htpasswd\_users** variable to create the specified user(s) and password(s) or the **openshift\_master\_htpasswd\_file** variable to specify a pre-generated flat file (the *htpasswd* file) with the users and passwords already created.

Because OpenShift Container Platform requires a hashed password to configure HTPasswd authentication, you can use the **htpasswd** command, [as shown in the following section](#), to generate the hashed password(s) for your user(s) or to create the flat file with the users and associated hashed passwords.

The following example changes the authentication method from the default **deny all** setting to **htpasswd** and use the specified file to generate user IDs and passwords for the **jsmith** and **bloblaw** users.

```
# htpasswd auth
openshift_master_identity_providers=[{'name': 'htpasswd_auth',
'login': 'true', 'challenge': 'true', 'kind':
'HTPasswdPasswordIdentityProvider', 'filename':
'/etc/origin/master/htpasswd'}]
# Defining htpasswd users
openshift_master_htpasswd_users={'jsmith':
'$apr1$wIwXkFLI$bAygtKGmPOqaJftB', 'bloblaw':
'7IRJ$20DmeLoxf4I6sUEKfiA$2aDJqLJe'}
# or
#openshift_master_htpasswd_file=<path/to/local/pre-
generated/htpasswdfile>
```

3. Re-run the ansible playbook for these modifications to take effect:

```
$ ansible-playbook -b -i ./hosts ~/src/openshift-
ansible/playbooks/deploy_cluster.yml
```

The playbook updates the configuration, and restarts the OpenShift Container Platform master service to apply the changes.

You have now modified the master and node configuration files using Ansible, but this is just a simple use case. From here you can see which **master** and **node configuration** options are [exposed to Ansible](#) and customize your own Ansible inventory.

### 6.3.1. Using the **htpasswd** command

To configure the OpenShift Container Platform cluster to use HTPasswd authentication, you need at least one user with a hashed password to include in the [inventory file](#).

You can:

- [Generate the username and password](#) to add directly to the `./hosts` inventory file.
- [Create a flat file](#) to pass the credentials to the `./hosts` inventory file.

To create a user and hashed password:

1. Run the following command to add the specified user:

```
$ htpasswd -n <user_name>
```



#### NOTE

You can include the `-b` option to supply the password on the command line:

```
$ htpasswd -nb <user_name> <password>
```

2. Enter and confirm a clear-text password for the user.

For example:

```
$ htpasswd -n myuser
New password:
Re-type new password:
myuser:$apr1$vdW.cI3j$WSKIOzUPs6Q
```

The command generates a hashed version of the password.

You can then use the hashed password when configuring [HTPasswd authentication](#). The hashed password is the string after the `:`. In the above example, you would enter:

```
openshift_master_htpasswd_users={'myuser':
'$apr1$wIWXkFLI$bAygtISk2eKGmqaJftB'}
```

To create a flat file with a user name and hashed password:

1. Execute the following command:

```
$ htpasswd -c </path/to/users.htpasswd> <user_name>
```



#### NOTE

You can include the `-b` option to supply the password on the command line:

```
$ htpasswd -c -b <user_name> <password>
```

2. Enter and confirm a clear-text password for the user.

For example:

```
htpasswd -c users.HTPasswd user1
New password:
Re-type new password:
Adding password for user user1
```

The command generates a file that includes the user name and a hashed version of the user's password.

You can then use the password file when configuring [HTPasswd authentication](#).



### NOTE

For more information on the `htpasswd` command, see [HTPasswd Identity Provider](#).

## 6.4. MAKING MANUAL CONFIGURATION CHANGES

After installing OpenShift Container Platform using the [quick install](#) tool, you can make modifications to the master and node configuration files to customize your cluster.

### Use Case: Configure the cluster to use HTPasswd authentication

To manually modify a configuration file:

1. Open the configuration file you want to modify, which in this case is the `/etc/origin/master/master-config.yaml` file:
2. Add the following new variables to the `identityProviders` stanza of the file:

```
oauthConfig:
  ...
  identityProviders:
    - name: my_htpasswd_provider
      challenge: true
      login: true
      mappingMethod: claim
      provider:
        apiVersion: v1
        kind: HTPasswdPasswordIdentityProvider
        file: /path/to/users.HTPasswd
```

3. Save your changes and close the file.
4. Restart the master for the changes to take effect:

```
$ systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

You have now manually modified the master and node configuration files, but this is just a simple use case. From here you can see all the [master](#) and [node configuration](#) options, and further customize your own cluster by making further modifications.

## 6.5. MASTER CONFIGURATION FILES

This section reviews parameters mentioned in the `master-config.yaml` file.

You can [create a new master configuration file](#) to see the valid options for your installed version of OpenShift Container Platform.



## IMPORTANT

Whenever you modify the ***master-config.yaml*** file, you must restart the master for the changes to take effect. See [Restarting OpenShift Container Platform services](#).

### 6.5.1. Admission Control Configuration

**Table 6.1. Admission Control Configuration Parameters**

| Parameter Name                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|-------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>AdmissionConfig</b>        | Contains the <a href="#">admission control plug-in</a> configuration. OpenShift Container Platform has a configurable list of admission controller plug-ins that are triggered whenever API objects are created or modified. This option allows you to override the default list of plug-ins; for example, disabling some plug-ins, adding others, changing the ordering, and specifying configuration. Both the list of plug-ins and their configuration can be controlled from Ansible.                                                                                            |
| <b>APIServerArguments</b>     | Key-value pairs that will be passed directly to the Kube API server that match the API servers' command line arguments. These are not migrated, but if you reference a value that does not exist the server will not start. These values may override other settings in <b>KubernetesMasterConfig</b> , which may cause invalid configurations. Use <b>APIServerArguments</b> with the <b>event-ttl</b> value to store events in etcd. The default is <b>2h</b> , but it can be set to less to prevent memory growth:<br><br><pre>apiServerArguments:   event-ttl:     - "15m"</pre> |
| <b>ControllerArguments</b>    | Key-value pairs that will be passed directly to the Kube controller manager that match the controller manager's command line arguments. These are not migrated, but if you reference a value that does not exist the server will not start. These values may override other settings in <b>KubernetesMasterConfig</b> , which may cause invalid configurations.                                                                                                                                                                                                                      |
| <b>DefaultAdmissionConfig</b> | Used to enable or disable various admission plug-ins. When this type is present as the <b>configuration</b> object under <b>pluginConfig</b> and if the admission plug-in supports it, this will cause an <b>off by default</b> admission plug-in to be enabled.                                                                                                                                                                                                                                                                                                                     |
| <b>PluginConfig</b>           | Allows specifying a configuration file per admission control plug-in.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <b>PluginOrderOverride</b>    | A list of admission control plug-in names that will be installed on the master. Order is significant. If empty, a default list of plug-ins is used.                                                                                                                                                                                                                                                                                                                                                                                                                                  |

| Parameter Name            | Description                                                                                                                                                                                                                                                                                                                                   |
|---------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>SchedulerArguments</b> | Key-value pairs that will be passed directly to the Kube scheduler that match the scheduler's command line arguments. These are not migrated, but if you reference a value that does not exist the server will not start. These values may override other settings in <b>KubernetesMasterConfig</b> , which may cause invalid configurations. |

## 6.5.2. Asset Configuration

**Table 6.2. Asset Configuration Parameters**

| Parameter Name              | Description                                                                                                                                                                                                                                                                                                                                                               |
|-----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>AssetConfig</b>          | If present, then the asset server starts based on the defined parameters. For example:                                                                                                                                                                                                                                                                                    |
|                             | <pre> assetConfig:   logoutURL: ""   masterPublicURL: https://master.ose32.example.com:8443   publicURL: https://master.ose32.example.com:8443/console/   servingInfo:     bindAddress: 0.0.0.0:8443     bindNetwork: tcp4     certFile: master.server.crt     clientCA: ""     keyFile: master.server.key     maxRequestsInFlight: 0     requestTimeoutSeconds: 0 </pre> |
| <b>corsAllowedOrigins</b>   | To access the API server from a web application using a different host name, you must whitelist that host name by specifying <b>corsAllowedOrigins</b> in the configuration field or by specifying the <b>--cors-allowed-origins</b> option on <b>openshift start</b> . No pinning or escaping is done to the value. See <a href="#">Web Console</a> for example usage.   |
| <b>DisabledFeatures</b>     | A list of features that should not be started. You will likely want to set this as <b>null</b> . It is very unlikely that anyone will want to manually disable features and that is not encouraged.                                                                                                                                                                       |
| <b>Extensions</b>           | Files to serve from the asset server file system under a subcontext.                                                                                                                                                                                                                                                                                                      |
| <b>ExtensionDevelopment</b> | When set to <b>true</b> , tells the asset server to reload extension scripts and stylesheets for every request rather than only at startup. It lets you develop extensions without having to restart the server for every change.                                                                                                                                         |

| Parameter Name              | Description                                                                                                                                      |
|-----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>ExtensionProperties</b>  | Key- (string) and value- (string) pairs that will be injected into the console under the global variable <b>OPENSHIFT_EXTENSION_PROPERTIES</b> . |
| <b>ExtensionScripts</b>     | File paths on the asset server files to load as scripts when the web console loads.                                                              |
| <b>ExtensionStylesheets</b> | File paths on the asset server files to load as style sheets when the web console loads.                                                         |
| <b>LoggingPublicURL</b>     | The public endpoint for logging (optional).                                                                                                      |
| <b>LogoutURL</b>            | An optional, absolute URL to redirect web browsers to after logging out of the web console. If not specified, the built-in logout page is shown. |
| <b>MasterPublicURL</b>      | How the web console can access the OpenShift Container Platform server.                                                                          |
| <b>MetricsPublicURL</b>     | The public endpoint for metrics (optional).                                                                                                      |
| <b>PublicURL</b>            | URL of the asset server.                                                                                                                         |

### 6.5.3. Authentication and Authorization Configuration

Table 6.3. Authentication and Authorization Parameters

| Parameter Name                 | Description                                                                                                                                                                                      |
|--------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>authConfig</b>              | Holds authentication and authorization configuration options.                                                                                                                                    |
| <b>AuthenticationCacheSize</b> | Indicates how many authentication results should be cached. If 0, the default cache size is used.                                                                                                |
| <b>AuthorizationCacheTTL</b>   | Indicates how long an authorization result should be cached. It takes a valid time duration string (e.g. "5m"). If empty, you get the default timeout. If zero (e.g. "0m"), caching is disabled. |

### 6.5.4. Controller Configuration

Table 6.4. Controller Configuration Parameters

| Parameter Name | Description |
|----------------|-------------|
|                |             |

| Parameter Name            | Description                                                                                                                                                                                                                                                                                                                                 |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Controllers</b>        | List of the controllers that should be started. If set to <b>none</b> , no controllers will start automatically. The default value is * which will start all controllers. When using *, you may exclude controllers by prepending a - in front of their name. No other values are recognized at this time.                                  |
| <b>ControllerLeaseTTL</b> | Enables controller election, instructing the master to attempt to acquire a lease before controllers start and renewing it within a number of seconds defined by this value. Setting this value non-negative forces <b>pauseControllers=true</b> . This value defaults off (0, or omitted) and controller election can be disabled with -1. |
| <b>PauseControllers</b>   | Instructs the master to not automatically start controllers, but instead to wait until a notification to the server is received before launching them.                                                                                                                                                                                      |

### 6.5.5. etcd Configuration

Table 6.5. etcd Configuration Parameters

| Parameter Name        | Description                                                                                                                                                                                             |
|-----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Address</b>        | The advertised host:port for client connections to etcd.                                                                                                                                                |
| <b>etcdClientInfo</b> | Contains information about how to connect to etcd. Specifies if etcd is run as embedded or non-embedded, and the hosts. The rest of the configuration is handled by the Ansible inventory. For example: |

```

etcdClientInfo:
  ca: ca.crt
  certFile: master.etcd-client.crt
  keyFile: master.etcd-client.key
  urls:
    - https://m1-aos.example.com:4001

```

| Parameter Name                  | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|---------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>etcdConfig</b>               | <p>If present, then etcd starts based on the defined parameters. For example:</p> <pre data-bbox="631 332 1382 866"> etcdConfig:   address: master.ose32.example.com:4001   peerAddress: master.ose32.example.com:7001   peerServingInfo:     bindAddress: 0.0.0.0:7001     certFile: etcd.server.crt     clientCA: ca.crt     keyFile: etcd.server.key   servingInfo:     bindAddress: 0.0.0.0:4001     certFile: etcd.server.crt     clientCA: ca.crt     keyFile: etcd.server.key   storageDirectory:     /var/lib/origin/openshift.local.etcd </pre> |
| <b>etcdStorageConfig</b>        | Contains information about how API resources are stored in etcd. These values are only relevant when etcd is the backing store for the cluster.                                                                                                                                                                                                                                                                                                                                                                                                          |
| <b>KubernetesStoragePrefix</b>  | The path within etcd that the Kubernetes resources will be rooted under. This value, if changed, will mean existing objects in <b>etcd</b> will no longer be located. The default value is <b>kubernetes.io</b> .                                                                                                                                                                                                                                                                                                                                        |
| <b>KubernetesStorageVersion</b> | The API version that Kubernetes resources in <b>etcd</b> should be serialized to. This value should <b>not</b> be advanced until all clients in the cluster that read from etcd have code that allows them to read the new version.                                                                                                                                                                                                                                                                                                                      |
| <b>OpenShiftStoragePrefix</b>   | The path within etcd that the OpenShift Container Platform resources will be rooted under. This value, if changed, will mean existing objects in etcd will no longer be located. The default value is <b>openshift.io</b> .                                                                                                                                                                                                                                                                                                                              |
| <b>OpenShiftStorageVersion</b>  | API version that OS resources in <b>etcd</b> should be serialized to. This value should <b>not</b> be advanced until all clients in the cluster that read from <b>etcd</b> have code that allows them to read the new version.                                                                                                                                                                                                                                                                                                                           |
| <b>PeerAddress</b>              | The advertised host:port for peer connections to <b>etcd</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>PeerServingInfo</b>          | Describes how to start serving the <b>etcd</b> peer.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |

| Parameter Name     | Description                                                                                                                                                                                                                                                        |
|--------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>ServingInfo</b> | <p>Describes how to start serving. For example:</p> <pre>servingInfo:   bindAddress: 0.0.0.0:8443   bindNetwork: tcp4   certFile: master.server.crt   clientCA: ca.crt   keyFile: master.server.key   maxRequestsInFlight: 500   requestTimeoutSeconds: 3600</pre> |
| <b>StorageDir</b>  | The path to the <b>etcd</b> storage directory.                                                                                                                                                                                                                     |

## 6.5.6. Grant Configuration

**Table 6.6. Grant Configuration Parameters**

| Parameter Name            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|---------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>GrantConfig</b>        | Describes how to handle grants.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <b>GrantHandlerAuto</b>   | Auto-approves client authorization grant requests.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| <b>GrantHandlerDeny</b>   | Auto-denies client authorization grant requests.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <b>GrantHandlerPrompt</b> | Prompts the user to approve new client authorization grant requests.                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| <b>Method</b>             | <p>Determines the default strategy to use when an OAuth client requests a grant. This method will be used only if the specific OAuth client does not provide a strategy of their own. Valid grant handling methods are:</p> <ul style="list-style-type: none"> <li>• auto: always approves grant requests, useful for trusted clients</li> <li>• prompt: prompts the end user for approval of grant requests, useful for third-party clients</li> <li>• deny: always denies grant requests, useful for black-listed clients</li> </ul> |

## 6.5.7. Image Configuration

**Table 6.7. Image Configuration Parameters**

| Parameter Name | Description                                                  |
|----------------|--------------------------------------------------------------|
| <b>Format</b>  | The format of the name to be built for the system component. |

| Parameter Name | Description                                                    |
|----------------|----------------------------------------------------------------|
| <b>Latest</b>  | Determines if the latest tag will be pulled from the registry. |

## 6.5.8. Image Policy Configuration

**Table 6.8. Image Policy Configuration Parameters**

| Parameter Name                                    | Description                                                                                                                                                                                                                                                                                                                                                                                                                |
|---------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>DisableScheduledImport</b>                     | Allows scheduled background import of images to be disabled.                                                                                                                                                                                                                                                                                                                                                               |
| <b>MaxImagesBulkImportedPerRepository</b>         | Controls the number of images that are imported when a user does a bulk import of a Docker repository. This number defaults to 5 to prevent users from importing large numbers of images accidentally. Set <b>-1</b> for no limit.                                                                                                                                                                                         |
| <b>MaxScheduledImageImportsPerMinute</b>          | The maximum number of scheduled image streams that will be imported in the background per minute. The default value is 60.                                                                                                                                                                                                                                                                                                 |
| <b>ScheduledImageImportMinimumIntervalSeconds</b> | The minimum number of seconds that can elapse between when image streams scheduled for background import are checked against the upstream repository. The default value is 15 minutes.                                                                                                                                                                                                                                     |
| <b>AllowedRegistriesForImport</b>                 | Limits the docker registries that normal users may import images from. Set this list to the registries that you trust to contain valid Docker images and that you want applications to be able to import from. Users with permission to create Images or ImageStreamMappings via the API are not affected by this policy - typically only administrators or system integrations will have those permissions.               |
| <b>InternalRegistryHostname</b>                   | Sets the hostname for the default internal image registry. The value must be in <b>hostname[:port]</b> format. For backward compatibility, users can still use <b>OPENSHIFT_DEFAULT_REGISTRY</b> environment variable but this setting overrides the environment variable. When this is set, the internal registry must have its hostname set as well. See <a href="#">setting the registry hostname</a> for more details. |
| <b>ExternalRegistryHostname</b>                   | ExternalRegistryHostname sets the hostname for the default external image registry. The external hostname should be set only when the image registry is exposed externally. The value is used in <b>publicDockerImageRepository</b> field in ImageStreams. The value must be in <b>hostname[:port]</b> format.                                                                                                             |

## 6.5.9. Kubernetes Master Configuration

**Table 6.9. Kubernetes Master Configuration Parameters**

| Parameter Name                  | Description                                                                                                                                                                 |
|---------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>APILevels</b>                | A list of API levels that should be enabled on startup, v1 as examples.                                                                                                     |
| <b>DisabledAPIGroupVersions</b> | A map of groups to the versions (or *) that should be disabled.                                                                                                             |
| <b>KubeletClientInfo</b>        | Contains information about how to connect to kubelets.                                                                                                                      |
| <b>KubernetesMasterConfig</b>   | Contains information about how to connect to kubelet's KubernetesMasterConfig. If present, then start the kubernetes master with this process.                              |
| <b>MasterCount</b>              | The number of expected masters that should be running. This value defaults to 1 and may be set to a positive integer, or if set to -1, indicates this is part of a cluster. |
| <b>MasterIP</b>                 | The public IP address of Kubernetes resources. If empty, the first result from <b>net.InterfaceAddrs</b> will be used.                                                      |
| <b>MasterKubeConfig</b>         | File name for the <b>.kubeconfig</b> file that describes how to connect this node to the master.                                                                            |
| <b>ServicesNodePortRange</b>    | The range to use for assigning service public ports on a host. Default 30000-32767.                                                                                         |
| <b>ServicesSubnet</b>           | The subnet to use for assigning service IPs.                                                                                                                                |
| <b>StaticNodeNames</b>          | The list of nodes that are statically known.                                                                                                                                |

## 6.5.10. Network Configuration

Choose the CIDRs in the following parameters carefully, because the IPv4 address space is shared by all users of the nodes. OpenShift Container Platform reserves CIDRs from the IPv4 address space for its own use, and reserves CIDRs from the IPv4 address space for addresses that are shared between the external user and the cluster.

**Table 6.10. Network Configuration Parameters**

| Parameter Name            | Description                                                                                                                        |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------------|
| <b>ClusterNetworkCIDR</b> | The CIDR string to specify the global overlay network's L3 space. This is reserved for the internal use of the cluster networking. |

| Parameter Name                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>ExternalIPNetworkCIDRs</b> | Controls what values are acceptable for the service external IP field. If empty, no <b>externalIP</b> may be set. It may contain a list of CIDRs which are checked for access. If a CIDR is prefixed with !, IPs in that CIDR will be rejected. Rejections will be applied first, then the IP checked against one of the allowed CIDRs. You must ensure this range does not overlap with your nodes, pods, or service CIDRs for security reasons. |
| <b>HostSubnetLength</b>       | The number of bits to allocate to each host's subnet. For example, 8 would mean a /24 network on the host.                                                                                                                                                                                                                                                                                                                                        |
| <b>IngressIPNetworkCIDR</b>   | Controls the range to assign ingress IPs from for services of type <b>LoadBalancer</b> on bare metal. It may contain a single CIDR that it will be allocated from. By default <b>172.46.0.0/16</b> is configured. For security reasons, you should ensure that this range does not overlap with the CIDRs reserved for external IPs, nodes, pods, or services.                                                                                    |
| <b>HostSubnetLength</b>       | The number of bits to allocate to each host's subnet. For example, 8 would mean a /24 network on the host.                                                                                                                                                                                                                                                                                                                                        |

| Parameter Name           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|--------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>NetworkConfig</b>     | <p>To be passed to the compiled-in-network plug-in. Many of the options here can be controlled in the Ansible inventory.</p> <ul style="list-style-type: none"> <li>• <b>NetworkPluginName</b> (string)</li> <li>• <b>ClusterNetworkCIDR</b> (string)</li> <li>• <b>HostSubnetLength</b> (unsigned integer)</li> <li>• <b>ServiceNetworkCIDR</b> (string)</li> <li>• <b>ExternalIPNetworkCIDRs</b> (string array): Controls which values are acceptable for the service external IP field. If empty, no external IP may be set. It can contain a list of CIDRs which are checked for access. If a CIDR is prefixed with !, then IPs in that CIDR are rejected. Rejections are applied first, then the IP is checked against one of the allowed CIDRs. For security purposes, you should ensure this range does not overlap with your nodes, pods, or service CIDRs.</li> </ul> <p>For Example:</p> <pre>networkConfig:   clusterNetworks   - cidr: 10.3.0.0/16     hostSubnetLength: 8   networkPluginName: example/openshift-ovs-   subnet   # serviceNetworkCIDR must match   kubernetesMasterConfig.servicesSubnet   serviceNetworkCIDR: 179.29.0.0/16</pre> |
| <b>NetworkPluginName</b> | The name of the network plug-in to use.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <b>ServiceNetwork</b>    | The CIDR string to specify the service networks.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |

## 6.5.11. OAuth Authentication Configuration

Table 6.11. OAuth Configuration Parameters

| Parameter Name                     | Description                                                                                                                                                   |
|------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>AlwaysShowProviderSelection</b> | Forces the provider selection page to render even when there is only a single provider.                                                                       |
| <b>AssetPublicURL</b>              | Used for building valid client redirect URLs for external access.                                                                                             |
| <b>Error</b>                       | A path to a file containing a go template used to render error pages during the authentication or grant flow. If unspecified, the default error page is used. |

| Parameter Name           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|--------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>IdentityProviders</b> | Ordered list of ways for a user to identify themselves.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| <b>Login</b>             | A path to a file containing a go template used to render the login page. If unspecified, the default login page is used.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| <b>MasterCA</b>          | CA for verifying the TLS connection back to the <b>MasterURL</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <b>MasterPublicURL</b>   | Used for building valid client redirect URLs for external access.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <b>MasterURL</b>         | Used for making server-to-server calls to exchange authorization codes for access tokens.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <b>OAuthConfig</b>       | <p>If present, then the /oauth endpoint starts based on the defined parameters. For example:</p> <pre data-bbox="626 819 1414 1785"> oauthConfig:   assetPublicURL:     https://master.ose32.example.com:8443/console/   grantConfig:     method: auto   identityProviders:     - challenge: true       login: true       mappingMethod: claim       name: htpasswd_all       provider:         apiVersion: v1         kind: HTPasswdPasswordIdentityProvider         file: /etc/origin/openshift-passwd   masterCA: ca.crt   masterPublicURL:     https://master.ose32.example.com:8443   masterURL:     https://master.ose32.example.com:8443   sessionConfig:     sessionMaxAgeSeconds: 3600     sessionName: ssn     sessionSecretsFile:       /etc/origin/master/session-secrets.yaml   tokenConfig:     accessTokenMaxAgeSeconds: 86400     authorizeTokenMaxAgeSeconds: 500 </pre> |
| <b>OAuthTemplates</b>    | Allows for customization of pages like the login page.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| <b>ProviderSelection</b> | A path to a file containing a go template used to render the provider selection page. If unspecified, the default provider selection page is used.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |

| Parameter Name       | Description                                           |
|----------------------|-------------------------------------------------------|
| <b>SessionConfig</b> | Holds information about configuring sessions.         |
| <b>Templates</b>     | Allows you to customize pages like the login page.    |
| <b>TokenConfig</b>   | Contains options for authorization and access tokens. |

## 6.5.12. Project Configuration

Table 6.12. Project Configuration Parameters

| Parameter Name             | Description                                |
|----------------------------|--------------------------------------------|
| <b>DefaultNodeSelector</b> | Holds default project node label selector. |

| Parameter Name                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|-------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>ProjectConfig</b>          | <p>Holds information about project creation and defaults:</p> <ul style="list-style-type: none"> <li>• <b>DefaultNodeSelector</b> (string): Holds the default project node label selector.</li> <li>• <b>ProjectRequestMessage</b> (string): The string presented to a user if they are unable to request a project via the projectrequest API endpoint.</li> <li>• <b>ProjectRequestTemplate</b> (string): The template to use for creating projects in response to projectrequest. It is in the format &lt;namespace&gt;/&lt;template&gt;. It is optional, and if it is not specified, a default template is used.</li> <li>• <b>SecurityAllocator</b>: Controls the automatic allocation of UIDs and MCS labels to a project. If nil, allocation is disabled: <ul style="list-style-type: none"> <li>◦ <b>mcsAllocatorRange</b> (string): Defines the range of MCS categories that will be assigned to namespaces. The format is &lt;prefix&gt;/&lt;numberOfLabels&gt;[, &lt;maxCategory&gt;]. The default is <b>s0/2</b> and will allocate from c0 → c1023, which means a total of 535k labels are available. If this value is changed after startup, new projects may receive labels that are already allocated to other projects. The prefix may be any valid SELinux set of terms (including user, role, and type). However, leaving the prefix at its default allows the server to set them automatically. For example, <b>s0:/2</b> would allocate labels from s0:c0,c0 to s0:c511,c511 whereas <b>s0:/2,512</b> would allocate labels from s0:c0,c0,c0 to s0:c511,c511,511.</li> <li>◦ <b>mcsLabelsPerProject</b> (integer): Defines the number of labels to reserve per project. The default is <b>5</b> to match the default UID and MCS ranges.</li> <li>◦ <b>uidAllocatorRange</b> (string): Defines the total set of Unix user IDs (UIDs) automatically allocated to projects, and the size of the block each namespace gets. For example, <b>1000-1999/10</b> would allocate ten UIDs per namespace, and would be able to allocate up to 100 blocks before running out of space. The default is to allocate from 1 billion to 2 billion in 10k blocks, which is the expected size of ranges for container images when user namespaces are started.</li> </ul> </li> </ul> |
| <b>ProjectRequestMessage</b>  | The string presented to a user if they are unable to request a project via the project request API endpoint.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| <b>ProjectRequestTemplate</b> | The template to use for creating projects in response to <b>projectrequest</b> . It is in the format namespace/template and it is optional. If it is not specified, a default template is used.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |

### 6.5.13. Scheduler Configuration

Table 6.13. Scheduler Configuration Parameters

| Parameter Name             | Description                                                                                                 |
|----------------------------|-------------------------------------------------------------------------------------------------------------|
| <b>SchedulerConfigFile</b> | Points to a file that describes how to set up the scheduler. If empty, you get the default scheduling rules |

## 6.5.14. Security Allocator Configuration

**Table 6.14. Security Allocator Parameters**

| Parameter Name           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>MCSAllocatorRange</b> | Defines the range of MCS categories that will be assigned to namespaces. The format is <b>&lt;prefix&gt;/&lt;numberOfLabels&gt;[ , &lt;maxCategory&gt;]</b> . The default is <b>s0/2</b> and will allocate from c0 to c1023, which means a total of 535k labels are available (1024 choose 2 ~ 535k). If this value is changed after startup, new projects may receive labels that are already allocated to other projects. Prefix may be any valid SELinux set of terms (including user, role, and type), although leaving them as the default will allow the server to set them automatically. |
| <b>SecurityAllocator</b> | Controls the automatic allocation of UIDs and MCS labels to a project. If nil, allocation is disabled.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>UIDAllocatorRange</b> | Defines the total set of Unix user IDs (UIDs) that will be allocated to projects automatically, and the size of the block each namespace gets. For example, 1000-1999/10 will allocate ten UIDs per namespace, and will be able to allocate up to 100 blocks before running out of space. The default is to allocate from 1 billion to 2 billion in 10k blocks (which is the expected size of the ranges container images will use once user namespaces are started).                                                                                                                            |

## 6.5.15. Service Account Configuration

**Table 6.15. Service Account Configuration Parameters**

| Parameter Name               | Description                                                                                                                                                                                            |
|------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>LimitSecretReferences</b> | Controls whether or not to allow a service account to reference any secret in a namespace without explicitly referencing them.                                                                         |
| <b>ManagedNames</b>          | A list of service account names that will be auto-created in every namespace. If no names are specified, the <b>ServiceAccountsController</b> will not be started.                                     |
| <b>MasterCA</b>              | The CA for verifying the TLS connection back to the master. The service account controller will automatically inject the contents of this file into pods so they can verify connections to the master. |

| Parameter Name              | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|-----------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>PrivateKeyFile</b>       | A file containing a PEM-encoded private RSA key, used to sign service account tokens. If no private key is specified, the service account <b>TokensController</b> will not be started.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| <b>PublicKeyFiles</b>       | A list of files, each containing a PEM-encoded public RSA key. If any file contains a private key, the public portion of the key is used. The list of public keys is used to verify presented service account tokens. Each key is tried in order until the list is exhausted or verification succeeds. If no keys are specified, no service account authentication will be available.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <b>ServiceAccountConfig</b> | Holds options related to service accounts: <ul style="list-style-type: none"> <li>• <b>LimitSecretReferences</b> (boolean): Controls whether or not to allow a service account to reference any secret in a namespace without explicitly referencing them.</li> <li>• <b>ManagedNames</b> (string): A list of service account names that will be auto-created in every namespace. If no names are specified, then the <b>ServiceAccountsController</b> will not be started.</li> <li>• <b>MasterCA</b> (string): The certificate authority for verifying the TLS connection back to the master. The service account controller will automatically inject the contents of this file into pods so that they can verify connections to the master.</li> <li>• <b>PrivateKeyFile</b> (string): Contains a PEM-encoded private RSA key, used to sign service account tokens. If no private key is specified, then the service account <b>TokensController</b> will not be started.</li> <li>• <b>PublicKeyFiles</b> (string): A list of files, each containing a PEM-encoded public RSA key. If any file contains a private key, then OpenShift Container Platform uses the public portion of the key. The list of public keys is used to verify service account tokens; each key is tried in order until either the list is exhausted or verification succeeds. If no keys are specified, then service account authentication will not be available.</li> </ul> |

### 6.5.16. Serving Information Configuration

Table 6.16. Serving Information Configuration Parameters

| Parameter Name               | Description                                                                                                                                                                                                |
|------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>AllowRecursiveQueries</b> | Allows the DNS server on the master to answer queries recursively. Note that open resolvers can be used for DNS amplification attacks and the master DNS should not be made accessible to public networks. |
| <b>BindAddress</b>           | The <b>ip:port</b> to serve on.                                                                                                                                                                            |

| Parameter Name                         | Description                                                                                                           |
|----------------------------------------|-----------------------------------------------------------------------------------------------------------------------|
| <b>BindNetwork</b>                     | Controls limits and behavior for importing images.                                                                    |
| <b>CertFile</b>                        | A file containing a PEM-encoded certificate.                                                                          |
| <b>CertInfo</b>                        | TLS cert information for serving secure traffic.                                                                      |
| <b>ClientCA</b>                        | The certificate bundle for all the signers that you recognize for incoming client certificates.                       |
| <b>dnsConfig</b>                       | If present, then start the DNS server based on the defined parameters.<br>For example:                                |
|                                        | dnsConfig:<br>  bindAddress: 0.0.0.0:8053<br>  bindNetwork: tcp4                                                      |
| <b>DNSDomain</b>                       | Holds the domain suffix.                                                                                              |
| <b>DNSIP</b>                           | Holds the IP.                                                                                                         |
| <b>KeyFile</b>                         | A file containing a PEM-encoded private key for the certificate specified by <b>CertFile</b> .                        |
| <b>MasterClientConnectionOverrides</b> | Provides overrides to the client connection used to connect to the master.                                            |
| <b>MaxRequestsInFlight</b>             | The number of concurrent requests allowed to the server. If zero, no limit.                                           |
| <b>NamedCertificates</b>               | A list of certificates to use to secure requests to specific host names.                                              |
| <b>RequestTimeoutSecond</b>            | The number of seconds before requests are timed out. The default is 60 minutes. If -1, there is no limit on requests. |
| <b>ServingInfo</b>                     | The HTTP serving information for the assets.                                                                          |

## 6.5.17. Volume Configuration

Table 6.17. Volume Configuration Parameters

| Parameter Name                    | Description                                                                   |
|-----------------------------------|-------------------------------------------------------------------------------|
| <b>DynamicProvisioningEnabled</b> | A boolean to enable or disable dynamic provisioning. Default is <b>true</b> . |

| Parameter Name            | Description                                                                                                                                                                                                                                          |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| FSGroup                   | Can be specified to enable a quota on local storage use per unique FSGroup ID. At present this is only implemented for emptyDir volumes, and if the underlying <b>volumeDirectory</b> is on an XFS filesystem.                                       |
| <b>LocalQuota</b>         | Contains options for controlling local volume quota on the node.                                                                                                                                                                                     |
| <b>MasterVolumeConfig</b> | Contains options for configuring volume plug-ins in the master node.                                                                                                                                                                                 |
| <b>NodeVolumeConfig</b>   | Contains options for configuring volumes on the node.                                                                                                                                                                                                |
| <b>VolumeConfig</b>       | Contains options for configuring volume plug-ins in the node: <ul style="list-style-type: none"> <li>• <b>DynamicProvisioningEnabled</b> (boolean): Default value is <b>true</b>, and toggles dynamic provisioning off when <b>false</b>.</li> </ul> |
| <b>VolumeDirectory</b>    | The directory that volumes are stored under.                                                                                                                                                                                                         |

### 6.5.18. Basic Audit

Audit provides a security-relevant chronological set of records documenting the sequence of activities that have affected system by individual users, administrators, or other components of the system.

Audit works at the API server level, logging all requests coming to the server. Each audit log contains two entries:

1. The request line containing:
  - a. A Unique ID allowing to match the response line (see #2)
  - b. The source IP of the request
  - c. The HTTP method being invoked
  - d. The original user invoking the operation
  - e. The impersonated user for the operation (**self** meaning himself)
  - f. The impersonated group for the operation (**lookup** meaning user's group)
  - g. The namespace of the request or <none>
  - h. The URI as requested
2. The response line containing:
  - a. The unique ID from #1
  - b. The response code

Example output for user **admin** asking for a list of pods:

```
AUDIT: id="5c3b8227-4af9-4322-8a71-542231c3887b" ip="127.0.0.1"
method="GET" user="admin" as="" asgroups=""
namespace="default" uri="/api/v1/namespaces/default/pods"
AUDIT: id="5c3b8227-4af9-4322-8a71-542231c3887b" response="200"
```

The **openshift\_master\_audit\_config** variable enables API service auditing. It takes an array of the following options:

**Table 6.18. Audit Configuration Parameters**

| Parameter Name                  | Description                                                                                                       |
|---------------------------------|-------------------------------------------------------------------------------------------------------------------|
| <b>enabled</b>                  | A boolean to enable or disable audit logs. Default is <b>false</b> .                                              |
| <b>auditFilePath</b>            | File path where the requests should be logged to. If not set, logs are printed to master logs.                    |
| <b>maximumFileRetentionDays</b> | Specifies maximum number of days to retain old audit log files based on the time stamp encoded in their filename. |
| <b>maximumRetainedFiles</b>     | Specifies the maximum number of old audit log files to retain.                                                    |
| <b>maximumFileSizeMegabytes</b> | Specifies maximum size in megabytes of the log file before it gets rotated. Defaults to 100MB.                    |

## Example Audit Configuration

```
auditConfig:
  auditFilePath: "/var/log/audit-ocp.log"
  enabled: true
  maximumFileRetentionDays: 10
  maximumFileSizeMegabytes: 10
  maximumRetainedFiles: 10
```

## Advanced Setup for the Audit Log

If you want more advanced setup for the audit log, you can use:

```
openshift_master_audit_config={"enabled": true}
```

The directory in **auditFilePath** will be created if it does not exist.

```
openshift_master_audit_config={"enabled": true, "auditFilePath": "/var/log/openpaas-oscp-audit/openpaas-oscp-audit.log",
"maximumFileRetentionDays": 14, "maximumFileSizeMegabytes": 500,
"maximumRetainedFiles": 5}
```

## 6.5.19. Advanced Audit

The advanced audit feature provides several improvements over the [basic audit functionality](#), including fine-grained events filtering and multiple output back ends. The following table contains additional options you can use.

**Table 6.19. Advanced Audit Configuration Parameters**

| Parameter Name             | Description                                                                                                                                                                                                          |
|----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>policyFile</b>          | Path to the file that defines the audit policy configuration.                                                                                                                                                        |
| <b>policyConfiguration</b> | An embedded audit policy configuration.                                                                                                                                                                              |
| <b>logFormat</b>           | Specifies the format of the saved audit logs. Allowed values are <b>legacy</b> (the format used in basic audit), and <b>json</b> .                                                                                   |
| <b>webHookKubeConfig</b>   | Path to a <b>.kubeconfig</b> -formatted file that defines the audit webhook configuration, where the events are sent to.                                                                                             |
| <b>webHookMode</b>         | Specifies the strategy for sending audit events. Allowed values are <b>block</b> (blocks processing another event until the previous has fully processed) and <b>batch</b> (buffers events and delivers in batches). |

To enable the advanced audit feature, you must provide either **policyFile** or **policyConfiguration** describing the audit policy rules:

### Sample Audit Policy Configuration

```

apiVersion: audit.k8s.io/v1beta1
kind: Policy
rules:

    # Do not log watch requests by the "system:kube-proxy" on endpoints or
    # services
    - level: None ①
        users: ["system:kube-proxy"] ②
        verbs: ["watch"] ③
        resources: ④
        - group: ""
            resources: ["endpoints", "services"]

    # Do not log authenticated requests to certain non-resource URL paths.
    - level: None
        userGroups: ["system:authenticated"] ⑤
        nonResourceURLs: ⑥
        - "/api*" # Wildcard matching.
        - "/version"

    # Log the request body of configmap changes in kube-system.
    - level: Request
        resources:
            - group: "" # core API group
                resources: ["configmaps"]

```

```

# This rule only applies to resources in the "kube-system" namespace.
# The empty string "" can be used to select non-namespaced resources.
namespaces: ["kube-system"] 7

# Log configmap and secret changes in all other namespaces at the
metadata level.
- level: Metadata
  resources:
    - group: "" # core API group
      resources: ["secrets", "configmaps"]

# Log all other resources in core and extensions at the request level.
- level: Request
  resources:
    - group: "" # core API group
    - group: "extensions" # Version of group should NOT be included.

# A catch-all rule to log all other requests at the Metadata level.
- level: Metadata 8

# Log login failures from the web console or CLI. Review the logs and
refine your policies.
- level: Metadata
  nonResourceURLs:
    - /login* 9
    - /oauth* 10

```

**1 8** There are four possible levels every event can be logged at:

- **None** - Do not log events that match this rule.
- **Metadata** - Log request metadata (requesting user, time stamp, resource, verb, etc.), but not request or response body. This is the same level as the one used in basic audit.
- **Request** - Log event metadata and request body, but not response body.
- **RequestResponse** - Log event metadata, request, and response bodies.

**2** A list of users the rule applies to. An empty list implies every user.

**3** A list of verbs this rule applies to. An empty list implies every verb. This is Kubernetes verb associated with API requests (including **get**, **list**, **watch**, **create**, **update**, **patch**, **delete**, **deletecollection**, and **proxy**).

**4** A list of resources the rule applies to. An empty list implies every resource. Each resource is specified as a group it is assigned to (for example, an empty for Kubernetes core API, batch, build.openshift.io, etc.), and a resource list from that group.

**5** A list of groups the rule applies to. An empty list implies every group.

**6** A list of non-resources URLs the rule applies to.

**7** A list of namespaces the rule applies to. An empty list implies every namespace.

**9** Endpoint used by the web console.

- 10** Endpoint used by the CLI.

For more information on advanced audit, see the [Kubernetes documentation](#)

### 6.5.20. Specifying TLS ciphers for etcd

You can specify the [supported TLS ciphers](#) to use in communication between the master and etcd servers.

1. On each etcd node, upgrade etcd:

```
# yum update etcd iptables-services
```

2. Confirm that your etcd version is 3.2.22 or later:

```
# etcd --version
etcd Version: 3.2.22
```

3. On each master host, specify the ciphers to enable in the `/etc/origin/master/master-config.yaml` file:

```
servingInfo:
  ...
  minTLSVersion: VersionTLS12
  cipherSuites:
    - TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256
    - TLS_RSA_WITH_AES_256_CBC_SHA
    - TLS_RSA_WITH_AES_128_CBC_SHA
  ...
```

4. On each master host, restart the master service:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

5. Confirm that the cipher is applied. For example, for TLSv1.2 cipher **ECDHE-RSA-AES128-GCM-SHA256**, run the following command:

```
# openssl s_client -connect etcd1.example.com:2379 1
CONNECTED(00000003)
depth=0 CN = etcd1.example.com
verify error:num=20:unable to get local issuer certificate
verify return:1
depth=0 CN = etcd1.example.com
verify error:num=21:unable to verify the first certificate
verify return:1
139905367488400:error:14094412:SSL routines:ssl3_read_bytes:sslv3
alert bad certificate:s3_pkt.c:1493:SSL alert number 42
139905367488400:error:140790E5:SSL routines:ssl23_write:ssl
handshake failure:s23_lib.c:177:
---
Certificate chain
  0 s:/CN=etcd1.example.com
```

```
i:/CN=etcd-signer@1529635004
---
Server certificate
-----BEGIN CERTIFICATE-----
MIIEkjCCAnqgAwIBAgIBATANBgkqhkiG9w0BAQsFADAhMR8wHQYDVQQDDBZldGNk
.....
....
eif87qttt0Sl1vS8DG1KQ01o0BlNkg==
-----END CERTIFICATE-----
subject=/CN=etcd1.example.com
issuer=/CN=etcd-signer@1529635004
---
Acceptable client certificate CA names
/CN=etcd-signer@1529635004
Client Certificate Types: RSA sign, ECDSA sign
Requested Signature Algorithms:
RSA+SHA256:ECDSA+SHA256:RSA+SHA384:ECDSA+SHA384:RSA+SHA1:ECDSA+SHA1
Shared Requested Signature Algorithms:
RSA+SHA256:ECDSA+SHA256:RSA+SHA384:ECDSA+SHA384:RSA+SHA1:ECDSA+SHA1
Peer signing digest: SHA384
Server Temp Key: ECDH, P-256, 256 bits
---
SSL handshake has read 1666 bytes and written 138 bytes
---
New, TLSv1/SSLv3, Cipher is ECDHE-RSA-AES128-GCM-SHA256
Server public key is 2048 bit
Secure Renegotiation IS supported
Compression: NONE
Expansion: NONE
No ALPN negotiated
SSL-Session:
Protocol : TLSv1.2
Cipher   : ECDHE-RSA-AES128-GCM-SHA256
Session-ID:
Session-ID-ctx:
Master-Key:
1EFA00A91EE5FC5EDDCFC67C8ECD060D44FD3EB23D834EDED929E4B74536F273C0F9
299935E5504B562CD56E76ED208D
Key-Ag  : None
Krb5 Principal: None
PSK identity: None
PSK identity hint: None
Start Time: 1529651744
Timeout   : 300 (sec)
Verify return code: 21 (unable to verify the first certificate)
```

- ① **etcd1.example.com** is the name of an etcd host.

## 6.6. NODE CONFIGURATION FILES

The following ***node-config.yaml*** file is a sample node configuration file that was generated with the default values as of writing. You can [create a new node configuration file](#) to see the valid options for your installed version of OpenShift Container Platform.

## Example 6.2. Sample Node Configuration File

```

allowDisabledDocker: false
apiVersion: v1
authConfig:
  authenticationCacheSize: 1000
  authenticationCacheTTL: 5m
  authorizationCacheSize: 1000
  authorizationCacheTTL: 5m
dnsDomain: cluster.local
dnsIP: 10.0.2.15 1
dockerConfig:
  execHandlerName: native
imageConfig:
  format: openshift/origin-${component}:${version}
  latest: false
iptablesSyncPeriod: 5s
kind: NodeConfig
masterKubeConfig: node.kubeconfig
networkConfig:
  mtu: 1450
  networkPluginName: ""
nodeIP: ""
nodeName: node1.example.com
podManifestConfig: 2
  path: "/path/to/pod-manifest-file" 3
  fileCheckIntervalSeconds: 30 4
proxyArguments:
  proxy-mode:
    - iptables 5
volumeConfig:
  localQuota:
    perFSGroup: null 6
servingInfo:
  bindAddress: 0.0.0.0:10250
  bindNetwork: tcp4
  certFile: server.crt
  clientCA: node-client-ca.crt
  keyFile: server.key
  namedCertificates: null
volumeDirectory: /root/openshift.local.volumes

```

- 1** Configures an IP address to be prepended to a pod's */etc/resolv.conf* by adding the address here.
- 2** Allows pods to be placed directly on certain set of nodes, or on all nodes without going through the scheduler. You can then use pods to perform the same administrative tasks and support the same services on each node.
- 3** Specifies the path for the **pod manifest file** or directory. If it is a directory, then it is expected to contain one or more manifest files. This is used by the Kubelet to create pods on the node.
- 4** This is the interval (in seconds) for checking the manifest file for new data. The interval must be a positive value.

- 5** The [service proxy implementation](#) to use.
- 6** Preliminary support for local emptyDir volume quotas, set this value to a resource quantity representing the desired quota per FSGroup, per node. (i.e. 1Gi, 512Mi, etc) Currently requires that the **volumeDirectory** be on an XFS filesystem mounted with the 'gquota' option, and the matching security context constraint's fsGroup type set to 'MustRunAs'.

The node configuration file determines the resources of a node. See the [Allocating node resources section in the Cluster Administrator guide](#) for more information.

### 6.6.1. Pod and Node Configuration

**Table 6.20. Pod and Node Configuration Parameters**

| Parameter Name            | Description                                                                                                                                                                                                                                |
|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>NodeConfig</b>         | The fully specified configuration starting an OpenShift Container Platform node.                                                                                                                                                           |
| <b>NodeIP</b>             | Node may have multiple IPs, so this specifies the IP to use for pod traffic routing. If not specified, network parse/lookup on the <b>nodeName</b> is performed and the first non-loopback address is used.                                |
| <b>nodeName</b>           | The value used to identify this particular node in the cluster. If possible, this should be your fully qualified hostname. If you are describing a set of static nodes to the master, this value must match one of the values in the list. |
| <b>PodEvictionTimeout</b> | Controls grace period for deleting pods on failed nodes. It takes valid time duration string. If empty, you get the default pod eviction timeout.                                                                                          |
| <b>ProxyClientInfo</b>    | Specifies the client cert/key to use when proxying to pods.                                                                                                                                                                                |

### 6.6.2. Docker Configuration

**Table 6.21. Docker Configuration Parameters**

| Parameter Name             | Description                                                                                                                           |
|----------------------------|---------------------------------------------------------------------------------------------------------------------------------------|
| <b>AllowDisabledDocker</b> | If true, the kubelet will ignore errors from Docker. This means that a node can start on a machine that does not have docker started. |
| <b>DockerConfig</b>        | Holds Docker related configuration options                                                                                            |
| <b>ExecHandlerName</b>     | The handler to use for executing commands in Docker containers.                                                                       |

### 6.6.3. Parallel Image Pulls with Docker 1.9+

If you are using Docker 1.9+, you may want to consider enabling parallel image pulling, as the default is to pull images one at a time.



### NOTE

There is a potential issue with data corruption prior to Docker 1.9. However, starting with 1.9, the corruption issue is resolved and it is safe to switch to parallel pulls.

```
kubeletArguments:
  serialize-image-pulls:
    - "false" ①
```

- ① Change to true to disable parallel pulls. (This is the default config)

## 6.7. PASSWORDS AND OTHER SENSITIVE DATA

For some [authentication configurations](#), an LDAP **bindPassword** or OAuth **clientSecret** value is required. Instead of specifying these values directly in the master configuration file, these values may be provided as environment variables, external files, or in encrypted files.

### Environment Variable Example

```
...
bindPassword:
  env: BIND_PASSWORD_ENV_VAR_NAME
```

### External File Example

```
...
bindPassword:
  file: bindPassword.txt
```

### Encrypted External File Example

```
...
bindPassword:
  file: bindPassword.encrypted
  keyFile: bindPassword.key
```

To create the encrypted file and key file for the above example:

```
$ oc adm ca encrypt --genkey=bindPassword.key --out=bindPassword.encrypted
> Data to encrypt: B1ndPass0rd!
```

Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

**WARNING**

Encrypted data is only as secure as the decrypting key. Care should be taken to limit filesystem permissions and access to the key file.

## 6.8. CREATING NEW CONFIGURATION FILES

When defining an OpenShift Container Platform configuration from scratch, start by creating new configuration files.

For master host configuration files, use the `openshift start` command with the `--write-config` option to write the configuration files. For node hosts, use the `oc adm create-node-config` command to write the configuration files.

The following commands write the relevant launch configuration file(s), certificate files, and any other necessary files to the specified `--write-config` or `--node-dir` directory.

Generated certificate files are valid for two years, while the certification authority (CA) certificate is valid for five years. This can be altered with the `--expire-days` and `--signer-expire-days` options, but for security reasons, it is recommended to not make them greater than these values.

To create configuration files for an all-in-one server (a master and a node on the same host) in the specified directory:

```
$ openshift start --write-config=/openshift.local.config
```

To create a [master configuration file](#) and other required files in the specified directory:

```
$ openshift start master --write-config=/openshift.local.config/master
```

To create a [node configuration file](#) and other related files in the specified directory:

```
$ oc adm create-node-config \
  --node-dir=/openshift.local.config/node- \
  --node=<node_hostname> \
  --hostnames=<node_hostname>,<ip_address> \
  --certificate-authority="/path/to/ca.crt" \
  --signer-cert="/path/to/ca.crt" \
  --signer-key="/path/to/ca.key"
  --signer-serial="/path/to/ca.serial.txt"
  --node-client-certificate-authority="/path/to/ca.crt"
```

When creating node configuration files, the `--hostnames` option accepts a comma-delimited list of every host name or IP address you want server certificates to be valid for.

## 6.9. LAUNCHING SERVERS USING CONFIGURATION FILES

Once you have modified the master and/or node configuration files to your specifications, you can use them when launching servers by specifying them as an argument. Keep in mind that if you specify a configuration file, none of the other command line options you pass are respected.

To launch an all-in-one server using a master configuration and a node configuration file:

```
$ openshift start --master-config=/openshift.local.config/master/master-
config.yaml --node-config=/openshift.local.config/node-
<node_hostname>/node-config.yaml
```

To launch a master server using a master configuration file:

```
$ openshift start master --config=/openshift.local.config/master/master-
config.yaml
```

To launch a node server using a node configuration file:

```
$ openshift start node --config=/openshift.local.config/node-
<node_hostname>/node-config.yaml
```

## 6.10. CONFIGURING LOGGING LEVELS

OpenShift Container Platform uses the **`systemd-journald.service`** to collect log messages for debugging, using five log message severities. The logging levels are based on Kubernetes logging conventions, as follows:

**Table 6.22. Log Level Options**

| Option | Description                                          |
|--------|------------------------------------------------------|
| 0      | Errors and warnings only                             |
| 2      | Normal information                                   |
| 4      | Debugging-level information                          |
| 6      | API-level debugging information (request / response) |
| 8      | Body-level API debugging information                 |

You can control which INFO messages are logged by setting the loglevel option in the in **`/etc/sysconfig/atomic-openshift-node`**, the **`/etc/sysconfig/atomic-openshift-master-api`** file and the **`/etc/sysconfig/atomic-openshift-master-controllers`** file. Configuring the logs to collect all messages can lead to large logs that are difficult to interpret and can take up excessive space. Collecting all messages should only be used in debug situations.



### NOTE

Messages with FATAL, ERROR, WARNING and some INFO severities appear in the logs regardless of the log configuration.

You can view logs for the master or the node system using the following command:

```
# journalctl -r -u <journal_name>
```

Use the **-r** option to show the newest entries first.

For example:

```
# journalctl -r -u atomic-openshift-master-controllers  
# journalctl -r -u atomic-openshift-master-api  
# journalctl -r -u atomic-openshift-node.service
```

To change the logging level:

1. Edit the **/etc/sysconfig/atomic-openshift-master** file for the master or **/etc/sysconfig/atomic-openshift-node** file for the nodes.
2. Enter a value from the **Log Level Options** table above in the **OPTIONS=--loglevel=** field.

For example:

```
OPTIONS=--loglevel=4
```

3. Restart the master or node host as appropriate. See [Restarting OpenShift Container Platform services](#).

After the restart, all new log messages will conform to the new setting. Older messages do not change.



## NOTE

The default log level can be set using the Advanced Install. For more information, see [Cluster Variables](#).

The following examples are excerpts from a master **journald** log at various log levels. Timestamps and system information have been removed from these examples.

### Excerpt of journalctl -u atomic-openshift-master-controllers.service output at loglevel=0

```
4897 plugins.go:77] Registered admission plugin "NamespaceLifecycle"  
4897 start_master.go:290] Warning: assetConfig.loggingPublicURL: Invalid  
value: "": required to view aggregated container logs in the console,  
master start will continue.  
4897 start_master.go:290] Warning: assetConfig.metricsPublicURL: Invalid  
value: "": required to view cluster metrics in the console, master start  
will continue.  
4897 start_master.go:290] Warning: aggregatorConfig.proxyClientInfo:  
Invalid value: "": if no client certificate is specified, the aggregator  
will be unable to proxy to remote servers,  
4897 start_master.go:412] Starting controllers on 0.0.0.0:8444 (v3.7.14)  
4897 start_master.go:416] Using images from "openshift3/ose-  
<component>:v3.7.14"  
4897 standalone_apiserver.go:106] Started health checks at 0.0.0.0:8444  
4897 plugins.go:77] Registered admission plugin "NamespaceLifecycle"  
4897 configgetter.go:53] Initializing cache sizes based on 0MB limit  
4897 leaderelection.go:105] Attempting to acquire openshift-master-
```

```

controllers lease as master-bkr-hv03-guest44.dsal.lab.eng.bos.redhat.com-
10.19.41.74-xtz6lbqb, renewing every 3s, hold
4897 leaderelection.go:179] attempting to acquire leader lease...
systemd[1]: Started Atomic OpenShift Master Controllers.
4897 leaderelection.go:189] successfully acquired lease kube-
system/openshift-master-controllers
4897 event.go:218] Event(v1.ObjectReference{Kind:"ConfigMap",
Namespace:"kube-system", Name:"openshift-master-controllers",
UID:"aca86731-ffbe-11e7-8d33-525400c845a8", APIVersion:"v1",
4897 start_master.go:627] Started serviceaccount-token controller
4897 factory.go:351] Creating scheduler from configuration: {{ }
[{{NoVolumeZoneConflict <nil>} {MaxEBSVolumeCount <nil>}
{MaxGCEPDVolumeCount <nil>} {MaxAzureDiskVolumeCount <nil>} {Mat
4897 factory.go:360] Registering predicate: NoVolumeZoneConflict
4897 plugins.go:145] Predicate type NoVolumeZoneConflict already
registered, reusing.
4897 factory.go:360] Registering predicate: MaxEBSVolumeCount
4897 plugins.go:145] Predicate type MaxEBSVolumeCount already registered,
reusing.
4897 factory.go:360] Registering predicate: MaxGCEPDVolumeCount

```

### **Excerpt of journalctl -u atomic-openshift-master-controllers.service output at loglevel=2**

```

4897 master.go:47] Initializing SDN master of type "redhat/openshift-ovs-
subnet"
4897 master.go:107] Created ClusterNetwork default (network:
"10.128.0.0/14", hostSubnetBits: 9, serviceNetwork: "172.30.0.0/16",
pluginName: "redhat/openshift-ovs-subnet")
4897 start_master.go:690] Started "openshift.io/sdn"
4897 start_master.go:680] Starting "openshift.io/service-serving-cert"
4897 controllermanager.go:466] Started "namespace"
4897 controllermanager.go:456] Starting "daemonset"
4897 controller_utils.go:1025] Waiting for caches to sync for namespace
controller
4897 shared_informer.go:298] resyncPeriod 120000000000 is smaller than
resyncCheckPeriod 600000000000 and the informer has already started.
Changing it to 600000000000
4897 start_master.go:690] Started "openshift.io/service-serving-cert"
4897 start_master.go:680] Starting "openshift.io/image-signature-import"
4897 start_master.go:690] Started "openshift.io/image-signature-import"
4897 start_master.go:680] Starting "openshift.io/templateinstance"
4897 controllermanager.go:466] Started "daemonset"
4897 controllermanager.go:456] Starting "statefulset"
4897 daemoncontroller.go:222] Starting daemon sets controller
4897 controller_utils.go:1025] Waiting for caches to sync for daemon sets
controller
4897 controllermanager.go:466] Started "statefulset"
4897 controllermanager.go:456] Starting "cronjob"
4897 stateful_set.go:147] Starting stateful set controller
4897 controller_utils.go:1025] Waiting for caches to sync for stateful set
controller
4897 start_master.go:690] Started "openshift.io/templateinstance"
4897 start_master.go:680] Starting "openshift.io/horizontalpodautoscaling"

```

### **Excerpt of journalctl -u atomic-openshift-master-controllers.service output at loglevel=4**

```

4897 factory.go:366] Registering priority: Zone
4897 factory.go:401] Creating scheduler with fit predicates
'map[GeneralPredicates:{} CheckNodeMemoryPressure:{}]
CheckNodeDiskPressure:{} Region:{} NoVolumeZoneC
4897 controller_utils.go:1025] Waiting for caches to sync for tokens
controller
4897 controllermanager.go:108] Version: v1.7.6+a08f5eeb62
4897 leaderelection.go:179] attempting to acquire leader lease...
4897 leaderelection.go:189] successfully acquired lease kube-system/kube-
controller-manager
4897 event.go:218] Event(v1.ObjectReference{Kind:"ConfigMap",
Namespace:"kube-system", Name:"kube-controller-manager", UID:"acb3e9c6-
ffbe-11e7-8d33-525400c845a8", APIVersion:"v1", Resou
4897 controller_utils.go:1032] Caches are synced for tokens controller
4897 plugins.go:101] No cloud provider specified.
4897 controllermanager.go:481] "serviceaccount-token" is disabled
4897 controllermanager.go:450] "bootstrapsigner" is disabled
4897 controllermanager.go:450] "tokencleaner" is disabled
4897 controllermanager.go:456] Starting "garbagecollector"
4897 start_master.go:680] Starting "openshift.io/build"
4897 controllermanager.go:466] Started "garbagecollector"
4897 controllermanager.go:456] Starting "deployment"
4897 garbagecollector.go:126] Starting garbage collector controller
4897 controller_utils.go:1025] Waiting for caches to sync for garbage
collector controller
4897 controllermanager.go:466] Started "deployment"
4897 controllermanager.go:450] "horizontalpodautoscaling" is disabled
4897 controllermanager.go:456] Starting "disruption"
4897 deployment_controller.go:152] Starting deployment controller

```

### **Excerpt of journalctl -u atomic-openshift-master-controllers.service output at loglevel=8**

```

4897 plugins.go:77] Registered admission plugin "NamespaceLifecycle"
4897 start_master.go:290] Warning: assetConfig.loggingPublicURL: Invalid
value: "": required to view aggregated container logs in the console,
master start will continue.
4897 start_master.go:290] Warning: assetConfig.metricsPublicURL: Invalid
value: "": required to view cluster metrics in the console, master start
will continue.
4897 start_master.go:290] Warning: aggregatorConfig.proxyClientInfo:
Invalid value: "": if no client certificate is specified, the aggregator
will be unable to proxy to remote serv
4897 start_master.go:412] Starting controllers on 0.0.0.0:8444 (v3.7.14)
4897 start_master.go:416] Using images from "openshift3/ose-
<component>:v3.7.14"
4897 standalone_apiserver.go:106] Started health checks at 0.0.0.0:8444
4897 plugins.go:77] Registered admission plugin "NamespaceLifecycle"
4897 configgetter.go:53] Initializing cache sizes based on 0MB limit
4897 leaderelection.go:105] Attempting to acquire openshift-master-
controllers lease as master-bkr-hv03-guest44.dsal.lab.eng.bos.redhat.com-
10.19.41.74-xtz6lbqb, renewing every 3s,
4897 leaderelection.go:179] attempting to acquire leader lease...
systemd[1]: Started Atomic OpenShift Master Controllers.
4897 leaderelection.go:189] successfully acquired lease kube-
system/openshift-master-controllers

```

```
4897 event.go:218] Event(v1.ObjectReference{Kind:"ConfigMap",
Namespace:"kube-system", Name:"openshift-master-controllers",
UID:"aca86731-ffbe-11e7-8d33-525400c845a8", APIVersion:""
4897 start_master.go:627] Started serviceaccount-token controller
```

### Excerpt of journalctl -u atomic-openshift-master-api.service output at loglevel=2

```
4613 plugins.go:77] Registered admission plugin "NamespaceLifecycle"
4613 master.go:320] Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
4613 master.go:329] Starting OAuth2 API at /oauth
4613 master.go:320] Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
4613 master.go:329] Starting OAuth2 API at /oauth
4613 master.go:320] Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
4613 master.go:329] Starting OAuth2 API at /oauth
4613 swagger.go:38] No API exists for predefined swagger description
/oapi/v1
4613 swagger.go:38] No API exists for predefined swagger description
/api/v1
[restful] 2018/01/22 16:53:14 log.go:33: [restful/swagger] listing is
available at https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/swaggerapi
[restful] 2018/01/22 16:53:14 log.go:33: [restful/swagger] https://bkr-
hv03-guest44.dsal.lab.eng.bos.redhat.com:8443/swaggerui/ is mapped to
folder /swagger-ui/
4613 master.go:320] Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
4613 master.go:329] Starting OAuth2 API at /oauth
4613 swagger.go:38] No API exists for predefined swagger description
/oapi/v1
4613 swagger.go:38] No API exists for predefined swagger description
/api/v1
[restful] 2018/01/22 16:53:14 log.go:33: [restful/swagger] listing is
available at https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/swaggerapi
[restful] 2018/01/22 16:53:14 log.go:33: [restful/swagger] https://bkr-
hv03-guest44.dsal.lab.eng.bos.redhat.com:8443/swaggerui/ is mapped to
folder /swagger-ui/
Starting Web Console https://bkr-hv03-
guest44.dsal.lab.eng.bos.redhat.com:8443/console/
Starting OAuth2 API at /oauth
No API exists for predefined swagger description /oapi/v1
No API exists for predefined swagger description /api/v1
```

## 6.11. RESTARTING OPENSHIFT CONTAINER PLATFORM SERVICES

To apply configuration changes, you must restart OpenShift Container Platform services.

- To restart master, run the command:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

- To restart node hosts, on each node, run the command:

```
# systemctl restart atomic-openshift-node
```

# CHAPTER 7. OPENSHIFT ANSIBLE BROKER CONFIGURATION

## 7.1. OVERVIEW

When the [OpenShift Ansible broker](#) (OAB) is deployed in a cluster, its behavior is largely dictated by the broker's configuration file loaded on startup. The broker's configuration is stored as a ConfigMap object in the broker's namespace (`openshift-ansible-service-broker` by default).

### Example OpenShift Ansible Broker Configuration File

```

registry: ①
  - type: dockerhub
    name: docker
    url: https://registry.hub.docker.com
    org: <dockerhub_org>
    fail_on_error: false
  - type: rhcc
    name: rhcc
    url: https://registry.access.redhat.com
    fail_on_error: true
    white_list:
      - "^\w+\.|-apb$"
      - "\w+\.|-apb$"
    black_list:
      - "bar\.\w+|-apb$"
      - "^\w+my\.-apb$"
  - type: local_openshift
    name: lo
    namespaces:
      - openshift
    white_list:
      - "\w+\.|-apb$"

dao: ②
  etcd_host: localhost
  etcd_port: 2379

log: ③
  logfile: /var/log/ansible-service-broker/asb.log
  stdout: true
  level: debug
  color: true

openshift: ④
  host: ""
  ca_file: ""
  bearer_token_file: ""
  image_pull_policy: IfNotPresent
  sandbox_role: "edit"
  keep_namespace: false
  keep_namespace_on_error: true

broker: ⑤
  bootstrap_on_startup: true
  dev_broker: true
  launch_apb_on_bind: false
  recovery: true
  output_request: true

```

```

ssl_cert_key: /path/to/key
ssl_cert: /path/to/cert
refresh_interval: "600s"
auth:
  - type: basic
    enabled: true
secrets: ⑥
  - title: Database credentials
    secret: db_creds
    apb_name: dh-rhscl-postgresql-app

```

- ① See [Registry Configuration](#) for details.
- ② See [DAO Configuration](#) for details.
- ③ See [Log Configuration](#) for details.
- ④ See [OpenShift Configuration](#) for details.
- ⑤ See [Broker Configuration](#) for details.
- ⑥ See [Secrets Configuration](#) for details.

## 7.2. MODIFYING THE OPENSHIFT ANSIBLE BROKER CONFIGURATION

To modify the OAB's default broker configuration after it has been deployed:

1. Edit the **broker-config** ConfigMap object in the OAB's namespace as a user with **cluster-admin** privileges:

```
$ oc edit configmap broker-config -n openshift-ansible-service-broker
```

2. After saving any updates, redeploy the OAB's deployment configuration for the changes to take effect:

```
$ oc rollout latest dc/asb -n openshift-ansible-service-broker
```

## 7.3. REGISTRY CONFIGURATION

The **registry** section allows you to define the registries that the broker should look at for APBs.

**Table 7.1. registry Section Configuration Options**

| Field       | Description                                                                                                               | Required |
|-------------|---------------------------------------------------------------------------------------------------------------------------|----------|
| <b>name</b> | The name of the registry. Used by the broker to identify APBs from this registry.                                         | Y        |
| <b>user</b> | The user name for authenticating to the registry. Not used when <b>auth_type</b> is set to <b>secret</b> or <b>file</b> . | N        |

| Field                | Description                                                                                                                                                                                                                                                                                                                                               | Required                                                                        |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------|
| <b>pass</b>          | The password for authenticating to the registry. Not used when <b>auth_type</b> is set to <b>secret</b> or <b>file</b> .                                                                                                                                                                                                                                  | N                                                                               |
| <b>auth_type</b>     | How the broker should read the registry credentials if they are not defined in the broker configuration via <b>user</b> and <b>pass</b> . Can be <b>secret</b> (uses a secret in the broker namespace) or <b>file</b> (uses a mounted file).                                                                                                              | N                                                                               |
| <b>auth_name</b>     | Name of the secret or file storing the registry credentials that should be read. Used when <b>auth_type</b> is set to <b>secret</b> .                                                                                                                                                                                                                     | N, only required when <b>auth_type</b> is set to <b>secret</b> or <b>file</b> . |
| <b>org</b>           | The namespace or organization that the image is contained in.                                                                                                                                                                                                                                                                                             | N                                                                               |
| <b>type</b>          | The type of registry. Available adapters are <b>mock</b> , <b>rhcc</b> , <b>openshift</b> , <b>dockerhub</b> , and <b>local_openshift</b> .                                                                                                                                                                                                               | Y                                                                               |
| <b>namespaces</b>    | The list of namespaces to configure the <b>local_openshift</b> registry type with. By default, a user should use <b>openshift</b> .                                                                                                                                                                                                                       | N                                                                               |
| <b>url</b>           | The URL that is used to retrieve image information. Used extensively for RHCC while the <b>dockerhub</b> type uses hard-coded URLs.                                                                                                                                                                                                                       | N                                                                               |
| <b>fail_on_error</b> | Should this registry fail, the bootstrap request if it fails. Will stop the execution of other registries loading.                                                                                                                                                                                                                                        | N                                                                               |
| <b>white_list</b>    | The list of regular expressions used to define which image names should be allowed through. Must have a white list to allow APBs to be added to the catalog. The most permissive regular expression that you can use is <code>. * -apb\$</code> if you would want to retrieve all APBs in a registry. See <a href="#">APB Filtering</a> for more details. | N                                                                               |
| <b>black_list</b>    | The list of regular expressions used to define which images names should never be allowed through. See <a href="#">APB Filtering</a> for more details.                                                                                                                                                                                                    | N                                                                               |
| <b>images</b>        | The list of images to be used with an OpenShift Container Registry.                                                                                                                                                                                                                                                                                       | N                                                                               |

### 7.3.1. Production or Development

A *production* broker configuration is designed to be pointed at a trusted container distribution registry, such as the Red Hat Container Catalog (RHCC):

```
registry:
```

```

- name: rhcc
  type: rhcc
  url: https://registry.access.redhat.com
  tag: v3.9
  white_list:
    - ".*-apb$"
- type: local_openshift
  name: localregistry
  namespaces:
    - openshift
  white_list: []

```

However, a *development* broker configuration is primarily used by developers working on the broker. To enable developer settings, set the registry name to **dev** and the **dev\_broker** field in the **broker** section to **true**:

```

registry:
  name: dev

broker:
  dev_broker: true

```

### 7.3.2. Storing Registry Credentials

The broker configuration determines how the broker should read any registry credentials. They can be read from the **user** and **pass** values in the **registry** section, for example:

```

registry:
- name: isv
  type: openshift
  url: https://registry.connect.redhat.com
  user: <user>
  pass: <password>

```

If you want to ensure these credentials are not publicly accessible, the **auth\_type** field in the **registry** section can be set to the **secret** or **file** type. The **secret** type configures a registry to use a secret from the broker's namespace, while the **file** type configures a registry to use a secret that has been mounted as a volume.

To use the **secret** or **file** type:

1. The associated secret should have the values **username** and **password** defined. When using a secret, you must ensure that the **openshift-ansible-service-broker** namespace exists, as this is where the secret will be read from.

For example, create a **reg-creds.yaml** file:

```

$ cat reg-creds.yaml
---
username: <username>
password: <password>

```

2. Create a secret from this file in the **openshift-ansible-service-broker** namespace:

```
$ oc create secret generic \
  registry-credentials-secret \
  --from-file reg-creds.yaml \
  -n openshift-ansible-service-broker
```

3. Choose whether you want to use the **secret** or **file** type:

- To use the **secret** type:

- In the broker configuration, set **auth\_type** to **secret** and **auth\_name** to the name of the secret:

```
registry:
  - name: isv
    type: openshift
    url: https://registry.connect.redhat.com
    auth_type: secret
    auth_name: registry-credentials-secret
```

- Set the namespace where the secret is located:

```
openshift:
  namespace: openshift-ansible-service-broker
```

- To use the **file** type:

- Edit the **asb** deployment configuration to mount your file into **/tmp/registry-credentials/reg-creds.yaml**:

```
$ oc edit dc/asb -n openshift-ansible-service-broker
```

In the **containers.volumeMounts** section, add:

```
volumeMounts:
  - mountPath: /tmp/registry-credentials
    name: reg-auth
```

In the **volumes** section, add:

```
volumes:
  - name: reg-auth
    secret:
      defaultMode: 420
      secretName: registry-credentials-secret
```

- In the broker configuration, set **auth\_type** to **file** and **auth\_file** to the location of the file:

```
registry:
  - name: isv
    type: openshift
```

```
url: https://registry.connect.redhat.com
auth_type: file
auth_name: /tmp/registry-credentials/reg-creds.yaml
```

### 7.3.3. Mock Registry

A mock registry is useful for reading local APB specs. Instead of going out to a registry to search for image specs, this uses a list of local specs. Set the name of the registry to **mock** to use the mock registry.

```
registry:
- name: mock
  type: mock
```

### 7.3.4. Dockerhub Registry

The **dockerhub** type allows you to load APBs from a specific organization in the DockerHub. For example, the [ansibleplaybookbundle](#) organization.

```
registry:
- name: dockerhub
  type: dockerhub
  org: ansibleplaybookbundle
  user: <user>
  pass: <password>
  white_list:
    - ".-* -apb$"
```

### 7.3.5. APB Filtering

APBs can be filtered out by their image name using a combination of the **white\_list** or **black\_list** parameters, set on a registry basis inside the broker's configuration.

Both are optional lists of regular expressions that will be run over the total set of discovered APBs for a given registry to determine matches.

**Table 7.2. APB Filter Behavior**

| Present        | Allowed                                          | Blocked                               |
|----------------|--------------------------------------------------|---------------------------------------|
| Only whitelist | Matches a regex in list.                         | Any APB that does not match.          |
| Only blacklist | All APBs that do not match.                      | APBs that match a regex in list.      |
| Both present   | Matches regex in whitelist but not in blacklist. | APBs that match a regex in blacklist. |
| None           | No APBs from the registry.                       | All APBs from that registry.          |

For example:

## Whitelist Only

```
white_list:
  - "foo.*-apb$"
  - "^my-apb$"
```

Anything matching on **foo.\*-apb\$** and only **my-apb** will be allowed through in this case. All other APBs will be rejected.

## Blacklist Only

```
black_list:
  - "bar.*-apb$"
  - "^foobar-apb$"
```

Anything matching on **bar.\*-apb\$** and only **foobar-apb** will be blocked in this case. All other APBs will be allowed through.

## Whitelist and Blacklist

```
white_list:
  - "foo.*-apb$"
  - "^my-apb$"
black_list:
  - "^foo-rootkit-apb$"
```

Here, **foo-rootkit-apb** is specifically blocked by the blacklist despite its match in the whitelist because the whitelist match is overridden.

Otherwise, only those matching on **foo.\*-apb\$** and **my-apb** will be allowed through.

## Example Broker Configuration registry Section:

```
registry:
  - type: dockerhub
    name: dockerhub
    url: https://registry.hub.docker.com
    user: <user>
    pass: <password>
    org: <org>
    white_list:
      - "foo.*-apb$"
      - "^my-apb$"
    black_list:
      - "bar.*-apb$"
      - "^foobar-apb$"
```

### 7.3.6. Local OpenShift Container Registry

Using the **local\_openshift** type will allow you to load APBs from the OpenShift Container Registry that is internal to the OpenShift Container Platform cluster. You can configure the namespaces in which you want to look for published APBs.

```
registry:
  - type: local_openshift
    name: lo
    namespaces:
      - openshift
    white_list:
      - ".*-apb$"
```

### 7.3.7. Red Hat Container Catalog Registry

Using the **rhcc** type will allow you to load APBs that are published to the [Red Hat Container Catalog](#) (RHCC) registry.

```
registry:
  - name: rhcc
    type: rhcc
    url: https://registry.access.redhat.com
    white_list:
      - ".*-apb$"
```

### 7.3.8. ISV Registry

Using the **openshift** type allows you to load APBs that are published to the ISV container registry at [registry.connect.redhat.com](#).

```
registry:
  - name: isv
    type: openshift
    user: <user> ①
    pass: <password>
    url: https://registry.connect.redhat.com
    images: ②
      - <image_1>
      - <image_2>
    white_list:
      - ".*-apb$"
```

① See [Storing Registry Credentials](#) for other authentication options.

② Because the **openshift** type currently cannot search the configured registry, it is required that you configure the broker with a list of images you would like to source from for when the broker bootstraps. The image names must be the fully qualified name without the registry URL.

### 7.3.9. Multiple Registries

You can use more than one registry to separate APBs into logical organizations and be able to manage them from the same broker. The registries must have a unique, non-empty name. If there is no unique name, the service broker will fail to start with an error message alerting you to the problem.

```
registry:
  - name: dockerhub
    type: dockerhub
```

```

org: ansibleplaybookbundle
user: <user>
pass: <password>
white_list:
  - ".*-apb$"
- name: rhcc
  type: rhcc
  url: <rhcc_url>
  white_list:
    - ".*-apb$"

```

## 7.4. DAO CONFIGURATION

| Field            | Description                                                | Required |
|------------------|------------------------------------------------------------|----------|
| <b>etcd_host</b> | The URL of the etcd host.                                  | Y        |
| <b>etcd_port</b> | The port to use when communicating with <b>etcd_host</b> . | Y        |

## 7.5. LOG CONFIGURATION

| Field          | Description                       | Required |
|----------------|-----------------------------------|----------|
| <b>logfile</b> | Where to write the broker's logs. | Y        |
| <b>stdout</b>  | Write logs to stdout.             | Y        |
| <b>level</b>   | Level of the log output.          | Y        |
| <b>color</b>   | Color the logs.                   | Y        |

## 7.6. OPENSHIFT CONFIGURATION

| Field                    | Description                                 | Required |
|--------------------------|---------------------------------------------|----------|
| <b>host</b>              | OpenShift Container Platform host.          | N        |
| <b>ca_file</b>           | Location of the certificate authority file. | N        |
| <b>bearer_token_file</b> | Location of bearer token to be used.        | N        |
| <b>image_pull_policy</b> | When to pull the image.                     | Y        |

| Field                          | Description                                                                                                        | Required |
|--------------------------------|--------------------------------------------------------------------------------------------------------------------|----------|
| <b>namespace</b>               | The namespace that the broker has been deployed to. Important for things like passing parameter values via secret. | Y        |
| <b>sandbox_role</b>            | Role to give to an APB sandbox environment.                                                                        | Y        |
| <b>keep_namespace</b>          | Always keep namespace after an APB execution.                                                                      | N        |
| <b>keep_namespace_on_error</b> | Keep namespace after an APB execution has an error.                                                                | N        |

## 7.7. BROKER CONFIGURATION

The **broker** section tells the broker what functionality should be enabled and disabled. It will also tell the broker where to find files on disk that will enable the full functionality.

| Field                       | Description                                                                                                     | Default Value | Required |
|-----------------------------|-----------------------------------------------------------------------------------------------------------------|---------------|----------|
| <b>dev_broker</b>           | Allow development routes to be accessible.                                                                      | <b>false</b>  | N        |
| <b>launch_apb_on_bind</b>   | Allow bind to be a no-op.                                                                                       | <b>false</b>  | N        |
| <b>bootstrap_on_startup</b> | Allow the broker attempt to bootstrap itself on start up. Will retrieve the APBs from configured registries.    | <b>false</b>  | N        |
| <b>recovery</b>             | Allow the broker to attempt to recover itself by dealing with pending jobs noted in etcd.                       | <b>false</b>  | N        |
| <b>output_request</b>       | Allow the broker to output the requests to the log file as they come in for easier debugging.                   | <b>false</b>  | N        |
| <b>ssl_cert_key</b>         | Tells the broker where to find the TLS key file. If not set, the API server will attempt to create one.         | ""            | N        |
| <b>ssl_cert</b>             | Tells the broker where to find the TLS <b>.crt</b> file. If not set, the API server will attempt to create one. | ""            | N        |
| <b>refresh_interval</b>     | The interval to query registries for new image specs.                                                           | <b>"600s"</b> | N        |
| <b>auto_escalate</b>        | Allows the broker to escalate the permissions of a user while running the APB.                                  | <b>false</b>  | N        |

| Field              | Description                                               | Default Value                 | Required |
|--------------------|-----------------------------------------------------------|-------------------------------|----------|
| <b>cluster_url</b> | Sets the prefix for the URL that the broker is expecting. | <b>ansible-service-broker</b> | N        |



### NOTE

Async bind and unbind is an experimental feature and is not supported or enabled by default. With the absence of async bind, setting **launch\_apb\_on\_bind** to **true** can cause the bind action to timeout and will span a retry. The broker will handle this with "409 Conflicts" because it is the same bind request with different parameters.

## 7.8. SECRETS CONFIGURATION

The **secrets** section creates associations between secrets in the broker's namespace and APBs the broker runs. The broker uses these rules to mount secrets into running APBs, allowing the user to use secrets to pass parameters without exposing them to the catalog or users.

The section is a list where each entry has the following structure:

| Field           | Description                                                                                                                                       | Required |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------|----------|
| <b>title</b>    | The title of the rule. This is just for display and output purposes.                                                                              | Y        |
| <b>apb_name</b> | The name of the APB to associate with the specified secret. This is the fully qualified name ( <b>&lt;registry_name&gt;-&lt;image_name&gt;</b> ). | Y        |
| <b>secret</b>   | The name of the secret to pull parameters from.                                                                                                   | Y        |

You can download and use the [\*\*create\\_broker\\_secret.py\*\*](#) file to create and format this configuration section.

```
secrets:
- title: Database credentials
  secret: db_creds
  apb_name: dh-rhscl-postgresql-apb
```

## 7.9. RUNNING BEHIND A PROXY

When running the OAB inside of a proxied OpenShift Container Platform cluster, it is important to understand its core concepts and consider them within the context of a proxy used for external network access.

As an overview, the broker itself runs as a pod within the cluster. It has a requirement for external network access depending on how its registries have been configured.

### 7.9.1. Registry Adapter Whitelists

The broker's configured registry adapters must be able to communicate with their external registries in order to bootstrap successfully and load remote APB manifests. These requests can be made via the proxy, however, the proxy must ensure that the required remote hosts are accessible.

Example required whitelisted hosts:

| Registry Adapter Type  | Whitelisted Hosts                                                           |
|------------------------|-----------------------------------------------------------------------------|
| <code>rhcc</code>      | <code>registry.access.redhat.com</code> ,<br><code>access.redhat.com</code> |
| <code>dockerhub</code> | <code>docker.io</code>                                                      |

### 7.9.2. Configuring the Broker Behind a Proxy Using Ansible

If during initial installation you configure your OpenShift Container Platform cluster to run behind a proxy (see [Configuring Global Proxy Options](#)), when the OAB is deployed it will:

- inherit those cluster-wide proxy settings automatically and
- generate the required `NO_PROXY` list, including the `cidr` fields and `serviceNetworkCIDR`,

and no further configuration is needed.

### 7.9.3. Configuring the Broker Behind a Proxy Manually

If your cluster's global proxy options were not configured during initial installation or prior to the broker being deployed, or if you have modified the global proxy settings, you must manually configure the broker for external access via proxy:

1. Before attempting to run the OAB behind a proxy, review [Working with HTTP Proxies](#) and ensure your cluster is configured accordingly to run behind a proxy.  
In particular, the cluster must be configured to *not* proxy internal cluster requests. This is typically configured with a `NO_PROXY` setting of:

```
.cluster.local,.svc,<serviceNetworkCIDR_value>,<master_IP>,
<master_domain>,.default
```

in addition to any other desired `NO_PROXY` settings. See [Configuring NO\\_PROXY](#) for more details.



#### NOTE

Brokers deploying unversioned, or v1 APBs *must* also add `172.30.0.1` to their `NO_PROXY` list. APBs prior to v2 extracted their credentials from running APB pods via an `exec` HTTP request, rather than a secret exchange. Unless you are running a broker with experimental proxy support in a cluster prior to OpenShift Container Platform 3.9, you probably do not have to worry about this.

2. Edit the broker's `DeploymentConfig` as a user with `cluster-admin` privileges:

```
$ oc edit dc/asb -n openshift-ansible-service-broker
```

3. Set the following environment variables:

- **HTTP\_PROXY**
- **HTTPS\_PROXY**
- **NO\_PROXY**

**NOTE**

See [Setting Proxy Environment Variables in Pods](#) for more information.

4. After saving any updates, redeploy the OAB's deployment configuration for the changes to take effect:

```
$ oc rollout latest dc/asb -n openshift-ansible-service-broker
```

#### 7.9.4. Setting Proxy Environment Variables in Pods

It is common that APB pods themselves may require external access via proxy as well. If the broker recognizes it has a proxy configuration, it will transparently apply these environment variables to the APB pods that it spawns. As long as the modules used within the APB respect proxy configuration via environment variable, the APB will also use these settings to perform its work.

Finally, it is possible the services spawned by the APB may also require external network access via proxy. The APB *must* be authored to set these environment variables explicitly if recognizes them in its own execution environment, or the cluster operator must manually modify the required services to inject them into their environments.

# CHAPTER 8. ADDING HOSTS TO AN EXISTING CLUSTER

## 8.1. OVERVIEW

Depending on how your OpenShift Container Platform cluster was installed, you can add new hosts (either nodes or masters) to your installation by using the install tool for quick installations, or by using the `scaleup.yml` playbook for advanced installations.

## 8.2. ADDING HOSTS USING THE QUICK INSTALLER TOOL

If you used the quick install tool to install your OpenShift Container Platform cluster, you can use the quick install tool to add a new node host to your existing cluster.



### NOTE

Currently, you can not use the quick installer tool to add new master hosts. You must use the [advanced installation](#) method to do so.

If you used the installer in either [interactive](#) or [unattended](#) mode, you can re-run the installation as long as you have an [installation configuration file](#) at `~/.config/openshift/installer.cfg.yml` (or specify a different location with the `-c` option).



### IMPORTANT

See the [cluster limits](#) section for the recommended maximum number of nodes.

To add nodes to your installation:

1. Ensure you have the latest installer and playbooks by updating the **atomic-openshift-utils** package:

```
# yum update atomic-openshift-utils
```

2. Run the installer with the **scaleup** subcommand in interactive or unattended mode:

```
# atomic-openshift-installer [-u] [-c </path/to/file>] scaleup
```

3. The installer detects your current environment and allows you to add additional nodes:

```
*** Installation Summary ***
```

```
Hosts:
```

- 100.100.1.1
  - OpenShift master
  - OpenShift node
  - Etcd (Embedded)
  - Storage

```
Total OpenShift masters: 1
```

```
Total OpenShift nodes: 1
```

---

We have detected this previously installed OpenShift environment.

This tool will guide you through the process of adding additional nodes to your cluster.

Are you ready to continue? [y/N]:

Choose (y) and follow the on-screen instructions to complete your desired task.

## 8.3. ADDING HOSTS

You can add new hosts to your cluster by running the ***scaleup.yml*** playbook. This playbook queries the master, generates and distributes new certificates for the new hosts, and then runs the configuration playbooks on only the new hosts. Before running the ***scaleup.yml*** playbook, complete all prerequisite [host preparation](#) steps.



### IMPORTANT

The ***scaleup.yml*** playbook configures only the new host. It does not update ***NO\_PROXY*** in master services, and it does not restart master services.

You must have an existing inventory file, for example ***/etc/ansible/hosts***, that is representative of your current cluster configuration in order to run the ***scaleup.yml*** playbook. If you previously used the ***atomic-openshift-installer*** command to run your installation, you can check ***~/.config/openshift/hosts*** for the last inventory file that the installer generated and use that file as your inventory file. You can modify this file as required. You must then specify the file location with ***-i*** when you run the ***ansible-playbook***.



### IMPORTANT

See the [cluster limits](#) section for the recommended maximum number of nodes.

### Procedure

1. Ensure you have the latest playbooks by updating the ***atomic-openshift-utils*** package:

```
# yum update atomic-openshift-utils
```

2. Edit your ***/etc/ansible/hosts*** file and add ***new\_<host\_type>*** to the ***[OSEv3:children]*** section:  
For example, to add a new node host, add ***new\_nodes***:

```
[OSEv3:children]
masters
nodes
new_nodes
```

To add new master hosts, add ***new\_masters***.

3. Create a ***[new\_<host\_type>]*** section to specify host information for the new hosts. Format this section like an existing section, as shown in the following example of adding a new node:

```
[nodes]
master[1:3].example.com
node1.example.com openshift_node_labels="{'region': 'primary',
'zone': 'east'}"
node2.example.com openshift_node_labels="{'region': 'primary',
'zone': 'west'}"
infra-node1.example.com openshift_node_labels="{'region': 'infra',
'zone': 'default'}"
infra-node2.example.com openshift_node_labels="{'region': 'infra',
'zone': 'default'}"

[new_nodes]
node3.example.com openshift_node_labels="{'region': 'primary',
'zone': 'west'}"
```

See [Configuring Host Variables](#) for more options.

When adding new masters, add hosts to both the **[new\_masters]** section and the **[new\_nodes]** section to ensure that the new master host is part of the OpenShift SDN.

```
[masters]
master[1:2].example.com

[new_masters]
master3.example.com

[nodes]
master[1:2].example.com
node1.example.com openshift_node_labels="{'region': 'primary',
'zone': 'east'}"
node2.example.com openshift_node_labels="{'region': 'primary',
'zone': 'west'}"
infra-node1.example.com openshift_node_labels="{'region': 'infra',
'zone': 'default'}"
infra-node2.example.com openshift_node_labels="{'region': 'infra',
'zone': 'default'}"

[new_nodes]
master3.example.com
```



## IMPORTANT

If you label a master host with the **region=infra** label and have no other dedicated infrastructure nodes, you must also explicitly mark the host as schedulable by adding **openshift\_schedulable=true** to the entry. Otherwise, the registry and router pods cannot be placed anywhere.

- Run the **scaleup.yml** playbook. If your inventory file is located somewhere other than the default of **/etc/ansible/hosts**, specify the location with the **-i** option.

- For additional nodes:

```
# ansible-playbook [-i /path/to/file] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
node/scaleup.yml
```

- For additional masters:

```
# ansible-playbook [-i /path/to/file] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
master/scaleup.yml
```

5. After the playbook runs, [verify the installation](#).
6. Move any hosts that you defined in the **[new\_<host\_type>]** section to their appropriate section. By moving these hosts, subsequent playbook runs that use this inventory file treat the nodes correctly. You can keep the empty **[new\_<host\_type>]** section. For example, when adding new nodes:

```
[nodes]
master[1:3].example.com
node1.example.com openshift_node_labels="{'region': 'primary',
'zone': 'east'}"
node2.example.com openshift_node_labels="{'region': 'primary',
'zone': 'west'}"
node3.example.com openshift_node_labels="{'region': 'primary',
'zone': 'west'}"
infra-node1.example.com openshift_node_labels="{'region': 'infra',
'zone': 'default'}"
infra-node2.example.com openshift_node_labels="{'region': 'infra',
'zone': 'default'}"

[new_nodes]
```

## 8.4. ADDING ETCD HOSTS TO EXISTING CLUSTER

You can add new etcd hosts to your cluster by running the *etcd scaleup* playbook. This playbook queries the master, generates and distributes new certificates for the new hosts, and then runs the configuration playbooks on the new hosts only. Before running the etcd **scaleup.yml** playbook, complete all prerequisite [host preparation](#) steps.

To add an etcd host to an existing cluster:

1. Ensure you have the latest playbooks by updating the **atomic-openshift-utils** package:

```
$ yum update atomic-openshift-utils
```

2. Edit your **/etc/ansible/hosts** file, add **new\_<host\_type>** to the **[OSEv3:children]** group and add hosts under the **new\_<host\_type>** group:

For example, to add a new etcd, add **new\_etcd**:

```
[OSEv3:children]
masters
nodes
etcd
new_etcd
```

```
[etcd]
etcd1.example.com
etcd2.example.com

[new_etcd]
etcd3.example.com
```

- Run the etcd ***scaleup.yml*** playbook. If your inventory file is located somewhere other than the default of **/etc/ansible/hosts**, specify the location with the **-i** option.

```
$ ansible-playbook [-i /path/to/file] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    etcd/scaleup.yml
```

- After the playbook completes successfully, [verify the installation](#).

## 8.5. REPLACING EXISTING MASTERS WITH ETCD COLOCATED

Follow these steps when you are migrating your machines to a different data center and the network and IPs assigned to it will change.

- Back up the primary **etcd** and **master** nodes.



### IMPORTANT

Ensure that you back up the **/etc/etcd/** directory, as noted in the [etcd backup](#) instructions.

- Provision as many new machines as there are masters to replace.
- Add or expand the cluster. for example, if you want to add 3 masters with etcd colocated, scale up 3 master nodes or 3 etcd nodes.
  - Add a **master**. In step 3 of that process, add the host of the new data center in **[new\_masters]** and **[new\_nodes]** and run the master ***scaleup.yml*** playbook.
  - Put the same host in the **etcd** section and run the etcd ***scaleup.yml*** playbook.
  - Verify that the host was added:
- Verify that the master host IP was added:
- Verify that etcd was added. The value of **ETCDCTL\_API** depends on the version being used:

```
# source /etc/etcd/etcd.conf
# ETCDCTL_API=2 etcdctl --cert-file=$ETCD_PEER_CERT_FILE --key-
file=$ETCD_PEER_KEY_FILE \
--ca-file=/etc/etcd/ca.crt --endpoints=$ETCD_LISTEN_CLIENT_URLS
member list
```

- f. Copy `/etc/origin/master/ca.serial.txt` from the `/etc/origin/master` directory to the new master host that is listed first in your inventory file. By default, this is `/etc/ansible/hosts`.
4. Remove the etcd hosts.
- a. Copy the `/etc/etcd/ca` directory to the new etcd host that is listed first in your inventory file. By default, this is `/etc/ansible/hosts`.
  - b. Remove the old etcd clients from the `master-config.yaml` file:
- ```
# grep etcdClientInfo -A 11 /etc/origin/master/master-config.yaml
```
- c. Restart the masters:
- ```
# systemctl restart atomic-openshift-master-*
```
- d. Remove the old etcd members from the cluster. The value of `ETCDCTL_API` depends on the version being used:
- ```
# source /etc/etcd/etcd.conf
# ETCDCTL_API=2 etcdctl --cert-file=$ETCD_PEER_CERT_FILE --key-file=$ETCD_PEER_KEY_FILE \
--ca-file=/etc/etcd/ca.crt --endpoints=$ETCD_LISTEN_CLIENT_URLS
member list
```
- e. Take the IDs from the output of the command above and remove the old members using the IDs:
- ```
# etcdctl --cert-file=$ETCD_PEER_CERT_FILE --key-file=$ETCD_PEER_KEY_FILE \
--ca-file=/etc/etcd/ca.crt --endpoints=$ETCD_LISTEN_CLIENT_URL
member remove 1609b5a3a078c227
```
- f. Stop and disable the etcd services on the old etcd hosts:
- ```
# systemctl stop etcd
# systemctl disable etcd
```
5. Shut down old master API and controller services:
- ```
# systemctl stop atomic-openshift-master-api
```
6. Remove the master nodes from the HA proxy configuration, which was installed as a load balancer by default during the native installation process.
7. Decommission the machine.
- a. Stop the `atomic-openshift-node` service on the master to be removed:
- ```
# systemctl stop atomic-openshift-node
```
- b. Delete the node resource:

```
# oc delete node
```

## 8.6. MIGRATING THE NODES

You can migrate nodes individually or in groups (of 2, 5, 10, and so on), depending on what you are comfortable with and how the services on the node are run and scaled.

1. For the migration node or nodes, provision new VMs for the node's use in the new data center.
2. To add the new node, [scale up the infrastructure](#). Ensure the labels for the new node are set properly and that your new API servers are added to your load balancer and successfully serving traffic.
3. Evaluate and scale down.
  - a. Mark the current node (in the old data center) [unscheduled](#).
  - b. [Evacuate the node](#), so that pods on it are scheduled to other nodes.
  - c. Verify that the evacuated services are running on the new nodes.
4. Remove the node.
  - a. Verify that the node is empty and does not have running processes.
  - b. Stop the service or delete the node.

# CHAPTER 9. LOADING THE DEFAULT IMAGE STREAMS AND TEMPLATES

## 9.1. OVERVIEW

Your OpenShift Container Platform installation includes useful sets of Red Hat-provided [image streams](#) and [templates](#) to make it easy for developers to create new applications. By default, the [quick](#) and [advanced installation](#) methods automatically create these sets in the **openshift** project, which is a default global project to which all users have view access.

## 9.2. OFFERINGS BY SUBSCRIPTION TYPE

Depending on the active subscriptions on your Red Hat account, the following sets of image streams and templates are provided and supported by Red Hat. Contact your Red Hat sales representative for further subscription details.

### 9.2.1. OpenShift Container Platform Subscription

The core set of image streams and templates are provided and supported with an active *OpenShift Container Platform subscription*. This includes the following technologies:

Type	Technology
Languages & Frameworks	<ul style="list-style-type: none"><li>• <a href="#">.NET Core</a></li><li>• <a href="#">Node.js</a></li><li>• <a href="#">Perl</a></li><li>• <a href="#">PHP</a></li><li>• <a href="#">Python</a></li><li>• <a href="#">Ruby</a></li></ul>
Databases	<ul style="list-style-type: none"><li>• <a href="#">MariaDB</a></li><li>• <a href="#">MongoDB</a></li><li>• <a href="#">MySQL</a></li><li>• <a href="#">PostgreSQL</a></li></ul>
Middleware Services	<ul style="list-style-type: none"><li>• <a href="#">Red Hat JBoss Web Server</a> (Tomcat)</li><li>• <a href="#">Red Hat Single Sign-on</a></li></ul>

Type	Technology
Other Services	<ul style="list-style-type: none"> <li>• <a href="#">Jenkins</a></li> <li>• <a href="#">Jenkins Slaves</a></li> </ul>

## 9.2.2. xPaaS Middleware Add-on Subscriptions

Support for xPaaS middleware images are provided by *xPaaS Middleware add-on subscriptions*, which are separate subscriptions for each xPaaS product. If the relevant subscription is active on your account, image streams and templates are provided and supported for the following technologies:

Type	Technology
Middleware Services	<ul style="list-style-type: none"> <li>• <a href="#">Red Hat JBoss A-MQ</a></li> <li>• <a href="#">Red Hat JBoss BPM Suite Intelligent Process Server</a></li> <li>• <a href="#">Red Hat JBoss BRMS Decision Server</a></li> <li>• <a href="#">Red Hat JBoss Data Grid</a></li> <li>• <a href="#">Red Hat JBoss EAP</a></li> <li>• <a href="#">Red Hat JBoss Fuse Integration Services</a></li> <li>• <a href="#">Red Hat JBoss Data Virtualization</a></li> </ul>

## 9.3. BEFORE YOU BEGIN

Before you consider performing the tasks in this topic, confirm if these image streams and templates are already registered in your OpenShift Container Platform cluster by doing one of the following:

- Log into the web console and click **Add to Project**
- List them for the **openshift** project using the CLI:

```
$ oc get is -n openshift
$ oc get templates -n openshift
```

If the default image streams and templates are ever removed or changed, you can follow this topic to create the default objects yourself. Otherwise, the following instructions are not necessary.

## 9.4. PREREQUISITES

Before you can create the default image streams and templates:

- The [Integrated Docker registry](#) service must be deployed in your OpenShift Container Platform installation.

- You must be able to run the `oc create` command with [cluster-admin privileges](#), because they operate on the default `openshift` project.
- You must have installed the `atomic-openshift-utils` RPM package. See [Software Prerequisites](#) for instructions.
- Define shell variables for the directories containing image streams and templates. This significantly shortens the commands in the following sections. To do this:

```
$ IMAGESTREAMDIR="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.9/image-streams";
 \
 XPAASSTREAMDIR="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.9/xpaas-streams";
 \
 XPAASTEMPLATES="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.9/xpaas-
templates"; \
 DBTEMPLATES="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.9/db-templates";
 \
 QSTEMPLATES="/usr/share/ansible/openshift-
ansible/roles/openshift_examples/files/examples/v3.9/quickstart-
templates"
```

## 9.5. CREATING IMAGE STREAMS FOR OPENSHIFT CONTAINER PLATFORM IMAGES

If your node hosts are subscribed using Red Hat Subscription Manager and you want to use the core set of image streams that used Red Hat Enterprise Linux (RHEL) 7 based images:

```
$ oc create -f $IMAGESTREAMDIR/image-streams-rhel7.json -n openshift
```

Alternatively, to create the core set of image streams that use the CentOS 7 based images:

```
$ oc create -f $IMAGESTREAMDIR/image-streams-centos7.json -n openshift
```

Creating both the CentOS and RHEL sets of image streams is not possible, because they use the same names. To have both sets of image streams available to users, either create one set in a different project, or edit one of the files and modify the image stream names to make them unique.

## 9.6. CREATING IMAGE STREAMS FOR XPAAS MIDDLEWARE IMAGES

The xPaaS Middleware image streams provide images for **JBoss EAP**, **JBoss JWS**, **JBoss A-MQ**, **JBoss Fuse Integration Services**, **Decision Server**, **JBoss Data Virtualization** and **JBoss Data Grid**. They can be used to build applications for those platforms using the provided templates.

To create the xPaaS Middleware set of image streams:

```
$ oc create -f $XPAASSTREAMDIR/jboss-image-streams.json -n openshift
```

**NOTE**

Access to the images referenced by these image streams requires the relevant xPaaS Middleware subscriptions.

## 9.7. CREATING DATABASE SERVICE TEMPLATES

The database service templates make it easy to run a database image which can be utilized by other components. For each database ([MongoDB](#), [MySQL](#), and [PostgreSQL](#)), two templates are defined.

One template uses ephemeral storage in the container which means data stored will be lost if the container is restarted, for example if the pod moves. This template should be used for demonstration purposes only.

The other template defines a persistent volume for storage, however it requires your OpenShift Container Platform installation to have [persistent volumes](#) configured.

To create the core set of database templates:

```
$ oc create -f $DBTEMPLATES -n openshift
```

After creating the templates, users are able to easily instantiate the various templates, giving them quick access to a database deployment.

## 9.8. CREATING INSTANT APP AND QUICKSTART TEMPLATES

The Instant App and Quickstart templates define a full set of objects for a running application. These include:

- [Build configurations](#) to build the application from source located in a GitHub public repository
- [Deployment configurations](#) to deploy the application image after it is built.
- [Services](#) to provide load balancing for the application [pods](#).
- [Routes](#) to provide external access to the application.

Some of the templates also define a database deployment and service so the application can perform database operations.

**NOTE**

The templates which define a database use ephemeral storage for the database content. These templates should be used for demonstration purposes only as all database data will be lost if the database pod restarts for any reason.

Using these templates, users are able to easily instantiate full applications using the various language images provided with OpenShift Container Platform. They can also customize the template parameters during instantiation so that it builds source from their own repository rather than the sample repository, so this provides a simple starting point for building new applications.

To create the core Instant App and Quickstart templates:

```
$ oc create -f $QSTEMPLATES -n openshift
```

There is also a set of templates for creating applications using various xPaaS Middleware products (**JBoss EAP**, **JBoss JWS**, **JBoss A-MQ**, **JBoss Fuse Integration Services**, **Decision Server**, and **JBoss Data Grid**), which can be registered by running:

```
$ oc create -f $XPAASTEMPLATES -n openshift
```



#### NOTE

The xPaaS Middleware templates require the [xPaaS Middleware image streams](#), which in turn require the relevant xPaaS Middleware subscriptions.



#### NOTE

The templates which define a database use ephemeral storage for the database content. These templates should be used for demonstration purposes only as all database data will be lost if the database pod restarts for any reason.

## 9.9. WHAT'S NEXT?

With these artifacts created, developers can now [log into the web console](#) and follow the flow for creating [from a template](#). Any of the database or application templates can be selected to create a running database service or application in the current project. Note that some of the application templates define their own database services as well.

The example applications are all built out of GitHub repositories which are referenced in the templates by default, as seen in the **SOURCE\_REPOSITORY\_URL** parameter value. Those repositories can be forked, and the fork can be provided as the **SOURCE\_REPOSITORY\_URL** parameter value when creating from the templates. This allows developers to experiment with creating their own applications.

You can direct your developers to the [Using the Instant App and Quickstart Templates](#) section in the Developer Guide for these instructions.

# CHAPTER 10. CONFIGURING CUSTOM CERTIFICATES

## 10.1. OVERVIEW

Administrators can configure custom serving certificates for the public host names of the OpenShift Container Platform API and [web console](#). This can be done during an [advanced installation](#) or configured after installation.

## 10.2. CONFIGURING CUSTOM CERTIFICATES DURING INSTALLATION

During [advanced installations](#), custom certificates can be configured using the `openshift_master_named_certificates` and `openshift_master_overwrite_named_certificates` parameters, which are configurable in the inventory file. More details are available about [configuring custom certificates with Ansible](#).

### Custom Certificate Configuration Parameters

```
openshift_master_overwrite_named_certificates=true ①
openshift_master_named_certificates=[{"certfile": "/path/on/host/to/crt-
file", "keyfile": "/path/on/host/to/key-file", "names": ["public-master-
host.com"], "cafle": "/path/on/host/to/ca-file"}] ②
openshift_hosted_router_certificate={"certfile": "/path/on/host/to/app-
crt-file", "keyfile": "/path/on/host/to/app-key-file", "cafle":
"/path/on/host/to/app-ca-file"} ③
```

- ① If you provide a value for the `openshift_master_named_certificates` parameter, set this parameter to `true`.
- ② Provisions a [master API certificate](#).
- ③ Provisions a [wildcard API certificate](#).

Example parameters for a master API certificate:

```
openshift_master_overwrite_named_certificates=true
openshift_master_named_certificates=[{"names":
["master.148.251.233.173.nip.io"], "certfile": "/home/cloud-user/master-
bundle.cert.pem", "keyfile": "/home/cloud-
user/master.148.251.233.173.nip.io.key.pem" }]
```

Example parameters for a wildcard API certificate:

```
openshift_hosted_router_certificate={"certfile": "/home/cloud-user/star-
apps.148.251.233.173.nip.io.cert.pem", "keyfile": "/home/cloud-user/star-
apps.148.251.233.173.nip.io.key.pem", "cafle": "/home/cloud-user/ca-
chain.cert.pem"}
```

## 10.3. CONFIGURING CUSTOM CERTIFICATES FOR THE WEB CONSOLE OR CLI

You can specify custom certificates for the web console and for the CLI through the **servingInfo** section of the [master configuration file](#):

- The **servingInfo.namedCertificates** section serves up custom certificates for the web console.
- The **servingInfo** section serves up custom certificates for the CLI and other API calls.

You can configure multiple certificates this way, and each certificate can be associated with [multiple host names](#), [multiple routers](#), or the [OpenShift Container Platform image registry](#).

A default certificate must be configured in the **servingInfo.certFile** and **servingInfo.keyFile** configuration sections in addition to **namedCertificates**.



### NOTE

The **namedCertificates** section should be configured only for the host name associated with the **masterPublicURL** and **oauthConfig.assetPublicURL** settings in the `/etc/origin/master/master-config.yaml` file. Using a custom serving certificate for the host name associated with the **masterURL** will result in TLS errors as infrastructure components will attempt to contact the master API using the internal **masterURL** host.

## Custom Certificates Configuration

```
servingInfo:
  logoutURL: ""
  masterPublicURL: https://openshift.example.com:8443
  publicURL: https://openshift.example.com:8443/console/
  bindAddress: 0.0.0.0:8443
  bindNetwork: tcp4
  certFile: master.server.crt ①
  clientCA: ""
  keyFile: master.server.key ②
  maxRequestsInFlight: 0
  requestTimeoutSeconds: 0
  namedCertificates:
    - certFile: wildcard.example.com.crt ③
      keyFile: wildcard.example.com.key ④
      names:
        - "openshift.example.com"
  metricsPublicURL: "https://metrics.os.example.com/hawkular/metrics"
```

① ② Path to certificate and key files for the CLI and other API calls.

③ ④ Path to certificate and key files for the web console.

The **openshift\_master\_cluster\_public\_hostname** and **openshift\_master\_cluster\_hostname** parameters in the [Ansible inventory file](#), by default `/etc/ansible/hosts`, must be different. If they are the same, the named certificates will fail and you will need to re-install them.

```
# Native HA with External LB VIPs
openshift_master_cluster_hostname=internal.paas.example.com
openshift_master_cluster_public_hostname=external.paas.example.com
```

For more information on using DNS with OpenShift Container Platform, see the [DNS installation prerequisites](#).

This approach allows you to take advantage of the self-signed certificates generated by OpenShift Container Platform and add custom trusted certificates to individual components as needed.

Note that the internal infrastructure certificates remain self-signed, which might be perceived as bad practice by some security or PKI teams. However, any risk here is minimal, as the only clients that trust these certificates are other components within the cluster. All external users and systems use custom trusted certificates.

Relative paths are resolved based on the location of the master configuration file. Restart the server to pick up the configuration changes.

## 10.4. CONFIGURING A CUSTOM MASTER HOST CERTIFICATE

In order to facilitate trusted connections with external users of OpenShift Container Platform, you can provision a named certificate that matches the domain name provided in the `openshift_master_cluster_public_hostname` parameter in the [Ansible inventory file](#), by default `/etc/ansible/hosts`.

You must place this certificate in a directory accessible to Ansible and add the path in the Ansible inventory file, as follows:

```
openshift_master_named_certificates=[{"certfile": "/path/to/console.ocp-c1.myorg.com.crt", "keyfile": "/path/to/console.ocp-c1.myorg.com.key", "names": ["console.ocp-c1.myorg.com"]}]
```

Where the parameter values are:

- **certfile** is the path to the file that contains the OpenShift Container Platform router certificate.
- **keyfile** is the path to the file that contains the OpenShift Container Platform wildcard key.
- **names** is the cluster public hostname.

The file paths must be local to the system where Ansible runs. Certificates are copied to master hosts and are deployed within the `/etc/origin/master` directory.

When securing the registry, add the service hostnames and IP addresses to the server certificate for the registry. The Subject Alternative Names (SAN) must contain the following.

- Two service hostnames:

```
docker-registry.default.svc.cluster.local
docker-registry.default.svc
```

- Service IP address.

For example:

```
172.30.252.46
```

■ Use the following command to get the Docker registry service IP address:

```
oc get service docker-registry --template='{{.spec.clusterIP}}'
```

- Public hostname.

```
docker-registry-default.apps.example.com
```

Use the following command to get the Docker registry public hostname:

```
oc get route docker-registry --template '{{.spec.host}}'
```

For example, the server certificate should contain SAN details similar to the following:

```
X509v3 Subject Alternative Name:  
DNS:docker-registry-public.openshift.com, DNS:docker-  
registry.default.svc, DNS:docker-registry.default.svc.cluster.local,  
DNS:172.30.2.98, IP Address:172.30.2.98
```

## 10.5. CONFIGURING A CUSTOM WILDCARD CERTIFICATE FOR THE DEFAULT ROUTER

You can configure the OpenShift Container Platform default router with a default wildcard certificate. A default wildcard certificate provides a convenient way for applications that are deployed in OpenShift Container Platform to use default encryption without needing custom certificates.



### NOTE

Default wildcard certificates are recommended for non-production environments only.

In order to configure a default wildcard certificate, provision a certificate that is valid for .

<app\_domain>, where <app\_domain> is the value of `openshift_master_default_subdomain` in the [Ansible inventory file](#), by default `/etc/ansible/hosts`. Once provisioned, place the certificate, key, and ca certificate files on your Ansible host, and add the following line to your Ansible inventory file.

```
openshift_hosted_router_certificate={"certfile": "/path/to/apps.c1-  
ocp.myorg.com.crt", "keyfile": "/path/to/apps.c1-ocp.myorg.com.key",  
"cafle": "/path/to/apps.c1-ocp.myorg.com.ca.crt"}
```

For example:

```
openshift_hosted_router_certificate={"certfile": "/home/cloud-user/star-  
apps.148.251.233.173.nip.io.cert.pem", "keyfile": "/home/cloud-user/star-  
apps.148.251.233.173.nip.io.key.pem", "cafle": "/home/cloud-user/ca-  
chain.cert.pem"}
```

Where the parameter values are:

- **certfile** is the path to the file that contains the OpenShift Container Platform router certificate.

- **keyfile** is the path to the file that contains the OpenShift Container Platform wildcard key.
- **cafile** is the path to the file that contains the root CA for this key and certificate. If an intermediate CA is in use, the file should contain both the intermediate and root CA.

If these certificate files are new to your OpenShift Container Platform cluster, run the Ansible **`deploy_router.yml`** playbook to add these files to the OpenShift Container Platform configuration files. The playbook adds the certificate files to the **`/etc/origin/master`** directory.

```
# ansible-playbook [-i /path/to/inventory] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
hosted/deploy_router.yml
```

If [the certificates are not new](#), for example, you want to change existing certificates or replace expired certificates, run the following playbook:

```
ansible-playbook /usr/share/ansible/openshift-ansible/playbooks/redeploy-
certificates.yml
```



#### NOTE

For this playbook to run, the certificate names must not change. If the certificate names change, rerun the Ansible **`deploy_cluster.yml`** playbook as if the certificates were new.

## 10.6. CONFIGURING A CUSTOM CERTIFICATE FOR THE IMAGE REGISTRY

The OpenShift Container Platform image registry is an internal service that facilitates builds and deployments. Most of the communication with the registry is handled by internal components in OpenShift Container Platform. As such, you should not need to replace the certificate used by the registry service itself.

However, by default, the registry uses routes to allow external systems and users to do pulls and pushes of images. You can use a *re-encrypt route* with a custom certificate that is presented to external users instead of using the internal, self-signed certificate.

To configure this, add the [following lines](#) of code to the [OSEv3:vars] section of the Ansible inventory file, by default `/etc/ansible/hosts` file. Specify the certificates to use with the registry route.

```
openshift_hosted_registry_routehost=registry.apps.c1-ocp.myorg.com ①
openshift_hosted_registry_routecertificates={"certfile": "/path/to/registry.apps.c1-ocp.myorg.com.crt", "keyfile": "/path/to/registry.apps.c1-ocp.myorg.com.key", "cafile": "/path/to/registry.apps.c1-ocp.myorg.com-ca.crt"} ②
openshift_hosted_registry_routetermination=reencrypt ③
```

① The host name of the registry.

② The locations of the **cacert**, **root**, and **cafile** files.

- **certfile** is the path to the file that contains the OpenShift Container Platform router certificate.

- **keyfile** is the path to the file that contains the OpenShift Container Platform wildcard key.
- **cafile** is the path to the file that contains the root CA for this key and certificate. If an intermediate CA is in use, the file should contain both the intermediate and root CA.

**3** Specify where encryption is performed:

- Set to **reencrypt** with a *re-encrypt route* to terminate encryption at the edge router and re-encrypt it with a new certificate supplied by the destination.
- Set to **passthrough** to terminate encryption at the destination. The destination is responsible for decrypting traffic.

## 10.7. CONFIGURING A CUSTOM CERTIFICATE FOR A LOAD BALANCER

If your OpenShift Container Platform cluster uses the default load balancer or an enterprise-level load balancer, you can use custom certificates to make the web console and API available externally using a publicly-signed custom certificate, leaving the existing internal certificates for the internal endpoints.

To configure OpenShift Container Platform to use custom certificates in this way:

1. Edit the **servingInfo** section of the [master configuration file](#):

```
servingInfo:
  logoutURL: ""
  masterPublicURL: https://openshift.example.com:8443
  publicURL: https://openshift.example.com:8443/console/
  bindAddress: 0.0.0.0:8443
  bindNetwork: tcp4
  certFile: master.server.crt
  clientCA: ""
  keyFile: master.server.key
  maxRequestsInFlight: 0
  requestTimeoutSeconds: 0
  namedCertificates:
    - certFile: wildcard.example.com.crt 1
      keyFile: wildcard.example.com.key 2
      names:
        - "openshift.example.com"
  metricsPublicURL:
  "https://metrics.os.example.com/hawkular/metrics"
```

- 1 Path to the certificate file for the web console.
- 2 Path to the key file for the web console.

**NOTE**

Configure the `namedCertificates` section for only the host name associated with the `masterPublicURL` and `oauthConfig.assetPublicURL` settings. Using a custom serving certificate for the host name associated with the `masterURL` causes TLS errors as infrastructure components attempt to contact the master API using the internal masterURL host.

2. Specify the `openshift_master_cluster_public_hostname` and `openshift_master_cluster_hostname` parameters in the Ansible inventory file, by default `/etc/ansible/hosts`. These values must be different. If they are the same, the named certificates will fail.

```
# Native HA with External LB VIPs
openshift_master_cluster_hostname=paas.example.com ①
openshift_master_cluster_public_hostname=public.paas.example.com ②
```

- ① The FQDN for internal load balancer configured for SSL passthrough.
- ② The FQDN for external the load balancer with custom (public) certificate.

For information specific to your load balancer environment, refer to [the OpenShift Container Platform Reference Architecture for your provider](#) and [Custom Certificate SSL Termination \(Production\)](#).

## 10.8. RETROFIT CUSTOM CERTIFICATES INTO A CLUSTER

You can retrofit custom master and custom router certificates into an existing OpenShift Container Platform cluster by editing the the Ansible inventory file, by default `/etc/ansible/hosts`, and running a playbook.

### 10.8.1. Retrofit Custom Master Certificates into a Cluster

To retrofit custom certificates:

1. Edit the Ansible inventory file to set the `openshift_master_overwrite_named_certificates=true`.
2. Specify the path to the certificate using the `openshift_master_named_certificates` parameter.

```
openshift_master_overwrite_named_certificates=true
openshift_master_named_certificates=[{"certfile":
"/path/on/host/to/crt-file", "keyfile": "/path/on/host/to/key-file",
"names": ["public-master-host.com"], "cafile": "/path/on/host/to/ca-
file"}] ①
```

- ① Path to a master API certificate.

3. Run the following playbook:

```
ansible-playbook /usr/share/ansible/openshift-
ansible/playbooks/redeploy-certificates.yml
```

## 10.8.2. Retrofit Custom Router Certificates into a Cluster

To retrofit custom router certificates:

1. Edit the Ansible inventory file to set the `openshift_master_overwrite_named_certificates=true`.
2. Specify the path to the certificate using the `openshift_hosted_router_certificate` parameter.

```
openshift_master_overwrite_named_certificates=true
openshift_hosted_router_certificate={"certfile":
"/path/on/host/to/app-crt-file", "keyfile": "/path/on/host/to/app-
key-file", "cafile": "/path/on/host/to/app-ca-file"} ①
```

① Path to a [wildcard API certificate](#).

3. Run the following playbook:

```
ansible-playbook /usr/share/ansible/openshift-
ansible/playbooks/redeploy-router-certificates.yml
```

## 10.9. USING CUSTOM CERTIFICATES WITH OTHER COMPONENTS

For information on how other components, such as Logging & Metrics, use custom certificates, see [Certificate Management](#).

# CHAPTER 11. REDEPLOYING CERTIFICATES

## 11.1. OVERVIEW

OpenShift Container Platform uses certificates to provide secure connections for the following components:

- masters (API server and controllers)
- etcd
- nodes
- registry
- router

You can use Ansible playbooks provided with the installer to automate checking expiration dates for cluster certificates. Playbooks are also provided to automate backing up and redeploying these certificates, which can fix common certificate errors.

Possible use cases for redeploying certificates include:

- The installer detected the wrong host names and the issue was identified too late.
- The certificates are expired and you need to update them.
- You have a new CA and want to create certificates using it instead.

## 11.2. CHECKING CERTIFICATE EXPIRATIONS

You can use the installer to warn you about any certificates expiring within a configurable window of days and notify you about any certificates that have already expired. Certificate expiry playbooks use the Ansible role `openshift_certificate_expiry`.

Certificates examined by the role include:

- Master and node service certificates
- Router and registry service certificates from etcd secrets
- Master, node, router, registry, and `kubeconfig` files for `cluster-admin` users
- etcd certificates (including embedded)

### 11.2.1. Role Variables

The `openshift_certificate_expiry` role uses the following variables:

**Table 11.1. Core Variables**

Variable Name	Default Value	Description
<code>openshift_certificate_expiry_config_base</code>	<code>/etc/origin</code>	Base OpenShift Container Platform configuration directory.
<code>openshift_certificate_expiry_warning_days</code>	<code>30</code>	Flag certificates that will expire in this many days from now.
<code>openshift_certificate_expiry_show_all</code>	<code>no</code>	Include healthy (non-expired and non-warning) certificates in results.

**Table 11.2. Optional Variables**

Variable Name	Default Value	Description
<code>openshift_certificate_expiry_generate_html_report</code>	<code>no</code>	Generate an HTML report of the expiry check results.
<code>openshift_certificate_expiry_html_report_path</code>	<code>/tmp/cert-expiry-report.html</code>	The full path for saving the HTML report.
<code>openshift_certificate_expiry_save_json_results</code>	<code>no</code>	Save expiry check results as a JSON file.
<code>openshift_certificate_expiry_json_results_path</code>	<code>/tmp/cert-expiry-report.json</code>	The full path for saving the JSON report.

### 11.2.2. Running Certificate Expiration Playbooks

The OpenShift Container Platform installer provides a set of example certificate expiration playbooks, using different sets of configuration for the `openshift_certificate_expiry` role.

These playbooks must be used with an [inventory file](#) that is representative of the cluster. For best results, run `ansible-playbook` with the `-v` option.

Using the `easy-mode.yaml` example playbook, you can try the role out before tweaking it to your specifications as needed. This playbook:

- Produces JSON and stylized HTML reports in `/tmp/`.
- Sets the warning window very large, so you will almost always get results back.
- Includes all certificates (healthy or not) in the results.

#### `easy-mode.yaml` Playbook

```
- name: Check cert expirys
  hosts: nodes:masters:etcd
  become: yes
```

```

gather_facts: no
vars:
  openshift_certificate_expiry_warning_days: 1500
  openshift_certificate_expiry_save_json_results: yes
  openshift_certificate_expiry_generate_html_report: yes
  openshift_certificate_expiry_show_all: yes
roles:
  - role: openshift_certificate_expiry

```

To run the ***easy-mode.yaml*** playbook:

```
$ ansible-playbook -v -i <inventory_file> \
  /usr/share/ansible/openshift-ansible/playbooks/openshift-
checks/certificate_expiry/easy-mode.yaml
```

### Other Example Playbooks

The other example playbooks are also available to run directly out of the **/usr/share/ansible/openshift-ansible/playbooks/certificate\_expiry/** directory.

**Table 11.3. Other Example Playbooks**

File Name	Usage
<b><i>default.yaml</i></b>	Produces the default behavior of the <b>openshift_certificate_expiry</b> role.
<b><i>html_and_json_default_paths.yaml</i></b>	Generates HTML and JSON artifacts in their default paths.
<b><i>longer_warning_period.yaml</i></b>	Changes the expiration warning window to 1500 days.
<b><i>longer-warning-period-json-results.yaml</i></b>	Changes the expiration warning window to 1500 days and saves the results as a JSON file.

To run any of these example playbooks:

```
$ ansible-playbook -v -i <inventory_file> \
  /usr/share/ansible/openshift-ansible/playbooks/openshift-
checks/certificate_expiry/<playbook>
```

### 11.2.3. Output Formats

As noted above, there are two ways to format your check report. In JSON format for machine parsing, or as a stylized HTML page for easy skimming.

#### HTML Report

An example of an HTML report is provided with the installer. You can open the following file in your browser to view it:

***/usr/share/ansible/openshift-ansible/roles/openshift\_certificate\_expiry/examples/cert-expiry-report.html***

## JSON Report

There are two top-level keys in the saved JSON results: **data** and **summary**.

The **data** key is a hash where the keys are the names of each host examined and the values are the check results for the certificates identified on each respective host.

The **summary** key is a hash that summarizes the total number of certificates:

- examined on the entire cluster
- that are OK
- expiring within the configured warning window
- already expired

For an example of the full JSON report, see `/usr/share/ansible/openshift-ansible/roles/openshift_certificate_expiry/examples/cert-expiry-report.json`.

The summary from the JSON data can be easily checked for warnings or expirations using a variety of command-line tools. For example, using **grep** you can look for the word **summary** and print out the two lines after the match (**-A2**):

```
$ grep -A2 summary /tmp/cert-expiry-report.json
  "summary": {
    "warning": 16,
    "expired": 0
```

If available, the **jq** tool can also be used to pick out specific values. The first two examples below show how to select just one value, either **warning** or **expired**. The third example shows how to select both values at once:

```
$ jq '.summary.warning' /tmp/cert-expiry-report.json
16

$ jq '.summary.expired' /tmp/cert-expiry-report.json
0

$ jq '.summary.warning,.summary.expired' /tmp/cert-expiry-report.json
16
0
```

## 11.3. REDEPLOYING CERTIFICATES

Use the following playbooks to redeploy master, etcd, node, registry, and router certificates on all relevant hosts. You can redeploy all of them at once using the current CA, redeploy certificates for specific components only, or redeploy a newly generated or custom CA on its own.

Just like the certificate expiry playbooks, these playbooks must be run with an [inventory file](#) that is representative of the cluster.


In particular, the inventory must specify or override all host names and IP addresses set via the following variables such that they match the current cluster configuration:

- **openshift\_hostname**

- `openshift_public_hostname`
- `openshift_ip`
- `openshift_public_ip`
- `openshift_master_cluster_hostname`
- `openshift_master_cluster_public_hostname`


The playbooks you need are provided by:

```
# yum install atomic-openshift-utils
```



#### NOTE

The validity (length in days until they expire) for any certificates auto-generated while redeploying can be configured via Ansible as well. See [Configuring Certificate Validity](#).



#### NOTE

OpenShift Container Platform CA and etcd certificates expire after five years. Signed OpenShift Container Platform certificates expire after two years.

### 11.3.1. Redeploying All Certificates Using the Current OpenShift Container Platform and etcd CA

The `redeploy-certificates.yml` playbook does *not* regenerate the OpenShift Container Platform CA certificate. New master, etcd, node, registry, and router certificates are created using the current CA certificate to sign new certificates.

This also includes serial restarts of:

- etcd
- master services
- node services

To redeploy master, etcd, and node certificates using the current OpenShift Container Platform CA, run this playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/redeploy-
    certificates.yml
```

### 11.3.2. Redeploying a New or Custom OpenShift Container Platform CA

The `openshift-master/redeployOpenshiftCa.yml` playbook redeploys the OpenShift Container Platform CA certificate by generating a new CA certificate and distributing an updated bundle to all components including client `kubeconfig` files and the node's database of trusted CAs (the CA-trust).

This also includes serial restarts of:

- master services
- node services
- docker

Additionally, you can specify a [custom CA certificate](#) when redeploying certificates instead of relying on a CA generated by OpenShift Container Platform.

When the master services are restarted, the registry and routers can continue to communicate with the master without being redeployed because the master's serving certificate is the same, and the CA the registry and routers have are still valid.

To redeploy a newly generated or custom CA:

1. If you want to use a custom CA, set the following variable in your inventory file. To use the current CA, skip this step.

```
# Configure custom ca certificate
# NOTE: CA certificate will not be replaced with existing clusters.
# This option may only be specified when creating a new cluster or
# when redeploying cluster certificates with the redeploy-
certificates
# playbook.
openshift_master_ca_certificate={'certfile': '</path/to/ca.crt>',
'keyfile': '</path/to/ca.key>'} 
```

If the CA certificate is issued by an intermediate CA, the bundled certificate must contain the full chain (the intermediate and root certificates) for the CA in order to validate child certificates.

For example:

```
$ cat intermediate/certs/intermediate.cert.pem \
certs/ca.cert.pem >> intermediate/certs/ca-chain.cert.pem 
```

2. Run the ***openshift-master/redeployOpenshiftCa.yml*** playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
/usr/share/ansible/openshift-ansible/playbooks/openshift-
master/redeploy-openshift-ca.yml 
```

With the new OpenShift Container Platform CA in place, you can then use the [\*\*\*openshift-
master/redeployCertificates.yml\*\*\* playbook](#) at your discretion whenever you want to redeploy certificates signed by the new CA on all components.

### 11.3.3. Redeploying a New etcd CA

The ***openshift-etcd/redeployCa.yml*** playbook redeploys the etcd CA certificate by generating a new CA certificate and distributing an updated bundle to all etcd peers and master clients.

This also includes serial restarts of:

- etcd
- master services

To redeploy a newly generated etcd CA:

1. Run the ***openshift-etcd/redeploy-ca.yml*** playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    etcd/redeploy-ca.yml
```

With the new etcd CA in place, you can then use the ***openshift-etcd/redeploy-certificates.yml*** playbook at your discretion whenever you want to redeploy certificates signed by the new etcd CA on etcd peers and master clients. Alternatively, you can use the ***redeploy-certificates.yml*** playbook to redeploy certificates for OpenShift Container Platform components in addition to etcd peers and master clients.

#### 11.3.4. Redeploying Master Certificates Only

The ***openshift-master/redeploy-certificates.yml*** playbook only redeploys master certificates. This also includes serial restarts of master services.

To redeploy master certificates, run this playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    master/redeploy-certificates.yml
```



#### IMPORTANT

After running this playbook, you need to regenerate any **service signing certificate or key pairs** by deleting existing secrets that contain service serving certificates or removing and re-adding annotations to appropriate services.

#### 11.3.5. Redeploying etcd Certificates Only

The ***openshift-etcd/redeploy-certificates.yml*** playbook only redeploys etcd certificates including master client certificates.

This also include serial restarts of:

- etcd
- master services.

To redeploy etcd certificates, run this playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    etcd/redeploy-certificates.yml
```

#### 11.3.6. Redeploying Node Certificates Only

The ***openshift-node/redeploy-certificates.yml*** playbook only redeploys node certificates. This also include serial restarts of node services.

To redeploy node certificates, run this playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    node/redeploy-certificates.yml
```

## 11.3.7. Redeploying Registry or Router Certificates Only

The *openshift-hosted/redeploy-registry-certificates.yml* and *openshift-hosted/redeploy-router-certificates.yml* playbooks replace installer-created certificates for the registry and router. If custom certificates are in use for these components, see [Redeploying Custom Registry or Router Certificates](#) to replace them manually.

### 11.3.7.1. Redeploying Registry Certificates Only

To redeploy registry certificates, run the following playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    hosted/redeploy-registry-certificates.yml
```

### 11.3.7.2. Redeploying Router Certificates Only

To redeploy router certificates, run the following playbook, specifying your inventory file:

```
$ ansible-playbook -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
    hosted/redeploy-router-certificates.yml
```

## 11.3.8. Redeploying Custom Registry or Router Certificates

When nodes are evacuated due to a redeployed CA, registry and router pods are restarted. If the registry and router certificates were not also redeployed with the new CA, this can cause outages because they cannot reach the masters using their old certificates.

The playbooks for redeploying certificates cannot redeploy custom registry or router certificates, so to address this issue, you can manually redeploy the registry and router certificates.

### 11.3.8.1. Redeploying Registry Certificates Manually

To redeploy registry certificates manually, you must add new registry certificates to a secret named **registry-certificates**, then redeploy the registry:

1. Switch to the **default** project for the remainder of these steps:

```
$ oc project default
```

2. If your registry was initially created on OpenShift Container Platform 3.1 or earlier, it may still be using environment variables to store certificates (which has been deprecated in favor of using secrets).
  - a. Run the following and look for the **OPENSHIFT\_CA\_DATA**, **OPENSHIFT\_CERT\_DATA**, **OPENSHIFT\_KEY\_DATA** environment variables:

```
$ oc env dc/docker-registry --list
```

- b. If they do not exist, skip this step. If they do, create the following **ClusterRoleBinding**:

```
$ cat <<EOF |  
apiVersion: v1  
groupNames: null  
kind: ClusterRoleBinding  
metadata:  
    creationTimestamp: null  
    name: registry-registry-role  
roleRef:  
    kind: ClusterRole  
    name: system:registry  
subjects:  
- kind: ServiceAccount  
  name: registry  
  namespace: default  
userNames:  
- system:serviceaccount:default:registry  
EOF  
oc create -f -
```

Then, run the following to remove the environment variables:

```
$ oc env dc/docker-registry OPENSHIFT_CA_DATA-  
OPENSHIFT_CERT_DATA- OPENSHIFT_KEY_DATA- OPENSHIFT_MASTER-
```

3. Set the following environment variables locally to make later commands less complex:

```
$ REGISTRY_IP=`oc get service docker-registry -o  
jsonpath='{.spec.clusterIP}'`  
$ REGISTRY_HOSTNAME=`oc get route/docker-registry -o  
jsonpath='{.spec.host}'`
```

4. Create new registry certificates:

```
$ oc adm ca create-server-cert \  
  --signer-cert=/etc/origin/master/ca.crt \  
  --signer-key=/etc/origin/master/ca.key \  
  --hostnames=$REGISTRY_IP,docker-registry.default.svc,docker-  
  registry.default.svc.cluster.local,$REGISTRY_HOSTNAME \  
  --cert=/etc/origin/master/registry.crt \  
  --key=/etc/origin/master/registry.key \  
  --signer-serial=/etc/origin/master/ca.serial.txt
```

Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

5. Update the **registry-certificates** secret with the new registry certificates:

```
$ oc create secret generic registry-certificates \  
  --from-  
  file=/etc/origin/master/registry.crt,/etc/origin/master/registry.key
```

```
\` -o json --dry-run | oc replace -f -
```

6. Redeploy the registry:

```
\` $ oc rollout latest dc/docker-registry
```

### 11.3.8.2. Redeploying Router Certificates Manually

When routers are initially deployed, an annotation is added to the router's service that automatically creates a [service serving certificate secret](#).

To redeploy router certificates manually, that service serving certificate can be triggered to be recreated by deleting the secret, removing and re-adding annotations to the **router** service, then redeploying the router:

1. Switch to the **default** project for the remainder of these steps:

```
\` $ oc project default
```

2. If your router was initially created on OpenShift Container Platform 3.1 or earlier, it might still use environment variables to store certificates, which has been deprecated in favor of using service serving certificate secret.

- a. Run the following command and look for the **OPENSHIFT\_CA\_DATA**, **OPENSHIFT\_CERT\_DATA**, **OPENSHIFT\_KEY\_DATA** environment variables:

```
\` $ oc env dc/router --list
```

- b. If those variables exist, create the following **ClusterRoleBinding**:

```
$ cat <<EOF |
apiVersion: v1
groupNames: null
kind: ClusterRoleBinding
metadata:
  creationTimestamp: null
  name: router-router-role
roleRef:
  kind: ClusterRole
  name: system:router
  subjects:
  - kind: ServiceAccount
    name: router
    namespace: default
  usernames:
  - system:serviceaccount:default:router
EOF
oc create -f -
```

- c. If those variables exist, run the following command to remove them:

```
\` $ oc env dc/router OPENSHIFT_CA_DATA- OPENSHIFT_CERT_DATA-
  OPENSHIFT_KEY_DATA- OPENSHIFT_MASTER-
```

3. Obtain a certificate.

- If you use an external Certificate Authority (CA) to sign your certificates, create a new certificate and provide it to OpenShift Container Platform by following your internal processes.
- If you use the internal OpenShift Container Platform CA to sign certificates, run the following commands:



### IMPORTANT

The following commands generate a certificate that is internally signed. It will be trusted by only clients that trust the OpenShift Container Platform CA.

```
$ cd /root
$ mkdir cert ; cd cert
$ oc adm ca create-server-cert \
  --signer-cert=/etc/origin/master/ca.crt \
  --signer-key=/etc/origin/master/ca.key \
  --signer-serial=/etc/origin/master/ca.serial.txt \
  --hostnames='*.hostnames.for.the.certificate' \
  --cert=router.crt \
  --key=router.key \
```

These commands generate the following files:

- A new certificate named ***router.crt***.
- A copy of the signing CA certificate chain, ***/etc/origin/master/ca.crt***. This chain can contain more than one certificate if you use intermediate CAs.
- A corresponding private key named ***router.key***.

4. Create a new file that concatenates the generated certificates:

```
$ cat router.crt /etc/origin/master/ca.crt router.key > router.pem
```

5. Before you generate a new secret, back up the current one:

```
$ oc export secret router-certs > ~/old-router-certs-secret.yaml
```

6. Create a new secret to hold the new certificate and key, and replace the contents of the existing secret:

```
$ oc create secret tls router-certs --cert=router.pem \ ①
  --key=router.key -o json --dry-run | \
  oc replace -f -
```

① ***router.pem*** is the file that contains the concatenation of the certificates that you generated.

7. Remove the following annotations from the **router** service:

```
$ oc annotate service router \  
  service.alpha.openshift.io/serving-cert-secret-name- \  
  service.alpha.openshift.io/serving-cert-signed-by-
```

8. Re-add the annotations:

```
$ oc annotate service router \  
  service.alpha.openshift.io/serving-cert-secret-name=router-certs
```

9. Redeploy the router:

```
$ oc rollout latest dc/router
```

# CHAPTER 12. CONFIGURING AUTHENTICATION AND USER AGENT

## 12.1. OVERVIEW

The OpenShift Container Platform master includes a built-in OAuth server. Developers and administrators obtain OAuth access tokens to authenticate themselves to the API.

As an administrator, you can configure OAuth using the [master configuration file](#) to specify an identity provider. It is a best practice to configure your identity provider during [advanced installation](#), but you can configure it after installation.




### NOTE

OpenShift Container Platform user names containing /, :, and % are not supported.


If you installed OpenShift Container Platform using the [Quick Installation](#) or [Advanced Installation](#) method, the [Deny All](#) identity provider is used by default, which denies access for all user names and passwords. To allow access, you must choose a different identity provider and configure the master configuration file appropriately (located at `/etc/origin/master/master-config.yaml` by default).

When you run a master without a configuration file, the [Allow All](#) identity provider is used by default, which allows any non-empty user name and password to log in. This is useful for testing purposes. To use other identity providers, or to modify any [token](#), [grant](#), or [session options](#), you must run the master from a configuration file.



### NOTE

[Roles](#) need to be assigned to administer the setup with an external user.



### NOTE

After making changes to an identity provider, you must restart the master services for the changes to take effect:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

## 12.2. IDENTITY PROVIDER PARAMETERS

There are four parameters common to all identity providers:

Parameter	Description
<code>name</code>	The provider name is prefixed to provider user names to form an identity name.

Parameter	Description
<b>challenge</b>	<p>When <b>true</b>, unauthenticated token requests from non-web clients (like the CLI) are sent a <b>WWW-Authenticate</b> challenge header. Not supported by all identity providers.</p> <p>To prevent cross-site request forgery (CSRF) attacks against browser clients Basic authentication challenges are only sent if a <b>X-CSRF-Token</b> header is present on the request. Clients that expect to receive Basic <b>WWW-Authenticate</b> challenges should set this header to a non-empty value.</p>
<b>login</b>	<p>When <b>true</b>, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider. Not supported by all identity providers.</p> <p>If you want users to be sent to a branded page before being redirected to the identity provider's login, then set <b>oauthConfig</b> → <b>alwaysShowProviderSelection: true</b> in the master configuration file. This provider selection page can be <a href="#">customized</a>.</p>
<b>mappingMethod</b>	<p>Defines how new identities are mapped to users when they log in. Enter one of the following values:</p> <ul style="list-style-type: none"> <li><b>claim</b> The default value. Provisions a user with the identity's preferred user name. Fails if a user with that user name is already mapped to another identity.</li> <li><b>lookup</b> Looks up an existing identity, user identity mapping, and user, but does not automatically provision users or identities. This allows cluster administrators to set up identities and users manually, or using an external process. Using this method requires you to manually provision users. See <a href="#">Manually Provisioning a User When Using the Lookup Mapping Method</a>.</li> <li><b>generate</b> Provisions a user with the identity's preferred user name. If a user with the preferred user name is already mapped to an existing identity, a unique user name is generated. For example, <b>myuser2</b>. This method should not be used in combination with external processes that require exact matches between OpenShift Container Platform user names and identity provider user names, such as LDAP group sync.</li> <li><b>add</b> Provisions a user with the identity's preferred user name. If a user with that user name already exists, the identity is mapped to the existing user, adding to any existing identity mappings for the user. Required when multiple identity providers are configured that identify the same set of users and map to the same user names.</li> </ul>



### NOTE

When adding or changing identity providers, you can map identities from the new provider to existing users by setting the **mappingMethod** parameter to **add**.

## 12.3. CONFIGURING IDENTITY PROVIDERS

OpenShift Container Platform supports configuring only a single identity provider. However, you can extend the basic authentication for more complex configurations such as [LDAP failover](#).

You can use these parameters to define the identity provider during installation or after installation.

### 12.3.1. Configuring identity providers with Ansible

For initial [advanced installations](#), the [Deny All](#) identity provider is configured by default, though it can be [overridden during installation](#) using the [`openshift\_master\_identity\_providers`](#) parameter, which is configurable in the inventory file. Session options in the OAuth configuration are also configurable in the inventory file.

#### Example 12.1. Example identity provider configuration with Ansible

```
# htpasswd auth
openshift_master_identity_providers=[{'name': 'htpasswd_auth', 'login': 'true', 'challenge': 'true', 'kind': 'HTPasswdPasswordIdentityProvider', 'filename': '/etc/origin/master/htpasswd'}]
# Defining htpasswd users
#openshift_master_htpasswd_users={'user1': '<pre-hashed password>', 'user2': '<pre-hashed password>'}
# or
#openshift_master_htpasswd_file=<path to local pre-generated htpasswd file>

# Allow all auth
#openshift_master_identity_providers=[{'name': 'allow_all', 'login': 'true', 'challenge': 'true', 'kind': 'AllowAllPasswordIdentityProvider'}]

# LDAP auth
#openshift_master_identity_providers=[{'name': 'my_ldap_provider', 'challenge': 'true', 'login': 'true', 'kind': 'LDAPPasswordIdentityProvider', 'attributes': {'id': ['dn'], 'email': ['mail'], 'name': ['cn'], 'preferredUsername': ['uid']}, 'bindDN': '', 'bindPassword': '', 'ca': '', 'insecure': 'false', 'url': 'ldap://ldap.example.com:389/ou=users,dc=example,dc=com?uid'}]
# Configuring the ldap ca certificate ①
#openshift_master_ldap_ca=<ca text>
# or
#openshift_master_ldap_ca_file=<path to local ca file to use>

# Available variables for configuring certificates for other identity providers:
#openshift_master_openid_ca
#openshift_master_openid_ca_file
#openshift_master_request_header_ca
#openshift_master_request_header_ca_file
```

- ① If you specify your CA certificate location in the [`openshift\_master\_identity\_providers`](#) parameter, do not specify a certificate value in the [`openshift\_master\_ldap\_ca`](#) parameter or path in the [`openshift\_master\_ldap\_ca\_file`](#) parameter.

### 12.3.2. Configuring identity providers in the master configuration file

You can configure the master host for authentication using your desired identity provider by modifying the [master configuration file](#).

### Example 12.2. Example identity provider configuration in the master configuration file

```
...
oauthConfig:
  identityProviders:
    - name: htpasswd_auth
      challenge: true
      login: true
      mappingMethod: "claim"
...
...
```

When set to the default `claim` value, OAuth will fail if the identity is mapped to a previously-existing user name.

### 12.3.3. Configuring an identity provider or method

#### 12.3.3.1. Manually provisioning a user when using the lookup mapping method

When using the `lookup` mapping method, user provisioning is done by an external system, via the API. Typically, identities are automatically mapped to users during login. The 'lookup' mapping method automatically disables this automatic mapping, which requires you to provision users manually.

For more information on identity objects, see the [Identity](#) user API object.

If you are using the `lookup` mapping method, use the following steps for each user after configuring the identity provider:

1. Create an OpenShift Container Platform User, if not created already:

```
$ oc create user <username>
```

For example, the following command creates a OpenShift Container Platform User **bob**:

```
$ oc create user bob
```

2. Create an OpenShift Container Platform Identity, if not created already. Use the name of the identity provider and the name that uniquely represents this identity in the scope of the identity provider:

```
$ oc create identity <identity-provider>:<user-id-from-identity-provider>
```

The `<identity-provider>` is the name of the identity provider in the master configuration, as shown in the appropriate identity provider section below.

For example, the following commands creates an Identity with identity provider **ldap\_provider** and the identity provider user name **bob\_s**.

```
$ oc create identity ldap_provider:bob_s
```

3. Create a user/identity mapping for the created user and identity:

```
$ oc create useridentitymapping <identity-provider>:<user-id-from-  
identity-provider> <username>
```

For example, the following command maps the identity to the user:

```
$ oc create useridentitymapping ldap_provider:bob_s bob
```

### 12.3.4. Allow all

Set **AllowAllPasswordIdentityProvider** in the **identityProviders** stanza to allow any non-empty user name and password to log in.

#### Example 12.3. Master Configuration Using AllowAllPasswordIdentityProvider

```
oauthConfig:  
  ...  
  identityProviders:  
    - name: my_allow_provider ①  
      challenge: true ②  
      login: true ③  
      mappingMethod: claim ④  
      provider:  
        apiVersion: v1  
        kind: AllowAllPasswordIdentityProvider
```

- ① This provider name is prefixed to provider user names to form an identity name.
- ② When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- ③ When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- ④ Controls how mappings are established between this provider's identities and user objects, [as described above](#).

### 12.3.5. Deny all

Set **DenyAllPasswordIdentityProvider** in the **identityProviders** stanza to deny access for all user names and passwords.

#### Example 12.4. Master Configuration Using DenyAllPasswordIdentityProvider

```
oauthConfig:  
  ...  
  identityProviders:  
    - name: my_deny_provider ①
```

```

challenge: true 2
login: true 3
mappingMethod: claim 4
provider:
  apiVersion: v1
  kind: DenyAllPasswordIdentityProvider

```

- 1** This provider name is prefixed to provider user names to form an identity name.
- 2** When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- 3** When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- 4** Controls how mappings are established between this provider's identities and user objects, [as described above](#).

### 12.3.6. HTPasswd

Set **HTPasswdPasswordIdentityProvider** in the **identityProviders** stanza to validate user names and passwords against a flat file generated using [htpasswd](#).



#### NOTE

The **htpasswd** utility is in the **httpd-tools** package:

```
# yum install httpd-tools
```

OpenShift Container Platform supports the Bcrypt, SHA-1, and MD5 cryptographic hash functions, and MD5 is the default for **htpasswd**. Plaintext, encrypted text, and other hash functions are not currently supported.

The flat file is reread if its modification time changes, without requiring a server restart.

To use the **htpasswd** command:

- To create a flat file with a user name and hashed password, run:

```
$ htpasswd -c </path/to/users.htpasswd> <user_name>
```

Then, enter and confirm a clear-text password for the user. The command generates a hashed version of the password.

For example:

```

htpasswd -c users.htpasswd user1
New password:
Re-type new password:
Adding password for user user1

```

**NOTE**

You can include the **-b** option to supply the password on the command line:

```
$ htpasswd -c -b <user_name> <password>
```

For example:

```
$ htpasswd -c -b file user1 MyPassword!
Adding password for user user1
```

- To add or update a login to the file, run:

```
$ htpasswd </path/to/users.htpasswd> <user_name>
```

- To remove a login from the file, run:

```
$ htpasswd -D </path/to/users.htpasswd> <user_name>
```

### Example 12.5. Master Configuration Using HTPasswdPasswordIdentityProvider

```
oauthConfig:
  ...
  identityProviders:
    - name: my_htpasswd_provider ①
      challenge: true ②
      login: true ③
      mappingMethod: claim ④
      provider:
        apiVersion: v1
        kind: HTPasswdPasswordIdentityProvider
        file: /path/to/users.htpasswd ⑤
```

- ① This provider name is prefixed to provider user names to form an identity name.
- ② When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- ③ When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- ④ Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- ⑤ File generated using [htpasswd](#).

### 12.3.7. Keystone

[Keystone](#) is an OpenStack project that provides identity, token, catalog, and policy services. You can integrate your OpenShift Container Platform cluster with Keystone to enable shared authentication with

an OpenStack Keystone v3 server configured to store users in an internal database. Once configured, this configuration allows users to log in to OpenShift Container Platform with their Keystone credentials.

### 12.3.7.1. Configuring authentication on the master

1. If you have:

- Already completed the installation of Openshift, then copy the `/etc/origin/master/master-config.yaml` file into a new directory; for example:

```
$ cd /etc/origin/master
$ mkdir keystoneconfig; cp master-config.yaml keystoneconfig
```

- Not yet installed OpenShift Container Platform, then start the OpenShift Container Platform API server, specifying the hostname of the (future) OpenShift Container Platform master and a directory to store the configuration file created by the start command:

```
$ openshift start master --public-master=<apiserver> --write-config=<directory>
```

For example:

```
$ openshift start master --public-master=https://myapiserver.com:8443 --write-config=keystoneconfig
```



#### NOTE

If you are installing with Ansible, then you must add the `identityProvider` configuration to the Ansible playbook. If you use the following steps to modify your configuration manually after installing with Ansible, then you will lose any modifications whenever you re-run the install tool or upgrade.

2. Edit the new `keystoneconfig/master-config.yaml` file's `identityProviders` stanza, and copy the example `KeystonePasswordIdentityProvider` configuration and paste it to replace the existing stanza:

```
oauthConfig:
  ...
  identityProviders:
    - name: my_keystone_provider ①
      challenge: true ②
      login: true ③
      mappingMethod: claim ④
      provider:
        apiVersion: v1
        kind: KeystonePasswordIdentityProvider
        domainName: default ⑤
        url: http://keystone.example.com:5000 ⑥
        ca: ca.pem ⑦
        certFile: keystone.pem ⑧
        keyFile: keystonekey.pem ⑨
```

- 1 This provider name is prefixed to provider user names to form an identity name.
- 2 When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- 3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5 Keystone domain name. In Keystone, usernames are domain-specific. Only a single domain is supported.
- 6 The URL to use to connect to the Keystone server (required).
- 7 Optional: Certificate bundle to use to validate server certificates for the configured URL.
- 8 Optional: Client certificate to present when making requests to the configured URL.
- 9 Key for the client certificate. Required if **certFile** is specified.

3. Make the following modifications to the **identityProviders** stanza:

- a. Change the provider **name** ("my\_keystone\_provider") to match your Keystone server. This name is prefixed to provider user names to form an identity name.
- b. If required, [change \*\*mappingMethod\*\*](#) to control how mappings are established between the provider's identities and user objects.
- c. Change the **domainName** to the domain name of your OpenStack Keystone server. In Keystone, user names are domain-specific. Only a single domain is supported.
- d. Specify the **url** to use to connect to your OpenStack Keystone server.
- e. Optionally, change the **ca** to the certificate bundle to use in order to validate server certificates for the configured URL.
- f. Optionally, change the **certFile** to the client certificate to present when making requests to the configured URL.
- g. If **certFile** is specified, then you must change the **keyFile** to the key for the client certificate.

4. Save your changes and close the file.

5. Start the OpenShift Container Platform API server, specifying the configuration file you just modified:

```
$ openshift start master --config=<path/to/modified/config>/master-config.yaml
```

Once configured, any user logging in to the OpenShift Container Platform web console will be prompted to log in using their Keystone credentials.

### 12.3.7.2. Creating Users with Keystone Authentication

You do not create users in OpenShift Container Platform when integrating with an external authentication provider, such as, in this case, Keystone. Keystone is the system of record, meaning that users are defined in a Keystone database, and any user with a valid Keystone user name for the configured authentication server can log in.

To add a user to OpenShift Container Platform, the user must exist in the Keystone database, and if required you must create a new Keystone account for the user.

### 12.3.7.3. Verifying Users

Once one or more users have logged in, you can run `oc get users` to view a list of users and verify that users were created successfully:

#### Example 12.6. Output of `oc get users` command

```
$ oc get users
NAME          UID                           FULL NAME
IDENTITIES
bobsmith      a0c1d95c-1cb5-11e6-a04a-002186a28631   Bob Smith
keystone:bobsmith ①
```

- ① Identities in OpenShift Container Platform are comprised of the identity provider name prefixed to the Keystone user name.

From here, you might want to learn how to [manage user roles](#).

### 12.3.8. LDAP authentication

Set **LDAPPasswordIdentityProvider** in the **identityProviders** stanza to validate user names and passwords against an LDAPv3 server, using simple bind authentication.



#### NOTE

If you require failover for your LDAP server, instead of following these steps, extend the basic authentication method by [configuring SSSD for LDAP failover](#).

During authentication, the LDAP directory is searched for an entry that matches the provided user name. If a single unique match is found, a simple bind is attempted using the distinguished name (DN) of the entry plus the provided password.

These are the steps taken:

1. Generate a search filter by combining the attribute and filter in the configured **url** with the user-provided user name.
2. Search the directory using the generated filter. If the search does not return exactly one entry, deny access.
3. Attempt to bind to the LDAP server using the DN of the entry retrieved from the search, and the user-provided password.

4. If the bind is unsuccessful, deny access.
5. If the bind is successful, build an identity using the configured attributes as the identity, email address, display name, and preferred user name.

The configured **url** is an RFC 2255 URL, which specifies the LDAP host and search parameters to use. The syntax of the URL is:

```
ldap://host:port/basedn?attribute?scope?filter
```

For the above example:

URL Component	Description
<b>ldap</b>	For regular LDAP, use the string <b>ldap</b> . For secure LDAP (LDAPS), use <b>ldaps</b> instead.
<b>host:port</b>	The name and port of the LDAP server. Defaults to <b>localhost:389</b> for ldap and <b>localhost:636</b> for LDAPS.
<b>basedn</b>	The DN of the branch of the directory where all searches should start from. At the very least, this must be the top of your directory tree, but it could also specify a subtree in the directory.
<b>attribute</b>	The attribute to search for. Although RFC 2255 allows a comma-separated list of attributes, only the first attribute will be used, no matter how many are provided. If no attributes are provided, the default is to use <b>uid</b> . It is recommended to choose an attribute that will be unique across all entries in the subtree you will be using.
<b>scope</b>	The scope of the search. Can be either <b>one</b> or <b>sub</b> . If the scope is not provided, the default is to use a scope of <b>sub</b> .
<b>filter</b>	A valid LDAP search filter. If not provided, defaults to <b>(objectClass=*)</b>

When doing searches, the attribute, filter, and provided user name are combined to create a search filter that looks like:

```
((<filter>)(<attribute>=<username>))
```

For example, consider a URL of:

```
ldap://ldap.example.com/o=Acme?cn?sub?(enabled=true)
```

When a client attempts to connect using a user name of **bob**, the resulting search filter will be **(&(enabled=true)(cn=bob))**.

If the LDAP directory requires authentication to search, specify a **bindDN** and **bindPassword** to use to perform the entry search.

## Master Configuration Using LDAPPASSWORDIdentityProvider

```

oauthConfig:
  ...
  identityProviders:
    - name: "my_ldap_provider" ①
      challenge: true ②
      login: true ③
      mappingMethod: claim ④
      provider:
        apiVersion: v1
        kind: LDAPPASSWORDIdentityProvider
        attributes:
          id: ⑤
          - dn
          email: ⑥
          - mail
          name: ⑦
          - cn
          preferredUsername: ⑧
          - uid
        bindDN: "" ⑨
        bindPassword: "" ⑩
        ca: my-ldap-ca-bundle.crt ⑪
        insecure: false ⑫
      url: "ldap://ldap.example.com/ou=users,dc=acme,dc=com?uid" ⑬

```

- ① This provider name is prefixed to the returned user ID to form an identity name.
- ② When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- ③ When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- ④ Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- ⑤ List of attributes to use as the identity. First non-empty attribute is used. At least one attribute is required. If none of the listed attribute have a value, authentication fails.
- ⑥ List of attributes to use as the email address. First non-empty attribute is used.
- ⑦ List of attributes to use as the display name. First non-empty attribute is used.
- ⑧ List of attributes to use as the preferred user name when provisioning a user for this identity. First non-empty attribute is used.
- ⑨ Optional DN to use to bind during the search phase.
- ⑩ Optional password to use to bind during the search phase. This value may also be provided in an [environment variable, external file, or encrypted file](#).
- ⑪ Certificate bundle to use to validate server certificates for the configured URL. If empty, system trusted roots are used. Only applies if **insecure: false**.

- 12 When **true**, no TLS connection is made to the server. When **false**, **ldaps://** URLs connect using TLS, and **ldap://** URLs are upgraded to TLS.
- 13 An RFC 2255 URL which specifies the LDAP host and search parameters to use, as described above.



#### NOTE

To whitelist users for an LDAP integration, use the **lookup** mapping method. Before a login from LDAP would be allowed, a cluster administrator must create an identity and user object for each LDAP user.

### 12.3.9. Basic authentication (remote)

Basic Authentication is a generic backend integration mechanism that allows users to log in to OpenShift Container Platform with credentials validated against a remote identity provider.

Because basic authentication is generic, you can use this identity provider for advanced authentication configurations. You can configure [LDAP failover](#) or use the [containerized basic authentication](#) repository as a starting point for another advanced remote basic authentication configuration.

#### CAUTION

Basic authentication must use an HTTPS connection to the remote server to prevent potential snooping of the user ID and password and man-in-the-middle attacks.

With **BasicAuthPasswordIdentityProvider** configured, users send their user name and password to OpenShift Container Platform, which then validates those credentials against a remote server by making a server-to-server request, passing the credentials as a Basic Auth header. This requires users to send their credentials to OpenShift Container Platform during login.



#### NOTE

This only works for user name/password login mechanisms, and OpenShift Container Platform must be able to make network requests to the remote authentication server.

Set **BasicAuthPasswordIdentityProvider** in the **identityProviders** stanza to validate user names and passwords against a remote server using a server-to-server Basic authentication request. User names and passwords are validated against a remote URL that is protected by Basic authentication and returns JSON.

A **401** response indicates failed authentication.

A non-**200** status, or the presence of a non-empty "error" key, indicates an error:

```
{"error":"Error message"}
```

A **200** status with a **sub** (subject) key indicates success:

```
{"sub":"userid"} ①
```

- ① The subject must be unique to the authenticated user and must not be able to be modified.

A successful response may optionally provide additional data, such as:

- A display name using the **name** key. For example:

```
{"sub": "userid", "name": "User Name", ...}
```

- An email address using the **email** key. For example:

```
{"sub": "userid", "email": "user@example.com", ...}
```

- A preferred user name using the **preferred\_username** key. This is useful when the unique, unchangeable subject is a database key or UID, and a more human-readable name exists. This is used as a hint when provisioning the OpenShift Container Platform user for the authenticated identity. For example:

```
{"sub": "014fbff9a07c", "preferred_username": "bob", ...}
```

### 12.3.9.1. Configuring authentication on the master

1. If you have:

- Already completed the installation of Openshift, then copy the **/etc/origin/master/master-config.yaml** file into a new directory; for example:

```
$ mkdir basicauthconfig; cp master-config.yaml basicauthconfig
```

- Not yet installed OpenShift Container Platform, then start the OpenShift Container Platform API server, specifying the hostname of the (future) OpenShift Container Platform master and a directory to store the configuration file created by the start command:

```
$ openshift start master --public-master=<apiserver> --write-config=<directory>
```

For example:

```
$ openshift start master --public-master=https://myapiserver.com:8443 --write-config=basicauthconfig
```



#### NOTE

If you are installing with Ansible, then you must add the **identityProvider** configuration to the Ansible playbook. If you use the following steps to modify your configuration manually after installing with Ansible, then you will lose any modifications whenever you re-run the install tool or upgrade.

2. Edit the new **master-config.yaml** file's **identityProviders** stanza, and copy [the example BasicAuthPasswordIdentityProvider configuration](#) and paste it to replace the existing stanza:

```
oauthConfig:
```

```
...
```

```

identityProviders:
- name: my_remote_basic_auth_provider ①
  challenge: true ②
  login: true ③
  mappingMethod: claim ④
  provider:
    apiVersion: v1
    kind: BasicAuthPasswordIdentityProvider
    url: https://www.example.com/remote-idp ⑤
    ca: /path/to/ca.file ⑥
    certFile: /path/to/client.crt ⑦
    keyFile: /path/to/client.key ⑧

```

- ① This provider name is prefixed to the returned user ID to form an identity name.
- ② When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider.
- ③ When **true**, unauthenticated token requests from web clients (like the web console) are redirected to a login page backed by this provider.
- ④ Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- ⑤ URL accepting credentials in Basic authentication headers.
- ⑥ Optional: Certificate bundle to use to validate server certificates for the configured URL.
- ⑦ Optional: Client certificate to present when making requests to the configured URL.
- ⑧ Key for the client certificate. Required if **certFile** is specified.

Make the following modifications to the **identityProviders** stanza:

- a. Set the provider **name** to something unique and relevant to your deployment. This name is prefixed to the returned user ID to form an identity name.
- b. If required, [set \*\*mappingMethod\*\*](#) to control how mappings are established between the provider's identities and user objects.
- c. Specify the HTTPS **url** to use to connect to a server that accepts credentials in Basic authentication headers.
- d. Optionally, set the **ca** to the certificate bundle to use in order to validate server certificates for the configured URL, or leave it empty to use the system-trusted roots.
- e. Optionally, remove or set the **certFile** to the client certificate to present when making requests to the configured URL.
- f. If **certFile** is specified, then you must set the **keyFile** to the key for the client certificate.
3. Save your changes and close the file.
4. Start the OpenShift Container Platform API server, specifying the configuration file you just modified:

```
$ openshift start master --config=<path/to/modified/config>/master-config.yaml
```

Once configured, any user logging in to the OpenShift Container Platform web console will be prompted to log in using their Basic authentication credentials.

### 12.3.9.2. Troubleshooting

The most common issue relates to network connectivity to the backend server. For simple debugging, run `curl` commands on the master. To test for a successful login, replace the `<user>` and `<password>` in the following example command with valid credentials. To test an invalid login, replace them with false credentials.

```
curl --cacert /path/to/ca.crt --cert /path/to/client.crt --key /path/to/client.key -u <user>:<password> -v https://www.example.com/remote-idp
```

#### Successful responses

A **200** status with a `sub` (subject) key indicates success:

```
{"sub": "userid"}
```

The subject must be unique to the authenticated user, and must not be able to be modified.

A successful response may optionally provide additional data, such as:

- A display name using the `name` key:

```
{"sub": "userid", "name": "User Name", ...}
```

- An email address using the `email` key:

```
{"sub": "userid", "email": "user@example.com", ...}
```

- A preferred user name using the `preferred_username` key:

```
{"sub": "014fbff9a07c", "preferred_username": "bob", ...}
```

The `preferred_username` key is useful when the unique, unchangeable subject is a database key or UID, and a more human-readable name exists. This is used as a hint when provisioning the OpenShift Container Platform user for the authenticated identity.

#### Failed responses

- A **401** response indicates failed authentication.
- A non-**200** status or the presence of a non-empty "error" key indicates an error:  
`{"error": "Error message"}`

### 12.3.10. Request header

Set `RequestHeaderIdentityProvider` in the `identityProviders` stanza to identify users from request

header values, such as **X-Remote-User**. It is typically used in combination with an authenticating proxy, which sets the request header value. This is similar to how [the remote user plug-in in OpenShift Enterprise 2](#) allowed administrators to provide Kerberos, LDAP, and many other forms of enterprise authentication.

You can also use the request header identity provider for advanced configurations such as [SAML authentication](#).

For users to authenticate using this identity provider, they must access **https://<master>/oauth/authorize** (and subpaths) via an authenticating proxy. To accomplish this, configure the OAuth server to redirect unauthenticated requests for OAuth tokens to the proxy endpoint that proxies to **https://<master>/oauth/authorize**.

To redirect unauthenticated requests from clients expecting browser-based login flows:

1. Set the **login** parameter to **true**.
2. Set the **provider.loginURL** parameter to the authenticating proxy URL that will authenticate interactive clients and then proxy the request to **https://<master>/oauth/authorize**.

To redirect unauthenticated requests from clients expecting **WWW-Authenticate** challenges:

1. Set the **challenge** parameter to **true**.
2. Set the **provider.challengeURL** parameter to the authenticating proxy URL that will authenticate clients expecting **WWW-Authenticate** challenges and then proxy the request to **https://<master>/oauth/authorize**.

The **provider.challengeURL** and **provider.loginURL** parameters can include the following tokens in the query portion of the URL:

- **\${url}** is replaced with the current URL, escaped to be safe in a query parameter.  
For example: **https://www.example.com/sso-login?then=\${url}**
- **\${query}** is replaced with the current query string, unescaped.  
For example: **https://www.example.com/auth-proxy/oauth/authorize?\${query}**



### WARNING

If you expect unauthenticated requests to reach the OAuth server, a **clientCA** parameter MUST be set for this identity provider, so that incoming requests are checked for a valid client certificate before the request's headers are checked for a user name. Otherwise, any direct request to the OAuth server can impersonate any identity from this provider, merely by setting a request header.

#### Example 12.7. Master Configuration Using RequestHeaderIdentityProvider

```
oauthConfig:  
  ...  
  identityProviders:
```

```

- name: my_request_header_provider ①
  challenge: true ②
  login: true ③
  mappingMethod: claim ④
  provider:
    apiVersion: v1
    kind: RequestHeaderIdentityProvider
    challengeURL: "https://www.example.com/challenging-
proxy/oauth/authorize?${query}" ⑤
    loginURL: "https://www.example.com/login-proxy/oauth/authorize?
${query}" ⑥
    clientCA: /path/to/client-ca.file ⑦
    clientCommonNames: ⑧
      - my-auth-proxy
    headers: ⑨
      - X-Remote-User
      - SSO-User
    emailHeaders: ⑩
      - X-Remote-User-Email
    nameHeaders: ⑪
      - X-Remote-User-Display-Name
    preferredUsernameHeaders: ⑫
      - X-Remote-User-Login

```

- ① This provider name is prefixed to the user name in the request header to form an identity name.
- ② **RequestHeaderIdentityProvider** can only respond to clients that request **WWW-Authenticate** challenges by redirecting to a configured **challengeURL**. The configured URL should respond with a **WWW-Authenticate** challenge.
- ③ **RequestHeaderIdentityProvider** can only respond to clients requesting a login flow by redirecting to a configured **loginURL**. The configured URL should respond with a login flow.
- ④ Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- ⑤ Optional: URL to redirect unauthenticated **/oauth/authorize** requests to, that will authenticate browser-based clients and then proxy their request to **https://<master>/oauth/authorize**. The URL that proxies to **https://<master>/oauth/authorize** must end with **/authorize** (with no trailing slash), and also proxy subpaths, in order for OAuth approval flows to work properly.  **\${url}** is replaced with the current URL, escaped to be safe in a query parameter.  **\${query}** is replaced with the current query string.
- ⑥ Optional: URL to redirect unauthenticated **/oauth/authorize** requests to, that will authenticate clients which expect **WWW-Authenticate** challenges, and then proxy them to **https://<master>/oauth/authorize**.  **\${url}** is replaced with the current URL, escaped to be safe in a query parameter.  **\${query}** is replaced with the current query string.
- ⑦ Optional: PEM-encoded certificate bundle. If set, a valid client certificate must be presented and validated against the certificate authorities in the specified file before the request headers are checked for user names.
- ⑧

Optional: list of common names (**cn**). If set, a valid client certificate with a Common Name (**cn**) in the specified list must be presented before the request headers are checked for user names.

- 9** Header names to check, in order, for the user identity. The first header containing a value is used as the identity. Required, case-insensitive.
- 10** Header names to check, in order, for an email address. The first header containing a value is used as the email address. Optional, case-insensitive.
- 11** Header names to check, in order, for a display name. The first header containing a value is used as the display name. Optional, case-insensitive.
- 12** Header names to check, in order, for a preferred user name, if different than the immutable identity determined from the headers specified in **headers**. The first header containing a value is used as the preferred user name when provisioning. Optional, case-insensitive.

### Example 12.8. Apache Authentication Using RequestHeaderIdentityProvider

This example configures an authentication proxy on the same host as the master. Having the proxy and master on the same host is merely a convenience and may not be suitable for your environment. For example, if you were already [running a router](#) on the master, port 443 would not be available.

It is also important to note that while this reference configuration uses Apache's **mod\_auth\_form**, it is by no means required and other proxies can easily be used if the following requirements are met:

1. Block the **X-Remote-User** header from client requests to prevent spoofing.
2. Enforce client certificate authentication in the **RequestHeaderIdentityProvider** configuration.
3. Require the **X-Csrf-Token** header be set for all authentication request using the challenge flow.
4. Only the **/oauth/authorize** endpoint and its subpaths should be proxied, and redirects should not be rewritten to allow the backend server to send the client to the correct location.
5. The URL that proxies to **https://<master>/oauth/authorize** must end with **/authorize** (with no trailing slash). For example:
  - **https://proxy.example.com/login-proxy/authorize?...** → **https://<master>/oauth/authorize?...**
6. Subpaths of the URL that proxies to **https://<master>/oauth/authorize** must proxy to subpaths of **https://<master>/oauth/authorize**. For example:
  - **https://proxy.example.com/login-proxy/authorize/approve?...** → **https://<master>/oauth/authorize/approve?...**

### Installing the Prerequisites

The **mod\_auth\_form** module is shipped as part of the **mod\_session** package that is found in the [Optional channel](#):

```
# yum install -y httpd mod_ssl mod_session apr-util-openssl
```

Generate a CA for validating requests that submit the trusted header. This CA should be used as the file name for **clientCA** in the master's identity provider configuration.

```
# oc adm ca create-signer-cert \
--cert='/etc/origin/master/proxyca.crt' \
--key='/etc/origin/master/proxyca.key' \
--name='openshift-proxy-signer@1432232228' \
--serial='/etc/origin/master/proxyca.serial.txt'
```

The **oc adm ca create-signer-cert** command generates a certificate that is valid for five years. This can be altered with the **--expire-days** option, but for security reasons, it is recommended to not make it greater than this value.

Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

Generate a client certificate for the proxy. This can be done using any x509 certificate tooling. For convenience, the **oc adm** CLI can be used:

```
# oc adm create-api-client-config \
--certificate-authority='/etc/origin/master/proxyca.crt' \
--client-dir='/etc/origin/master/proxy' \
--signer-cert='/etc/origin/master/proxyca.crt' \
--signer-key='/etc/origin/master/proxyca.key' \
--signer-serial='/etc/origin/master/proxyca.serial.txt' \
--user='system:proxy' ①

# pushd /etc/origin/master
# cp master.server.crt /etc/pki/tls/certs/localhost.crt ②
# cp master.server.key /etc/pki/tls/private/localhost.key
# cp ca.crt /etc/pki/CA/certs/ca.crt
# cat proxy/system\proxy.crt \
proxy/system\proxy.key > \
/etc/pki/tls/certs/authproxy.pem
# popd
```

- ① The user name can be anything, however it is useful to give it a descriptive name as it will appear in logs.
- ② When running the authentication proxy on a different host name than the master, it is important to generate a certificate that matches the host name instead of using the default master certificate as shown above. The value for **masterPublicURL** in the **/etc/origin/master/master-config.yaml** file must be included in the **X509v3 Subject Alternative Name** in the certificate that is specified for **SSLCertificateFile**. If a new certificate needs to be created, the **oc adm ca create-server-cert** command can be used.

The **oc adm create-api-client-config** command generates a certificate that is valid for two years. This can be altered with the **--expire-days** option, but for security reasons, it is recommended to not make it greater than this value. Run **oc adm** commands only from the first master listed in the Ansible host inventory file, by default **/etc/ansible/hosts**.

## Configuring Apache

This proxy does not need to reside on the same host as the master. It uses a client certificate to connect to the master, which is configured to trust the **X-Remote-User** header.

1. Create the certificate for the Apache configuration. The certificate that you specify as the **SSLProxyMachineCertificateFile** parameter value is the proxy's client cert that is used to authenticate the proxy to the server. It must use **TLS Web Client Authentication** as the extended key type.
2. Configure Apache per the following:

```

LoadModule auth_form_module modules/mod_auth_form.so
LoadModule session_module modules/mod_session.so
LoadModule request_module modules/mod_request.so

# Nothing needs to be served over HTTP. This virtual host simply
# redirects to
# HTTPS.
<VirtualHost *:80>
    DocumentRoot /var/www/html
    RewriteEngine On
    RewriteRule ^(.*)$ https:// %{HTTP_HOST}$1 [R,L]
</VirtualHost>

<VirtualHost *:443>
    # This needs to match the certificates you generated. See the CN and
    X509v3
    # Subject Alternative Name in the output of:
    # openssl x509 -text -in /etc/pki/tls/certs/localhost.crt
    ServerName www.example.com

    DocumentRoot /var/www/html
    SSLEngine on
    SSLCertificateFile /etc/pki/tls/certs/localhost.crt
    SSLCertificateKeyFile /etc/pki/tls/private/localhost.key
    SSLCACertificateFile /etc/pki/CA/certs/ca.crt

    SSLProxyEngine on
    SSLProxyCACertificateFile /etc/pki/CA/certs/ca.crt
    # It's critical to enforce client certificates on the Master. Otherwise
    # requests could spoof the X-Remote-User header by accessing the
Master's
    # /oauth/authorize endpoint directly.
    SSLProxyMachineCertificateFile /etc/pki/tls/certs/authproxy.pem

    # Send all requests to the console
    RewriteEngine On
    RewriteRule ^/console(.*)$ https:// %{HTTP_HOST}:8443/console$1
[R,L]

    # In order to using the challenging-proxy an X-Csrf-Token must be
present.
    RewriteCond %{REQUEST_URI} ^/challenging-proxy
    RewriteCond %{HTTP:X-Csrf-Token} ^$ [NC]
    RewriteRule ^.* - [F,L]

<Location /challenging-proxy/oauth/authorize>
```

```

# Insert your backend server name/ip here.
ProxyPass https://[MASTER]:8443/oauth/authorize
AuthType basic
</Location>

<Location /login-proxy/oauth/authorize>
# Insert your backend server name/ip here.
ProxyPass https://[MASTER]:8443/oauth/authorize

# mod_auth_form providers are implemented by mod_authn_dbm,
mod_authn_file,
# mod_authn_dbd, mod_authnz_ldap and mod_authn_socache.
AuthFormProvider file
AuthType form
AuthName openshift
ErrorDocument 401 /login.html
</Location>

<ProxyMatch /oauth/authorize>
AuthUserFile /etc/origin/master/htpasswd
AuthName openshift
Require valid-user
RequestHeader set X-Remote-User %{REMOTE_USER}s env=REMOTE_USER

# For ldap:
# AuthBasicProvider ldap
# AuthLDAPURL "ldap://ldap.example.com:389/ou=People,dc=my-
domain,dc=com?uid?sub?(objectClass=*)"

# It's possible to remove the mod_auth_form usage and replace it with
# something like mod_auth_kerb, mod_auth_gssapi or even
mod_auth_mellon.
# The former would be able to support both the login and challenge
flows
# from the Master. Mellon would likely only support the login flow.

# For Kerberos
# yum install mod_auth_gssapi
# AuthType GSSAPI
# GssapiCredStore keytab:/etc/httpd.keytab
</ProxyMatch>

</VirtualHost>

RequestHeader unset X-Remote-User

```

### Additional mod\_auth\_form Requirements

A sample login page is available from the [openshift\\_extras](#) repository. This file should be placed in the **DocumentRoot** location (`/var/www/html` by default).

### Creating Users

At this point, you can create the users in the system Apache is using to store accounts information. In this example, file-backed authentication is used:

```
# yum -y install httpd-tools
# touch /etc/origin/master/htpasswd
# htpasswd /etc/origin/master/htpasswd <user_name>
```

## Configuring the Master

The **identityProviders** stanza in the */etc/origin/master/master-config.yaml* file must be updated as well:

```
identityProviders:
- name: requestheader
  challenge: true
  login: true
  provider:
    apiVersion: v1
    kind: RequestHeaderIdentityProvider
    challengeURL: "https://[MASTER]/challenging-proxy/oauth/authorize?${query}"
    loginURL: "https://[MASTER]/login-proxy/oauth/authorize?${query}"
    clientCA: /etc/origin/master/proxyca.crt
    headers:
      - X-Remote-User
```

## Restarting Services

Finally, restart the following services:

```
# systemctl restart httpd
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
```

## Verifying the Configuration

1. Test by bypassing the proxy. You should be able to request a token if you supply the correct client certificate and header:

```
# curl -L -k -H "X-Remote-User: joe" \
--cert /etc/pki/tls/certs/authproxy.pem \
https://[MASTER]:8443/oauth/token/request
```

2. If you do not supply the client certificate, the request should be denied:

```
# curl -L -k -H "X-Remote-User: joe" \
https://[MASTER]:8443/oauth/token/request
```

3. This should show a redirect to the configured **challengeURL** (with additional query parameters):

```
# curl -k -v -H 'X-Csrf-Token: 1' \
'<masterPublicURL>/oauth/authorize?client_id=openshift-
challenging-client&response_type=token'
```

4. This should show a 401 response with a **WWW-Authenticate** basic challenge:

```
# curl -k -v -H 'X-Csrf-Token: 1' \
    '<redirected challengeURL from step 3 +query>'
```

5. This should show a redirect with an access token:

```
# curl -k -v -u <your_user>:<your_password> \
    -H 'X-Csrf-Token: 1' '<redirected_challengeURL_from_step_3
+query>'
```

### 12.3.11. GitHub

GitHub uses OAuth, and you can integrate your OpenShift Container Platform cluster to use that OAuth authentication. OAuth basically facilitates a token exchange flow.

Configuring GitHub authentication allows users to log in to OpenShift Container Platform with their GitHub credentials. To prevent anyone with any GitHub user ID from logging in to your OpenShift Container Platform cluster, you can restrict access to only those in specific GitHub organizations.

### 12.3.12. Registering the application on GitHub

1. On GitHub, click [Settings](#) → [OAuth applications](#) → [Developer applications](#) → [Register an application](#) to navigate to the page for a new OAuth application.
2. Type an application name. For example: **My OpenShift Install**
3. Type a homepage URL. For example: <https://myapiserver.com:8443>
4. Optionally, type an application description.
5. Type the authorization callback URL, where the end of the URL contains the identity provider **name** (defined in the **identityProviders** stanza of the [master configuration file](#), which you configure in the next section of this topic):

```
<apiserver>/oauth2callback/<identityProviderName>
```

For example:

```
https://myapiserver.com:8443/oauth2callback/github/
```

6. Click **Register application**. GitHub provides a Client ID and a Client Secret. Keep this window open so you can copy these values and paste them into the master configuration file.

### 12.3.13. Configuring authentication on the master

1. If you have:

- Already completed the installation of Openshift, then copy the [/etc/origin/master/master-config.yaml](#) file into a new directory; for example:

```
$ cd /etc/origin/master
$ mkdir githubconfig; cp master-config.yaml githubconfig
```

- Not yet installed OpenShift Container Platform, then start the OpenShift Container Platform API server, specifying the hostname of the (future) OpenShift Container Platform master and a directory to store the configuration file created by the start command:

```
$ openshift start master --public-master=<apiserver> --write-config=<directory>
```

For example:

```
$ openshift start master --public-master=https://myapiserver.com:8443 --write-config=githubconfig
```



### NOTE

If you are installing with Ansible, then you must add the **identityProvider** configuration to the Ansible playbook. If you use the following steps to modify your configuration manually after installing with Ansible, then you will lose any modifications whenever you re-run the install tool or upgrade.



### NOTE

Using **openshift start master** on its own would auto-detect host names, but GitHub must be able to redirect to the exact host name that you specified when registering the application. For this reason, you cannot auto-detect the ID because it might redirect to the wrong address. Instead, you must specify the hostname that web browsers use to interact with your OpenShift Container Platform cluster.

- Edit the new **master-config.yaml** file's **identityProviders** stanza, and copy the example **GitHubIdentityProvider** configuration and paste it to replace the existing stanza:

```
oauthConfig:
  ...
  identityProviders:
    - name: github 1
      challenge: false 2
      login: true 3
      mappingMethod: claim 4
      provider:
        apiVersion: v1
        kind: GitHubIdentityProvider
        clientID: ... 5
        clientSecret: ... 6
        organizations: 7
          - myorganization1
          - myorganization2
        teams: 8
          - myorganization1/team-a
          - myorganization2/team-b
```

**1** This provider name is prefixed to the GitHub numeric user ID to form an identity name. It is also used to build the callback URL.

- 2** GitHubIdentityProvider cannot be used to send **WWW-Authenticate** challenges.
- 3** When **true**, unauthenticated token requests from web clients (like the web console) are redirected to GitHub to log in.
- 4** Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5** The client ID of a [registered GitHub OAuth application](#). The application must be configured with a callback URL of `<master>/oauth2callback/<identityProviderName>`.
- 6** The client secret issued by GitHub. This value may also be provided in an [environment variable, external file, or encrypted file](#).
- 7** Optional list of organizations. If specified, only GitHub users that are members of at least one of the listed organizations will be allowed to log in. If the GitHub OAuth application configured in **clientID** is not owned by the organization, an organization owner must grant third-party access in order to use this option. This can be done during the first GitHub login by the organization's administrator, or from the GitHub organization settings. Cannot be used in combination with the **teams** field.
- 8** Optional list of teams. If specified, only GitHub users that are members of at least one of the listed teams will be allowed to log in. If the GitHub OAuth application configured in **clientID** is not owned by the team's organization, an organization owner must grant third-party access in order to use this option. This can be done during the first GitHub login by the organization's administrator, or from the GitHub organization settings. Cannot be used in combination with the **organizations** field.

3. Make the following modifications to the **identityProviders** stanza:

- a. Change the provider **name** to match the callback URL you configured on GitHub.  
For example, if you defined the callback URL as  
<https://myapiserver.com:8443/oauth2callback/github/> then the **name** must be **github**.
- b. Change **clientID** to the Client ID from GitHub that you [registered previously](#).
- c. Change **clientSecret** to the Client Secret from GitHub that you [registered previously](#).
- d. Change **organizations** or **teams** to include a list of one or more GitHub organizations or teams to which a user must have membership in order to authenticate. If specified, only GitHub users that are members of at least one of the listed organizations or teams will be allowed to log in. If this is not specified, then any person with a valid GitHub account can log in.

4. Save your changes and close the file.

5. Start the OpenShift Container Platform API server, specifying the configuration file you just modified:

```
$ openshift start master --config=<path/to/modified/config>/master-config.yaml
```

Once configured, any user logging in to the OpenShift Container Platform web console will be prompted to log in using their GitHub credentials. On their first login, the user must click **authorize application** to

permit GitHub to use their user name, password, and organization membership with OpenShift Container Platform. The user is then redirected back to the web console.

### 12.3.14. Creating users with GitHub authentication

You do not create users in OpenShift Container Platform when integrating with an external authentication provider, such as, in this case, GitHub. GitHub is the system of record, meaning that users are defined by GitHub, and any user belonging to a specified organization can log in.

To add a user to OpenShift Container Platform, you must add that user to an approved organization on GitHub, and if required create a new GitHub account for the user.

### 12.3.15. Verifying users

Once one or more users have logged in, you can run `oc get users` to view a list of users and verify that users were created successfully:

#### Example 12.9. Output of `oc get users` command

```
$ oc get users
NAME          UID                                     FULL NAME
IDENTITIES
bobsmith      433b5641-066f-11e6-a6d8-acfc32c1ca87   Bob Smith
github:873654  1
```

- 1 Identities in OpenShift Container Platform are comprised of the identity provider name and GitHub's internal numeric user ID. This way, if a user changes their GitHub user name or e-mail they can still log in to OpenShift Container Platform instead of relying on the credentials attached to the GitHub account. This creates a stable login.

From here, you might want to learn how to [control user roles](#).

### 12.3.16. GitLab

Set `GitLabIdentityProvider` in the `identityProviders` stanza to use [GitLab.com](#) or any other GitLab instance as an identity provider, using the [OAuth integration](#). The OAuth provider feature requires GitLab version 7.7.0 or higher.



#### NOTE

Using GitLab as an identity provider requires users to get a token using `<master>/oauth/token/request` to use with command-line tools.

#### Example 12.10. Master Configuration Using `GitLabIdentityProvider`

```
oauthConfig:
  ...
  identityProviders:
    - name: gitlab 1
      challenge: true 2
```

```

login: true 3
mappingMethod: claim 4
provider:
  apiVersion: v1
  kind: GitLabIdentityProvider
  url: ... 5
  clientID: ... 6
  clientSecret: ... 7
  ca: ... 8

```

- 1** This provider name is prefixed to the GitLab numeric user ID to form an identity name. It is also used to build the callback URL.
- 2** When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider. This uses the [Resource Owner Password Credentials](#) grant flow to obtain an access token from GitLab.
- 3** When **true**, unauthenticated token requests from web clients (like the web console) are redirected to GitLab to log in.
- 4** Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5** The host URL of a GitLab OAuth provider. This could either be `https://gitlab.com/` or any other self hosted instance of GitLab.
- 6** The client ID of a [registered GitLab OAuth application](#). The application must be configured with a callback URL of `<master>/oauth2callback/<identityProviderName>`.
- 7** The client secret issued by GitLab. This value may also be provided in an [environment variable](#), [external file](#), or [encrypted file](#).
- 8** CA is an optional trusted certificate authority bundle to use when making requests to the GitLab instance. If empty, the default system roots are used.

### 12.3.17. Google

Set **GoogleIdentityProvider** in the **identityProviders** stanza to use Google as an identity provider, using [Google's OpenID Connect integration](#).



#### NOTE

Using Google as an identity provider requires users to get a token using `<master>/oauth/token/request` to use with command-line tools.

**WARNING**

Using Google as an identity provider allows any Google user to authenticate to your server. You can limit authentication to members of a specific hosted domain with the **hostedDomain** configuration attribute, as shown below.

**Example 12.11. Master Configuration Using GoogleIdentityProvider**


```
oauthConfig:
  ...
  identityProviders:
    - name: google 1
      challenge: false 2
      login: true 3
      mappingMethod: claim 4
      provider:
        apiVersion: v1
        kind: GoogleIdentityProvider
        clientID: ... 5
        clientSecret: ... 6
        hostedDomain: "" 7
```

- 1** This provider name is prefixed to the Google numeric user ID to form an identity name. It is also used to build the redirect URL.
- 2** **GoogleIdentityProvider** cannot be used to send **WWW-Authenticate** challenges.
- 3** When **true**, unauthenticated token requests from web clients (like the web console) are redirected to Google to log in.
- 4** Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5** The client ID of a [registered Google project](#). The project must be configured with a redirect URI of `<master>/oauth2callback/<identityProviderName>`.
- 6** The client secret issued by Google. This value may also be provided in an [environment variable](#), [external file](#), or [encrypted file](#).
- 7** Optional [hosted domain](#) to restrict sign-in accounts to. If empty, any Google account is allowed to authenticate.

**12.3.18. OpenID connect**

Set **OpenIDIdentityProvider** in the **identityProviders** stanza to integrate with an OpenID Connect identity provider using an [Authorization Code Flow](#).

You can [configure Red Hat Single Sign-On](#) as an OpenID Connect identity provider for OpenShift Container Platform.



### NOTE

**ID Token** and **Userinfo** decryptions are not supported.

By default, the **openid** scope is requested. If required, extra scopes can be specified in the **extraScopes** field.

Claims are read from the JWT **id\_token** returned from the OpenID identity provider and, if specified, from the JSON returned by the **Userinfo** URL.

At least one claim must be configured to use as the user's identity. The standard identity claim is **sub**.

You can also indicate which claims to use as the user's preferred user name, display name, and email address. If multiple claims are specified, the first one with a non-empty value is used. The standard claims are:

<b>sub</b>	Short for "subject identifier." The remote identity for the user at the issuer.
<b>preferred_username</b>	The preferred user name when provisioning a user. A shorthand name that the user wants to be referred to as, such as <code>janedoe</code> . Typically a value that corresponds to the user's login or username in the authentication system, such as username or email.
<b>email</b>	Email address.
<b>name</b>	Display name.

See the [OpenID claims documentation](#) for more information.



### NOTE

Using an OpenID Connect identity provider requires users to get a token using `<master>/oauth/token/request` to use with command-line tools.

## Standard Master Configuration Using OpenIDIdentityProvider

```

oauthConfig:
  ...
  identityProviders:
    - name: my_openid_connect ①
      challenge: true ②
      login: true ③
      mappingMethod: claim ④
      provider:
        apiVersion: v1
        kind: OpenIDIdentityProvider
        clientID: ... ⑤
        clientSecret: ... ⑥
        claims:

```

```

id: 7
- sub
preferredUsername:
- preferred_username
name:
- name
email:
- email
urls:
  authorize: https://myidp.example.com/oauth2/authorize 8
  token: https://myidp.example.com/oauth2/token 9

```

- 1 This provider name is prefixed to the value of the identity claim to form an identity name. It is also used to build the redirect URL.
- 2 When **true**, unauthenticated token requests from non-web clients (like the CLI) are sent a **WWW-Authenticate** challenge header for this provider. This requires the OpenID provider to support the [Resource Owner Password Credentials](#) grant flow.
- 3 When **true**, unauthenticated token requests from web clients (like the web console) are redirected to the authorize URL to log in.
- 4 Controls how mappings are established between this provider's identities and user objects, [as described above](#).
- 5 The client ID of a client registered with the OpenID provider. The client must be allowed to redirect to **<master>/oauth2callback/<identityProviderName>**.
- 6 The client secret. This value may also be provided in an [environment variable](#), [external file](#), or [encrypted file](#).
- 7 List of claims to use as the identity. First non-empty claim is used. At least one claim is required. If none of the listed claims have a value, authentication fails. For example, this uses the value of the **sub** claim in the returned **id\_token** as the user's identity.
- 8 Authorization Endpoint described in the OpenID spec. Must use **https**.
- 9 Token Endpoint described in the OpenID spec. Must use **https**.

A custom certificate bundle, extra scopes, extra authorization request parameters, and **userInfo** URL can also be specified:

#### Example 12.12. Full Master Configuration Using OpenIDIdentityProvider

```

oauthConfig:
...
identityProviders:
- name: my_openid_connect
  challenge: false
  login: true
  mappingMethod: claim
  provider:
    apiVersion: v1
    kind: OpenIDIdentityProvider
    clientID: ...

```

```

clientSecret: ...
ca: my-openid-ca-bundle.crt ①
extraScopes: ②
- email
- profile
extraAuthorizeParameters: ③
  include_granted_scopes: "true"
claims:
  id: ④
  - custom_id_claim
  - sub
  preferredUsername: ⑤
    - preferred_username
    - email
  name: ⑥
    - nickname
    - given_name
    - name
  email: ⑦
    - custom_email_claim
    - email
urls:
  authorize: https://myidp.example.com/oauth2/authorize
  token: https://myidp.example.com/oauth2/token
  userInfo: https://myidp.example.com/oauth2/userinfo ⑧

```

- ① Certificate bundle to use to validate server certificates for the configured URLs. If empty, system trusted roots are used.
- ② Optional list of scopes to request, in addition to the **openid** scope, during the authorization token request.
- ③ Optional map of extra parameters to add to the authorization token request.
- ④ List of claims to use as the identity. First non-empty claim is used. At least one claim is required. If none of the listed claims have a value, authentication fails.
- ⑤ List of claims to use as the preferred user name when provisioning a user for this identity. First non-empty claim is used.
- ⑥ List of claims to use as the display name. First non-empty claim is used.
- ⑦ List of claims to use as the email address. First non-empty claim is used.
- ⑧ [UserInfo Endpoint](#) described in the OpenID spec. Must use **https**.

## 12.4. TOKEN OPTIONS

The OAuth server generates two kinds of tokens:

Access tokens	Longer-lived tokens that grant access to the API.
Authorize codes	Short-lived tokens whose only use is to be exchanged for an access token.

Use the **tokenConfig** stanza to set token options:

#### Example 12.13. Master Configuration Token Options

```
oauthConfig:
  ...
  tokenConfig:
    accessTokenMaxAgeSeconds: 86400 1
    authorizeTokenMaxAgeSeconds: 300 2
```

- 1** Set **accessTokenMaxAgeSeconds** to control the lifetime of access tokens. The default lifetime is 24 hours.
- 2** Set **authorizeTokenMaxAgeSeconds** to control the lifetime of authorize codes. The default lifetime is five minutes.



#### NOTE

You can override the **accessTokenMaxAgeSeconds** value [through an OAuthClient object definition](#).

## 12.5. GRANT OPTIONS

When the OAuth server receives token requests for a client to which the user has not previously granted permission, the action that the OAuth server takes is dependent on the OAuth client's grant strategy.

When the OAuth client requesting token does not provide its own grant strategy, the server-wide default strategy is used. To configure the default strategy, set the **method** value in the **grantConfig** stanza.

Valid values for **method** are:

<b>auto</b>	Auto-approve the grant and retry the request.
<b>prompt</b>	Prompt the user to approve or deny the grant.
<b>deny</b>	Auto-deny the grant and return a failure error to the client.

#### Example 12.14. Master Configuration Grant Options

```
oauthConfig:
  ...
  grantConfig:
```

```
method: auto
```

## 12.6. SESSION OPTIONS

The OAuth server uses a signed and encrypted cookie-based session during login and redirect flows.

Use the **sessionConfig** stanza to set session options:

### Example 12.15. Master Configuration Session Options

```
oauthConfig:
  ...
  sessionConfig:
    sessionMaxAgeSeconds: 300 1
    sessionName: ssn 2
    sessionSecretsFile: "..." 3
```

- 1** Controls the maximum age of a session; sessions auto-expire once a token request is complete. If [auto-grant](#) is not enabled, sessions must last as long as the user is expected to take to approve or reject a client authorization request.
- 2** Name of the cookie used to store the session.
- 3** File name containing serialized **SessionSecrets** object. If empty, a random signing and encryption secret is generated at each server start.

If no **sessionSecretsFile** is specified, a random signing and encryption secret is generated at each start of the master server. This means that any logins in progress will have their sessions invalidated if the master is restarted. It also means they will not be able to decode sessions generated by one of the other masters.

To specify the signing and encryption secret to use, specify a **sessionSecretsFile**. This allows you separate secret values from the configuration file and keep the configuration file distributable, for example for debugging purposes.

Multiple secrets can be specified in the **sessionSecretsFile** to enable rotation. New sessions are signed and encrypted using the first secret in the list. Existing sessions are decrypted and authenticated by each secret until one succeeds.

### Example 12.16. Session Secret Configuration:

```
apiVersion: v1
kind: SessionSecrets
secrets: 1
  - authentication: "..." 2
    encryption: "..." 3
  - authentication: "..."
    encryption: "..."
  ...
```

- 1 List of secrets used to authenticate and encrypt cookie sessions. At least one secret must be specified. Each secret must set an authentication and encryption secret.
- 2 Signing secret, used to authenticate sessions using HMAC. Recommended to use a secret with 32 or 64 bytes.
- 3 Encrypting secret, used to encrypt sessions. Must be 16, 24, or 32 characters long, to select AES-128, AES-192, or AES-256.

## 12.7. PREVENTING CLI VERSION MISMATCH WITH USER AGENT

OpenShift Container Platform implements a user agent that can be used to prevent an application developer's CLI accessing the OpenShift Container Platform API.

User agents for the OpenShift Container Platform CLI are constructed from a set of values within OpenShift Container Platform:

```
<command>/<version> (<platform>/<architecture>) <client>/<git_commit>
```

So, for example, when:

- <command> = **oc**
- <version> = The client version. For example, **v3.3.0**. Requests made against the Kubernetes API at **/api** receive the Kubernetes version, while requests made against the OpenShift Container Platform API at **/oapi** receive the OpenShift Container Platform version (as specified by **oc version**)
- <platform> = **linux**
- <architecture> = **amd64**
- <client> = **openshift**, or **kubernetes** depending on if the request is made against the Kubernetes API at **/api**, or the OpenShift Container Platform API at **/oapi**
- <git\_commit> = The Git commit of the client version (for example, **f034127**)

the user agent will be:

```
oc/v3.3.0 (linux/amd64) openshift/f034127
```

As an OpenShift Container Platform administrator, you can prevent clients from accessing the API with the **userAgentMatching** configuration setting of a master configuration. So, if a client is using a particular library or binary, they will be prevented from accessing the API.


The following user agent example denies the Kubernetes 1.2 client binary, OpenShift Origin 1.1.3 binary, and the POST and PUT **httpVerbs**:

```
policyConfig:
  userAgentMatchingConfig:
    defaultRejectionMessage: "Your client is too old. Go to
https://example.org to update it."
```

```
deniedClients:  
- regex: '\w+/v(?:1\.1\.1)|(?:1\.0\.1) \(.+/.+\) openshift/\w{7}'  
- regex: '\w+/v(?:1\.1\.3) \(.+/.+\) openshift/\w{7}'  
  httpVerbs:  
    - POST  
    - PUT  
- regex: '\w+/v1\.2\.0 \(.+/.+\) kubernetes/\w{7}'  
  httpVerbs:  
    - POST  
    - PUT  
requiredClients: null
```

Administrators can also deny clients that do not exactly match the expected clients:

```
policyConfig:  
  userAgentMatchingConfig:  
    defaultRejectionMessage: "Your client is too old. Go to  
    https://example.org to update it."  
    deniedClients: []  
    requiredClients:  
      - regex: '\w+/v1\.1\.3 \(.+/.+\) openshift/\w{7}'  
      - regex: '\w+/v1\.2\.0 \(.+/.+\) kubernetes/\w{7}'  
        httpVerbs:  
          - POST  
          - PUT
```



### NOTE

When the client's user agent mismatches the configuration, errors occur. To ensure that mutating requests match, enforce a whitelist. Rules are mapped to specific verbs, so you can ban mutating requests while allowing non-mutating requests.

# CHAPTER 13. SYNCING GROUPS WITH LDAP

## 13.1. OVERVIEW

As an OpenShift Container Platform administrator, you can use groups to manage users, change their permissions, and enhance collaboration. Your organization may have already created user groups and stored them in an LDAP server. OpenShift Container Platform can sync those LDAP records with internal OpenShift Container Platform records, enabling you to manage your groups in one place. OpenShift Container Platform currently supports group sync with LDAP servers using three common schemas for defining group membership: RFC 2307, Active Directory, and augmented Active Directory.



### NOTE

You must have [cluster-admin](#) privileges to sync groups.

## 13.2. CONFIGURING LDAP SYNC

Before you can [run LDAP sync](#), you need a sync configuration file. This file contains LDAP client configuration details:

- Configuration for connecting to your LDAP server.
- Sync configuration options that are dependent on the schema used in your LDAP server.

A sync configuration file can also contain an administrator-defined list of name mappings that maps OpenShift Container Platform Group names to groups in your LDAP server.

### 13.2.1. LDAP Client Configuration

#### Example 13.1. LDAP Client Configuration

```
url: ldap://10.0.0.0:389 ①
bindDN: cn=admin,dc=example,dc=com ②
bindPassword: password ③
insecure: false ④
ca: my-ldap-ca-bundle.crt ⑤
```

- ① The connection protocol, IP address of the LDAP server hosting your database, and the port to connect to, formatted as `scheme://host:port`.
- ② Optional distinguished name (DN) to use as the Bind DN. OpenShift Container Platform uses this if elevated privilege is required to retrieve entries for the sync operation.
- ③ Optional password to use to bind. OpenShift Container Platform uses this if elevated privilege is necessary to retrieve entries for the sync operation. This value may also be provided in an [environment variable](#), [external file](#), or [encrypted file](#).
- ④ When `true`, no TLS connection is made to the server. When `false`, secure LDAP (`ldaps://`) URLs connect using TLS, and insecure LDAP (`ldap://`) URLs are upgraded to TLS.
- ⑤ The certificate bundle to use for validating server certificates for the configured URL. If empty, OpenShift Container Platform uses system-trusted roots. This only applies if `insecure` is set to `false`.

### 13.2.2. LDAP Query Definition

Sync configurations consist of LDAP query definitions for the entries that are required for synchronization. The specific definition of an LDAP query depends on the schema used to store membership information in the LDAP server.

#### Example 13.2. LDAP Query Definition

```
baseDN: ou=users,dc=example,dc=com ①
scope: sub ②
derefAliases: never ③
timeout: 0 ④
filter: (objectClass=inetOrgPerson) ⑤
pageSize: 0 ⑥
```

- ① The distinguished name (DN) of the branch of the directory where all searches will start from. It is required that you specify the top of your directory tree, but you can also specify a subtree in the directory.
- ② The scope of the search. Valid values are **base**, **one**, or **sub**. If this is left undefined, then a scope of **sub** is assumed. Descriptions of the scope options can be found in the [table below](#).
- ③ The behavior of the search with respect to aliases in the LDAP tree. Valid values are **never**, **search**, **base**, or **always**. If this is left undefined, then the default is to **always** dereference aliases. Descriptions of the dereferencing behaviors can be found in the [table below](#).
- ④ The time limit allowed for the search by the client, in seconds. A value of 0 imposes no client-side limit.
- ⑤ A valid LDAP search filter. If this is left undefined, then the default is **(objectClass=\*)**.
- ⑥ The optional maximum size of response pages from the server, measured in LDAP entries. If set to 0, no size restrictions will be made on pages of responses. Setting paging sizes is necessary when queries return more entries than the client or server allow by default.

**Table 13.1. LDAP Search Scope Options**

LDAP Search Scope	Description
<b>base</b>	Only consider the object specified by the base DN given for the query.
<b>one</b>	Consider all of the objects on the same level in the tree as the base DN for the query.
<b>sub</b>	Consider the entire subtree rooted at the base DN given for the query.

**Table 13.2. LDAP Dereferencing Behaviors**

Dereferencing Behavior	Description
<b>never</b>	Never dereference any aliases found in the LDAP tree.
<b>search</b>	Only dereference aliases found while searching.
<b>base</b>	Only dereference aliases while finding the base object.
<b>always</b>	Always dereference all aliases found in the LDAP tree.

### 13.2.3. User-Defined Name Mapping

A user-defined name mapping explicitly maps the names of OpenShift Container Platform Groups to unique identifiers that find groups on your LDAP server. The mapping uses normal YAML syntax. A user-defined mapping can contain an entry for every group in your LDAP server or only a subset of those groups. If there are groups on the LDAP server that do not have a user-defined name mapping, the default behavior during sync is to use the attribute specified as the Group's name.

#### Example 13.3. User-Defined Name Mapping

```
groupUIDNameMapping:
  "cn=group1,ou=groups,dc=example,dc=com": firstgroup
  "cn=group2,ou=groups,dc=example,dc=com": secondgroup
  "cn=group3,ou=groups,dc=example,dc=com": thirdgroup
```

## 13.3. RUNNING LDAP SYNC

Once you have created a [sync configuration file](#), then sync can begin. OpenShift Container Platform allows administrators to perform a number of different sync types with the same server.



#### NOTE

By default, all group synchronization or pruning operations are dry-run, so you must set the **--confirm** flag on the **sync-groups** command in order to make changes to OpenShift Container Platform Group records.

To sync all groups from the LDAP server with OpenShift Container Platform:

```
$ oc adm groups sync --sync-config=config.yaml --confirm
```

To sync all Groups already in OpenShift Container Platform that correspond to groups in the LDAP server specified in the configuration file:

```
$ oc adm groups sync --type=openshift --sync-config=config.yaml --confirm
```

To sync a subset of LDAP groups with OpenShift Container Platform, you can use whitelist files, blacklist files, or both:

**NOTE**

Any combination of blacklist files, whitelist files, or whitelist literals will work; whitelist literals can be included directly in the command itself. This applies to groups found on LDAP servers, as well as Groups already present in OpenShift Container Platform. Your files must contain one unique group identifier per line.

```
$ oc adm groups sync --whitelist=<whitelist_file> \
    --sync-config=config.yaml \
    --confirm
$ oc adm groups sync --blacklist=<blacklist_file> \
    --sync-config=config.yaml \
    --confirm
$ oc adm groups sync <group_unique_identifier> \
    --sync-config=config.yaml \
    --confirm
$ oc adm groups sync <group_unique_identifier> \
    --whitelist=<whitelist_file> \
    --blacklist=<blacklist_file> \
    --sync-config=config.yaml \
    --confirm
$ oc adm groups sync --type=openshift \
    --whitelist=<whitelist_file> \
    --sync-config=config.yaml \
    --confirm
```

## 13.4. RUNNING A GROUP PRUNING JOB

An administrator can also choose to remove groups from OpenShift Container Platform records if the records on the LDAP server that created them are no longer present. The prune job will accept the same sync configuration file and white- or black-lists as used for the sync job.


For example, if groups had previously been synchronized from LDAP using some *config.yaml* file, and some of those groups no longer existed on the LDAP server, the following command would determine which Groups in OpenShift Container Platform corresponded to the deleted groups in LDAP and then remove them from OpenShift Container Platform:

```
$ oc adm groups prune --sync-config=config.yaml --confirm
```

## 13.5. SYNC EXAMPLES

This section contains examples for the [RFC 2307](#), [Active Directory](#), and [augmented Active Directory](#) schemas. All of the following examples synchronize a group named **admins** that has two members: **Jane** and **Jim**. Each example explains:

- How the group and users are added to the LDAP server.
- What the LDAP sync configuration file looks like.
- What the resulting Group record in OpenShift Container Platform will be after synchronization.

**NOTE**

These examples assume that all users are direct members of their respective groups. Specifically, no groups have other groups as members. See [Nested Membership Sync Example](#) for information on how to sync nested groups.

**13.5.1. RFC 2307**

In the RFC 2307 schema, both users (Jane and Jim) and groups exist on the LDAP server as first-class entries, and group membership is stored in attributes on the group. The following snippet of **ldif** defines the users and group for this schema:

**Example 13.4. LDAP Entries Using RFC 2307 Schema: *rfc2307.ldif***

```

dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com

dn: ou=groups,dc=example,dc=com
objectClass: organizationalUnit
ou: groups


dn: cn=admins,ou=groups,dc=example,dc=com ①
objectClass: groupOfNames
cn: admins
owner: cn=admin,dc=example,dc=com
description: System Administrators
member: cn=Jane,ou=users,dc=example,dc=com ②
member: cn=Jim,ou=users,dc=example,dc=com

```

- ① The group is a first-class entry in the LDAP server.
- ② Members of a group are listed with an identifying reference as attributes on the group.

To sync this group, you must first create the configuration file. The RFC 2307 schema requires you to provide an LDAP query definition for both user and group entries, as well as the attributes with which to represent them in the internal OpenShift Container Platform records.

For clarity, the Group you create in OpenShift Container Platform should use attributes other than the distinguished name whenever possible for user- or administrator-facing fields. For example, identify the users of a Group by their e-mail, and use the name of the group as the common name. The following configuration file creates these relationships:



### NOTE

If using user-defined name mappings, your [configuration file](#) will differ.

#### Example 13.5. LDAP Sync Configuration Using RFC 2307 Schema: `rfc2307_config.yaml`

```
kind: LDAPSvcSyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389 1
insecure: false 2
rfc2307:
  groupsQuery:
    baseDN: "ou=groups,dc=example,dc=com"
    scope: sub
    derefAliases: never
    pageSize: 0
  groupUIDAttribute: dn 3
  groupNameAttributes: [ cn ] 4
  groupMembershipAttributes: [ member ] 5
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never
    pageSize: 0
  userUIDAttribute: dn 6
  userNameAttributes: [ mail ] 7
  tolerateMemberNotFoundErrors: false
  tolerateMemberOutOfScopeErrors: false
```

- 1** The IP address and host of the LDAP server where this group's record is stored.
- 2** When `true`, no TLS connection is made to the server. When `false`, secure LDAP (`ldaps://`) URLs connect using TLS, and insecure LDAP (`ldap://`) URLs are upgraded to TLS.
- 3** The attribute that uniquely identifies a group on the LDAP server. You cannot specify `groupsQuery` filters when using DN for groupUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).
- 4** The attribute to use as the name of the Group.
- 5** The attribute on the group that stores the membership information.
- 6** The attribute that uniquely identifies a user on the LDAP server. You cannot specify `usersQuery` filters when using DN for userUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).

- 7** The attribute to use as the name of the user in the OpenShift Container Platform Group record.

To run sync with the *rfc2307\_config.yaml* file:

```
$ oc adm groups sync --sync-config=rfc2307_config.yaml --confirm
```

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

#### Example 13.6. OpenShift Container Platform Group Created Using *rfc2307\_config.yaml*

```
apiVersion: user.openshift.io/v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400 1
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com 2
    openshift.io/ldap.url: LDAP_SERVER_IP:389 3
  creationTimestamp:
    name: admins 4
  users: 5
    - jane.smith@example.com
    - jim.adams@example.com
```

- 1** The last time this Group was synchronized with the LDAP server, in ISO 6801 format.
- 2** The unique identifier for the group on the LDAP server.
- 3** The IP address and host of the LDAP server where this Group's record is stored.
- 4** The name of the Group as specified by the sync file.
- 5** The users that are members of the Group, named as specified by the sync file.

#### 13.5.1.1. RFC2307 with User-Defined Name Mappings

When syncing groups with user-defined name mappings, the configuration file changes to contain these mappings as shown below.

#### Example 13.7. LDAP Sync Configuration Using RFC 2307 Schema With User-Defined Name Mappings: *rfc2307\_config\_user\_defined.yaml*

```
kind: LDAPSNCConfig
apiVersion: v1
groupUIDNameMapping:
  "cn=admins,ou=groups,dc=example,dc=com": Administrators 1
  rfc2307:
    groupsQuery:
      baseDN: "ou=groups,dc=example,dc=com"
      scope: sub
```

```

derefAliases: never
pageSize: 0
groupUIDAttribute: dn 2
groupNameAttributes: [ cn ] 3
groupMembershipAttributes: [ member ]
usersQuery:
  baseDN: "ou=users,dc=example,dc=com"
  scope: sub
  derefAliases: never
  pageSize: 0
userUIDAttribute: dn 4
userNameAttributes: [ mail ]
tolerateMemberNotFoundErrors: false
tolerateMemberOutOfScopeErrors: false

```

- 1** The user-defined name mapping.
- 2** The unique identifier attribute that is used for the keys in the user-defined name mapping. You cannot specify **groupsQuery** filters when using DN for groupUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).
- 3** The attribute to name OpenShift Container Platform Groups with if their unique identifier is not in the user-defined name mapping.
- 4** The attribute that uniquely identifies a user on the LDAP server. You cannot specify **usersQuery** filters when using DN for userUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).

To run sync with the *rfc2307\_config\_user\_defined.yaml* file:

```
$ oc adm groups sync --sync-config=rfc2307_config_user_defined.yaml --confirm
```

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

#### Example 13.8. OpenShift Container Platform Group Created Using *rfc2307\_config\_user\_defined.yaml*

```

apiVersion: user.openshift.io/v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com
    openshift.io/ldap.url: LDAP_SERVER_IP:389
  creationTimestamp:
    name: Administrators 1
  users:
    - jane.smith@example.com
    - jim.adams@example.com

```

- 1** The name of the Group as specified by the user-defined name mapping.

### 13.5.2. RFC 2307 with User-Defined Error Tolerances

By default, if the groups being synced contain members whose entries are outside of the scope defined in the member query, the group sync fails with an error:

Error determining LDAP group membership for "<group>": membership lookup for user "<user>" in group "<group>" failed because of "search for entry with dn="<user-dn>" would search outside of the base dn specified (dn="<base-dn>"").

This often indicates a mis-configured **baseDN** in the **usersQuery** field. However, in cases where the **baseDN** intentionally does not contain some of the members of the group, setting **tolerateMemberOutOfScopeErrors: true** allows the group sync to continue. Out of scope members will be ignored.

Similarly, when the group sync process fails to locate a member for a group, it fails outright with errors:

Error determining LDAP group membership for "<group>": membership lookup for user "<user>" in group "<group>" failed because of "search for entry with base dn="<user-dn>" refers to a non-existent entry".

Error determining LDAP group membership for "<group>": membership lookup for user "<user>" in group "<group>" failed because of "search for entry with base dn="<user-dn>" and filter "<filter>" did not return any results".

This often indicates a mis-configured **usersQuery** field. However, in cases where the group contains member entries that are known to be missing, setting **tolerateMemberNotFoundErrors: true** allows the group sync to continue. Problematic members will be ignored.



#### WARNING

Enabling error tolerances for the LDAP group sync causes the sync process to ignore problematic member entries. If the LDAP group sync is not configured correctly, this could result in synced OpenShift Container Platform groups missing members.

#### Example 13.9. LDAP Entries Using RFC 2307 Schema With Problematic Group Membership: *rfc2307\_problematic\_users.ldif*

```
dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
```

```

objectClass: organizationalPerson
objectClass: inetOrgPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com

dn: ou=groups,dc=example,dc=com
objectClass: organizationalUnit
ou: groups

dn: cn=admins,ou=groups,dc=example,dc=com
objectClass: groupOfNames
cn: admins
owner: cn=admin,dc=example,dc=com
description: System Administrators
member: cn=Jane,ou=users,dc=example,dc=com
member: cn=Jim,ou=users,dc=example,dc=com
member: cn=INVALID,ou=users,dc=example,dc=com ①
member: cn=Jim,ou=OUTOFSCOPE,dc=example,dc=com ②

```

- ① A member that does not exist on the LDAP server.
- ② A member that may exist, but is not under the **baseDN** in the user query for the sync job.

In order to tolerate the errors in the above example, the following additions to your sync configuration file must be made:

#### Example 13.10. LDAP Sync Configuration Using RFC 2307 Schema Tolerating Errors: *rfc2307\_config\_tolerating.yaml*

```

kind: LDAPSsyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389
rfc2307:
  groupsQuery:
    baseDN: "ou=groups,dc=example,dc=com"
    scope: sub
    derefAliases: never
  groupUIDAttribute: dn
  groupNameAttributes: [ cn ]
  groupMembershipAttributes: [ member ]
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"

```

```

    scope: sub
    derefAliases: never
    userUIDAttribute: dn 1
    userNameAttributes: [ mail ]
    tolerateMemberNotFoundErrors: true 2
    tolerateMemberOutOfScopeErrors: true 3

```

- 2** When **true**, the sync job tolerates groups for which some members were not found, and members whose LDAP entries are not found are ignored. The default behavior for the sync job is to fail if a member of a group is not found.
- 3** When **true**, the sync job tolerates groups for which some members are outside the user scope given in the **usersQuery** base DN, and members outside the member query scope are ignored. The default behavior for the sync job is to fail if a member of a group is out of scope.
- 1** The attribute that uniquely identifies a user on the LDAP server. You cannot specify **usersQuery** filters when using DN for userUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).

To run sync with the *rfc2307\_config\_tolerating.yaml* file:

```
$ oc adm groups sync --sync-config=rfc2307_config_tolerating.yaml --confirm
```

OpenShift Container Platform creates the following group record as a result of the above sync operation:

#### Example 13.11. OpenShift Container Platform Group Created Using *rfc2307\_config.yaml*

```

apiVersion: user.openshift.io/v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com
    openshift.io/ldap.url: LDAP_SERVER_IP:389
  creationTimestamp:
  name: admins
users: 1
- jane.smith@example.com
- jim.adams@example.com

```

- 1** The users that are members of the group, as specified by the sync file. Members for which lookup encountered tolerated errors are absent.

### 13.5.3. Active Directory

In the Active Directory schema, both users (Jane and Jim) exist in the LDAP server as first-class entries, and group membership is stored in attributes on the user. The following snippet of **ldif** defines the users and group for this schema:

**Example 13.12. LDAP Entries Using Active Directory Schema: *active\_directory.ldif***

```

dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com
memberOf: admins 1

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com
memberOf: admins

```

- 1** The user's group memberships are listed as attributes on the user, and the group does not exist as an entry on the server. The **memberOf** attribute does not have to be a literal attribute on the user; in some LDAP servers, it is created during search and returned to the client, but not committed to the database.

To sync this group, you must first create the configuration file. The Active Directory schema requires you to provide an LDAP query definition for user entries, as well as the attributes to represent them with in the internal OpenShift Container Platform Group records.

For clarity, the Group you create in OpenShift Container Platform should use attributes other than the distinguished name whenever possible for user- or administrator-facing fields. For example, identify the users of a Group by their e-mail, but define the name of the Group by the name of the group on the LDAP server. The following configuration file creates these relationships:

**Example 13.13. LDAP Sync Configuration Using Active Directory Schema: *active\_directory\_config.yaml***

```

kind: LDAPSsyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389
activeDirectory:
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never

```

```

filter: (objectclass=inetOrgPerson)
pageSize: 0
userNameAttributes: [ mail ] ①
groupMembershipAttributes: [ memberOf ] ②

```

- ① The attribute to use as the name of the user in the OpenShift Container Platform Group record.
- ② The attribute on the user that stores the membership information.

To run sync with the ***active\_directory\_config.yaml*** file:

```
$ oc adm groups sync --sync-config=active_directory_config.yaml --confirm
```

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

#### Example 13.14. OpenShift Container Platform Group Created Using *active\_directory\_config.yaml*

```

apiVersion: user.openshift.io/v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400 ①
    openshift.io/ldap.uid: admins ②
    openshift.io/ldap.url: LDAP_SERVER_IP:389 ③
  creationTimestamp:
    name: admins ④
  users: ⑤
    - jane.smith@example.com
    - jim.adams@example.com

```

- ① The last time this Group was synchronized with the LDAP server, in ISO 8601 format.
- ② The unique identifier for the group on the LDAP server.
- ③ The IP address and host of the LDAP server where this Group's record is stored.
- ④ The name of the group as listed in the LDAP server.
- ⑤ The users that are members of the Group, named as specified by the sync file.

#### 13.5.4. Augmented Active Directory

In the augmented Active Directory schema, both users (Jane and Jim) and groups exist in the LDAP server as first-class entries, and group membership is stored in attributes on the user. The following snippet of **ldif** defines the users and group for this schema:

### Example 13.15. LDAP Entries Using Augmented Active Directory Schema: *augmented\_active\_directory.ldif*

```

dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com
memberOf: cn=admins,ou=groups,dc=example,dc=com ①

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com
memberOf: cn=admins,ou=groups,dc=example,dc=com

dn: ou=groups,dc=example,dc=com
objectClass: organizationalUnit
ou: groups

dn: cn=admins,ou=groups,dc=example,dc=com ②
objectClass: groupOfNames
cn: admins
owner: cn=admin,dc=example,dc=com
description: System Administrators
member: cn=Jane,ou=users,dc=example,dc=com
member: cn=Jim,ou=users,dc=example,dc=com

```

- ① The user's group memberships are listed as attributes on the user.
- ② The group is a first-class entry on the LDAP server.

To sync this group, you must first create the configuration file. The augmented Active Directory schema requires you to provide an LDAP query definition for both user entries and group entries, as well as the attributes with which to represent them in the internal OpenShift Container Platform Group records.

For clarity, the Group you create in OpenShift Container Platform should use attributes other than the distinguished name whenever possible for user- or administrator-facing fields. For example, identify the users of a Group by their e-mail, and use the name of the Group as the common name. The following configuration file creates these relationships.

**Example 13.16. LDAP Sync Configuration Using Augmented Active Directory Schema: *augmented\_active\_directory\_config.yaml***

```
kind: LDAPSsyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389
augmentedActiveDirectory:
  groupsQuery:
    baseDN: "ou=groups,dc=example,dc=com"
    scope: sub
    derefAliases: never
    pageSize: 0
  groupUIDAttribute: dn 1
  groupNameAttributes: [ cn ] 2
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never
    filter: (objectclass=inetOrgPerson)
    pageSize: 0
  userNameAttributes: [ mail ] 3
  groupMembershipAttributes: [ memberOf ] 4
```

- 1** The attribute that uniquely identifies a group on the LDAP server. You cannot specify **groupsQuery** filters when using DN for groupUIDAttribute. For fine-grained filtering, use the [whitelist / blacklist method](#).
- 2** The attribute to use as the name of the Group.
- 3** The attribute to use as the name of the user in the OpenShift Container Platform Group record.
- 4** The attribute on the user that stores the membership information.

To run sync with the ***augmented\_active\_directory\_config.yaml*** file:

```
$ oc adm groups sync --sync-config=augmented_active_directory_config.yaml
--confirm
```

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

**Example 13.17. OpenShift Group Created Using *augmented\_active\_directory\_config.yaml***

```
apiVersion: user.openshift.io/v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400 1
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com 2
    openshift.io/ldap.url: LDAP_SERVER_IP:389 3
  creationTimestamp:
  name: admins 4
```

```
users: 5
- jane.smith@example.com
- jim.adams@example.com
```

- 1 The last time this Group was synchronized with the LDAP server, in ISO 6801 format.
- 2 The unique identifier for the group on the LDAP server.
- 3 The IP address and host of the LDAP server where this Group's record is stored.
- 4 The name of the Group as specified by the sync file.
- 5 The users that are members of the Group, named as specified by the sync file.

## 13.6. NESTED MEMBERSHIP SYNC EXAMPLE

Groups in OpenShift Container Platform do not nest. The LDAP server must flatten group membership before the data can be consumed. Microsoft's Active Directory Server supports this feature via the [LDAP\\_MATCHING\\_RULE\\_IN\\_CHAIN](#) rule, which has the OID **1.2.840.113556.1.4.1941**. Furthermore, only explicitly [whitelisted](#) groups can be synced when using this matching rule.

This section has an example for the augmented Active Directory schema, which synchronizes a group named **admins** that has one user **Jane** and one group **otheradmins** as members. The **otheradmins** group has one user member: **Jim**. This example explains:

- How the group and users are added to the LDAP server.
- What the LDAP sync configuration file looks like.
- What the resulting Group record in OpenShift Container Platform will be after synchronization.

In the augmented Active Directory schema, both users (**Jane** and **Jim**) and groups exist in the LDAP server as first-class entries, and group membership is stored in attributes on the user or the group. The following snippet of **ldif** defines the users and groups for this schema:

### LDAP Entries Using Augmented Active Directory Schema With Nested Members: *augmented\_active\_directory\_nested.ldif*

```
dn: ou=users,dc=example,dc=com
objectClass: organizationalUnit
ou: users

dn: cn=Jane,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jane
sn: Smith
displayName: Jane Smith
mail: jane.smith@example.com
memberOf: cn=admins,ou=groups,dc=example,dc=com 1
```

```

dn: cn=Jim,ou=users,dc=example,dc=com
objectClass: person
objectClass: organizationalPerson
objectClass: inetOrgPerson
objectClass: testPerson
cn: Jim
sn: Adams
displayName: Jim Adams
mail: jim.adams@example.com
memberOf: cn=otheradmins,ou=groups,dc=example,dc=com ②

dn: ou=groups,dc=example,dc=com
objectClass: organizationalUnit
ou: groups

dn: cn=admins,ou=groups,dc=example,dc=com ③
objectClass: group
cn: admins
owner: cn=admin,dc=example,dc=com
description: System Administrators
member: cn=Jane,ou=users,dc=example,dc=com
member: cn=otheradmins,ou=groups,dc=example,dc=com

dn: cn=otheradmins,ou=groups,dc=example,dc=com ④
objectClass: group
cn: otheradmins
owner: cn=admin,dc=example,dc=com
description: Other System Administrators
memberOf: cn=admins,ou=groups,dc=example,dc=com ⑤ ⑥
member: cn=Jim,ou=users,dc=example,dc=com

```

① ② ⑤ The user's and group's memberships are listed as attributes on the object.

③ ④ The groups are first-class entries on the LDAP server.

⑥ The **otheradmins** group is a member of the **admins** group.

To sync nested groups with Active Directory, you must provide an LDAP query definition for both user entries and group entries, as well as the attributes with which to represent them in the internal OpenShift Container Platform Group records. Furthermore, certain changes are required in this configuration:

- The **oc adm groups sync** command must explicitly [whitelist](#) groups.
- The user's **groupMembershipAttributes** must include **"memberOf:1.2.840.113556.1.4.1941:"** to comply with the [LDAP\\_MATCHING\\_RULE\\_IN\\_CHAIN](#) rule.
- The **groupUIDAttribute** must be set to **dn**.
- The **groupsQuery**:
  - Must not set **filter**.
  - Must set a valid **derefAliases**.

- Should not set **baseDN** as that value is ignored.
- Should not set **scope** as that value is ignored.

For clarity, the Group you create in OpenShift Container Platform should use attributes other than the distinguished name whenever possible for user- or administrator-facing fields. For example, identify the users of a Group by their e-mail, and use the name of the Group as the common name. The following configuration file creates these relationships:


### LDAP Sync Configuration Using Augmented Active Directory Schema With Nested Members: *augmented\_active\_directory\_config\_nested.yaml*

```
kind: LDAPSsyncConfig
apiVersion: v1
url: ldap://LDAP_SERVICE_IP:389
augmentedActiveDirectory:
  groupsQuery: ①
    derefAliases: never
    pageSize: 0
  groupUUIDAttribute: dn ②
  groupNameAttributes: [ cn ] ③
  usersQuery:
    baseDN: "ou=users,dc=example,dc=com"
    scope: sub
    derefAliases: never
    filter: (objectclass=inetOrgPerson)
    pageSize: 0
 (userNameAttributes: [ mail ] ④
  groupMembershipAttributes: [ "memberOf:1.2.840.113556.1.4.1941:" ] ⑤
```

- ① **groupsQuery** filters cannot be specified. The **groupsQuery** base DN and scope values are ignored. **groupsQuery** must set a valid **derefAliases**.
- ② The attribute that uniquely identifies a group on the LDAP server. It must be set to **dn**.
- ③ The attribute to use as the name of the Group.
- ④ The attribute to use as the name of the user in the OpenShift Container Platform Group record. **mail** or **sAMAccountName** are preferred choices in most installations.
- ⑤ The attribute on the user that stores the membership information. Note the use of [LDAP\\_MATCHING\\_RULE\\_IN\\_CHAIN](#).

To run sync with the *augmented\_active\_directory\_config\_nested.yaml* file:

```
$ oc adm groups sync \
'cn=admins,ou=groups,dc=example,dc=com' \
--sync-config=augmented_active_directory_config_nested.yaml \
--confirm
```



#### NOTE

You must explicitly whitelist the **cn=admins, ou=groups, dc=example, dc=com** group.

OpenShift Container Platform creates the following Group record as a result of the above sync operation:

### OpenShift Group Created Using `augmented_active_directory_config_nested.yaml`

```
apiVersion: user.openshift.io/v1
kind: Group
metadata:
  annotations:
    openshift.io/ldap.sync-time: 2015-10-13T10:08:38-0400 1
    openshift.io/ldap.uid: cn=admins,ou=groups,dc=example,dc=com 2
    openshift.io/ldap.url: LDAP_SERVER_IP:389 3
  creationTimestamp:
    name: admins 4
  users: 5
    - jane.smith@example.com
    - jim.adams@example.com
```

- 1** The last time this Group was synchronized with the LDAP server, in ISO 6801 format.
- 2** The unique identifier for the group on the LDAP server.
- 3** The IP address and host of the LDAP server where this Group's record is stored.
- 4** The name of the Group as specified by the sync file.
- 5** The users that are members of the Group, named as specified by the sync file. Note that members of nested groups are included since the group membership was flattened by the Microsoft Active Directory Server.

## 13.7. LDAP SYNC CONFIGURATION SPECIFICATION

The object specification for the configuration file is below. Note that the different schema objects have different fields. For example, `v1.ActiveDirectoryConfig` has no `groupsQuery` field whereas `v1.RFC2307Config` and `v1.AugmentedActiveDirectoryConfig` both do.



### IMPORTANT

There is no support for binary attributes. All attribute data coming from the LDAP server must be in the format of a UTF-8 encoded string. For example, never use a binary attribute, such as `objectGUID`, as an ID attribute. You must use string attributes, such as `sAMAccountName` or `userPrincipalName`, instead.

### 13.7.1. v1.LDAPSyncConfig

`LDAPSsyncConfig` holds the necessary configuration options to define an LDAP group sync.

Name	Description	Schema
------	-------------	--------

Name	Description	Schema
<b>kind</b>	String value representing the REST resource this object represents. Servers may infer this from the endpoint the client submits requests to. Cannot be updated. In CamelCase. More info: <a href="https://github.com/kubernetes/community/blob/master/contributors/devel/api-conventions.md#types-kinds">https://github.com/kubernetes/community/blob/master/contributors/devel/api-conventions.md#types-kinds</a>	string
<b>apiVersion</b>	Defines the versioned schema of this representation of an object. Servers should convert recognized schemas to the latest internal value, and may reject unrecognized values. More info: <a href="https://github.com/kubernetes/community/blob/master/contributors/devel/api-conventions.md#resources">https://github.com/kubernetes/community/blob/master/contributors/devel/api-conventions.md#resources</a>	string
<b>url</b>	Host is the scheme, host and port of the LDAP server to connect to: <b>scheme://host:port</b>	string
<b>bindDN</b>	Optional DN to bind to the LDAP server with.	string
<b>bindPassword</b>	Optional password to bind with during the search phase.	v1.StringSource
<b>insecure</b>	If <b>true</b> , indicates the connection should not use TLS. Cannot be set to true with a URL scheme of <b>ldaps://</b> . If <b>false</b> , <b>ldaps://</b> URLs connect using TLS, and <b>ldap://</b> URLs are upgraded to a TLS connection using StartTLS as specified in <a href="https://tools.ietf.org/html/rfc2830">https://tools.ietf.org/html/rfc2830</a> .	boolean
<b>ca</b>	Optional trusted certificate authority bundle to use when making requests to the server. If empty, the default system roots are used.	string

Name	Description	Schema
<b>groupUIDNameMapping</b>	Optional direct mapping of LDAP group UIDs to OpenShift Container Platform Group names.	object
<b>rfc2307</b>	Holds the configuration for extracting data from an LDAP server set up in a fashion similar to RFC2307: first-class group and user entries, with group membership determined by a multi-valued attribute on the group entry listing its members.	<a href="#">v1.RFC2307Config</a>
<b>activeDirectory</b>	Holds the configuration for extracting data from an LDAP server set up in a fashion similar to that used in Active Directory: first-class user entries, with group membership determined by a multi-valued attribute on members listing groups they are a member of.	<a href="#">v1.ActiveDirectoryConfig</a>
<b>augmentedActiveDirectory</b>	Holds the configuration for extracting data from an LDAP server set up in a fashion similar to that used in Active Directory as described above, with one addition: first-class group entries exist and are used to hold metadata but not group membership.	<a href="#">v1.AugmentedActiveDirectoryConfig</a>

### 13.7.2. v1.StringSource

**StringSource** allows specifying a string inline, or externally via environment variable or file. When it contains only a string value, it marshals to a simple JSON string.

Name	Description	Schema
<b>value</b>	Specifies the cleartext value, or an encrypted value if <b>keyFile</b> is specified.	string
<b>env</b>	Specifies an environment variable containing the cleartext value, or an encrypted value if the <b>keyFile</b> is specified.	string

Name	Description	Schema
<b>file</b>	References a file containing the cleartext value, or an encrypted value if a <b>keyFile</b> is specified.	string
<b>keyFile</b>	References a file containing the key to use to decrypt the value.	string

### 13.7.3. v1.LDAPQuery

**LDAPQuery** holds the options necessary to build an LDAP query.

Name	Description	Schema
<b>baseDN</b>	DN of the branch of the directory where all searches should start from.	string
<b>scope</b>	The (optional) scope of the search. Can be <b>base</b> (only the base object), <b>one</b> (all objects on the base level), <b>sub</b> (the entire subtree). Defaults to <b>sub</b> if not set.	string
<b>derefAliases</b>	The (optional) behavior of the search with regards to aliases. Can be <b>never</b> (never dereference aliases), <b>search</b> (only dereference in searching), <b>base</b> (only dereference in finding the base object), <b>always</b> (always dereference). Defaults to <b>always</b> if not set.	string
<b>timeout</b>	Holds the limit of time in seconds that any request to the server can remain outstanding before the wait for a response is given up. If this is <b>0</b> , no client-side limit is imposed.	integer
<b>filter</b>	A valid LDAP search filter that retrieves all relevant entries from the LDAP server with the base DN.	string

Name	Description	Schema
<b>pageSize</b>	Maximum preferred page size, measured in LDAP entries. A page size of <b>0</b> means no paging will be done.	integer

### 13.7.4. v1.RFC2307Config

**RFC2307Config** holds the necessary configuration options to define how an LDAP group sync interacts with an LDAP server using the RFC2307 schema.

Name	Description	Schema
<b>groupsQuery</b>	Holds the template for an LDAP query that returns group entries.	<a href="#">v1.LDAPQuery</a>
<b>groupUIDAttribute</b>	Defines which attribute on an LDAP group entry will be interpreted as its unique identifier. ( <b>ldapGroupUID</b> )	string
<b>groupNameAttributes</b>	Defines which attributes on an LDAP group entry will be interpreted as its name to use for an OpenShift Container Platform group.	string array
<b>groupMembershipAttributes</b>	Defines which attributes on an LDAP group entry will be interpreted as its members. The values contained in those attributes must be queryable by your <b>UserUIDAttribute</b> .	string array
<b>usersQuery</b>	Holds the template for an LDAP query that returns user entries.	<a href="#">v1.LDAPQuery</a>
<b>userUIDAttribute</b>	Defines which attribute on an LDAP user entry will be interpreted as its unique identifier. It must correspond to values that will be found from the <b>GroupMembershipAttributes</b> .	string

Name	Description	Schema
<b>userNameAttributes</b>	Defines which attributes on an LDAP user entry will be used, in order, as its OpenShift Container Platform user name. The first attribute with a non-empty value is used. This should match your <b>PreferredUsername</b> setting for your <b>LDAPPasswordIdentityProvider</b> . The attribute to use as the name of the user in the OpenShift Container Platform Group record. <b>mail</b> or <b>sAMAccountName</b> are preferred choices in most installations.	string array
<b>tolerateMemberNotFoundErrors</b>	Determines the behavior of the LDAP sync job when missing user entries are encountered. If <b>true</b> , an LDAP query for users that does not find any will be tolerated and an only an error will be logged. If <b>false</b> , the LDAP sync job will fail if a query for users doesn't find any. The default value is 'false'. Misconfigured LDAP sync jobs with this flag set to 'true' can cause group membership to be removed, so it is recommended to use this flag with caution.	boolean
<b>tolerateMemberOutOfScopeErrors</b>	Determines the behavior of the LDAP sync job when out-of-scope user entries are encountered. If <b>true</b> , an LDAP query for a user that falls outside of the base DN given for the all user query will be tolerated and only an error will be logged. If <b>false</b> , the LDAP sync job will fail if a user query would search outside of the base DN specified by the all user query. Misconfigured LDAP sync jobs with this flag set to <b>true</b> can result in groups missing users, so it is recommended to use this flag with caution.	boolean

### 13.7.5. v1.ActiveDirectoryConfig

**ActiveDirectoryConfig** holds the necessary configuration options to define how an LDAP group sync interacts with an LDAP server using the Active Directory schema.

Name	Description	Schema
<b>usersQuery</b>	Holds the template for an LDAP query that returns user entries.	<a href="#">v1.LDAPQuery</a>
<b>userNameAttributes</b>	Defines which attributes on an LDAP user entry will be interpreted as its OpenShift Container Platform user name. The attribute to use as the name of the user in the OpenShift Container Platform Group record. <b>mail</b> or <b>sAMAccountName</b> are preferred choices in most installations.	string array
<b>groupMembershipAttributes</b>	Defines which attributes on an LDAP user entry will be interpreted as the groups it is a member of.	string array

### 13.7.6. v1.AugmentedActiveDirectoryConfig

**AugmentedActiveDirectoryConfig** holds the necessary configuration options to define how an LDAP group sync interacts with an LDAP server using the augmented Active Directory schema.

Name	Description	Schema
<b>usersQuery</b>	Holds the template for an LDAP query that returns user entries.	<a href="#">v1.LDAPQuery</a>
<b>userNameAttributes</b>	Defines which attributes on an LDAP user entry will be interpreted as its OpenShift Container Platform user name. The attribute to use as the name of the user in the OpenShift Container Platform Group record. <b>mail</b> or <b>sAMAccountName</b> are preferred choices in most installations.	string array
<b>groupMembershipAttributes</b>	Defines which attributes on an LDAP user entry will be interpreted as the groups it is a member of.	string array


Name	Description	Schema
<b>groupsQuery</b>	Holds the template for an LDAP query that returns group entries.	<a href="#">v1.LDAPQuery</a>
<b>groupUIDAttribute</b>	Defines which attribute on an LDAP group entry will be interpreted as its unique identifier. <b>(ldapGroupUID)</b>	string
<b>groupNameAttributes</b>	Defines which attributes on an LDAP group entry will be interpreted as its name to use for an OpenShift Container Platform group.	string array

# CHAPTER 14. CONFIGURING LDAP FAILOVER

OpenShift Container Platform provides an [authentication provider](#) for use with Lightweight Directory Access Protocol (LDAP) setups, but it can connect to only a single LDAP server. During OpenShift Container Platform installation, you can configure the System Security Services Daemon (SSSD) for LDAP failover to ensure access to your cluster if one LDAP server fails.

The setup for this configuration is advanced and requires a separate authentication server, also called an **remote basic authentication server**, for OpenShift Container Platform to communicate with. You configure this server to pass extra attributes, such as email addresses, to OpenShift Container Platform so it can display them in the web console.

This topic describes how to complete this set up on a dedicated physical or virtual machine (VM), but you can also configure SSSD in containers.



## IMPORTANT

You must complete all sections of this topic.

## 14.1. PREREQUISITES FOR CONFIGURING BASIC REMOTE AUTHENTICATION

- Before starting setup, you need to know the following information about your LDAP server:
  - Whether the directory server is powered by [FreeIPA](#), Active Directory, or another LDAP solution.
  - The Uniform Resource Identifier (URI) for the LDAP server, for example, **ldap.example.com**.
  - The location of the CA certificate for the LDAP server.
  - Whether the LDAP server corresponds to RFC 2307 or RFC2307bis for user groups.
- Prepare the servers:
  - ***remote-basic.example.com***: A VM to use as the remote basic authentication server.
    - Select an operating system that includes SSSD version 1.12.0 for this server such as Red Hat Enterprise Linux 7.0 or later.
  - ***openshift.example.com***: A new installation of OpenShift Container Platform.
    - You must not have an authentication method configured for this cluster.
    - Do not start OpenShift Container Platform on this cluster.

## 14.2. GENERATING AND SHARING CERTIFICATES WITH THE REMOTE BASIC AUTHENTICATION SERVER

Complete the following steps on the first master host listed in the Ansible host inventory file, by default `/etc/ansible/hosts`.

- To ensure that communication between the remote basic authentication server and OpenShift Container Platform is trustworthy, create a set of Transport Layer Security (TLS) certificates to use during the other phases of this set up. Run the following command:

```
# openshift start \
--public-master=https://openshift.example.com:8443 \
--write-config=/etc/origin/
```

The output includes the `/etc/origin/master/ca.crt` and `/etc/origin/master/ca.key` signing certificates.

- Use the signing certificate to generate keys to use on the remote basic authentication server:

```
# mkdir -p /etc/origin/remote-basic/
# oc adm ca create-server-cert \
--cert='/etc/origin/remote-basic/remote-basic.example.com.crt' \
--key='/etc/origin/remote-basic/remote-basic.example.com.key' \
--hostnames=remote-basic.example.com \ ①
--signer-cert='/etc/origin/master/ca.crt' \
--signer-key='/etc/origin/master/ca.key' \
--signer-serial='/etc/origin/master/ca.serial.txt'
```

- A comma-separated list of all the host names and interface IP addresses that need to access the remote basic authentication server.



### NOTE

The certificate files that you generate are valid for two years. You can alter this period by changing the `--expire-days` and `--signer-expire-days` values, but for security reasons, do not make them greater than 730.



### IMPORTANT

If you do not list all host names and interface IP addresses that need to access the remote basic authentication server, the HTTPS connection will fail.

- Copy the necessary certificates and key to the remote basic authentication server:

```
# scp /etc/origin/master/ca.crt \
root@remote-basic.example.com:/etc/pki/CA/certs/
# scp /etc/origin/remote-basic/remote-basic.example.com.crt \
root@remote-basic.example.com:/etc/pki/tls/certs/
# scp /etc/origin/remote-basic/remote-basic.example.com.key \
root@remote-basic.example.com:/etc/pki/tls/private/
```

## 14.3. CONFIGURING SSSD FOR LDAP FAILOVER

Complete these steps on the remote basic authentication server.

You can configure the SSSD to retrieve attributes, such as email addresses and display names, and pass them to OpenShift Container Platform to display in the web interface. In the following steps, you configure the SSSD to provide email addresses to OpenShift Container Platform:

1. Install the required SSSD and the web server components:

```
# yum install -y sssd \
    sssd-dbus \
    realmd \
    httpd \
    mod_session \
    mod_ssl \
    mod_lookup_identity \
    mod_authnz_pam \
    php \
    mod_php
```

2. Set up SSSD to authenticate this VM against the LDAP server. If the LDAP server is a FreeIPA or Active Directory environment, then use **realmd** to join this machine to the domain.

```
# realm join ldap.example.com
```

For more advanced cases, see the [System-Level Authentication Guide](#)

3. To use SSSD to manage failover situations for LDAP, add more entries to the **/etc/sssd/sssd.conf** file on the **Idap\_uri** line. Systems that are enrolled with FreeIPA can automatically handle failover by using DNS SRV records.
4. Modify the **[domain/DOMAINNAME]** section of the **/etc/sssd/sssd.conf** file and add this attribute:

```
[domain/example.com]
...
ldap_user_extra_attrs = mail ①
```

- ① Specify the correct attribute to retrieve email addresses for your LDAP solution. For IPA, specify **mail**. Other LDAP solutions might use another attribute, such as **email**.

5. Confirm that the **domain** parameter in the **/etc/sssd/sssd.conf** file contains only the domain name listed in the **[domain/DOMAINNAME]** section.

```
domains = example.com
```

6. Grant Apache permission to retrieve the email attribute. Add the following lines to the **[ifp]** section of the **/etc/sssd/sssd.conf** file:

```
[ifp]
user_attributes = +mail
allowed_uids = apache, root
```

7. To ensure that all of the changes are applied properly, restart SSSD:

```
$ systemctl restart sssd.service
```

- Test that the user information can be retrieved properly:

```
$ getent passwd <username>
username:*:12345:12345:Example User:/home/username:/usr/bin/bash
```

- Confirm that the mail attribute you specified returns an email address from your domain:

```
# dbus-send --print-reply --system --
dest=org.freedesktop.sssd.infopipe \
/org/freedesktop/sssd/infopipe
org.freedesktop.sssd.infopipe.GetUserAttr \
string:username \ ①
array:string:mail ②

method return time=1528091855.672691 sender=:1.2787 ->
destination=:1.2795 serial=13 reply_serial=2
array [
dict entry(
string "mail"
variant           array [
string "username@example.com"
]
)
]
```

- ① Provide a user name in your LDAP solution.
- ② Specify the attribute that you configured.

- Attempt to log into the VM as an LDAP user and confirm that you can log in using LDAP credentials. You can use either the local console or a remote service like SSH to log in.



### IMPORTANT

By default, all users can log into the remote basic authentication server by using their LDAP credentials. You can change this behavior:

- If you use IPA joined systems, [configure host-based access control](#).
- If you use Active Directory joined systems, use a [group policy object](#).
- For other cases, see the [SSSD configuration](#) documentation.

## 14.4. CONFIGURING APACHE TO USE SSSD

- Create a `/etc/pam.d/openshift` file that contains the following contents:


```
auth required pam_sss.so
account required pam_sss.so
```

This configuration enables PAM, the pluggable authentication module, to use `pam_sss.so` to determine authentication and access control when an authentication request is issued for the `openshift` stack.

2. Edit the `/etc/httpd/conf.modules.d/55-authnz_pam.conf` file and uncomment the following line:

```
LoadModule authnz_pam_module modules/mod_authnz_pam.so
```

3. To configure the Apache `httpd.conf` file for remote basic authentication, create the `openshift-remote-basic-auth.conf` file in the `/etc/httpd/conf.d` directory. Use the following template to provide your required settings and values:



## IMPORTANT

Carefully review the template and customize its contents to fit your environment.

```
LoadModule request_module modules/mod_request.so
LoadModule php7_module modules/libphp7.so

# Nothing needs to be served over HTTP. This virtual host simply
# redirects to
# HTTPS.
<VirtualHost *:80>
    DocumentRoot /var/www/html
    RewriteEngine On
    RewriteRule ^(.*)$ https:// %{HTTP_HOST}$1 [R,L]
</VirtualHost>

<VirtualHost *:443>
    # This needs to match the certificates you generated. See the CN
    and X509v3
    # Subject Alternative Name in the output of:
    # openssl x509 -text -in /etc/pki/tls/certs/remote-
    # basic.example.com.crt
    ServerName remote-basic.example.com

    DocumentRoot /var/www/html

    # Secure all connections with TLS
    SSLEngine on
    SSLCertificateFile /etc/pki/tls/certs/remote-basic.example.com.crt
    SSLCertificateKeyFile /etc/pki/tls/private/remote-
    basic.example.com.key
    SSLCACertificateFile /etc/pki/CA/certs/ca.crt

    # Require that TLS clients provide a valid certificate
    SSLVerifyClient require
    SSLVerifyDepth 10

    # Other SSL options that may be useful
    # SSLCertificateChainFile ...
    # SSLCARevocationFile ...

    # Send logs to a specific location to make them easier to find
    ErrorLog logs/remote_basic_error_log
    TransferLog logs/remote_basic_access_log
    LogLevel warn

    # PHP script that turns the Apache REMOTE_USER env var
```

```

# into a JSON formatted response that OpenShift understands
<Location /check_user.php>
    # all requests not using SSL are denied
    SSLRequireSSL
    # denies access when SSLRequireSSL is applied
    SSLOptions +StrictRequire
    # Require both a valid basic auth user (so REMOTE_USER is always
set)
    # and that the CN of the TLS client matches that of the
OpenShift master
    <RequireAll>
        Require valid-user
        Require expr %{SSL_CLIENT_S_DN_CN} == 'system:openshift-
master'
    </RequireAll>
    # Use basic auth since OpenShift will call this endpoint with a
basic challenge
    AuthType Basic
    AuthName openshift
    AuthBasicProvider PAM
    AuthPAMService openshift

    # Store attributes in environment variables. Specify the email
attribute that
        # you confirmed.
    LookupOutput Env
    LookupUserAttr mail REMOTE_USER_MAIL
    LookupUserGECOS REMOTE_USER_DISPLAY_NAME

    # Other options that might be useful

    # While REMOTE_USER is used as the sub field and serves as the
immutable ID,
    # REMOTE_USER_PREFERRED_USERNAME could be used to have a
different username
    # LookupUserAttr <attr_name> REMOTE_USER_PREFERRED_USERNAME

    # Group support may be added in a future release
    # LookupUserGroupsIter REMOTE_USER_GROUP
</Location>

    # Deny everything else
<Location ~ "^(?!\/check_user\.php).)*$">
    Deny from all
</Location>
</VirtualHost>

```

4. Create the ***check\_user.php*** script in the **/var/www/html** directory. Include the following code:

```

<?php
// Get the user based on the Apache var, this should always be
// set because we 'Require valid-user' in the configuration
$user = apache_getenv('REMOTE_USER');

// However, we assume it may not be set and
// build an error response by default

```

```

$data = array(
    'error' => 'remote PAM authentication failed'
);

// Build a success response if we have a user
if (!empty($user)) {
    $data = array(
        'sub' => $user
    );
    // Map of optional environment variables to optional JSON fields
    $env_map = array(
        'REMOTE_USER_MAIL' => 'email',
        'REMOTE_USER_DISPLAY_NAME' => 'name',
        'REMOTE_USER_PREFERRED_USERNAME' => 'preferred_username'
    );
}

// Add all non-empty environment variables to JSON data
foreach ($env_map as $env_name => $json_name) {
    $env_data = apache_getenv($env_name);
    if (!empty($env_data)) {
        $data[$json_name] = $env_data;
    }
}
}

// We always output JSON from this script
header('Content-Type: application/json', true);

// Write the response as JSON
echo json_encode($data);
?>

```

5. Enable Apache to load the module. Modify the **/etc/httpd/conf.modules.d/55-lookup\_identity.conf** file and uncomment the following line:

```
LoadModule lookup_identity_module modules/mod_lookup_identity.so
```

6. Set an SELinux boolean so that SELinux allows Apache to connect to SSSD over D-BUS:

```
# setsebool -P httpd_dbus_sssd on
```

7. Set a boolean to tell SELinux that it is acceptable for Apache to contact the PAM subsystem:

```
# setsebool -P allow_httpd_mod_auth_pam on
```

8. Start Apache:

```
# systemctl start httpd.service
```

## 14.5. CONFIGURING OPENSHIFT CONTAINER PLATFORM TO USE SSSD AS THE BASIC REMOTE AUTHENTICATION SERVER

Modify the default configuration of your cluster to use the new identity provider that you created. Complete the following steps on the first master host listed in the Ansible host inventory file.

1. Open the `/etc/origin/master/master-config.yaml` file.
2. Locate the **identityProviders** section and replace it with the following code:

```
identityProviders:  
- name: sssd  
  challenge: true  
  login: true  
  mappingMethod: claim  
  provider:  
    apiVersion: v1  
    kind: BasicAuthPasswordIdentityProvider  
    url: https://remote-basic.example.com/check_user.php  
    ca: /etc/origin/master/ca.crt  
    certFile: /etc/origin/master/openshift-master.crt  
    keyFile: /etc/origin/master/openshift-master.key
```

3. Start OpenShift Container Platform with the updated configuration:

```
# openshift start \  
--public-master=https://openshift.example.com:8443 \  
--master-config=/etc/origin/master/master-config.yaml \  
--node-config=/etc/origin/node-node1.example.com/node-  
config.yaml
```

4. Test a login by using the **oc** CLI:

```
oc login https://openshift.example.com:8443
```

You can log in only with valid LDAP credentials.

5. List the identities and confirm that an email address is displayed for each user name. Run the following command:

```
$ oc get identity -o yaml
```

# CHAPTER 15. CONFIGURING THE SDN

## 15.1. OVERVIEW

The [OpenShift SDN](#) enables communication between pods across the OpenShift Container Platform cluster, establishing a *pod network*. Three [SDN plug-ins](#) are currently available (**ovs-subnet**, **ovs-multitenant**, and **ovs-networkpolicy**), which provide different methods for configuring the pod network.

## 15.2. AVAILABLE SDN PROVIDERS

The upstream Kubernetes project does not come with a default network solution. Instead, Kubernetes has developed a Container Network Interface (CNI) to allow network providers for integration with their own SDN solutions.

There are several OpenShift SDN plug-ins available out of the box from Red Hat, as well as third-party plug-ins.

Red Hat has worked with a number of SDN providers to certify their SDN network solution on OpenShift Container Platform via the Kubernetes CNI interface, including a support process for their SDN plug-in through their product's entitlement process. Should you open a support case with OpenShift, Red Hat can facilitate an exchange process so that both companies are involved in meeting your needs.

The following SDN solutions are validated and supported on OpenShift Container Platform directly by the third-party vendor:

- Cisco Contiv (™)
- Juniper Contrail (™)
- Nokia Nuage (™)
- Tigera Calico (™)
- VMware NSX-T (™)

### Installing VMware NSX-T (™) on OpenShift Container Platform

VMware NSX-T (™) provides an SDN and security infrastructure to build cloud-native application environments. In addition to vSphere hypervisors (ESX), these environments include KVM and native public clouds.

The current integration requires a *new* install of both NSX-T and OpenShift Container Platform. Currently, NSX-T version 2.1 is supported, and only supports the use of ESX and KVM hypervisors at this time.

See the [NSX-T Container Plug-in for OpenShift - Installation and Administration Guide](#) for more information.

## 15.3. CONFIGURING THE POD NETWORK WITH ANSIBLE

For initial [advanced installations](#), the **ovs-subnet** plug-in is installed and configured by default, though it can be overridden during installation using the **os\_sdn\_network\_plugin\_name** parameter, which is configurable in the Ansible inventory file.

For example, to override the standard **ovs-subnet** plug-in and use the **ovs-multitenant** plug-in instead:



```
# Configure the multi-tenant SDN plugin (default is 'redhat/openshift-ovs-subnet')
os_sdn_network_plugin_name='redhat/openshift-ovs-multitenant'
```

See [Configuring Cluster Variables](#) for descriptions of networking-related Ansible variables that can be set in your inventory file.

For initial [quick installations](#), the **ovs-subnet** plug-in is installed and configured by default as well, and can be [reconfigured post-installation](#) using the **networkConfig** stanza of the **master-config.yaml** file.

## 15.4. CONFIGURING THE POD NETWORK ON MASTERS

The cluster administrators can control pod network settings on master hosts by modifying parameters in the **networkConfig** section of the [master configuration file](#) (located at `/etc/origin/master/master-config.yaml` by default):

### Configuring a pod network for a single CIDR

```
networkConfig:
  clusterNetworks:
    - cidr: 10.128.0.0/14 1
      hostSubnetLength: 9 2
    networkPluginName: "redhat/openshift-ovs-subnet" 3
    serviceNetworkCIDR: 172.30.0.0/16 4
```

- 1** Cluster network for node IP allocation
- 2** Number of bits for pod IP allocation within a node
- 3** Set to **redhat/openshift-ovs-subnet** for the **ovs-subnet** plug-in, **redhat/openshift-ovs-multitenant** for the **ovs-multitenant** plug-in, or **redhat/openshift-ovs-networkpolicy** for the **ovs-networkpolicy** plug-in
- 4** Service IP allocation for the cluster

Alternatively, you can create a pod network with multiple CIDR ranges by adding separate ranges into the **clusterNetworks** field with the range and the **hostSubnetLength**.

Multiple ranges can be used at once, and the range can be expanded or contracted. Nodes can be moved from one range to another by evacuating a node, then deleting and re-creating the node. See the [Managing Nodes](#) section for more information. Node allocations occur in the order listed, then when the range is full, move to the next on the list.

### Configuring a pod network for multiple CIDRs

```
networkConfig:
  clusterNetworks:
    - cidr: 10.128.0.0/14 1
      hostSubnetLength: 9 2
    - cidr: 10.132.0.0/14
      hostSubnetLength: 9
    externalIPNetworkCIDRs: null
    hostSubnetLength: 9
```

```
ingressIPNetworkCIDR: 172.29.0.0/16
```

```
networkPluginName: redhat/openshift-ovs-multitenant ③
```

```
serviceNetworkCIDR: 172.30.0.0/16
```

- ① Cluster network for node IP allocation.
- ② Number of bits for pod IP allocation within a node.
- ③ Set to **redhat/openshift-ovs-subnet** for the **ovs-subnet** plug-in, **redhat/openshift-ovs-multitenant** for the **ovs-multitenant** plug-in, or **redhat/openshift-ovs-networkpolicy** for the **ovs-networkpolicy** plug-in.

You can add elements to the **clusterNetworks** value, or remove them if no node is using that CIDR range, but be sure to restart the **atomic-openshift-master-api** and **atomic-openshift-master-controllers** services for any changes to take effect.



## IMPORTANT

The **hostSubnetLength** value cannot be changed after the cluster is first created, A **cidr** field can only be changed to be a larger network that still contains the original network if nodes are allocated within its range , and **serviceNetworkCIDR** can only be expanded. For example, given the default value of **10.128.0.0/14**, you could change **cidr** to **10.128.0.0/9** (i.e., the entire upper half of net 10) but not to**10.64.0.0/16**, because that does not overlap the original value.

You can change **serviceNetworkCIDR** from **172.30.0.0/16** to **172.30.0.0/15**, but not to **172.28.0.0/14**, because even though the original range is entirely inside the new range, the original range must be at the start of the CIDR.

## 15.5. CONFIGURING THE POD NETWORK ON NODES

The cluster administrators can control pod network settings on nodes by modifying parameters in the **networkConfig** section of the [node configuration file](#) (located at **/etc/origin/node/node-config.yaml** by default):

```
networkConfig:
  mtu: 1450 ①
  networkPluginName: "redhat/openshift-ovs-subnet" ②
```

- ① Maximum transmission unit (MTU) for the pod overlay network
- ② Set to **redhat/openshift-ovs-subnet** for the **ovs-subnet** plug-in, **redhat/openshift-ovs-multitenant** for the **ovs-multitenant** plug-in, or **redhat/openshift-ovs-networkpolicy** for the **ovs-networkpolicy** plug-in



## NOTE

You must change the MTU size on all masters and nodes that are part of the OpenShift Container Platform SDN. Also, the MTU size of the tun0 interface must be the same across all nodes that are part of the cluster.

## 15.6. MIGRATING BETWEEN SDN PLUG-INS

If you are already using one SDN plug-in and want to switch to another:

1. Change the `networkPluginName` parameter on all `masters` and `nodes` in their configuration files.
2. Restart the `atomic-openshift-master-api` and `atomic-openshift-master-controllers` services on all masters.
3. Stop the `atomic-origin-node` service on all masters and nodes.
4. If you are switching between OpenShift SDN plug-ins, restart the `openvswitch` service on all masters and nodes.
5. Restart the `atomic-openshift-node` service on all masters and nodes.
6. If you are switching from an OpenShift SDN plug-in to a third-party plug-in, then clean up OpenShift SDN-specific artifacts:

```
$ oc delete clusternetwork --all
$ oc delete hostsubnets --all
$ oc delete netnamespaces --all
```

When switching from the `ovs-subnet` to the `ovs-multitenant` OpenShift SDN plug-in, all the existing projects in the cluster will be fully isolated (assigned unique VNIDs). The cluster administrators can choose to [modify the project networks](#) using the administrator CLI.

Check VNIDs by running:

```
$ oc get netnamespace
```

### 15.6.1. Migrating from ovs-multitenant to ovs-networkpolicy

In addition to the generic plug-in migration steps above in the [Migrating between SDN plug-ins section](#), there is one additional step when migrating from the `ovs-multitenant` plug-in to the `ovs-networkpolicy` plug-in; you must ensure that every namespace has a unique `NetID`. This means that if you have previously [joined projects together](#) or [made projects global](#), you will need to undo that before switching to the `ovs-networkpolicy` plug-in, or the NetworkPolicy objects may not function correctly.

A helper script is available that fixes `NetID`'s, creates NetworkPolicy objects to isolate previously-isolated namespaces, and enables connections between previously-joined namespaces.

Use the following steps to migrate to the `ovs-networkpolicy` plug-in, by using this helper script, while still running the `ovs-multitenant` plug-in:

1. Download the script and add the execution file permission:

```
$ curl -O
https://raw.githubusercontent.com/openshift/origin/master/contrib/migration/migrate-network-policy.sh
$ chmod a+x migrate-network-policy.sh
```

2. Run the script (requires the cluster administrator role).

```
$ ./migrate-network-policy.sh
```

After running this script, every namespace is fully isolated from every other namespace, therefore connection attempts between pods in different namespaces will fail until you complete the migration to the **ovs-networkpolicy** plug-in.

If you want newly-created namespaces to also have the same policies by default, you can set [default NetworkPolicy objects](#) to be created matching the **default-deny** and **allow-from-global-namespaces** policies created by the migration script.



#### NOTE

In case of script failures or other errors, or if you later decide you want to revert back to the **ovs-multitenant** plug-in, you can use the [un-migration script](#). This script undoes the changes made by the migration script and re-joins previously-joined namespaces.

## 15.7. EXTERNAL ACCESS TO THE CLUSTER NETWORK

If a host that is external to OpenShift Container Platform requires access to the cluster network, you have two options:

1. Configure the host as an OpenShift Container Platform node but mark it [unschedulable](#) so that the master does not schedule containers on it.
2. Create a tunnel between your host and a host that is on the cluster network.

Both options are presented as part of a practical use-case in the documentation for configuring [routing from an edge load-balancer to containers within OpenShift SDN](#).

## 15.8. USING FLANNEL

As an alternate to the default SDN, OpenShift Container Platform also provides Ansible playbooks for installing **flannel**-based networking. This is useful if running OpenShift Container Platform within a cloud provider platform that also relies on SDN, such as Red Hat OpenStack Platform, and you want to avoid encapsulating packets twice through both platforms.

Flannel uses a single IP network space for all of the containers allocating a contiguous subset of the space to each instance. Consequently, nothing prevents a container from attempting to contact any IP address in the same network space. This hinders multi-tenancy because the network cannot be used to isolate containers in one application from another.

Depending on whether you prefer multi-tenancy isolation or performance, you should determine the appropriate choice when deciding between OpenShift SDN (multi-tenancy) and flannel (performance) for internal networks.



#### IMPORTANT

Flannel is only supported for OpenShift Container Platform on Red Hat OpenStack Platform.



## IMPORTANT

The current version of Neutron enforces port security on ports by default. This prevents the port from sending or receiving packets with a MAC address different from that on the port itself. Flannel creates virtual MACs and IP addresses and must send and receive packets on the port, so port security must be disabled on the ports that carry flannel traffic.

To enable flannel within your OpenShift Container Platform cluster:

1. Neutron port security controls must be configured to be compatible with Flannel. The default configuration of Red Hat OpenStack Platform disables user control of **port\_security**. Configure Neutron to allow users to control the **port\_security** setting on individual ports.
  - a. On the Neutron servers, add the following to the */etc/neutron/plugins/ml2/ml2\_conf.ini* file:

```
[ml2]
...
extension_drivers = port_security
```

- b. Then, restart the Neutron services:

```
service neutron-dhcp-agent restart
service neutron-ovs-cleanup restart
service neutron-metadata-agentrestart
service neutron-l3-agent restart
service neutron-plugin-openvswitch-agent restart
service neutron-vpn-agent restart
service neutron-server restart
```

2. When creating the OpenShift Container Platform instances on Red Hat OpenStack Platform, disable both port security and security groups in the ports where the container network flannel interface will be:

```
neutron port-update $port --no-security-groups --port-security-
enabled=False
```



## NOTE

Flannel gather information from etcd to configure and assign the subnets in the nodes. Therefore, the security group attached to the etcd hosts should allow access from nodes to port 2379/tcp, and nodes security group should allow egress communication to that port on the etcd hosts.

- a. Set the following variables in your Ansible inventory file before running the installation:

```
openshift_use_openshift_sdn=false ①
openshift_use_flannel=true ②
flannel_interface=eth0
```

- ① Set **openshift\_use\_openshift\_sdn** to **false** to disable the default SDN.
- ② Set **openshift\_use\_flannel** to **true** to enable **flannel** in place.

- b. Optionally, you can specify the interface to use for inter-host communication using the **flannel\_interface** variable. Without this variable, the OpenShift Container Platform installation uses the default interface.



#### NOTE

Custom networking CIDR for pods and services using flannel will be supported in a future release. [BZ#1473858](#)

3. After the OpenShift Container Platform installation, add a set of iptables rules on every OpenShift Container Platform node:

```
iptables -A DOCKER -p all -j ACCEPT  
iptables -t nat -A POSTROUTING -o eth1 -j MASQUERADE
```

To persist those changes in the **/etc/sysconfig/iptables** use the following command on every node:

```
cp /etc/sysconfig/iptables{,.orig}  
sh -c "tac /etc/sysconfig/iptables.orig | sed -e '0,/:DOCKER -/  
s/:DOCKER -/:DOCKER ACCEPT/' | awk '\"\\!\"p && /POSTROUTING/{print \\"-  
A POSTROUTING -o eth1 -j MASQUERADE\"; p=1} 1' | tac >  
/etc/sysconfig/iptables"
```



#### NOTE

The **iptables-save** command saves all the current *in memory* iptables rules. However, because Docker, Kubernetes and OpenShift Container Platform create a high number of iptables rules (services, etc.) not designed to be persisted, saving these rules can become problematic.

To isolate container traffic from the rest of the OpenShift Container Platform traffic, Red Hat recommends creating an isolated tenant network and attaching all the nodes to it. If you are using a different network interface (eth1), remember to configure the interface to start at boot time through the **/etc/sysconfig/network-scripts/ifcfg-eth1** file:

```
DEVICE=eth1  
TYPE=Ethernet  
BOOTPROTO=dhcp  
ONBOOT=yes  
DEFROUTE=no  
PEERDNS=no
```

# CHAPTER 16. CONFIGURING NUAGE SDN

## 16.1. NUAGE SDN AND OPENSHIFT CONTAINER PLATFORM

Nuage Networks Virtualized Services Platform (VSP) provides virtual networking and software-defined networking (SDN) infrastructure to Docker container environments that simplifies IT operations and expands OpenShift Container Platform's native networking capabilities.


Nuage Networks VSP supports Docker-based applications running on OpenShift Container Platform to accelerate the provisioning of virtual networks between pods and traditional workloads, and to enable security policies across the entire cloud infrastructure. VSP allows for the automation of security appliances to include granular security and microsegmentation policies for container applications.

Integrating VSP with the OpenShift Container Platform application workflow allows business applications to be quickly turned up and updated by removing the network lag faced by DevOps teams. VSP supports different workflows with OpenShift Container Platform in order to accommodate scenarios where users can choose ease-of-use or complete control using policy-based automation.

See [Networking](#) for more information on how VSP is integrated with OpenShift Container Platform.

## 16.2. DEVELOPER WORKFLOW

This workflow is used in developer environments and requires little input from the developer in setting up the networking. In this workflow, **nuage Openshift Monitor** is responsible for creating the VSP constructs (Zone, Subnets, etc.) needed to provide appropriate policies and networking for pods created in an OpenShift Container Platform project. When a project is created, a default zone and default subnet for that project are created by **nuage Openshift Monitor**. When the default subnet created for a given project gets depleted, **nuage Openshift Monitor** dynamically creates additional subnets.



### NOTE

A separate VSP Zone is created for each OpenShift Container Platform project ensuring isolation amongst the projects.

## 16.3. OPERATIONS WORKFLOW

This workflow is used by operations teams rolling out applications. In this workflow, the network and security policies are first configured on the VSD in accordance with the rules set by the organization to deploy applications. Administrative users can potentially create multiple zones and subnets and map them to the same project using labels. While spinning up the pods, the user can use the Nuage Labels to specify what network a pod needs to attach to and what network policies need to be applied to it. This allows for deployments where inter- and intra-project traffic can be controlled in a fine-grained manner. For example, inter-project communication is enabled on a project by project basis. This may be used to connect projects to common services that are deployed in a shared project.

## 16.4. INSTALLATION

The VSP integration with OpenShift Container Platform works for both virtual machines (VMs) and bare metal OpenShift Container Platform installations.

An environment with High Availability (HA) can be configured with multiple masters and multiple nodes.

Nuage VSP integration in multi-master mode only supports the native HA configuration method

described in this section. This can be combined with any load balancing solution, the default being HAProxy. The inventory file contains three master hosts, the nodes, an etcd server, and a host that functions as the HAProxy to balance the master API on all master hosts. The HAProxy host is defined in the [lb] section of the inventory file enabling Ansible to automatically install and configure HAProxy as the load balancing solution.

In the Ansible nodes file, the following parameters need to be specified in order to setup Nuage VSP as the network plug-in:

```
# Create and OSEv3 group that contains masters, nodes, load-balancers,
and etcd hosts
masters
nodes
etcd
lb

# Nuage specific parameters
openshift_use_openshift_sdn=False
openshift_use_nuage=True
os_sdn_network_plugin_name='nuage/vsp-openshift'
openshift_node_proxy_mode='userspace'

# VSP related parameters
vsd_api_url=https://192.168.103.200:8443
vsp_version=v4_0
enterprise=nuage
domain=openshift
vsc_active_ip=192.168.103.201
vsc_standby_ip=192.168.103.202
uplink_interface=eth0

# rpm locations
nuage_openshift_rpm=http://location_of_rpm_server/openshift/RPMS/x86_64/n
uage-openshift-monitor-4.0.X.1830.el7.centos.x86_64.rpm
vrs_rpm=http://location_of_rpm_server/openshift/RPMS/x86_64/nuage-
openvswitch-4.0.X.225.el7.x86_64.rpm
plugin_rpm=http://location_of_rpm_server/openshift/RPMS/x86_64/vsp-
openshift-4.0.X1830.el7.centos.x86_64.rpm

# Required for Nuage Monitor REST server and HA
openshift_master_cluster_method=native
openshift_master_cluster_hostname=lb.nuageopenshift.com
openshift_master_cluster_public_hostname=lb.nuageopenshift.com
nuage_openshift_monitor_rest_server_port=9443

# Optional parameters
nuage_interface_mtu=1460
nuage_master_adminusername='admin's user-name'
nuage_master_adminuserpasswd='admin's password'
nuage_master_cspadminpasswd='csp admin password'
nuage_openshift_monitor_log_dir=/var/log/nuage-openshift-monitor

# Required for brownfield install (where a {product-title} cluster exists
without Nuage as the networking plugin)
nuage_dockker_bridge=lbr0
```

```
# Specify master hosts
[masters]
fqdn_of_master_1
fqdn_of_master_2
fqdn_of_master_3

# Specify load balancer host
[lb]
fqdn_of_load_balancer
```

# CHAPTER 17. CONFIGURING FOR AMAZON WEB SERVICES (AWS)

## 17.1. OVERVIEW

OpenShift Container Platform can be configured to access an [AWS EC2 infrastructure](#), including using [AWS volumes as persistent storage](#) for application data. After you configure AWS, some additional configurations must be completed on the OpenShift Container Platform hosts.

## 17.2. PERMISSIONS

Configuring AWS for OpenShift Container Platform requires the following permissions:

**Table 17.1. Master Permissions**

Elastic Compute Cloud(EC2)	<code>ec2:DescribeVolume, ec2&gt;CreateVolume, ec2/CreateTags, ec2:DescribeInstance, ec2:AttachVolume, ec2:DetachVolume, ec2&gt;DeleteVolume, ec2:DescribeSubnets, ec2:CreateSecurityGroup, ec2:DescribeSecurityGroups, ec2:DescribeRouteTables, ec2:AuthorizeSecurityGroupIngress, ec2:RevokeSecurityGroupIngress, ec2:DeleteSecurityGroup</code>
Elastic Load Balancing	<code>elasticloadbalancing:DescribeTags, elasticloadbalancing&gt;CreateLoadBalancerListeners, elasticloadbalancing:ConfigureHealthCheck, elasticloadbalancing&gt;DeleteLoadBalancerListeners, elasticloadbalancing:RegisterInstancesWithLoadBalancer, elasticloadbalancing:DescribeLoadBalancers, elasticloadbalancing&gt;CreateLoadBalancer, elasticloadbalancing&gt;DeleteLoadBalancer, elasticloadbalancing:ModifyLoadBalancerAttributes ,</code> <code>elasticloadbalancing:DescribeLoadBalancerAttributes</code>

**Table 17.2. Node Permissions**

Elastic Compute Cloud(EC2)	<code>ec2:DescribeInstance*</code>
----------------------------	------------------------------------



## IMPORTANT

- Every master host, node host, and subnet must have the `kubernetes.io/cluster/<name>,Value=<clusterid>` tag.
- One security group, preferably the one linked to the nodes, must have the `kubernetes.io/cluster/<name>,Value=<clusterid>` tag.
  - Do not tag all security groups with the `kubernetes.io/cluster/<name>,Value=<clusterid>` tag or the Elastic Load Balancing (ELB) will not be able to create a load balancer.

### 17.3. CONFIGURING A SECURITY GROUP

When installing OpenShift Container Platform on AWS, ensure that you set up the appropriate security groups.

These are some ports that you must have in your security groups, without which the installation fails. You may need more depending on the cluster configuration you want to install. For more information and to adjust your security groups accordingly, see [Required Ports](#) for more information.

<b>All OpenShift Container Platform Hosts</b>	<ul style="list-style-type: none"> <li>● tcp/22 from host running the installer/Ansible</li> </ul>
<b>etcd Security Group</b>	<ul style="list-style-type: none"> <li>● tcp/2379 from masters</li> <li>● tcp/2380 from etcd hosts</li> </ul>
<b>Master Security Group</b>	<ul style="list-style-type: none"> <li>● tcp/8443 from 0.0.0.0/0</li> <li>● tcp/53 from all OpenShift Container Platform hosts for environments installed prior to or upgraded to 3.2</li> <li>● udp/53 from all OpenShift Container Platform hosts for environments installed prior to or upgraded to 3.2</li> <li>● tcp/8053 from all OpenShift Container Platform hosts for new environments installed with 3.2</li> <li>● udp/8053 from all OpenShift Container Platform hosts for new environments installed with 3.2</li> </ul>
<b>Node Security Group</b>	<ul style="list-style-type: none"> <li>● tcp/10250 from masters</li> <li>● udp/4789 from nodes</li> </ul>
<b>Infrastructure Nodes (ones that can host the OpenShift Container Platform router)</b>	<ul style="list-style-type: none"> <li>● tcp/443 from 0.0.0.0/0</li> <li>● tcp/80 from 0.0.0.0/0</li> </ul>

<b>CRI-O</b>	If using CRI-O, you must open tcp/10010 to allow <b>oc exec</b> and <b>oc rsh</b> operations.
--------------	---

If configuring external load-balancers (ELBs) for load balancing the masters and/or routers, you also need to configure Ingress and Egress security groups for the ELBs appropriately.

### 17.3.1. Overriding Detected IP Addresses and Host Names

In AWS, situations that require overriding the variables include:

Variable	Usage
<b>hostname</b>	The user is installing in a VPC that is not configured for both <b>DNS hostnames</b> and <b>DNS resolution</b> .
<b>ip</b>	You have multiple network interfaces configured and want to use one other than the default. You must also set the <b>openshift_set_node_ip</b> parameter to <b>True</b> , or the SDN attempts to use the <b>hostname</b> setting or tries to resolve the host name for the IP address.
<b>public_hostname</b>	<ul style="list-style-type: none"> <li>A master instance where the VPC subnet is not configured for <b>Auto-assign Public IP</b>. For external access to this master, you need to have an ELB or other load balancer configured that would provide the external access needed, or you need to connect over a VPN connection to the internal name of the host.</li> <li>A master instance where metadata is disabled.</li> <li>This value is not actually used by the nodes.</li> </ul>
<b>public_ip</b>	<ul style="list-style-type: none"> <li>A master instance where the VPC subnet is not configured for <b>Auto-assign Public IP</b>.</li> <li>A master instance where metadata is disabled.</li> <li>This value is not actually used by the nodes.</li> </ul>



#### WARNING

If **openshift\_hostname** is set to a value other than the metadata-provided **private-dns-name** value, the native cloud integration for those providers will no longer work.

For EC2 hosts in particular, they must be deployed in a VPC that has both **DNS host names** and **DNS resolution** enabled, and **openshift\_hostname** should not be overridden.

## 17.4. CONFIGURING AWS VARIABLES

To set the required AWS variables, create a **/etc/origin/cloudprovider/aws.conf** file with the following contents on all of your OpenShift Container Platform hosts, both masters and nodes:

```
[Global]
Zone = us-east-1c ①
```

- ① This is the Availability Zone of your AWS Instance and where your EBS Volume resides; this information is obtained from the AWS Management Console.

## 17.5. CONFIGURING OPENSHIFT CONTAINER PLATFORM MASTERS FOR AWS

You can set the AWS configuration on your OpenShift Container Platform master hosts in two ways:

- using Ansible and the advanced installation tool
- manually, by modifying the **master-config.yaml** file

### 17.5.1. Configuring OpenShift Container Platform for AWS with Ansible

During advanced installations, AWS can be configured using the **openshift\_cloudprovider\_aws\_access\_key**, **openshift\_cloudprovider\_aws\_secret\_key**, **openshift\_cloudprovider\_kind**, **openshift\_clusterid** parameters, which are configurable in the inventory file.

#### Example AWS Configuration with Ansible

```
# Cloud Provider Configuration
#
# Note: You may make use of environment variables rather than store
# sensitive configuration within the ansible inventory.
# For example:
#openshift_cloudprovider_aws_access_key="{{
#lookup('env', 'AWS_ACCESS_KEY_ID') }}"
#openshift_cloudprovider_aws_secret_key="{{
#lookup('env', 'AWS_SECRET_ACCESS_KEY') }}"
#
#openshift_clusterid=unique_identifier_per_availability_zone
#
# AWS (Using API Credentials)
#openshift_cloudprovider_kind=aws
#openshift_cloudprovider_aws_access_key=aws_access_key_id
#openshift_cloudprovider_aws_secret_key=aws_secret_access_key
#
# AWS (Using IAM Profiles)
#openshift_cloudprovider_kind=aws
# Note: IAM roles must exist before launching the instances.
```

**NOTE**

When Ansible configures AWS, the following files are created for you:

- */etc/origin/cloudprovider/aws.conf*
- */etc/origin/master/master-config.yaml*
- */etc/origin/node/node-config.yaml*
- */etc/sysconfig/atomic-openshift-master-api*
- */etc/sysconfig/atomic-openshift-master-controllers*
- */etc/sysconfig/atomic-openshift-node*

### 17.5.2. Manually Configuring OpenShift Container Platform Masters for AWS

Edit or [create](#) the master configuration file on all masters (*/etc/origin/master/master-config.yaml* by default) and update the contents of the **apiServerArguments** and **controllerArguments** sections:

```
kubernetesMasterConfig:
  ...
  apiServerArguments:
    cloud-provider:
      - "aws"
    cloud-config:
      - "/etc/origin/cloudprovider/aws.conf"
  controllerArguments:
    cloud-provider:
      - "aws"
    cloud-config:
      - "/etc/origin/cloudprovider/aws.conf"
```

Currently, the **nodeName** must match the instance name in AWS in order for the cloud provider integration to work properly. The name must also be RFC1123 compliant.

**IMPORTANT**

When triggering a containerized installation, only the directories of */etc/origin* and */var/lib/origin* are mounted to the master and node container. Therefore, *aws.conf* should be in */etc/origin/* instead of */etc/*.

### 17.5.3. Manually Configuring OpenShift Container Platform Nodes for AWS

Edit or [create](#) the node configuration file on all nodes (*/etc/origin/node/node-config.yaml* by default) and update the contents of the **kubeletArguments** section:

```
kubeletArguments:
  cloud-provider:
    - "aws"
  cloud-config:
    - "/etc/origin/cloudprovider/aws.conf"
```

**IMPORTANT**

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, `aws.conf` should be in `/etc/origin/` instead of `/etc/`.

## 17.6. SETTING KEY VALUE ACCESS PAIRS

Make sure the following environment variables are set in the `/etc/sysconfig/atomic-openshift-master-api` file and `/etc/sysconfig/atomic-openshift-master-controllers` file on masters and the `/etc/sysconfig/atomic-openshift-node` file on nodes:

```
AWS_ACCESS_KEY_ID=<key_ID>
AWS_SECRET_ACCESS_KEY=<secret_key>
```

**NOTE**

Access keys are obtained when setting up your AWS IAM user.

## 17.7. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
# systemctl restart atomic-openshift-node
```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

## 17.8. LABELING CLUSTERS FOR AWS

Starting with OpenShift Container Platform version 3.7 of the **atomic-openshift-installer**, if you configured AWS provider credentials, you must also ensure that all hosts are labeled.

To correctly identify which resources are associated with a cluster, tag resources with the key **kubernetes.io/cluster/<clusterid>**, where:

- <clusterid> is a unique name for the cluster.

Set the corresponding value to **owned** if the node belongs exclusively to the cluster or **toshares** if it is a resource shared with other systems.

Tagging all resources with the **kubernetes.io/cluster/<clusterid>,Value=(owned|shared)** tag avoids potential issues with multiple zones or multiple clusters.



#### NOTE

In versions prior to OpenShift Container Platform version 3.6, this was **Key=KubernetesCluster, Value=clusterid**.

See [Pods and Services](#) to learn more about labeling and tagging in OpenShift Container Platform.

### 17.8.1. Resources That Need Tags

There are four types of resources that need to be tagged:

- Instances
- Security Groups
- Load Balancers
- EBS Volumes

### 17.8.2. Tagging an Existing Cluster

A cluster uses the value of the **kubernetes.io/cluster/<clusterid>,Value=(owned|shared)** tag to determine which resources belong to the AWS cluster. This means that all relevant resources must be labeled with the **kubernetes.io/cluster/<clusterid>,Value=(owned|shared)** tag using the same values for that key. These resources include:

- All hosts.
- All relevant load balancers to be used in the AWS instances.
- All EBS volumes. The EBS Volumes that need to be tagged can be found with:

```
$ oc get pv -o json|jq '.items[] .spec.awsElasticBlockStore.volumeID'
```
- All relevant security groups to be used with the AWS instances.

**NOTE**

Do not tag all existing security groups with the `kubernetes.io/cluster/<name>,Value=<clusterid>` tag, or the Elastic Load Balancing (ELB) will not be able to create a load balancer.

After tagging any resources, restart the master services on the master and the node service on all nodes. See the [Applying Configuration Section](#).

# CHAPTER 18. CONFIGURING FOR OPENSTACK

## 18.1. OVERVIEW

When deployed on [OpenStack](#), OpenShift Container Platform can be configured to access OpenStack infrastructure, including [using OpenStack Cinder volumes as persistent storage](#) for application data.

## 18.2. PERMISSIONS

Configuring OpenStack for OpenShift Container Platform requires the following role:

member	For creating assets(instances, networking ports, floating ips, volumes, and so on.) you need the member role for the tenant.
--------	--

## 18.3. CONFIGURING A SECURITY GROUP

When installing OpenShift Container Platform on OpenStack, ensure that you set up the appropriate security groups.

These are some ports that you must have in your security groups, without which the installation fails. You may need more depending on the cluster configuration you want to install. For more information and to adjust your security groups accordingly, see [Required Ports](#) for more information.

All OpenShift Container Platform Hosts	<ul style="list-style-type: none"><li>tcp/22 from host running the installer/Ansible</li></ul>
etcd Security Group	<ul style="list-style-type: none"><li>tcp/2379 from masters</li><li>tcp/2380 from etcd hosts</li></ul>
Master Security Group	<ul style="list-style-type: none"><li>tcp/8443 from 0.0.0.0/0</li><li>tcp/53 from all OpenShift Container Platform hosts for environments installed prior to or upgraded to 3.2</li><li>udp/53 from all OpenShift Container Platform hosts for environments installed prior to or upgraded to 3.2</li><li>tcp/8053 from all OpenShift Container Platform hosts for new environments installed with 3.2</li><li>udp/8053 from all OpenShift Container Platform hosts for new environments installed with 3.2</li></ul>
Node Security Group	<ul style="list-style-type: none"><li>tcp/10250 from masters</li><li>udp/4789 from nodes</li></ul>

Infrastructure Nodes (ones that can host the OpenShift Container Platform router)	<ul style="list-style-type: none"> <li>tcp/443 from 0.0.0.0/0</li> <li>tcp/80 from 0.0.0.0/0</li> </ul>
CRI-O	If using CRI-O, you must open tcp/10010 to allow <b>oc exec</b> and <b>oc rsh</b> operations.

If configuring external load-balancers (ELBs) for load balancing the masters and/or routers, you also need to configure Ingress and Egress security groups for the ELBs appropriately.

## 18.4. CONFIGURING OPENSTACK VARIABLES

To set the required OpenStack variables, create a `/etc/cloud.conf` file with the following contents on all of your OpenShift Container Platform hosts, both masters and nodes:

```
[Global]
auth-url = <OS_AUTH_URL>
username = <OS_USERNAME>
password = <password>
domain-id = <OS_USER_DOMAIN_ID>
tenant-id = <OS_TENANT_ID>
region = <OS_REGION_NAME>

[LoadBalancer]
subnet-id = <UUID of the load balancer subnet>
```

Consult your OpenStack administrators for values of the `OS_` variables, which are commonly used in OpenStack configuration.

## 18.5. CONFIGURING OPENSIFT CONTAINER PLATFORM MASTERS FOR OPENSTACK

You can set an OpenStack configuration on your OpenShift Container Platform master and node hosts in two different ways:


- Using Ansible and the advanced installation tool
- Manually, by modifying the `master-config.yaml` and `node-config.yaml` files.

### 18.5.1. Configuring OpenShift Container Platform for OpenStack with Ansible

During [advanced installations](#), OpenStack can be configured using [the following parameters](#), which are configurable in the inventory file:

- `openshift_cloudprovider_kind`
- `openshift_cloudprovider_openstack_auth_url`
- `openshift_cloudprovider_openstack_username`
- `openshift_cloudprovider_openstack_password`

- `openshift_cloudprovider_openstack_domain_id`
- `openshift_cloudprovider_openstack_domain_name`
- `openshift_cloudprovider_openstack_tenant_id`
- `openshift_cloudprovider_openstack_tenant_name`
- `openshift_cloudprovider_openstack_region`
- `openshift_cloudprovider_openstack_lb_subnet_id`



### IMPORTANT

If a parameter value in the Ansible inventory file contains special characters, such as #, { or }, you must double-escape the value (that is enclose the value in both single and double quotation marks). For example, to use `mypasswordwith###hashsigns` as a value for the variable `openshift_cloudprovider_openstack_password`, declare it as  
`openshift_cloudprovider_openstack_password='\"mypasswordwith###hash signs\"'` in the Ansible host inventory file.

#### Example 18.1. Example OpenStack Configuration with Ansible

```
# Cloud Provider Configuration
#
# Note: You may make use of environment variables rather than store
# sensitive configuration within the ansible inventory.
# For example:
#openshift_cloudprovider_openstack_username="{{ lookup('env', 'USERNAME') }}"
#openshift_cloudprovider_openstack_password="{{ lookup('env', 'PASSWORD') }}"
#
# Openstack
#openshift_cloudprovider_kind=openstack
#openshift_cloudprovider_openstack_auth_url=http://openstack.example.com
:35357/v2.0/
#openshift_cloudprovider_openstack_username=username
#openshift_cloudprovider_openstack_password=password
#openshift_cloudprovider_openstack_domain_id=domain_id
#openshift_cloudprovider_openstack_domain_name=domain_name
#openshift_cloudprovider_openstack_tenant_id=tenant_id
#openshift_cloudprovider_openstack_tenant_name=tenant_name
#openshift_cloudprovider_openstack_region=region
#openshift_cloudprovider_openstack_lb_subnet_id=subnet_id
```

#### 18.5.2. Manually Configuring OpenShift Container Platform Masters for OpenStack

Edit or [create](#) the master configuration file on all masters (`/etc/origin/master/master-config.yaml` by default) and update the contents of the `apiServerArguments` and `controllerArguments` sections:

```

kubernetesMasterConfig:
  ...
  apiServerArguments:
    cloud-provider:
      - "openstack"
    cloud-config:
      - "/etc/cloud.conf"
  controllerArguments:
    cloud-provider:
      - "openstack"
    cloud-config:
      - "/etc/cloud.conf"

```



### IMPORTANT

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, `cloud.conf` should be in `/etc/origin/` instead of `/etc/`.

## 18.5.3. Manually Configuring OpenShift Container Platform Nodes for OpenStack

Edit or [create](#) the node configuration file on all nodes (`/etc/origin/node/node-config.yaml` by default) and update the contents of the `kubeletArguments` and `nodeName` sections:

```

nodeName:
  <instance_name> ①

kubeletArguments:
  cloud-provider:
    - "openstack"
  cloud-config:
    - "/etc/cloud.conf"

```

- ① Name of the OpenStack instance where the node runs (i.e., name of the virtual machine)

Currently, the `nodeName` **must** match the instance name in Openstack in order for the cloud provider integration to work properly. The name must also be RFC1123 compliant.



### IMPORTANT

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, `cloud.conf` should be in `/etc/origin/` instead of `/etc/`.

## 18.6. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```

# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
# systemctl restart atomic-openshift-node

```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

# CHAPTER 19. CONFIGURING FOR GCE

## 19.1. OVERVIEW

OpenShift Container Platform can be configured to access a Google Compute Engine (GCE) infrastructure, including using GCE volumes as persistent storage for application data. After GCE is configured properly, some additional configurations will need to be completed on the OpenShift Container Platform hosts.

## 19.2. PERMISSIONS

Configuring GCE for OpenShift Container Platform requires the following role:

roles/owner	To create service accounts, cloud storage, instances, images, templates, Cloud DNS entries, and deploy load balancers and health checks. It is helpful to also have <b>delete</b> permissions to be able to redeploy the environment while testing.
-------------	---

## 19.3. CONFIGURING MASTERS

You can set the GCE configuration on your OpenShift Container Platform master hosts in two ways:

- Using Ansible and the advanced installation tool.
- Manually by modifying the *master-config.yaml* file.

### 19.3.1. Configuring OpenShift Container Platform Masters for GCE with Ansible

During advanced installations, GCE can be configured using the `openshift_cloudprovider_kind` parameter, which is configurable in the inventory file.



#### IMPORTANT

- When using GCE, the `openshift_gcp_project` and `openshift_gcp_prefix` parameters must be defined.
- For running load balancer services using the Google compute platform, the nodes (Compute Engine VM instances) must be tagged with `<openshift_gcp_prefix>ocp` (add `oCP` suffix). For example, if the value of `openshift_gcp_prefix` parameter is set to `mycluster`, the nodes must be tagged with `myclusteroCP`. See [Adding and Removing Network Tags](#) for more information on how to add network tags to Compute Engine VM instances.

#### Example GCE Configuration with Ansible

```
# Cloud Provider Configuration
# openshift_cloudprovider_kind=gce
# openshift_gcp_project=<projectid> ①
# openshift_gcp_prefix=<uid> ②
# openshift_gcp_multizone=False ③
```

- 1 **openshift\_gcp\_project** is the project-id.
- 2 **openshift\_gcp\_prefix** is a unique string to identify each OpenShift cluster.
- 3 Use the **openshift\_gcp\_multizone** parameter to trigger multizone deployments on GCE. Its default value is **False**.



### NOTE

When Ansible configures GCE, the following files are created for you:

- **/etc/origin/cloudprovider/gce.conf**
- **/etc/origin/master/master-config.yaml**
- **/etc/origin/node/node-config.yaml**

The advanced installation configures single-zone support by default. If you want multizone support, edit the **/etc/origin/cloudprovider/gce.conf** as shown in [Configuring Multizone Support in a GCE Deployment](#).

### 19.3.2. Manually Configuring OpenShift Container Platform Masters for GCE

To configure the OpenShift Container Platform masters for GCE:

1. Edit or [create](#) the master configuration file (**/etc/origin/master/master-config.yaml** by default) on all masters and update the contents of the **apiServerArguments** and **controllerArguments** sections:

```
kubernetesMasterConfig:
  ...
  apiServerArguments:
    cloud-provider:
      - "gce"
    cloud-config:
      - "/etc/origin/cloudprovider/gce.conf"
  controllerArguments:
    cloud-provider:
      - "gce"
    cloud-config:
      - "/etc/origin/cloudprovider/gce.conf"
```



### IMPORTANT

When triggering a containerized installation, only the directories of **/etc/origin** and **/var/lib/origin** are mounted to the master and node container. Therefore, **master-config.yaml** should be in **/etc/origin/master** instead of **/etc/**.

2. Start or restart the OpenShift Container Platform services:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers
```

## 19.4. CONFIGURING NODES

To configure the OpenShift Container Platform nodes for GCE:

1. Edit or [create](#) the node configuration file (`/etc/origin/node/node-config.yaml` by default) on all nodes and update the contents of the `kubeletArguments` section:

```
kubeletArguments:
  cloud-provider:
    - "gce"
  cloud-config:
    - "/etc/origin/cloudprovider/gce.conf"
```

Currently, the **nodeName** must match the instance name in GCE in order for the cloud provider integration to work properly. The name must also be RFC1123 compliant.



### IMPORTANT

When triggering a containerized installation, only the directories of `/etc/origin` and `/var/lib/origin` are mounted to the master and node container. Therefore, `node-config.yaml` should be in `/etc/origin/node` instead of `/etc/`.

1. Start or restart the OpenShift Container Platform services all nodes.

```
# systemctl restart atomic-openshift-node
```

## 19.5. CONFIGURING MULTIZONE SUPPORT IN A GCE DEPLOYMENT

If manually configuring GCE, multizone support is not configured by default.



### NOTE

The advanced installation configures single-zone support by default.

If you want multizone support:

1. Edit or create a `/etc/origin/cloudprovider/gce.conf` file on all of your OpenShift Container Platform hosts, both masters and nodes.
2. Add the following contents:

```
[Global]
project-id = <project-id>
network-name = <network-name>
node-tags = <node-tags>
node-instance-prefix = <instance-prefix>
multizone = true
```

To return to single-zone support, set the `multizone` value to `false`.

## 19.6. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-controllers  
# systemctl restart atomic-openshift-node
```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

# CHAPTER 20. CONFIGURING FOR AZURE

## 20.1. OVERVIEW

OpenShift Container Platform can be configured to access a [Microsoft Azure infrastructure](#), including [using Azure disk as persistent storage](#) for application data. After Microsoft Azure is configured properly, some additional configurations need to be completed on the OpenShift Container Platform hosts.

## 20.2. PERMISSIONS

Configuring Microsoft Azure for OpenShift Container Platform requires the following role:

Contributor	To create and manage all types of Microsoft Azure resources.
-------------	--

For more information about adding administrator roles, see [Add or change Azure subscription administrators](#).

## 20.3. PREREQUISITES

- If you are using Microsoft Azure Disk as a persistent volume on the OpenShift Container Platform version 3.5 or later, you must enable Azure Cloud Provider.
- All OpenShift Container Platform node virtual machines (VMs) running in Microsoft Azure must belong to a single resource group.
- Microsoft Azure VMs must be named the same as OpenShift Container Platform nodes and this cannot include capital letters.
- If you plan to use Azure Managed Disks:
  - OpenShift Container Platform version 3.7 or later is required.
  - You must create VMs with Azure Managed Disks.
- If you plan to use unmanaged disks:
  - You must create VMs with unmanaged disks.
- If you are using a custom DNS configuration for your OpenShift Container Platform cluster or your cluster nodes are in different Microsoft Azure Virtual Networks (VNet), you must configure DNS so that each node in the cluster can resolve IP addresses for other nodes.

## 20.4. THE AZURE CONFIGURATION FILE

Configuring OpenShift Container Platform for Azure requires the `/etc/azure/azure.conf` file, on each node host.

If the file does not exist, create it, and add the following:

```
tenantId: <> 1
subscriptionId: <> 2
aadClientId: <> 3
```

```
aadClientSecret: <-> 4
aadTenantId: <-> 5
resourceGroup: <-> 6
cloud: <-> 7
location: <-> 8
vnetName: <-> 9
securityGroupName: <-> 10
primaryAvailabilitySetName: <-> 11
```

- 1 The AAD tenant ID for the subscription that the cluster is deployed in.
- 2 The Azure subscription ID that the cluster is deployed in.
- 3 The client ID for an AAD application with RBAC access to talk to Azure RM APIs.
- 4 The client secret for an AAD application with RBAC access to talk to Azure RM APIs.
- 5 Ensure this is the same as tenant ID (optional).
- 6 The Azure Resource Group name that the Azure VM belongs to.
- 7 The specific cloud region. For example, **AzurePublicCloud**.
- 8 The compact style Azure region. For example, **southeastasia** (optional).
- 9 Virtual network containing instances and used when creating load balancers.
- 10 Security group name associated with instances and load balancers.
- 11 Availability set to use when creating resources such as load balancers (optional).



### IMPORTANT

The NIC used for accessing the instance must have an **internal-dns-name** set or the node will not be able to rejoin the cluster, display build logs to the console, and will cause **oc rsh** to not work correctly.

## 20.5. CONFIGURING MASTERS

Edit or [create](#) the master configuration file on all masters (*/etc/origin/master/master-config.yaml* by default) and update the contents of the **apiServerArguments** and **controllerArguments** sections:

```
kubernetesMasterConfig:
  ...
  apiServerArguments:
    cloud-provider:
      - "azure"
    cloud-config:
      - "/etc/azure/azure.conf"
  controllerArguments:
    cloud-provider:
```

```

    - "azure"
cloud-config:
  - "/etc/azure/azure.conf"

```

**IMPORTANT**

When triggering a containerized installation, only the `/etc/origin` and `/var/lib/origin` directories are mounted to the master and node container. Therefore, `master-config.yaml` should be in `/etc/origin/master` instead of `/etc/`.

## 20.6. CONFIGURING NODES

1. Edit or [create](#) the node configuration file on all nodes (`/etc/origin/node/node-config.yaml` by default) and update the contents of the `kubeletArguments` section:

```

kubeletArguments:
  cloud-provider:
    - "azure"
  cloud-config:
    - "/etc/azure/azure.conf"

```

**IMPORTANT**

When triggering a containerized installation, only the `/etc/origin` and `/var/lib/origin` directories are mounted to the master and node container. Therefore, `node-config.yaml` should be in `/etc/origin/node` instead of `/etc/`.

## 20.7. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```

# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
# systemctl restart atomic-openshift-node

```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the `hostname` as the `externalID` (which would have been the case when no cloud provider was being used) to using the cloud provider's `instance-id` (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```

$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?=Taints)'

```

3. Delete the nodes:

```

$ oc delete node <node_name>

```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

# CHAPTER 21. CONFIGURING FOR VMWARE VSPHERE

## 21.1. OVERVIEW

OpenShift Container Platform can be configured to access [VMware vSphere](#) VMDK Volumes, including [using VMware vSphere VMDK Volumes as persistent storage](#) for application data.

The vSphere Cloud Provider allows using vSphere managed storage within OpenShift Container Platform and supports:

- Volumes,
- Persistent Volumes, and
- Storage Classes and provisioning of volumes.

## 21.2. ENABLING VMWARE VSPHERE CLOUD PROVIDER



### IMPORTANT

Enabling VMware vSphere requires installing the VMware Tools on each Node VM. See [Installing VMware tools](#) for more information.

To enable VMware vSphere cloud provider for OpenShift Container Platform:

1. Create a [VM folder](#) and move OpenShift Container Platform Node VMs to this folder.
2. Verify that the Node VM names complies with the regex `[a-z](()?[0-9a-z])?(\\. [a-z0-9](([0-9a-z])?[0-9a-z])?)*`.



### IMPORTANT

VM Names can not:

- begin with numbers.
- have any capital letters.
- have any special characters except -.
- be shorter than three characters and longer than 63 characters.

3. Set the `disk.EnableUUID` parameter to **TRUE** for each Node VM. This ensures that the VMDK always presents a consistent UUID to the VM, allowing the disk to be mounted properly. For every virtual machine node that will be participating in the cluster, follow the steps below using the [GOVC tool](#):
  - a. Set up the GOVC environment:

```
export GOVC_URL='vCenter IP OR FQDN'
export GOVC_USERNAME='vCenter User'
export GOVC_PASSWORD='vCenter Password'
export GOVC_INSECURE=1
```

- b. Find the Node VM paths:

```
govc ls /datacenter/vm/<vm-folder-name>
```

- c. Set disk.EnableUUID to true for all VMs:

```
govc vm.change -e="disk.enableUUID=1" -vm='VM Path'
```



### NOTE

If OpenShift Container Platform node VMs are created from a template VM, then **disk.EnableUUID=1** can be set on the template VM. VMs cloned from this template, inherit this property.

4. Create and assign roles to the vSphere Cloud Provider user and vSphere entities. vSphere Cloud Provider requires the following privileges to interact with vCenter. See the [vSphere Documentation Center](#) for steps to create a custom role, user and role assignment.

Roles	Privileges	Entities	Propagate to Children
manage-k8s-node-vms	Resource.AssignVMT oPool System.Anonymous System.Read System.View VirtualMachine.Config. AddExistingDisk VirtualMachine.Config. AddNewDisk VirtualMachine.Config. AddRemoveDevice VirtualMachine.Config. RemoveDisk VirtualMachine.Invent ory.Create VirtualMachine.Invent ory.Delete	Cluster, Hosts, VM Folder	Yes
manage-k8s-volumes	Datastore.AllocateSpa ce Datastore.FileManage ment System.Anonymous System.Read System.View	Datastore	No
k8s-system-read-and-spbm-profile-view	StorageProfile.View System.Anonymous System.Read System.View	vCenter	No

Roles	Privileges	Entities	Propagate to Children
ReadOnly	System.Anonymous System.Read System.View	Datacenter, Datastore Cluster, Datastore Storage Folder	No

**NOTE**

After enabling the vSphere Cloud Provider, Node names are set to the VM names from the vCenter Inventory.

**WARNING**

The `openshift_hostname` variable must match the virtual machine name and its host name. The `openshift_hostname` variable defines the `nodeName` value in the `node-config.yaml` file. This value is compared to the `nodeName` value determined by using the command `uname -n`. In case of a mismatch, the native cloud integration for those providers will not work.

## 21.3. THE VMWARE VSphere CONFIGURATION FILE

Configuring OpenShift Container Platform for VMware vSphere requires the `/etc/origin/cloudprovider/vsphere.conf` file, on each node host.

If the file does not exist, create it, and add the following:

```
[Global]
user = "username" ①
password = "password" ②
server = "10.10.0.2" ③
port = "443" ④
insecure-flag = "1" ⑤
datacenter = "datacenter-name" ⑥
datastore = "datastore-name" ⑦
working-dir = "vm-folder-path" ⑧
vm-uuid = "vm-uuid" ⑨

[Disk]
scsicontrollertype = pvscsi
```

- ① vCenter username for the vSphere cloud provider.
- ② vCenter password for the specified user.
- ③ IP Address or FQDN for the vCenter server.

- 4 (Optional) Port number for the vCenter server. Defaults to port **443**.
- 5 Set to **1** if the vCenter uses a self-signed cert.
- 6 Name of the data center on which Node VMs are deployed.
- 7 Name of the datastore to use for provisioning volumes using the storage classes or dynamic provisioning. If datastore is located in a storage folder or datastore is a member of datastore cluster, specify the full datastore path. Verify that vSphere Cloud Provider user has the read privilege set on the datastore cluster or storage folder to be able to find datastore.
- 8 (Optional) The vCenter VM folder path in which the node VMs are located. It can be set to an empty path(**working-dir = ""**), if Node VMs are located in the root VM folder.
- 9 (Optional) VM Instance UUID of the Node VM. It can be set to empty (**vm-uuid = ""**). If this is set to empty, this is retrieved from **/sys/class/dmi/id/product\_serial** file on virtual machine (requires root access).

## 21.4. CONFIGURING MASTERS

Edit or [create](#) the master configuration file on all masters (*/etc/origin/master/master-config.yaml* by default) and update the contents of the **apiServerArguments** and **controllerArguments** sections with the following:

```
kubernetesMasterConfig:
  admissionConfig:
    pluginConfig:
      {}
  apiServerArguments:
    cloud-provider:
      - "vsphere"
    cloud-config:
      - "/etc/origin/cloudprovider/vsphere.conf"
  controllerArguments:
    cloud-provider:
      - "vsphere"
    cloud-config:
      - "/etc/origin/cloudprovider/vsphere.conf"
```



### IMPORTANT

When triggering a containerized installation, only the */etc/origin* and */var/lib/origin* directories are mounted to the master and node container. Therefore, **master-config.yaml** must be in */etc/origin/master* rather than */etc/*.

## 21.5. CONFIGURING NODES

1. Edit or [create](#) the node configuration file on all nodes (*/etc/origin/node/node-config.yaml* by default) and update the contents of the **kubeletArguments** section:

```
kubeletArguments:
  cloud-provider:
    - "vsphere"
```

```
cloud-config:
  - "/etc/origin/cloudprovider/vsphere.conf"
```

**IMPORTANT**

When triggering a containerized installation, only the `/etc/origin` and `/var/lib/origin` directories are mounted to the master and node container. Therefore, `node-config.yaml` must be in `/etc/origin/node` rather than `/etc/`.

## 21.6. APPLYING CONFIGURATION CHANGES

Start or restart OpenShift Container Platform services on all master and node hosts to apply your configuration changes, see [Restarting OpenShift Container Platform services](#):

```
# systemctl restart atomic-openshift-master-api atomic-openshift-master-
controllers
# systemctl restart atomic-openshift-node
```

Switching from not using a cloud provider to using a cloud provider produces an error message. Adding the cloud provider tries to delete the node because the node switches from using the **hostname** as the **externalID** (which would have been the case when no cloud provider was being used) to using the cloud provider's **instance-id** (which is what the cloud provider specifies). To resolve this issue:

1. Log in to the CLI as a cluster administrator.
2. Check and back up existing node labels:

```
$ oc describe node <node_name> | grep -Poz '(?s)Labels.*\n.*(?=Taints)'
```

3. Delete the nodes:

```
$ oc delete node <node_name>
```

4. On each node host, restart the OpenShift Container Platform service.

```
# systemctl restart atomic-openshift-node
```

5. Add back any [labels on each node](#) that you previously had.

## 21.7. BACKUP OF PERSISTENT VOLUMES

OpenShift Container Platform provisions new volumes as **independent persistent disks** to freely attach and detach the volume on any node in the cluster. As a consequence, [it is not possible to back up volumes that use snapshots](#).

To create a backup of PVs:

1. Stop the application using the PV.
2. Clone the persistent disk.
3. Restart the application.

4. Create a backup of the cloned disk.
5. Delete the cloned disk.

# CHAPTER 22. CONFIGURING FOR LOCAL VOLUME

## 22.1. OVERVIEW

OpenShift Container Platform can be configured to access [local volumes](#) for application data.

Local volumes are persistent volumes (PV) representing locally-mounted file systems. In the future, they may be extended to raw block devices.

Local volumes are different from a hostPath. They have a special annotation that makes any pod that uses the PV to be scheduled on the same node where the local volume is mounted.

In addition, local volume includes a provisioner that automatically creates PVs for locally mounted devices. This provisioner is currently limited and it only scans pre-configured directories. It cannot dynamically provision volumes, which may be implemented in a future release.

The local volume provisioner allows using local storage within OpenShift Container Platform and supports:

- Volumes
- PVs



### NOTE

Local volumes is an alpha feature and may change in a future release of OpenShift Container Platform.

#### 22.1.1. Enable Local Volumes

Enable the **PersistentLocalVolumes** feature gate on all masters and nodes.

1. Edit or create the master configuration file on all masters (*/etc/origin/master/master-config.yaml* by default) and add **PersistentLocalVolumes=true** under the **apiServerArguments** and **controllerArguments** sections:

```
apiServerArguments:
  feature-gates:
    - PersistentLocalVolumes=true
  ...
controllerArguments:
  feature-gates:
    - PersistentLocalVolumes=true
  ...
```

2. On all nodes, edit or create the node configuration file (*/etc/origin/node/node-config.yaml* by default) and add **PersistentLocalVolumes=true** feature gate under **kubeletArguments**:

```
kubeletArguments:
  feature-gates:
    - PersistentLocalVolumes=true
```

## 22.1.2. Mount Local Volumes

All local volumes must be manually mounted before they can be consumed by OpenShift Container Platform as PVs.

All volumes must be mounted into the `/mnt/local-storage/<storage-class-name>/<volume>` path. The administrators are required to create the local devices as needed (by using any method such as a disk partition or an LVM), create suitable file systems on these devices, and mount them using a script or `/etc/fstab` entries.

### Example `/etc/fstab` entries

```
# device name      # mount point          # FS      # options # extra
/dev/sdb1         /mnt/local-storage/ssd/disk1 ext4    defaults 1 2
/dev/sdb2         /mnt/local-storage/ssd/disk2 ext4    defaults 1 2
/dev/sdb3         /mnt/local-storage/ssd/disk3 ext4    defaults 1 2
/dev/sdc1         /mnt/local-storage/hdd/disk1 ext4   defaults 1 2
/dev/sdc2         /mnt/local-storage/hdd/disk2 ext4   defaults 1 2
```

All volumes must be accessible to processes running within Docker containers. Change the labels of mounted file systems to allow that:

```
$ chcon -R unconfined_u:object_r:svirt_sandbox_file_t:s0 /mnt/local-
storage/
```

## 22.1.3. Configure Local Provisioner

OpenShift Container Platform depends on an external provisioner to create PVs for local devices and to clean them up when they are not needed (to enable reuse).



### NOTE

- The local volume provisioner is different from most provisioners and does not support dynamic provisioning.
- The local volume provisioner requires that the administrators preconfigure the local volumes on each node and mount them under discovery directories. The provisioner then manages the volumes by creating and cleaning up PVs for each volume.

This external provisioner should be configured using a **ConfigMap** to relate directories with StorageClasses. This configuration must be created before the provisioner is deployed.



### NOTE

(Optional) Create a standalone namespace for local volume provisioner and its configuration, for example: `oc new-project local-storage`

```
kind: ConfigMap
metadata:
  name: local-volume-config
data:
```

```

"local-ssd": | ①
{
    "hostDir": "/mnt/local-storage/ssd", ②
    "mountDir": "/mnt/local-storage/ssd" ③
}
"local-hdd": |
{
    "hostDir": "/mnt/local-storage/hdd",
    "mountDir": "/mnt/local-storage/hdd"
}

```

- ① Name of the StorageClass.
- ② Path to the directory on the host. It must be a subdirectory of **/mnt/local-storage**.
- ③ Path to the directory in the provisioner pod. We recommend using the same directory structure as used on the host.

With this configuration, the provisioner creates:

- One PV with StorageClass **local-ssd** for every subdirectory in **/mnt/local-storage/ssd**.
- One PV with StorageClass **local-hdd** for every subdirectory in **/mnt/local-storage/hdd**.

The **LocalPersistentVolumes** alpha feature now also requires the **VolumeScheduling** alpha feature. This is a breaking change, and the following changes are required:

- The **VolumeScheduling** feature gate must also be enabled on kube-scheduler and kube-controller-manager components.
- The **NoVolumeNodeConflict** predicate has been removed. For non-default schedulers, update your scheduler policy.
- The **CheckVolumeBinding** predicate must be enabled in non-default schedulers.

#### 22.1.4. Deploy Local Provisioner



##### NOTE

Before starting the provisioner, mount all local devices and create a **ConfigMap** with storage classes and their directories.

Install the local provisioner from the [\*\*local-storage-provisioner-template.yaml\*\*](#) file.

1. Create a service account that allows running pods as a root user, use hostPath volumes, and use any SELinux context to be able to monitor, manage, and clean local volumes:

```

$ oc create serviceaccount local-storage-admin
$ oc adm policy add-scc-to-user privileged -z local-storage-admin

```

To allow the provisioner pod to delete content on local volumes created by any pod, root privileges and any SELinux context are required. hostPath is required to access the **/mnt/local-storage** path on the host.

2. Install the template:

```
$ oc create -f
https://raw.githubusercontent.com/openshift/origin/master/examples/storage-examples/local-examples/local-storage-provisioner-template.yaml
```

3. Instantiate the template by specifying values for **configmap**, **account**, and **provisioner\_image** parameters:

```
$ oc new-app -p CONFIGMAP=local-volume-config \
-p SERVICE_ACCOUNT=local-storage-admin \
-p NAMESPACE=local-storage \
-p PROVISIONER_IMAGE=registry.access.redhat.com/openshift3/local-
storage-provisioner:v3.9 \ ①
local-storage-provisioner
```

① Replace **v3.9** with the right OpenShift Container Platform version.

4. Add the necessary storage classes:

```
oc create -f ./storage-class-ssd.yaml
oc create -f ./storage-class-hdd.yaml
```

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: local-ssd
provisioner: kubernetes.io/no-provisioner
volumeBindingMode: WaitForFirstConsumer
```

```
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: local-hdd
provisioner: kubernetes.io/no-provisioner
volumeBindingMode: WaitForFirstConsumer
```

See the [template](#) for other configurable options. This template creates a DaemonSet that runs a pod on every node. The pod watches directories specified in the **ConfigMap** and creates PVs for them automatically.

The provisioner runs as root to be able to clean up the directories when a PV is released and all data needs to be removed.

### 22.1.5. Adding New Devices

Adding a new device requires several manual steps:

1. Stop DaemonSet with the provisioner.
2. Create a subdirectory in the right directory on the node with the new device and mount it there.

3. Start the DaemonSet with the provisioner.


**IMPORTANT**

Omitting any of these steps may result in the wrong PV being created.

# CHAPTER 23. CONFIGURING PERSISTENT VOLUME CLAIM PROTECTION

## 23.1. OVERVIEW

OpenShift Container Platform can be configured to have the [persistent volume claim \(PVC\)](#) protection feature enabled. This feature ensures that PVCs in active use by a pod are not removed from the system, as this may result in data loss.



### NOTE

PVC protection is an alpha feature and may change in a future release of OpenShift Container Platform.

### 23.1.1. Enable PVC Protection

To enable the **PVCProtection** feature gate on all masters and nodes:

1. Edit or create the master configuration file on all masters (*/etc/origin/master/master-config.yaml* by default):
  - a. Add **PVCProtection=true** under the **apiServerArguments** and **controllerArguments** sections.
  - b. Add **PVCProtection** admission plugin configuration under the **admissionConfig** section.

```
admissionConfig:  
  pluginConfig:  
    PVCProtection:  
      configuration:  
        apiVersion: v1  
        disable: false  
        kind: DefaultAdmissionConfig  
...  
  kubernetesMasterConfig:  
...  
  apiServerArguments:  
    feature-gates:  
      - PVCProtection=true  
...  
  controllerArguments:  
    feature-gates:  
      - PVCProtection=true  
...
```

2. On all nodes, edit or create the node configuration file (*/etc/origin/node/node-config.yaml* by default), and add the **PVCProtection=true** feature gate under **kubeletArguments**:

```
kubeletArguments:  
  feature-gates:  
    - PVCProtection=true
```

3. On all masters and nodes, restart OpenShift Container Platform for the changes to take effect.

# CHAPTER 24. CONFIGURING PERSISTENT STORAGE

## 24.1. OVERVIEW

The Kubernetes [persistent volume](#) framework allows you to provision an OpenShift Container Platform cluster with persistent storage using networked storage available in your environment. This can be done after completing the initial OpenShift Container Platform installation depending on your application needs, giving users a way to request those resources without having any knowledge of the underlying infrastructure.

These topics show how to configure persistent volumes in OpenShift Container Platform using the following supported volume plug-ins:

- [NFS](#)
- [GlusterFS](#)
- [OpenStack Cinder](#)
- [Ceph RBD](#)
- [AWS Elastic Block Store \(EBS\)](#)
- [GCE Persistent Disk](#)
- [iSCSI](#)
- [Fibre Channel](#)
- [Azure Disk](#)
- [Azure File](#)
- [FlexVolume](#)
- [VMWare vSphere](#)
- [Dynamic Provisioning and Creating Storage Classes](#)
- [Volume Security](#)
- [Selector-Label Volume Binding](#)

## 24.2. PERSISTENT STORAGE USING NFS

### 24.2.1. Overview

OpenShift Container Platform clusters can be provisioned with [persistent storage](#) using NFS. Persistent volumes (PVs) and persistent volume claims (PVCs) provide a convenient method for sharing a volume across a project. While the NFS-specific information contained in a PV definition could also be defined directly in a pod definition, doing so does not create the volume as a distinct cluster resource, making the volume more susceptible to conflicts.

This topic covers the specifics of using the NFS persistent storage type. Some familiarity with OpenShift Container Platform and [NFS](#) is beneficial. See the [Persistent Storage](#) concept topic for details on the OpenShift Container Platform persistent volume (PV) framework in general.

## 24.2.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. To provision NFS volumes, a list of NFS servers and export paths are all that is required.

You must first create an object definition for the PV:

### Example 24.1. PV Object Definition Using NFS

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 ①
spec:
  capacity:
    storage: 5Gi ②
  accessModes:
    - ReadWriteOnce ③
  nfs: ④
    path: /tmp ⑤
    server: 172.17.0.2 ⑥
  persistentVolumeReclaimPolicy: Recycle ⑦
```

- ① The name of the volume. This is the PV identity in various `oc <command> pod` commands.
- ② The amount of storage allocated to this volume.
- ③ Though this appears to be related to controlling access to the volume, it is actually used similarly to labels and used to match a PVC to a PV. Currently, no access rules are enforced based on the `accessModes`.
- ④ The volume type being used, in this case the `nfs` plug-in.
- ⑤ The path that is exported by the NFS server.
- ⑥ The host name or IP address of the NFS server.
- ⑦ The reclaim policy for the PV. This defines what happens to a volume when released from its claim. Valid options are `Retain` (default) and `Recycle`. See [Reclaiming Resources](#).



### NOTE

Each NFS volume must be mountable by all schedulable nodes in the cluster.

Save the definition to a file, for example `nfs-pv.yaml`, and create the PV:

```
$ oc create -f nfs-pv.yaml
persistentvolume "pv0001" created
```

Verify that the PV was created:

# oc get pv	NAME	LABELS	CAPACITY	ACCESSMODES	STATUS
	CLAIM	REASON	AGE		
	pv0001	<none>	5368709120	RWO	Available
			31s		

The next step can be to create a PVC, which binds to the new PV:

### Example 24.2. PVC Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: nfs-claim1
spec:
  accessModes:
    - ReadWriteOnce ①
  resources:
    requests:
      storage: 1Gi ②
```

- ①** As mentioned above for PVs, the **accessModes** do not enforce security, but rather act as labels to match a PV to a PVC.
- ②** This claim looks for PVs offering **1Gi** or greater capacity.

Save the definition to a file, for example **nfs-claim.yaml**, and create the PVC:

```
# oc create -f nfs-claim.yaml
```

### 24.2.3. Enforcing Disk Quotas

You can use disk partitions to enforce disk quotas and size constraints. Each partition can be its own export. Each export is one PV. OpenShift Container Platform enforces unique names for PVs, but the uniqueness of the NFS volume's server and path is up to the administrator.

Enforcing quotas in this way allows the developer to request persistent storage by a specific amount (for example, 10Gi) and be matched with a corresponding volume of equal or greater capacity.

### 24.2.4. NFS Volume Security

This section covers NFS volume security, including matching permissions and SELinux considerations. The user is expected to understand the basics of POSIX permissions, process UIDs, supplemental groups, and SELinux.

**NOTE**

See the full [Volume Security](#) topic before implementing NFS volumes.

Developers request NFS storage by referencing, in the **volumes** section of their pod definition, either a PVC by name or the NFS volume plug-in directly.

The **/etc(exports** file on the NFS server contains the accessible NFS directories. The target NFS directory has POSIX owner and group IDs. The OpenShift Container Platform NFS plug-in mounts the container's NFS directory with the same POSIX ownership and permissions found on the exported NFS directory. However, the container is not run with its effective UID equal to the owner of the NFS mount, which is the desired behavior.

As an example, if the target NFS directory appears on the NFS server as:

```
# ls -lZ /opt/nfs -d
drwxrws---. nfsnobody 5555 unconfined_u:object_r:usr_t:s0  /opt/nfs

# id nfsnobody
uid=65534(nfsnobody) gid=65534(nfsnobody) groups=65534(nfsnobody)
```

Then the container must match SELinux labels, and either run with a UID of **65534** (**nfsnobody** owner) or with **5555** in its supplemental groups in order to access the directory.

**NOTE**

The owner ID of 65534 is used as an example. Even though NFS's **root\_squash** maps **root** (0) to **nfsnobody** (65534), NFS exports can have arbitrary owner IDs. Owner 65534 is not required for NFS exports.

#### 24.2.4.1. Group IDs

The recommended way to handle NFS access (assuming it is not an option to change permissions on the NFS export) is to use supplemental groups. Supplemental groups in OpenShift Container Platform are used for shared storage, of which NFS is an example. In contrast, block storage, such as Ceph RBD or iSCSI, use the **fsGroup** SCC strategy and the **fsGroup** value in the pod's **securityContext**.

**NOTE**

It is generally preferable to use supplemental group IDs to gain access to persistent storage versus using [user IDs](#). Supplemental groups are covered further in the full [Volume Security](#) topic.

Because the group ID on the [example target NFS directory](#) shown above is 5555, the pod can define that group ID using **supplementalGroups** under the pod-level **securityContext** definition. For example:

```
spec:
  containers:
    - name:
      ...
    securityContext: ①
      supplementalGroups: [5555] ②
```

- 1 **securityContext** must be defined at the pod level, not under a specific container.
- 2 An array of GIDs defined for the pod. In this case, there is one element in the array; additional GIDs would be comma-separated.

Assuming there are no custom SCCs that might satisfy the pod's requirements, the pod likely matches the **restricted** SCC. This SCC has the **supplementalGroups** strategy set to **RunAsAny**, meaning that any supplied group ID is accepted without range checking.

As a result, the above pod passes admissions and is launched. However, if group ID range checking is desired, a custom SCC, as described in [pod security and custom SCCs](#), is the preferred solution. A custom SCC can be created such that minimum and maximum group IDs are defined, group ID range checking is enforced, and a group ID of 5555 is allowed.



#### NOTE

To use a custom SCC, you must first add it to the appropriate service account. For example, use the **default** service account in the given project unless another has been specified on the pod specification. See [Add an SCC to a User, Group, or Project](#) for details.

#### 24.2.4.2. User IDs

User IDs can be defined in the container image or in the pod definition. The full [Volume Security](#) topic covers controlling storage access based on user IDs, and should be read prior to setting up NFS persistent storage.



#### NOTE

It is generally preferable to use [supplemental group IDs](#) to gain access to persistent storage versus using user IDs.

In the [example target NFS directory](#) shown above, the container needs its UID set to 65534 (ignoring group IDs for the moment), so the following can be added to the pod definition:

```
spec:
  containers: ①
    - name:
      ...
      securityContext:
        runAsUser: 65534 ②
```

- 1 Pods contain a **securityContext** specific to each container (shown here) and a pod-level **securityContext** which applies to all containers defined in the pod.
- 2 65534 is the **nfsnobody** user.

Assuming the **default** project and the **restricted** SCC, the pod's requested user ID of 65534 is not allowed, and therefore the pod fails. The pod fails for the following reasons:

- It requests 65534 as its user ID.

- All SCCs available to the pod are examined to see which SCC allows a user ID of 65534 (actually, all policies of the SCCs are checked but the focus here is on user ID).
- Because all available SCCs use **MustRunAsRange** for their **runAsUser** strategy, UID range checking is required.
- 65534 is not included in the SCC or project's user ID range.

It is generally considered a good practice not to modify the predefined SCCs. The preferred way to fix this situation is to create a custom SCC, as described in the full [Volume Security](#) topic. A custom SCC can be created such that minimum and maximum user IDs are defined, UID range checking is still enforced, and the UID of 65534 is allowed.



#### NOTE

To use a custom SCC, you must first add it to the appropriate service account. For example, use the **default** service account in the given project unless another has been specified on the pod specification. See [Add an SCC to a User, Group, or Project](#) for details.

#### 24.2.4.3. SELinux



#### NOTE

See the full [Volume Security](#) topic for information on controlling storage access in conjunction with using SELinux.

By default, SELinux does not allow writing from a pod to a remote NFS server. The NFS volume mounts correctly, but is read-only.

To enable writing to NFS volumes with SELinux enforcing on each node, run:

```
# setsebool -P virt_use_nfs 1
```

The **-P** option above makes the bool persistent between reboots.

The **virt\_use\_nfs** boolean is defined by the **docker-selinux** package. If an error is seen indicating that this bool is not defined, ensure this package has been installed.

#### 24.2.4.4. Export Settings

In order to enable arbitrary container users to read and write the volume, each exported volume on the NFS server should conform to the following conditions:

- Each export must be:

```
/<example_fs> *(rw,root_squash)
```

- The firewall must be configured to allow traffic to the mount point.

- For NFSv4, configure the default port **2049 (nfs)** and port **111 (portmapper)**.

#### NFSv4



```
# iptables -I INPUT 1 -p tcp --dport 2049 -j ACCEPT
# iptables -I INPUT 1 -p tcp --dport 111 -j ACCEPT
```

- For NFSv3, there are three ports to configure: **2049 (nfs)**, **20048 (mountd)**, and **111 (portmapper)**.

### NFSv3

```
# iptables -I INPUT 1 -p tcp --dport 2049 -j ACCEPT
# iptables -I INPUT 1 -p tcp --dport 20048 -j ACCEPT
# iptables -I INPUT 1 -p tcp --dport 111 -j ACCEPT
```

- The NFS export and directory must be set up so that it is accessible by the target pods. Either set the export to be owned by the container's primary UID, or supply the pod group access using **supplementalGroups**, as shown in [Group IDs](#) above. See the full [Volume Security](#) topic for additional pod security information as well.

## 24.2.5. Reclaiming Resources

NFS implements the OpenShift Container Platform **Recyclable** plug-in interface. Automatic processes handle reclamation tasks based on policies set on each persistent volume.

By default, PVs are set to **Retain**. NFS volumes which are set to **Recycle** are scrubbed (i.e., `rm -rf` is run on the volume) after being released from their claim (i.e., after the user's **PersistentVolumeClaim** bound to the volume is deleted). Once recycled, the NFS volume can be bound to a new claim.

Once claim to a PV is released (that is, the PVC is deleted), the PV object should not be re-used. Instead, a new PV should be created with the same basic volume details as the original.

For example, the administrator creates a PV named **nfs1**:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: nfs1
spec:
  capacity:
    storage: 1Mi
  accessModes:
    - ReadWriteMany
  nfs:
    server: 192.168.1.1
    path: "/"
```

The user creates **PVC1**, which binds to **nfs1**. The user then deletes **PVC1**, releasing claim to **nfs1**, which causes **nfs1** to be **Released**. If the administrator wishes to make the same NFS share available, they should create a new PV with the same NFS server details, but a different PV name:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: nfs2
spec:
  capacity:
```

```

storage: 1Mi
accessModes:
  - ReadWriteMany
nfs:
  server: 192.168.1.1
  path: "/"

```

Deleting the original PV and re-creating it with the same name is discouraged. Attempting to manually change the status of a PV from **Released** to **Available** causes errors and potential data loss.



#### NOTE

A PV with retention policy of **Recycle** scrubs (`rm -rf`) the data and marks it as **Available** for claim. The **Recycle** retention policy is deprecated starting in OpenShift Container Platform 3.6 and should be avoided. Anyone using recycler should use dynamic provision and volume deletion instead.

#### 24.2.6. Automation

Clusters can be provisioned with persistent storage using NFS in the following ways:

- Enforce storage quotas using disk partitions.
- Enforce security by restricting volumes to the project that has a claim to them.
- Configure reclamation of discarded resources for each PV.

There are many ways that you can use scripts to automate the above tasks. You can use an [example Ansible playbook](#) to help you get started.

#### 24.2.7. Additional Configuration and Troubleshooting

Depending on what version of NFS is being used and how it is configured, there may be additional configuration steps needed for proper export and security mapping. The following are some that may apply:

NFSv4 mount incorrectly shows all files with ownership of <b>nobody:nobody</b>	<ul style="list-style-type: none"> <li>• Could be attributed to the ID mapping settings (<code>/etc/idmapd.conf</code>) on your NFS</li> <li>• See <a href="#">this Red Hat Solution</a>.</li> </ul>
Disabling ID mapping on NFSv4	<ul style="list-style-type: none"> <li>• On both the NFS client and server, run: <pre># echo 'Y' &gt; /sys/module/nfsd/parameters/nfs4_disable_idmapping</pre> </li> </ul>

### 24.3. PERSISTENT STORAGE USING RED HAT GLUSTER STORAGE


## 24.3.1. Overview

Red Hat Gluster Storage can be configured to provide persistent storage and dynamic provisioning for OpenShift Container Platform. It can be used both containerized within OpenShift Container Platform (**Container-Native Storage**) and non-containerized on its own nodes (**Container-Ready Storage**).

### 24.3.1.1. Container-Native Storage

With Container-Native Storage, Red Hat Gluster Storage runs containerized directly on OpenShift Container Platform nodes. This allows for compute and storage instances to be scheduled and run from the same set of hardware.

**Figure 24.1. Architecture - Container-Native Storage**



OPENSIFT\_412816\_0716

Container-Native Storage is available starting with Red Hat Gluster Storage 3.1 update 3. See [Container-Native Storage for OpenShift Container Platform](#) for additional documentation.


### 24.3.1.2. Container-Ready Storage

With Container-Ready Storage, Red Hat Gluster Storage runs on its own dedicated nodes and is managed by an instance of [heketi](#), the GlusterFS volume management REST service. This heketi service can run either standalone or containerized. Containerization allows for an easy mechanism to provide high-availability to the service. This documentation will focus on the configuration where heketi is containerized.

### 24.3.1.3. Standalone Red Hat Gluster Storage

If you have a standalone Red Hat Gluster Storage cluster available in your environment, you can make use of volumes on that cluster using OpenShift Container Platform's GlusterFS volume plug-in. This solution is a conventional deployment where applications run on dedicated compute nodes, an OpenShift Container Platform cluster, and storage is provided from its own dedicated nodes.

**Figure 24.2. Architecture - Standalone Red Hat Gluster Storage Cluster Using OpenShift Container Platform's GlusterFS Volume Plug-in**



OPENSFIFT\_412816\_0716

See the [Red Hat Gluster Storage Installation Guide](#) and the [Red Hat Gluster Storage Administration Guide](#) for more on Red Hat Gluster Storage.



### IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

#### 24.3.1.4. GlusterFS Volumes

GlusterFS volumes present a POSIX-compliant filesystem and are comprised of one or more "bricks" across one or more nodes in their cluster. A brick is just a directory on a given storage node and is typically the mount point for a block storage device. GlusterFS handles distribution and replication of files across a given volume's bricks per that volume's configuration.

It is recommended to use heketi for most common volume management operations such as create, delete, and resize. OpenShift Container Platform expects heketi to be present when using the GlusterFS provisioner. heketi by default will create volumes that are three-ray replica, that is volumes where each file has three copies across three different nodes. As such it is recommended that any Red Hat Gluster Storage clusters which will be used by heketi have at least three nodes available.

There are many features available for GlusterFS volumes, but they are beyond the scope of this documentation.

#### 24.3.1.5. gluster-block Volumes

gluster-block volumes are volumes that can be mounted over iSCSI. This is done by creating a file on an existing GlusterFS volume and then presenting that file as a block device via an iSCSI target. Such GlusterFS volumes are called block-hosting volumes.

gluster-block volumes present a sort of trade-off. Being consumed as iSCSI targets, gluster-block volumes can only be mounted by one node/client at a time which is in contrast to GlusterFS volumes which can be mounted by multiple nodes/clients. Being files on the backend, however, allows for operations which are typically costly on GlusterFS volumes (e.g. metadata lookups) to be converted to ones which are typically much faster on GlusterFS volumes (e.g. reads and writes). This leads to potentially substantial performance improvements for certain workloads.




## IMPORTANT

At this time, it is recommended to only use gluster-block volumes for OpenShift Logging and OpenShift Metrics storage.

### 24.3.1.6. Gluster S3 Storage

The Gluster S3 service allows user applications to access GlusterFS storage via an S3 interface. The service binds to two GlusterFS volumes, one for object data and one for object metadata, and translates incoming S3 REST requests into filesystem operations on the volumes. It is recommended to run the service as a pod inside OpenShift Container Platform.



## IMPORTANT

At this time, use and installation of the Gluster S3 service is in tech preview.

### 24.3.2. Considerations

This section covers a few topics that should be taken into consideration when using Red Hat Gluster Storage with OpenShift Container Platform.

#### 24.3.2.1. Software Prerequisites

To access GlusterFS volumes, the `mount.glusterfs` command must be available on all schedulable nodes. For RPM-based systems, the `glusterfs-fuse` package must be installed:

```
# yum install glusterfs-fuse
```

This package comes installed on every RHEL system. However, it is recommended to update to the latest available version from Red Hat Gluster Storage. To do this, the following RPM repository must be enabled:

```
# subscription-manager repos --enable=rh-gluster-3-client-for-rhel-7-server-rpms
```

If `glusterfs-fuse` is already installed on the nodes, ensure that the latest version is installed:

```
# yum update glusterfs-fuse
```

#### 24.3.2.2. Hardware Requirements

Any nodes used in a Container-Native Storage or Container-Ready Storage cluster are considered storage nodes. Storage nodes can be grouped into distinct cluster groups, though a single node can not be in multiple groups. For each group of storage nodes:

- A minimum of three storage nodes per group is required.
- Each storage node must have a minimum of 8 GB of RAM. This is to allow running the Red Hat Gluster Storage pods, as well as other applications and the underlying operating system.
  - Each GlusterFS volume also consumes memory on every storage node in its storage cluster, which is about 30 MB. The total amount of RAM should be determined based on how many concurrent volumes are desired or anticipated.
- Each storage node must have at least one raw block device with no present data or metadata. These block devices will be used in their entirety for GlusterFS storage. Make sure the following are not present:
  - Partition tables (GPT or MSDOS)
  - Filesystems or residual filesystem signatures
  - LVM2 signatures of former Volume Groups and Logical Volumes
  - LVM2 metadata of LVM2 physical volumes

If in doubt, `wipefs -a <device>` should clear any of the above.



## IMPORTANT

It is recommended to plan for two clusters: one dedicated to storage for infrastructure applications (such as an OpenShift Container Registry) and one dedicated to storage for general applications. This would require a total of six storage nodes. This recommendation is made to avoid potential impacts on performance in I/O and volume creation.

### 24.3.2.3. Storage Sizing

Every GlusterFS cluster must be sized based on the needs of the anticipated applications that will use its storage. For example, there are sizing guides available for both [OpenShift Logging](#) and [OpenShift Metrics](#).

Some additional things to consider are:

- For each Container-Native Storage or Container-Ready Storage cluster, the default behavior is to create GlusterFS volumes with three-way replication. As such, the total storage to plan for should be the desired capacity times three.
  - As an example, each heketi instance creates a **heketidbstorage** volume that is 2 GB in size, requiring a total of 6 GB of raw storage across three nodes in the storage cluster. This capacity is always required and should be taken into consideration for sizing calculations.
  - Applications like an integrated OpenShift Container Registry share a single GlusterFS volume across multiple instances of the application.
- gluster-block volumes require the presence of a GlusterFS block-hosting volume with enough capacity to hold the full size of any given block volume's capacity.

- By default, if no such block-hosting volume exists, one will be automatically created at a set size. The default for this size is 100 GB. If there is not enough space in the cluster to create the new block-hosting volume, the creation of the block volume will fail. Both the auto-create behavior and the auto-created volume size are configurable.
- Applications with multiple instances that use gluster-block volumes, such as OpenShift Logging and OpenShift Metrics, will use one volume per instance.
- The Gluster S3 service binds to two GlusterFS volumes. In a default installation via the [Advanced Installer](#), these volumes are 1 GB each, consuming a total of 6 GB of raw storage.

#### 24.3.2.4. Volume Operation Behaviors

Volume operations, such as create and delete, can be impacted by a variety of environmental circumstances and can in turn affect applications as well.

- If the application pod requests a dynamically provisioned GlusterFS persistent volume claim (PVC), then extra time might have to be considered for the volume to be created and bound to the corresponding PVC. This effects the startup time for an application pod.



##### NOTE

Creation time of GlusterFS volumes scales linearly depending on the number of volumes. As an example, given 100 volumes in a cluster using recommended hardware specifications, each volume took approximately 6 seconds to be created, allocated, and bound to a pod.

- When a PVC is deleted, that action will trigger the deletion of the underlying GlusterFS volume. While PVCs will disappear immediately from the `oc get pvc` output, this does not mean the volume has been fully deleted. A GlusterFS volume can only be considered deleted when it does not show up in the command-line outputs for `heketi-cli volume list` and `gluster volume list`.



##### NOTE

The time to delete the GlusterFS volume and recycle its storage depends on and scales linearly with the number of active GlusterFS volumes. While pending volume deletes do not affect running applications, storage administrators should be aware of and be able to estimate how long they will take, especially when tuning resource consumption at scale.

#### 24.3.2.5. Volume Security

This section covers Red Hat Gluster Storage volume security, including Portable Operating System Interface [for Unix] (POSIX) permissions and SELinux considerations. Understanding the basics of [Volume Security](#), POSIX permissions, and SELinux is presumed.

##### 24.3.2.5.1. POSIX Permissions

Red Hat Gluster Storage volumes present POSIX-compliant file systems. As such, access permissions can be managed using standard command-line tools such as `chmod` and `chown`.

For Container-Native Storage and Container-Ready Storage, it is also possible to specify a group ID that will own the root of the volume at volume creation time. For static provisioning, this is specified as part of the **heketi-cli** volume creation command:

```
$ heketi-cli volume create --size=100 --gid=10001000
```



### WARNING

The PersistentVolume that will be associated with this volume must be annotated with the group ID so that pods consuming the PersistentVolume can have access to the file system. This annotation takes the form of:

`pv.beta.kubernetes.io/gid: "<GID>" ---`

For dynamic provisioning, the provisioner automatically generates and applies a group ID. It is possible to control the range from which this group ID is selected using the **gidMin** and **gidMax** StorageClass parameters (see [Dynamic Provisioning](#)). The provisioner also takes care of annotating the generated PersistentVolume with the group ID.

#### 24.3.2.5.2. SELinux

By default, SELinux does not allow writing from a pod to a remote Red Hat Gluster Storage server. To enable writing to Red Hat Gluster Storage volumes with SELinux on, run the following on each node running GlusterFS:

```
$ sudo setsebool -P virt_sandbox_use_fusefs on ①
$ sudo setsebool -P virt_use_fusefs on
```

① The **-P** option makes the boolean persistent between reboots.



### NOTE

The **virt\_sandbox\_use\_fusefs** boolean is defined by the **docker-selinux** package. If you get an error saying it is not defined, ensure that this package is installed.



### NOTE

If you use Atomic Host, the SELinux booleans are cleared when you upgrade Atomic Host. When you upgrade Atomic Host, you must set these boolean values again.

#### 24.3.3. Support Requirements

The following requirements must be met to create a supported integration of Red Hat Gluster Storage and OpenShift Container Platform.

For Container-Ready Storage or standalone Red Hat Gluster Storage:

- Minimum version: Red Hat Gluster Storage 3.1.3

- All Red Hat Gluster Storage nodes must have valid subscriptions to Red Hat Network channels and Subscription Manager repositories.
- Red Hat Gluster Storage nodes must adhere to the requirements specified in the [Planning Red Hat Gluster Storage Installation](#).
- Red Hat Gluster Storage nodes must be completely up to date with the latest patches and upgrades. Refer to the [Red Hat Gluster Storage Installation Guide](#) to upgrade to the latest version.
- A fully-qualified domain name (FQDN) must be set for each Red Hat Gluster Storage node. Ensure that correct DNS records exist, and that the FQDN is resolvable via both forward and reverse DNS lookup.

#### 24.3.4. Installation

For standalone Red Hat Gluster Storage, there is no component installation required to use it with OpenShift Container Platform. OpenShift Container Platform comes with a built-in GlusterFS volume driver, allowing it to make use of existing volumes on existing clusters. See [provisioning](#) for more on how to make use of existing volumes.

For Container-Native Storage and Container-Ready Storage, it is recommended to use the [Advanced Installer](#) to install the required components.

##### 24.3.4.1. Container-Ready Storage: Installing Red Hat Gluster Storage Nodes

For Container-Ready Storage, each Red Hat Gluster Storage node must have the appropriate system configurations (e.g. firewall ports, kernel modules) and the Red Hat Gluster Storage services must be running. The services should not be further configured, and should not have formed a Trusted Storage Pool.

The installation of Red Hat Gluster Storage nodes is beyond the scope of this documentation. For more information, see [Setting Up Container-Ready Storage](#).

##### 24.3.4.2. Using the Advanced Installer

The [Advanced Installer](#) can be used to install one or both of two GlusterFS node groups:

- **glusterfs**: A general storage cluster for use by user applications.
- **glusterfs-registry**: A dedicated storage cluster for use by infrastructure applications such as an integrated OpenShift Container Registry.

It is recommended to deploy both groups to avoid potential impacts on performance in I/O and volume creation. Both of these are defined in the inventory hosts file.

The definition of the clusters is done by including the relevant names in the **[OSEv3:children]** group, creating similarly named groups, and then populating the groups with the node information. The clusters can then be configured through a variety of variables in the **[OSEv3:vars]** group. **glusterfs** variables begin with **openshift\_storage\_glusterfs\_** and **glusterfs-registry** variables begin with **openshift\_storage\_glusterfs\_registry\_**. A few other variables, such as **openshift\_hosted\_registry\_storage\_kind**, interact with the GlusterFS clusters.

It is recommended to specify version tags for all containerized components. This is primarily to prevent components, particularly the Red Hat Gluster Storage pods, from upgrading after an outage which may lead to a cluster of widely disparate software versions. The relevant variables are:

- `openshift_storage_glusterfs_version`
- `openshift_storage_glusterfs_block_version`
- `openshift_storage_glusterfs_s3_version`
- `openshift_storage_glusterfs_heketi_version`
- `openshift_storage_glusterfs_registry_version`
- `openshift_storage_glusterfs_registry_block_version`
- `openshift_storage_glusterfs_registry_s3_version`
- `openshift_storage_glusterfs_registry_heketi_version`

For a complete list of variables, see the [GlusterFS role README](#) on GitHub.

Once the variables are configured, there are several playbooks available depending on the circumstances of the installation:

- The main playbook of the Advanced Installer can be used to deploy the GlusterFS clusters in tandem with an initial installation of OpenShift Container Platform.
  - This includes deploying an integrated OpenShift Container Registry that uses GlusterFS storage.
  - This does not include OpenShift Logging or OpenShift Metrics, as that is currently still a separate step. See [Container-Native Storage for OpenShift Logging and Metrics](#) for more information.
- `playbooks/openshift-glusterfs/config.yml` can be used to deploy the clusters onto an existing OpenShift Container Platform installation.
- `playbooks/openshift-glusterfs/registry.yml` can be used to deploy the clusters onto an existing OpenShift Container Platform installation. In addition, this will deploy an integrated OpenShift Container Registry which uses GlusterFS storage.



### IMPORTANT

There must not be a pre-existing registry in the OpenShift Container Platform cluster.

- `playbooks/openshift-glusterfs/uninstall.yml` can be used to remove existing clusters matching the configuration in the inventory hosts file. This is useful for cleaning up the OpenShift Container Platform environment in the case of a failed deployment due to configuration errors.



### NOTE

The GlusterFS playbooks are not guaranteed to be idempotent.

**NOTE**

Running the playbooks more than once for a given installation is currently not supported without deleting the entire GlusterFS installation (including disk data) and starting over.

**24.3.4.2.1. Example: Basic Container-Native Storage Installation**

1. In your inventory file, add **glusterfs** in the **[OSEv3:children]** section to enable the **[glusterfs]** group:

```
[OSEv3:children]
masters
nodes
glusterfs
```

2. Add a **[glusterfs]** section with entries for each storage node that will host the GlusterFS storage. For each node, set **glusterfs\_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_devices='[ "</path/to/device1/>", "
</path/to/device2>, ... ]'
```

For example:

```
[glusterfs]
node11.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node12.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node13.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

3. Add the hosts listed under **[glusterfs]** to the **[nodes]** group:

```
[nodes]
...
node11.example.com openshift_schedulable=True
node12.example.com openshift_schedulable=True
node13.example.com openshift_schedulable=True
```

**24.3.4.2.2. Example: Basic Container-Ready Storage Installation**

1. In your inventory file, add **glusterfs** in the **[OSEv3:children]** section to enable the **[glusterfs]** group:

```
[OSEv3:children]
masters
nodes
glusterfs
```

2. Include the following variables in the **[OSEv3:vars]** section, adjusting them as needed for your configuration:

```
[OSEv3:vars]
...
openshift_storage_glusterfs_is_native=false
openshift_storage_glusterfs_storageclass=true
openshift_storage_glusterfs_heketi_is_native=true
openshift_storage_glusterfs_heketi_executor=ssh
openshift_storage_glusterfs_heketi_ssh_port=22
openshift_storage_glusterfs_heketi_ssh_user=root
openshift_storage_glusterfs_heketi_ssh_sudo=false
openshift_storage_glusterfs_heketi_ssh_keyfile="/root/.ssh/id_rsa"
```

- Add a **[glusterfs]** section with entries for each storage node that will host the GlusterFS storage. For each node, set **glusterfs\_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Also, set **glusterfs\_ip** to the IP address of the node. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_ip=<ip_address> glusterfs_devices='[ "</path/to/device1/>", "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs]
gluster1.example.com glusterfs_ip=192.168.10.11 glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
gluster2.example.com glusterfs_ip=192.168.10.12 glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
gluster3.example.com glusterfs_ip=192.168.10.13 glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

#### 24.3.4.2.3. Example: Container-Native Storage with an Integrated OpenShift Container Registry

- In your inventory file, set the following variable under **[OSEv3:vars]**:

```
[OSEv3:vars]
...
openshift_hosted_registry_storage_kind=glusterfs
```

- Add **glusterfs\_registry** in the **[OSEv3:children]** section to enable the **[glusterfs\_registry]** group:

```
[OSEv3:children]
masters
nodes
glusterfs_registry
```

- Add a **[glusterfs\_registry]** section with entries for each storage node that will host the GlusterFS storage. For each node, set **glusterfs\_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_devices='[ "</path/to/device1/>", "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs_registry]
node11.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node12.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node13.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

- Add the hosts listed under **[glusterfs\_registry]** to the **[nodes]** group:

```
[nodes]
...
node11.example.com openshift_schedulable=True
node12.example.com openshift_schedulable=True
node13.example.com openshift_schedulable=True
```

#### 24.3.4.2.4. Example: Container-Native Storage for OpenShift Logging and Metrics

- In your inventory file, set the following variables under **[OSEv3:vars]**:

```
[OSEv3:vars]
...
openshift_metrics_hawkular_nodeselector={"role":"infra"} ①
openshift_metrics_cassandra_nodeselector={"role":"infra"} ②
openshift_metrics_heapster_nodeselector={"role":"infra"} ③
openshift_metrics_storage_kind=dynamic
openshift_metrics_cassandra_pvc_storage_class_name="glusterfs-
registry-block" ④

openshift_logging_es_nodeselector={"role":"infra"} ⑤
openshift_logging_kibana_nodeselector={"role":"infra"} ⑥
openshift_logging_curator_nodeselector={"role":"infra"} ⑦
openshift_logging_storage_kind=dynamic
openshift_logging_es_pvc_size=10Gi ⑧
openshift_logging_es_pvc_storage_class_name="glusterfs-registry-
block" ⑨

openshift_storage_glusterfs_registry_block_deploy=true
openshift_storage_glusterfs_registry_block_host_vol_size=50
openshift_storage_glusterfs_registry_block_storageclass=true
openshift_storage_glusterfs_registry_block_storageclass_default=true

openshift_storageclass_default=false
```

**1 2 3 5 6 7** It is recommended to run the integrated OpenShift Container Registry, Logging, and Metrics on nodes dedicated to "infrastructure" applications, that is applications deployed by administrators to provide services for the OpenShift Container Platform cluster.

**4 9**

Specify the StorageClass to be used for Logging and Metrics. This name is generated from the name of the target GlusterFS cluster (e.g., `glusterfs-<name>-block`). In this

- 8** OpenShift Logging requires that a PVC size be specified. The supplied value is only an example, not a recommendation.



#### NOTE

See the [GlusterFS role README](#) for details on these and other variables.

2. Add `glusterfs_registry` in the `[OSEv3:children]` section to enable the `[glusterfs_registry]` group:

```
[OSEv3:children]
masters
nodes
glusterfs_registry
```

3. Add a `[glusterfs_registry]` section with entries for each storage node that will host the GlusterFS storage. For each node, set `glusterfs_devices` to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_devices='[ "</path/to/device1/>", "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs_registry]
node11.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node12.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node13.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

4. Add the hosts listed under `[glusterfs_registry]` to the `[nodes]` group:

```
[nodes]
...
node11.example.com openshift_schedulable=True
node12.example.com openshift_schedulable=True
node13.example.com openshift_schedulable=True
```

5. Run the Advanced Installer. This can be either as part of an initial OpenShift Container Platform installation:

```
ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/prerequisites.yml

ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/deploy_cluster.yml
```

or brownfield:

```
ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/openshift-
glusterfs/config.yml
```

#### 24.3.4.2.5. Example: Container-Native Storage for Applications, Registry, Logging, and Metrics

- 1 In your inventory file, set the following variables under [OSEv3:vars]:

```
[OSEv3:vars]
...
openshift_registry_selector="role=infra" ①
openshift_hosted_registry_storage_kind=glusterfs

openshift_metrics_hawkular_nodeselector={"role":"infra"} ②
openshift_metrics_cassandra_nodeselector={"role":"infra"} ③
openshift_metrics_heapster_nodeselector={"role":"infra"} ④
openshift_metrics_storage_kind=dynamic
openshift_metrics_cassandra_pvc_storage_class_name="glusterfs-
registry-block" ⑤

openshift_logging_es_nodeselector={"role":"infra"} ⑥
openshift_logging_kibana_nodeselector={"role":"infra"} ⑦
openshift_logging_curator_nodeselector={"role":"infra"} ⑧
openshift_logging_storage_kind=dynamic
openshift_logging_es_pvc_size=10Gi ⑨
openshift_logging_es_pvc_storage_class_name="glusterfs-registry-
block" ⑩

openshift_storage_glusterfs_block_deploy=false

openshift_storage_glusterfs_registry_block_deploy=true
openshift_storage_glusterfs_registry_block_storageclass=true
openshift_storage_glusterfs_registry_block_storageclass_default=fals
e
```

**1 2 3 4 6 7 8** Running the integrated OpenShift Container Registry, Logging, and Metrics on infrastructure nodes is recommended. Infrastructure node are nodes dedicated to running applications deployed by administrators to provide services for the OpenShift Container Platform cluster.

**5 10** Specify the StorageClass to be used for Logging and Metrics. This name is generated from the name of the target GlusterFS cluster, for example **glusterfs-<name>-block**. In this example, <name> defaults to **registry**.

**9** Specifying a PVC size is required for OpenShift Logging. The supplied value is only an example, not a recommendation.

- 2 Add **glusterfs** and **glusterfs\_registry** in the [OSEv3:children] section to enable the [**glusterfs**] and [**glusterfs\_registry**] groups:

```
[OSEv3:children]
...

```

```
glusterfs
glusterfs_registry
```

- Add **[glusterfs]** and **[glusterfs\_registry]** sections with entries for each storage node that will host the GlusterFS storage. For each node, set **glusterfs\_devices** to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_devices='[ "</path/to/device1/>", "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs]
node11.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node12.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node13.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'

[glusterfs_registry]
node14.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node15.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
node16.example.com glusterfs_devices='[ "/dev/xvdc", "/dev/xvdd" ]'
```

- Add the hosts listed under **[glusterfs]** and **[glusterfs\_registry]** to the **[nodes]** group:

```
[nodes]
...
node11.example.com openshift_schedulable=True
openshift_node_labels="{'role': 'app'}" ①
node12.example.com openshift_schedulable=True
openshift_node_labels="{'role': 'app'}" ②
node13.example.com openshift_schedulable=True
openshift_node_labels="{'role': 'app'}" ③
node14.example.com openshift_schedulable=True
openshift_node_labels="{'role': 'infra'}" ④
node15.example.com openshift_schedulable=True
openshift_node_labels="{'role': 'infra'}" ⑤
node16.example.com openshift_schedulable=True
openshift_node_labels="{'role': 'infra'}" ⑥
```

**1 2 3 4 5 6** The nodes are marked to denote whether they will allow general applications or infrastructure applications to be scheduled on them. It is up to the administrator to configure how applications will be constrained.

- Run the Advanced Installer.

- For an initial OpenShift Container Platform installation:

```
ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/prerequisites.yml
```

```
ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/deploy_cluster.yml
```

- For a standalone installation onto an existing OpenShift Container Platform cluster:

```
ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/openshift-
glusterfs/config.yml
```

#### 24.3.4.2.6. Example: Container-Ready Storage for Applications, Registry, Logging, and Metrics

- In your inventory file, set the following variables under [OSEv3:vars]:

```
[OSEv3:vars]
...
openshift_registry_selector="role=infra" ①
openshift_hosted_registry_storage_kind=glusterfs

openshift_metrics_hawkular_nodeselector={"role":"infra"} ②
openshift_metrics_cassandra_nodeselector={"role":"infra"} ③
openshift_metrics_heapster_nodeselector={"role":"infra"} ④
openshift_metrics_storage_kind=dynamic
openshift_metrics_cassandra_pvc_storage_class_name="glusterfs-
registry-block" ⑤

openshift_logging_es_nodeselector={"role":"infra"} ⑥
openshift_logging_kibana_nodeselector={"role":"infra"} ⑦
openshift_logging_curator_nodeselector={"role":"infra"} ⑧
openshift_logging_storage_kind=dynamic
openshift_logging_es_pvc_size=10Gi ⑨
openshift_logging_es_pvc_storage_class_name="glusterfs-registry-
block" ⑩

openshift_storage_glusterfs_is_native=false
openshift_storage_glusterfs_block_deploy=false
openshift_storage_glusterfs_storageclass=true
openshift_storage_glusterfs_heketi_is_native=true
openshift_storage_glusterfs_heketi_executor=ssh
openshift_storage_glusterfs_heketi_ssh_port=22
openshift_storage_glusterfs_heketi_ssh_user=root
openshift_storage_glusterfs_heketi_ssh_sudo=false
openshift_storage_glusterfs_heketi_ssh_keyfile="/root/.ssh/id_rsa"

openshift_storage_glusterfs_is_native=false
openshift_storage_glusterfs_registry_block_deploy=true
openshift_storage_glusterfs_registry_block_storageclass=true
openshift_storage_glusterfs_registry_block_storageclass_default=true
openshift_storage_glusterfs_registry_heketi_is_native=true
openshift_storage_glusterfs_registry_heketi_executor=ssh
openshift_storage_glusterfs_registry_heketi_ssh_port=22
openshift_storage_glusterfs_registry_heketi_ssh_user=root
openshift_storage_glusterfs_registry_heketi_ssh_sudo=false
openshift_storage_glusterfs_registry_heketi_ssh_keyfile="/root/.ssh/
id_rsa"
```

**1 2 3 4 6 7 8** It is recommended to run the integrated OpenShift Container Registry on nodes dedicated to "infrastructure" applications, that is applications deployed by administrators to provide services for the OpenShift Container Platform cluster. It is up to the administrator to select and label nodes for infrastructure applications.

**5 10** Specify the StorageClass to be used for Logging and Metrics. This name is generated from the name of the target GlusterFS cluster (e.g., `glusterfs-<name>-block`). In this example, this defaults to `registry`.

**9** OpenShift Logging requires that a PVC size be specified. The supplied value is only an example, not a recommendation.

2. Add `glusterfs` and `glusterfs_registry` in the `[OSEv3:children]` section to enable the `[glusterfs]` and `[glusterfs_registry]` groups:

```
[OSEv3:children]
...
glusterfs
glusterfs_registry
```

3. Add `[glusterfs]` and `[glusterfs_registry]` sections with entries for each storage node that will host the GlusterFS storage. For each node, set `glusterfs_devices` to a list of raw block devices that will be completely managed as part of a GlusterFS cluster. There must be at least one device listed. Each device must be bare, with no partitions or LVM PVs. Also, set `glusterfs_ip` to the IP address of the node. Specifying the variable takes the form:

```
<hostname_or_ip> glusterfs_ip=<ip_address> glusterfs_devices='[ "</path/to/device1/>", "</path/to/device2>", ... ]'
```

For example:

```
[glusterfs]
gluster1.example.com glusterfs_ip=192.168.10.11 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
gluster2.example.com glusterfs_ip=192.168.10.12 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
gluster3.example.com glusterfs_ip=192.168.10.13 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'

[glusterfs_registry]
gluster4.example.com glusterfs_ip=192.168.10.14 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
gluster5.example.com glusterfs_ip=192.168.10.15 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
gluster6.example.com glusterfs_ip=192.168.10.16 glusterfs_devices='[
"/dev/xvdc", "/dev/xvdd" ]'
```

4. Run the Advanced Installer. This can be either as part of an initial OpenShift Container Platform installation:

```
ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/prerequisites.yml
```

```
ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/deploy_cluster.yml
```

or as a standalone operation onto an existing OpenShift Container Platform cluster:

```
ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/openshift-
glusterfs/config.yml
```

### 24.3.5. Uninstall Container-Native Storage

For Container-Native Storage, an OpenShift Container Platform install comes with a playbook to uninstall all resources and artifacts from the cluster. To use the playbook, provide the original inventory file that was used to install the target instance of Container-Native Storage and run the following playbook:

```
# ansible-playbook -i <path_to_inventory_file>
/usr/share/ansible/openshift-ansible/playbooks/openshift-
glusterfs/uninstall.yml
```

In addition, the playbook supports the use of a variable called **openshift\_storage\_glusterfs\_wipe** which, when enabled, destroys any data on the block devices that were used for Red Hat Gluster Storage backend storage. To use the **openshift\_storage\_glusterfs\_wipe** variable:

```
# ansible-playbook -i <path_to_inventory_file> -e
"openshift_storage_glusterfs_wipe=true"
/usr/share/ansible/openshift-ansible/playbooks/openshift-
glusterfs/uninstall.yml
```



#### WARNING

This procedure destroys data. Proceed with caution.

### 24.3.6. Provisioning

GlusterFS volumes can be provisioned either statically or dynamically. Static provisioning is available with all configurations. Only Container-Native Storage and Container-Ready Storage support dynamic provisioning.

#### 24.3.6.1. Static Provisioning

1. To enable static provisioning, first create a GlusterFS volume. See the [Red Hat Gluster Storage Administration Guide](#) for information on how to do this using the **gluster** command-line interface or the [heketi project site](#) for information on how to do this using **heketi-cli**. For this example, the volume will be named **myVol1**.
2. Define the following Service and Endpoints in **gluster-endpoints.yaml**:

```

---
apiVersion: v1
kind: Service
metadata:
  name: glusterfs-cluster ①
spec:
  ports:
    - port: 1
---
apiVersion: v1
kind: Endpoints
metadata:
  name: glusterfs-cluster ②
subsets:
  - addresses:
      - ip: 192.168.122.221 ③
    ports:
      - port: 1 ④
  - addresses:
      - ip: 192.168.122.222 ⑤
    ports:
      - port: 1 ⑥
  - addresses:
      - ip: 192.168.122.223 ⑦
    ports:
      - port: 1 ⑧

```

① ② These names must match.

③ ⑤ ⑦ The `ip` values must be the actual IP addresses of a Red Hat Gluster Storage server, not hostnames.

④ ⑥ ⑧ The port number is ignored.

3. From the OpenShift Container Platform master host, create the Service and Endpoints:


```
$ oc create -f gluster-endpoints.yaml
service "glusterfs-cluster" created
endpoints "glusterfs-cluster" created
```

4. Verify that the Service and Endpoints were created:

```
$ oc get services
NAME           CLUSTER_IP        EXTERNAL_IP   PORT(S)
SELECTOR      AGE
glusterfs-cluster  172.30.205.34 <none>       1/TCP
<none>        44s

$ oc get endpoints
NAME           ENDPOINTS
AGE
docker-registry  10.1.0.3:5000
4h
```

```
glusterfs-cluster
192.168.122.221:1,192.168.122.222:1,192.168.122.223:1    11s
kubernetes          172.16.35.3:8443
4d
```

**NOTE**

Endpoints are unique per project. Each project accessing the GlusterFS volume needs its own Endpoints.

- In order to access the volume, the container must run with either a user ID (UID) or group ID (GID) that has access to the file system on the volume. This information can be discovered in the following manner:

```
$ mkdir -p /mnt/glusterfs/myVol1
$ mount -t glusterfs 192.168.122.221:/myVol1 /mnt/glusterfs/myVol1
$ ls -lnZ /mnt/glusterfs/
drwxrwx---. 592 590 system_u:object_r:fusefs_t:s0      myVol1 1 2
```

- 1** The UID is 592.
- 2** The GID is 590.

- Define the following PersistentVolume (PV) in **gluster-pv.yaml**:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-default-volume 1
  annotations:
    pv.beta.kubernetes.io/gid: "590" 2
spec:
  capacity:
    storage: 2Gi 3
  accessModes: 4
    - ReadWriteMany
  glusterfs:
    endpoints: glusterfs-cluster 5
    path: myVol1 6
    readOnly: false
    persistentVolumeReclaimPolicy: Retain
```

- 1** The name of the volume.
- 2** The GID on the root of the GlusterFS volume.
- 3** The amount of storage allocated to this volume.
- 4** **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control.

- 5 The Endpoints resource previously created.
- 6 The GlusterFS volume that will be accessed.

7. From the OpenShift Container Platform master host, create the PV:

```
$ oc create -f gluster-pv.yaml
```

8. Verify that the PV was created:

```
$ oc get pv
NAME           LABELS      CAPACITY      ACCESSMODES
STATUS   CLAIM   REASON   AGE
gluster-default-volume <none>    2147483648   RWX
Available                               2s
```

9. Create a PersistentVolumeClaim (PVC) that will bind to the new PV in **gluster-claim.yaml**:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim ①
spec:
  accessModes:
  - ReadWriteMany ②
  resources:
    requests:
      storage: 1Gi ③
```

- 1 The claim name is referenced by the pod under its **volumes** section.
- 2 Must match the **accessModes** of the PV.
- 3 This claim will look for PVs offering **1Gi** or greater capacity.

10. From the OpenShift Container Platform master host, create the PVC:

```
$ oc create -f gluster-claim.yaml
```

11. Verify that the PV and PVC are bound:

```
$ oc get pv
NAME           LABELS      CAPACITY      ACCESSMODES      STATUS      CLAIM
REASON   AGE
gluster-pv    <none>    1Gi          RWX            Available
gluster-claim                         37s

$ oc get pvc
NAME           LABELS      STATUS      VOLUME      CAPACITY
ACCESSMODES   AGE
gluster-claim  <none>    Bound      gluster-pv  1Gi          RWX
24s
```

**NOTE**

PVCs are unique per project. Each project accessing the GlusterFS volume needs its own PVC. PVs are not bound to a single project, so PVCs across multiple projects may refer to the same PV.

#### 24.3.6.2. Dynamic Provisioning

- To enable dynamic provisioning, first create a **StorageClass** object definition. The definition below is based on the minimum requirements needed for this example to work with OpenShift Container Platform. See [Dynamic Provisioning and Creating Storage Classes](#) for additional parameters and specification definitions.

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: glusterfs
provisioner: kubernetes.io/glusterfs
parameters:
  resturl: "http://10.42.0.0:8080" 1
  restauthenabled: "false" 2
```

- 1** The heketi server URL.
- 2** Since authentication is not turned on in this example, set to **false**.

- From the OpenShift Container Platform master host, create the StorageClass:

```
# oc create -f gluster-storage-class.yaml
storageclass "glusterfs" created
```

- Create a PVC using the newly-created StorageClass. For example:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster1
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 30Gi
  storageClassName: glusterfs
```

- From the OpenShift Container Platform master host, create the PVC:

```
# oc create -f glusterfs-dyn-pvc.yaml
persistentvolumeclaim "gluster1" created
```

- View the PVC to see that the volume was dynamically created and bound to the PVC:

```
# oc get pvc
```

NAME	STATUS	VOLUME	CAPACITY	ACCESSMODES	STORAGECLASS	AGE
gluster1	Bound	pvc-78852230-d8e2-11e6-a3fa-0800279cf26f	30Gi	RwX	gluster-dyn	42s

## 24.4. PERSISTENT STORAGE USING OPENSTACK CINDER

### 24.4.1. Overview

You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [OpenStack Cinder](#). Some familiarity with Kubernetes and OpenStack is assumed.



#### IMPORTANT

Before you create persistent volumes (PVs) using Cinder, [configured OpenShift Container Platform for OpenStack](#).

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. You can [provision](#) OpenStack Cinder volumes dynamically.

Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [Persistent volume claims](#), however, are specific to a project or namespace and can be requested by users.



#### IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

### 24.4.2. Provisioning Cinder PVs

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring that OpenShift Container Platform is [configured for OpenStack](#), all that is required for Cinder is a Cinder volume ID and the [PersistentVolume API](#).

#### 24.4.2.1. Creating the Persistent Volume



#### NOTE

Cinder does not support the 'Recycle' reclaim policy.

You must define your PV in an object definition before creating it in OpenShift Container Platform:

1. Save your object definition to a file, for example **cinder-pv.yaml**:

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
spec:
  capacity:
    storage: "5Gi" 2
```

```

accessModes:
  - "ReadWriteOnce"
cinder: 3
  fsType: "ext3" 4
  volumeID: "f37a03aa-6212-4c62-a805-9ce139fab180" 5

```

- 1** The name of the volume that is used by [persistent volume claims](#) or pods.
- 2** The amount of storage allocated to this volume.
- 3** The volume type, in this case **cinder**.
- 4** File system type to mount.
- 5** The Cinder volume to use.



### IMPORTANT

Do not change the **fstype** parameter value after the volume is formatted and provisioned. Changing this value can result in data loss and pod failure.

## 2. Create the persistent volume:

```
# oc create -f cinder-pv.yaml

persistentvolume "pv0001" created
```

## 3. Verify that the persistent volume exists:

```
# oc get pv

NAME      LABELS      CAPACITY      ACCESSMODES      STATUS      CLAIM
REASON    AGE
pv0001    <none>     5Gi          RWO           Available
2s
```

Users can then [request storage using persistent volume claims](#), which can now utilize your new persistent volume.



### IMPORTANT

Persistent volume claims exist only in the user's namespace and can be referenced by a pod within that same namespace. Any attempt to access a persistent volume claim from a different namespace causes the pod to fail.

#### 24.4.2.2. Cinder PV format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted Cinder volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

#### 24.4.2.3. Cinder volume security

If you use Cinder PVs in your application, configure security for their deployment configurations.



#### NOTE

Review the [Volume Security](#) information before implementing Cinder volumes.

1. Create an [SCC](#) that uses the appropriate **fsGroup** strategy.
2. Create a service account and add it to the SCC:

```
[source, bash]
$ oc create serviceaccount <service_account>
$ oc adm policy add-scc-to-user <new_scc> -z <service_account> -n
<project>
```

3. In your application's deployment configuration, provide the service account name and **securityContext**:

```
apiVersion: v1
kind: ReplicationController
metadata:
  name: frontend-1
spec:
  replicas: 1 1
  selector: 2
    name: frontend
  template: 3
    metadata:
      labels: 4
        name: frontend 5
    spec:
      containers:
        - image: openshift/hello-openshift
          name: helloworld
          ports:
            - containerPort: 8080
              protocol: TCP
      restartPolicy: Always
      serviceAccountName: <service_account> 6
      securityContext:
        fsGroup: 7777 7
```

- 1** The number of copies of the pod to run.
- 2** The label selector of the pod to run.
- 3** A template for the pod the controller creates.

- 4 The labels on the pod must include labels from the label selector.
- 5 The maximum name length after expanding any parameters is 63 characters.
- 6 Specify the service account you created.
- 7 Specify an [fsGroup](#) for the pods.

## 24.5. PERSISTENT STORAGE USING CEPH RADOS BLOCK DEVICE (RBD)

### 24.5.1. Overview

OpenShift Container Platform clusters can be provisioned with [persistent storage](#) using Ceph RBD.

Persistent volumes (PVs) and [persistent volume claims \(PVCs\)](#) can share volumes across a single project. While the Ceph RBD-specific information contained in a PV definition could also be defined directly in a pod definition, doing so does not create the volume as a distinct cluster resource, making the volume more susceptible to conflicts.

This topic presumes some familiarity with OpenShift Container Platform and [Ceph RBD](#). See the [Persistent Storage](#) concept topic for details on the OpenShift Container Platform persistent volume (PV) framework in general.



#### NOTE

*Project* and *namespace* are used interchangeably throughout this document. See [Projects and Users](#) for details on the relationship.



#### IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

### 24.5.2. Provisioning

To provision Ceph volumes, the following are required:

- An existing storage device in your underlying infrastructure.
- The Ceph key to be used in an OpenShift Container Platform secret object.
- The Ceph image name.
- The file system type on top of the block storage (e.g., ext4).
- **ceph-common** installed on each schedulable OpenShift Container Platform node in your cluster:

```
# yum install ceph-common
```

#### 24.5.2.1. Creating the Ceph Secret

Define the authorization key in a secret configuration, which is then converted to base64 for use by OpenShift Container Platform.



### NOTE

In order to use Ceph storage to back a persistent volume, the secret must be created in the same project as the PVC and pod. The secret cannot simply be in the default project.

1. Run `ceph auth get-key` on a Ceph MON node to display the key value for the `client.admin` user:

```
apiVersion: v1
kind: Secret
metadata:
  name: ceph-secret
data:
  key: QVFBOFF2SlZheUJQRVJBQWgvS2cwT1laQUhPQno3akZwekxxdGc9PQ==
```

2. Save the secret definition to a file, for example `ceph-secret.yaml`, then create the secret:

```
$ oc create -f ceph-secret.yaml
```

3. Verify that the secret was created:

```
# oc get secret ceph-secret
NAME          TYPE      DATA   AGE
ceph-secret   Opaque    1      23d
```

#### 24.5.2.2. Creating the Persistent Volume



### NOTE

Ceph RBD does not support the 'Recycle' reclaim policy.

Developers request Ceph RBD storage by referencing either a PVC, or the Gluster volume plug-in directly in the `volumes` section of a pod specification. A PVC exists only in the user's namespace and can be referenced only by pods within that same namespace. Any attempt to access a PV from a different namespace causes the pod to fail.

1. Define the PV in an object definition before creating it in OpenShift Container Platform:

#### Example 24.3. Persistent Volume Object Definition Using Ceph RBD

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: ceph-pv ①
spec:
  capacity:
    storage: 2Gi ②
  accessModes:
    - ReadWriteOnce ③
  rbd: ④
```

```

monitors: ⑤
  - 192.168.122.133:6789
pool: rbd
image: ceph-image
user: admin
secretRef:
  name: ceph-secret ⑥
fsType: ext4 ⑦
readOnly: false
persistentVolumeReclaimPolicy: Retain

```

- ① The name of the PV that is referenced in pod definitions or displayed in various `oc volume` commands.
- ② The amount of storage allocated to this volume.
- ③ **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control. All block storage is defined to be single user (non-shared storage).
- ④ The volume type being used, in this case the **rbd** plug-in.
- ⑤ An array of Ceph monitor IP addresses and ports.
- ⑥ The Ceph secret used to create a secure connection from OpenShift Container Platform to the Ceph server.
- ⑦ The file system type mounted on the Ceph RBD block device.



## IMPORTANT

Changing the value of the **fstype** parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

2. Save your definition to a file, for example ***ceph-pv.yaml***, and create the PV:

```
# oc create -f ceph-pv.yaml
```

3. Verify that the persistent volume was created:

```

# oc get pv
NAME          LABELS      CAPACITY   ACCESSMODES
STATUS        CLAIM      REASON     AGE
ceph-pv       <none>    2147483648   RWO
Available                               2s

```

4. Create a PVC that will bind to the new PV:

### Example 24.4. PVC Object Definition

```

kind: PersistentVolumeClaim
apiVersion: v1
metadata:

```

```

name: ceph-claim
spec:
  accessModes: 1
    - ReadWriteOnce
  resources:
    requests:
      storage: 2Gi 2

```

- 1** The **accessModes** do not enforce access right, but instead act as labels to match a PV to a PVC.
- 2** This claim looks for PVs offering **2Gi** or greater capacity.

5. Save the definition to a file, for example **ceph-claim.yaml**, and create the PVC:

```
# oc create -f ceph-claim.yaml
```

### 24.5.3. Ceph Volume Security



#### NOTE

See the full [Volume Security](#) topic before implementing Ceph RBD volumes.

A significant difference between shared volumes (NFS and GlusterFS) and block volumes (Ceph RBD, iSCSI, and most cloud storage), is that the user and group IDs defined in the pod definition or container image are applied to the target physical storage. This is referred to as managing ownership of the block device. For example, if the Ceph RBD mount has its owner set to **123** and its group ID set to **567**, and if the pod defines its **runAsUser** set to **222** and its **fsGroup** to be **7777**, then the Ceph RBD physical mount's ownership will be changed to **222:7777**.



#### NOTE

Even if the user and group IDs are not defined in the pod specification, the resulting pod may have defaults defined for these IDs based on its matching SCC, or its project. See the full [Volume Security](#) topic which covers storage aspects of SCCs and defaults in greater detail.

A pod defines the group ownership of a Ceph RBD volume using the **fsGroup** stanza under the pod's **securityContext** definition:

```

spec:
  containers:
    - name:
      ...
  securityContext: 1
    fsGroup: 7777 2

```

- 1** The **securityContext** must be defined at the pod level, not under a specific container.
- 2** All containers in the pod will have the same fsGroup ID.

## 24.6. PERSISTENT STORAGE USING AWS ELASTIC BLOCK STORE

### 24.6.1. Overview

OpenShift Container Platform supports AWS Elastic Block Store volumes (EBS). You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [AWS EC2](#). Some familiarity with Kubernetes and AWS is assumed.



#### IMPORTANT

Before creating persistent volumes using AWS, OpenShift Container Platform must first be properly [configured for AWS ElasticBlockStore](#).

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. AWS Elastic Block Store volumes can be [provisioned dynamically](#). Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [Persistent volume claims](#), however, are specific to a project or namespace and can be requested by users.



#### IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

### 24.6.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring OpenShift is [configured for AWS Elastic Block Store](#), all that is required for OpenShift and AWS is an AWS EBS volume ID and the [PersistentVolume API](#).

#### 24.6.2.1. Creating the Persistent Volume



#### NOTE

AWS does not support the 'Recycle' reclaim policy.

You must define your persistent volume in an object definition before creating it in OpenShift Container Platform:

#### Example 24.5. Persistent Volume Object Definition Using AWS

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
spec:
  capacity:
    storage: "5Gi" 2
  accessModes:
    - "ReadWriteOnce"
```

```
awsElasticBlockStore: ③
  fsType: "ext4" ④
  volumeID: "vol-f37a03aa" ⑤
```

- ① The name of the volume. This will be how it is identified via [persistent volume claims](#) or from pods.
- ② The amount of storage allocated to this volume.
- ③ This defines the volume type being used, in this case the **awsElasticBlockStore** plug-in.
- ④ File system type to mount.
- ⑤ This is the AWS volume that will be used.



### IMPORTANT

Changing the value of the **fstype** parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

Save your definition to a file, for example **aws-pv.yaml**, and create the persistent volume:

```
# oc create -f aws-pv.yaml
persistentvolume "pv0001" created
```

Verify that the persistent volume was created:

# oc get pv	NAME	LABELS	CAPACITY	ACCESSMODES	STATUS	CLAIM	REASON
	AGE						
	pv0001	<none>	5Gi	RWO		Available	
	2s						

Users can then [request storage using persistent volume claims](#), which can now utilize your new persistent volume.



### IMPORTANT

Persistent volume claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume from a different namespace causes the pod to fail.

#### 24.6.2.2. Volume Format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted AWS volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

### 24.6.2.3. Maximum Number of EBS Volumes on a Node

By default, OpenShift Container Platform supports a maximum of 39 EBS volumes attached to one node. This limit is consistent with the [AWS Volume Limits](#).

OpenShift Container Platform can be configured to have a higher limit by setting the environment variable `KUBE_MAX_PD_VOLS`. However, AWS requires a particular naming scheme ([AWS Device Naming](#)) for attached devices, which only supports a maximum of 52 volumes. This limits the number of volumes that can be attached to a node via OpenShift Container Platform to 52.

## 24.7. PERSISTENT STORAGE USING GCE PERSISTENT DISK

### 24.7.1. Overview

OpenShift Container Platform supports GCE Persistent Disk volumes (gcePD). You can provision your OpenShift Container Platform cluster with persistent storage using [GCE](#). Some familiarity with Kubernetes and GCE is assumed.



#### IMPORTANT

Before creating persistent volumes using GCE, OpenShift Container Platform must first be properly [configured for GCE Persistent Disk](#).

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. GCE Persistent Disk volumes can be [provisioned dynamically](#). Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [Persistent volume claims](#), however, are specific to a project or namespace and can be requested by users.



#### IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

### 24.7.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring OpenShift Container Platform is [configured for GCE PersistentDisk](#), all that is required for OpenShift Container Platform and GCE is an GCE Persistent Disk volume ID and the [PersistentVolume API](#).

#### 24.7.2.1. Creating the Persistent Volume



#### NOTE

GCE does not support the 'Recycle' reclaim policy.

You must define your persistent volume in an object definition before creating it in OpenShift Container Platform:

#### Example 24.6. Persistent Volume Object Definition Using GCE

```

apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
spec:
  capacity:
    storage: "5Gi" 2
  accessModes:
    - "ReadWriteOnce"
  gcePersistentDisk: 3
    fsType: "ext4" 4
  pdName: "pd-disk-1" 5

```

- 1** The name of the volume. This will be how it is identified via [persistent volume claims](#) or from pods.
- 2** The amount of storage allocated to this volume.
- 3** This defines the volume type being used, in this case the **gcePersistentDisk** plug-in.
- 4** File system type to mount.
- 5** This is the GCE Persistent Disk volume that will be used.



## IMPORTANT

Changing the value of the **fstype** parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

Save your definition to a file, for example **gce-pv.yaml**, and create the persistent volume:

```
# oc create -f gce-pv.yaml
persistentvolume "pv0001" created
```

Verify that the persistent volume was created:

```
# oc get pv
NAME      LABELS      CAPACITY      ACCESSMODES      STATUS      CLAIM      REASON
AGE
pv0001    <none>     5Gi          RWO            Available
2s
```

Users can then [request storage using persistent volume claims](#), which can now utilize your new persistent volume.



## IMPORTANT

Persistent volume claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume from a different namespace causes the pod to fail.

### 24.7.2.2. Volume Format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows using unformatted GCE volumes as persistent volumes, because OpenShift Container Platform formats them before the first use.

## 24.8. PERSISTENT STORAGE USING iSCSI

### 24.8.1. Overview

You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [iSCSI](#). Some familiarity with Kubernetes and iSCSI is assumed.

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.



#### IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

### 24.8.2. Provisioning

Verify that the storage exists in the underlying infrastructure before mounting it as a volume in OpenShift Container Platform. All that is required for the iSCSI is the iSCSI target portal, a valid iSCSI Qualified Name (IQN), a valid LUN number, the filesystem type, and the **PersistentVolume** API.

Optionally, multipath portals and Challenge Handshake Authentication Protocol (CHAP) configuration can be provided.



#### NOTE

iSCSI does not support the 'Recycle' reclaim policy.

#### Example 24.7. Persistent Volume Object Definition

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi-pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.16.154.81:3260
    portals: ['10.16.154.82:3260', '10.16.154.83:3260']
    iqn: iqn.2014-12.example.server:storage.target00
```

```

lun: 0
fsType: 'ext4'
readOnly: false
chapAuthDiscovery: true
chapAuthSession: true
secretRef:
  name: chap-secret

```

#### 24.8.2.1. Enforcing Disk Quotas

Use LUN partitions to enforce disk quotas and size constraints. Each LUN is one persistent volume. Kubernetes enforces unique names for persistent volumes.

Enforcing quotas in this way allows the end user to request persistent storage by a specific amount (e.g., 10Gi) and be matched with a corresponding volume of equal or greater capacity.

#### 24.8.2.2. iSCSI Volume Security

Users request storage with a **PersistentVolumeClaim**. This claim only lives in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume across a namespace causes the pod to fail.

Each iSCSI LUN must be accessible by all nodes in the cluster.

#### 24.8.2.3. iSCSI Multipathing

For iSCSI-based storage, you can configure multiple paths by using the same IQN for more than one target portal IP address. Multipathing ensures access to the persistent volume when one or more of the components in a path fail.

To specify multi-paths in pod specification use the **portals** field. For example:

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi_pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.0.0.1:3260
    portals: ['10.0.2.16:3260', '10.0.2.17:3260', '10.0.2.18:3260'] ①
    iqn: iqn.2016-04.test.com:storage.target00
    lun: 0
    fsType: ext4
    readOnly: false

```

① Add additional target portals using the **portals** field.

#### 24.8.2.4. iSCSI Custom Initiator IQN

Configure the custom initiator iSCSI Qualified Name (IQN) if the iSCSI targets are restricted to certain IQNs, but the nodes that the iSCSI PVs are attached to are not guaranteed to have these IQNs.

To specify custom initiator IQN, use **initiatorName** field.

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: iscsi_pv
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  iscsi:
    targetPortal: 10.0.0.1:3260
    portals: ['10.0.2.16:3260', '10.0.2.17:3260', '10.0.2.18:3260']
    iqn: iqn.2016-04.test.com:storage.target00
    lun: 0
    initiatorName: iqn.2016-04.test.com:custom.iqn ①
    fsType: ext4
    readOnly: false
```

- ① To add an additional custom initiator IQN, use **initiatorName** field.

## 24.9. PERSISTENT STORAGE USING FIBRE CHANNEL

### 24.9.1. Overview

You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [Fibre Channel](#). Some familiarity with Kubernetes and Fibre Channel is assumed.

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.



#### IMPORTANT

High-availability of storage in the infrastructure is left to the underlying storage provider.

### 24.9.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. All that is required for Fibre Channel persistent storage is the **targetWWNs** (array of Fibre Channel target's World Wide Names), a valid **LUN** number, filesystem type, and the **PersistentVolume** API. Persistent volume and a LUN have one-to-one mapping between them.



#### NOTE

Fibre Channel does not support the 'Recycle' reclaim policy.

### Persistent Volumes Object Definition

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001
spec:
  capacity:
    storage: 1Gi
  accessModes:
    - ReadWriteOnce
  fc:
    targetWWNs: ['500a0981891b8dc5', '500a0981991b8dc5'] 1
    lun: 2
    fsType: ext4

```

- 1** Fibre Channel WWNs are identified as `/dev/disk/by-path/pci-<IDENTIFIER>-fc-0x<WWN>-lun-<LUN#>`, but you do not need to provide any part of the path leading up to the `WWN`, including the `0x`, and anything after, including the `-` (hyphen).



### IMPORTANT

Changing the value of the `fstype` parameter after the volume has been formatted and provisioned can result in data loss and pod failure.

#### 24.9.2.1. Enforcing Disk Quotas

Use LUN partitions to enforce disk quotas and size constraints. Each LUN is one persistent volume. Kubernetes enforces unique names for persistent volumes.

Enforcing quotas in this way allows the end user to request persistent storage by a specific amount (e.g., 10Gi) and be matched with a corresponding volume of equal or greater capacity.

#### 24.9.2.2. Fibre Channel Volume Security

Users request storage with a **PersistentVolumeClaim**. This claim only lives in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume across a namespace causes the pod to fail.

Each Fibre Channel LUN must be accessible by all nodes in the cluster.


## 24.10. PERSISTENT STORAGE USING AZURE DISK

### 24.10.1. Overview

OpenShift Container Platform supports [Microsoft Azure Disk](#) volumes. You can provision your OpenShift Container Platform cluster with [persistent storage](#) using Azure. Some familiarity with Kubernetes and Azure is assumed.

The Kubernetes [persistent volume](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure.

Azure Disk volumes can be [provisioned dynamically](#). Persistent volumes are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [Persistent volume claims](#), however, are specific to a project or namespace and can be requested by users.



### IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

#### 24.10.2. Prerequisites

Before creating persistent volumes using Azure, ensure your OpenShift Container Platform cluster meets the following requirements:

- OpenShift Container Platform must first be [configured for Azure Disk](#).
- Each node host in the infrastructure must match the Azure virtual machine name.
- Each node host must be in the same resource group.

#### 24.10.3. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring OpenShift Container Platform is [configured for Azure Disk](#), all that is required for OpenShift Container Platform and Azure is an Azure Disk Name and Disk URI and the [PersistentVolume API](#).

#### 24.10.4. Configuring Azure Disk for regional cloud


Azure has multiple regions on which to deploy an instance. To specify a desired region, add the following to the `azure.conf` file:

```
cloud: <region>
```

The region can be any of the following:

- German cloud: **AZUREGERMANCLOUD**
- China cloud: **AZURECHINACLOUD**
- Public cloud: **AZUREPUBLICCLOUD**
- US cloud: **AZUREUSGOVERNMENTCLOUD**

##### 24.10.4.1. Creating the Persistent Volume



### NOTE

Azure does not support the **Recycle** reclaim policy.

You must define your persistent volume in an object definition before creating it in OpenShift Container Platform:

```
Example 24.8. Persistent Volume Object Definition Using Azure
```

```

apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" 1
spec:
  capacity:
    storage: "5Gi" 2
  accessModes:
    - "ReadWriteOnce"
  azureDisk: 3
    diskName: test2.vhd 4
    diskURI: https://someaccount.blob.core.windows.net/vhds/test2.vhd 5
    cachingMode: ReadWrite 6
    fsType: ext4 7
    readOnly: false 8

```

- 1** The name of the volume. This will be how it is identified via [persistent volume claims](#) or from pods.
- 2** The amount of storage allocated to this volume.
- 3** This defines the volume type being used (**azureDisk** plug-in, in this example).
- 4** The name of the data disk in the blob storage.
- 5** The URI of the data disk in the blob storage.
- 6** Host caching mode: None, ReadOnly, or ReadWrite.
- 7** File system type to mount (for example, **ext4**, **xfs**, and so on).
- 8** Defaults to **false** (read/write). **ReadOnly** here will force the **ReadOnly** setting in **VolumeMounts**.



## IMPORTANT

Changing the value of the **fsType** parameter after the volume is formatted and provisioned can result in data loss and pod failure.

1. Save your definition to a file, for example **azure-pv.yaml**, and create the persistent volume:

```
# oc create -f azure-pv.yaml
persistentvolume "pv0001" created
```

2. Verify that the persistent volume was created:

```
# oc get pv
NAME      LABELS      CAPACITY      ACCESSMODES      STATUS      CLAIM
REASON    AGE
pv0001    <none>     5Gi          RWO           Available
2s
```

Now you can [request storage using persistent volume claims](#), which can now use your new persistent volume.



## IMPORTANT

For a pod that has a mounted volume through an Azure disk PVC, scheduling the pod to a new node takes a few minutes. Wait for two to three minutes to complete the *Disk Detach* operation, and then start a new deployment. If a new pod creation request is started before completing the *Disk Detach* operation, the *Disk Attach* operation initiated by the pod creation fails, resulting in pod creation failure.



## IMPORTANT

Persistent volume claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a persistent volume from a different namespace causes the pod to fail.

### 24.10.4.2. Volume Format

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that it contains a file system as specified by the **fsType** parameter in the persistent volume definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows unformatted Azure volumes to be used as persistent volumes because OpenShift Container Platform formats them before the first use.

## 24.11. PERSISTENT STORAGE USING AZURE FILE

### 24.11.1. Overview

OpenShift Container Platform supports [Microsoft Azure File](#) volumes. You can provision your OpenShift Container Platform cluster with [persistent storage](#) using Azure. Some familiarity with Kubernetes and Azure is assumed.



## IMPORTANT

High availability of storage in the infrastructure is left to the underlying storage provider.

### 24.11.2. Before you begin

1. Install **samba-client**, **samba-common**, and **cifs-utils** on all nodes:

```
$ sudo yum install samba-client samba-common cifs-utils
```

2. Enable SELinux booleans on all nodes:

```
$ /usr/sbin/setsebool -P virt_use_samba on  
$ /usr/sbin/setsebool -P virt_sandbox_use_samba on
```

3. Run the **mount** command to check **dir\_mode** and **file\_mode** permissions, for example:

```
$ mount
```

If the `dir_mode` and `file_mode` permissions are set to `0755`, change the default value `0755` to `0777` or `0775`. This manual step is required because the default `dir_mode` and `file_mode` permissions changed from `0777` to `0755` in OpenShift Container Platform 3.9. The following examples show configuration files with the changed values.

### PV configuration file example

```
# azf-pv.yaml
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "azpv"
spec:
  capacity:
    storage: "1Gi"
  accessModes:
    - "ReadWriteMany"
  azureFile:
    secretName: azure-secret
    shareName: azftest
    readOnly: false
  mountOptions:
    - dir_mode=0777
    - file_mode=0777
```

### Storage class configuration file example

```
$ azure-file-sc.yaml
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: azurefile
provisioner: kubernetes.io/azure-file
mountOptions:
  - dir_mode=0777
  - file_mode=0777
parameters:
  storageAccount: ocp39str
  location: centralus
```

#### 24.11.3. Configuring Azure File for regional cloud

While [Azure Disk is compatible with multiple regional clouds](#), Azure File supports only the Azure public cloud, because the endpoint is hard-coded.

#### 24.11.4. Creating the PV



##### NOTE

Azure File does not support the **Recycle** reclaim policy.

## 24.11.5. Creating the Azure Storage Account secret

Define the Azure Storage Account name and key in a secret configuration, which is then converted to base64 for use by OpenShift Container Platform.

- Obtain an Azure Storage Account name and key and encode to base64:

```
apiVersion: v1
kind: Secret
metadata:
  name: azure-secret
type: Opaque
data:
  azurestorageaccountname: azhzdGVzdA==
  azurestorageaccountkey:
eE1GMXpKYm5ub2pGTE1Ta0JwNTBteDAyckhzTUsyc2pVN21GdDRMMTNob0I3ZHJBYUo4
akQ2K0E0NDNqSm9nVjd5MkZVT2hRQ1dQbU02WWFOSHk3cWc9PQ==
```

- Save the secret definition to a file, for example ***azure-secret.yaml***, then create the secret:

```
$ oc create -f azure-secret.yaml
```

- Verify that the secret was created:

```
$ oc get secret azure-secret
NAME          TYPE      DATA   AGE
azure-secret   Opaque    1      23d
```

- Define the PV in an object definition before creating it in OpenShift Container Platform:

### PV object definition using Azure File example

```
apiVersion: "v1"
kind: "PersistentVolume"
metadata:
  name: "pv0001" ①
spec:
  capacity:
    storage: "5Gi" ②
  accessModes:
    - "ReadWriteMany"
  azureFile: ③
    secretName: azure-secret ④
    shareName: example ⑤
    readOnly: false ⑥
```

- ① The name of the volume. This is how it is identified via [PV claims](#) or from pods.
- ② The amount of storage allocated to this volume.
- ③ This defines the volume type being used: **azureFile** plug-in.
- ④ The name of the secret used.

- 5 The name of the file share.
- 6 Defaults to `false` (read/write). `ReadOnly` here forces the `ReadOnly` setting in `VolumeMounts`.

5. Save your definition to a file, for example `azure-file-pv.yaml`, and create the PV:

```
$ oc create -f azure-file-pv.yaml
persistentvolume "pv0001" created
```

6. Verify that the PV was created:

```
$ oc get pv
NAME      LABELS      CAPACITY      ACCESSMODES      STATUS      CLAIM
REASON    AGE
pv0001    <none>     5Gi          RWM            Available
2s
```

You can now [request storage using PV claims](#), which can now use your new PV.



### IMPORTANT

PV claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a PV from a different namespace causes the pod to fail.

## 24.12. PERSISTENT STORAGE USING FLEXVOLUME PLUG-INS

### 24.12.1. Overview

OpenShift Container Platform has built-in [volume plug-ins](#) to use different storage technologies. To use storage from a back-end that does not have a built-in plug-in, you can extend OpenShift Container Platform through FlexVolume drivers and provide [persistent storage](#) to applications.

### 24.12.2. FlexVolume drivers

A FlexVolume driver is an executable file that resides in a well-defined directory on all machines in the cluster, both masters and nodes. OpenShift Container Platform calls the FlexVolume driver whenever it needs to attach, detach, mount, or unmount a volume represented by a **PersistentVolume** with **flexVolume** as the source.

The first command-line argument of the driver is always an operation name. Other parameters are specific to each operation. Most of the operations take a JavaScript Object Notation (JSON) string as a parameter. This parameter is a complete JSON string, and not the name of a file with the JSON data.

The FlexVolume driver contains:

- All `flexVolume.options`.
- Some options from `flexVolume` prefixed by `kubernetes.io/`, such as `fsType` and `readwrite`.
- The content of the referenced secret, if specified, prefixed by `kubernetes.io/secret/`.

## FlexVolume driver JSON input example

```
{
  "fooServer": "192.168.0.1:1234", ①
    "fooVolumeName": "bar",
  "kubernetes.io/fsType": "ext4", ②
  "kubernetes.io/readwrite": "ro", ③
  "kubernetes.io/secret/<key name>": "<key value>", ④
  "kubernetes.io/secret/<another key name>": "<another key value>",
}
```

- ① All options from **flexVolume.options**.
- ② The value of **flexVolume.fsType**.
- ③ **ro/rw** based on **flexVolume.readOnly**.
- ④ All keys and their values from the secret referenced by **flexVolume.secretRef**.

OpenShift Container Platform expects JSON data on standard output of the driver. When not specified, the output describes the result of the operation.

## FlexVolume Driver Default Output

```
{
  "status": "<Success/Failure/Not supported>",
  "message": "<Reason for success/failure>"
}
```

Exit code of the driver should be **0** for success and **1** for error.

Operations should be idempotent, which means that the attachment of an already attached volume or the mounting of an already mounted volume should result in a successful operation.

The FlexVolume driver can work in two modes:

- with the master-initiated attach/detach operation, or
- without the master-initiated attach/detach operation.

The **attach/detach** operation is used by the OpenShift Container Platform master to attach a volume to a node and to detach it from a node. This is useful when a node becomes unresponsive for any reason. Then, the master can kill all pods on the node, detach all volumes from it, and attach the volumes to other nodes to resume the applications while the original node is still not reachable.



### IMPORTANT

Not all storage back-end supports master-initiated detachment of a volume from another machine.

#### 24.12.2.1. FlexVolume drivers with master-initiated attach/detach

A FlexVolume driver that supports master-controlled attach/detach must implement the following operations:

### **init**

Initializes the driver. It is called during initialization of masters and nodes.

- Arguments: none
- Executed on: master, node
- Expected output: default JSON

### **getvolumename**

Returns the unique name of the volume. This name must be consistent among all masters and nodes, because it is used in subsequent **detach** call as <**volume-name**>. Any / characters in the <**volume-name**> are automatically replaced by ~.

- Arguments: <**json**>
- Executed on: master, node
- Expected output: default JSON + **volumeName**:

```
{
  "status": "Success",
  "message": "",
  "volumeName": "foo-volume-bar" ①
}
```

① The unique name of the volume in storage back-end **foo**.

### **attach**

Attaches a volume represented by the JSON to a given node. This operation should return the name of the device on the node if it is known, that is, if it has been assigned by the storage back-end before it runs. If the device is not known, the device must be found on the node by the subsequent **waitforattach** operation.

- Arguments: <**json**> <**node-name**>
- Executed on: master
- Expected output: default JSON + **device**, if known:

```
{
  "status": "Success",
  "message": "",
  "device": "/dev/xvda" ①
}
```

① The name of the device on the node, if known.

### **waitforattach**

Waits until a volume is fully attached to a node and its device emerges. If the previous **attach** operation has returned <**device-name**>, it is provided as an input parameter. Otherwise, <**device-name**> is empty and the operation must find the device on the node.

- Arguments: <**device-name**> <**json**>
- Executed on: node
- Expected output: default JSON + **device**

```
{
  "status": "Success",
  "message": "",
  "device": "/dev/xvda" ①
}
```

① The name of the device on the node.

## **detach**

Detaches the given volume from a node. <**volume-name**> is the name of the device returned by the **getvolumename** operation. Any / characters in the <**volume-name**> are automatically replaced by ~.

- Arguments: <**volume-name**> <**node-name**>
- Executed on: master
- Expected output: default JSON

## **isattached**

Checks that a volume is attached to a node.

- Arguments: <**json**> <**node-name**>
- Executed on: master
- Expected output: default JSON + **attached**

```
{
  "status": "Success",
  "message": "",
  "attached": true ①
}
```

① The status of attachment of the volume to the node.

## **mountdevice**

Mounts a volume's device to a directory. <**device-name**> is name of the device as returned by the previous **waitforattach** operation.

- Arguments: <**mount-dir**> <**device-name**> <**json**>

- Executed on: node
- Expected output: default JSON

### **unmountdevice**

Unmounts a volume's device from a directory.

- Arguments: <mount-dir>
- Executed on: node

All other operations should return JSON with `{"status": "Not supported"}` and exit code 1.



### **NOTE**

Master-initiated attach/detach operations are enabled by default in OpenShift Container Platform 3.6. They may work in older versions, but must be explicitly enabled. See [Enabling Controller-managed Attachment and Detachment](#). When not enabled, the attach/detach operations are initiated by a node where the volume should be attached to or detached from. Syntax and all parameters of FlexVolume driver invocations are the same in both cases.

#### **24.12.2.2. FlexVolume drivers without master-initiated attach/detach**

FlexVolume drivers that do not support master-controlled attach/detach are executed only on the node and must implement these operations:

### **init**

Initializes the driver. It is called during initialization of all nodes.

- Arguments: none
- Executed on: node
- Expected output: default JSON

### **mount**

Mounts a volume to directory. This can include anything that is necessary to mount the volume, including attaching the volume to the node, finding its device, and then mounting the device.

- Arguments: <mount-dir> <json>
- Executed on: node
- Expected output: default JSON

### **unmount**

Unmounts a volume from a directory. This can include anything that is necessary to clean up the volume after unmounting, such as detaching the volume from the node.

- Arguments: <mount-dir>
- Executed on: node

- Expected output: default JSON

All other operations should return JSON with `{"status": "Not supported"}` and exit code **1**.

### 24.12.3. Installing FlexVolume drivers

To install the FlexVolume driver:

1. Ensure that the executable file exists on all masters and nodes in the cluster.
2. Place the executable file at the volume plug-in path: `/usr/libexec/kubernetes/kubelet-plugins/volume/exec/<vendor>-<driver>/<driver>`.

For example, to install the FlexVolume driver for the storage `foo`, place the executable file at: `/usr/libexec/kubernetes/kubelet-plugins/volume/exec/openshift.com~foo/foo`.

### 24.12.4. Consuming storage using FlexVolume drivers

Use the **PersistentVolume** object to reference the installed storage. Each **PersistentVolume** object in OpenShift Container Platform represents one storage asset, typically a volume, in the storage back-end.

#### Persistent volume object definition using FlexVolume drivers example

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 ①
spec:
  capacity:
    storage: 1Gi ②
  accessModes:
    - ReadWriteOnce
  flexVolume:
    driver: openshift.com/foo ③
    fsType: "ext4" ④
    secretRef: foo-secret ⑤
    readOnly: true ⑥
    options:
      fooServer: 192.168.0.1:1234
      fooVolumeName: bar
```

- ① The name of the volume. This is how it is identified through [persistent volume claims](#) or from pods. This name can be different from the name of the volume on back-end storage.
- ② The amount of storage allocated to this volume.
- ③ The name of the driver. This field is mandatory.
- ④ The file system that is present on the volume. This field is optional.
- ⑤ The reference to a secret. Keys and values from this secret are provided to the FlexVolume driver on invocation. This field is optional.

- 6** The read-only flag. This field is optional.
- 7** The additional options for the FlexVolume driver. In addition to the flags specified by the user in the **options** field, the following flags are also passed to the executable:

```
"fsType": "<FS type>",
"readwrite": "<rw>",
"secret/key1": "<secret1>"
...
"secret/keyN": "<secretN>"
```

**NOTE**

Secrets are passed only to mount/unmount call-outs.


## 24.13. USING VMWARE VSphere VOLUMES FOR PERSISTENT STORAGE

### 24.13.1. Overview

OpenShift Container Platform supports VMware vSphere's Virtual Machine Disk (VMDK) volumes. You can provision your OpenShift Container Platform cluster with [persistent storage](#) using [VMware vSphere](#). Some familiarity with Kubernetes and VMware vSphere is assumed.

The OpenShift Container Platform [persistent volume \(PV\)](#) framework allows administrators to provision a cluster with persistent storage and gives users a way to request those resources without having any knowledge of the underlying infrastructure. vSphere VMDK volumes can be [provisioned dynamically](#).

PVs are not bound to a single project or namespace; they can be shared across the OpenShift Container Platform cluster. [PV claims](#), however, are specific to a project or namespace and can be requested by users.

**IMPORTANT**

High availability of storage in the infrastructure is left to the underlying storage provider.

#### Prerequisites

Before creating PVs using vSphere, ensure your OpenShift Container Platform cluster meets the following requirements:

- OpenShift Container Platform must first be [configured for vSphere](#).
- Each node host in the infrastructure must match the vSphere VM name.
- Each node host must be in the same resource group.



## IMPORTANT

Create VMDK using one of the following methods before using them.

- Create using **vmkfstools**:

Access ESX through Secure Shell (SSH) and then use following command to create a VMDK volume:

```
vmkfstools -c 2G
/vmfs/volumes/DatastoreName/volumes/myDisk.vmdk
```

- Create using **vmware-vdiskmanager**:

```
shell vmware-vdiskmanager -c -t 0 -s 40GB -a lsilogic
myDisk.vmdk
```

### 24.13.2. Provisioning VMware vSphere volumes

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. After ensuring OpenShift Container Platform is [configured for vSphere](#), all that is required for OpenShift Container Platform and vSphere is a VM folder path, file system type, and the **PersistentVolume API**.

#### 24.13.2.1. Creating persistent volumes

You must define your PV in an object definition before creating it in OpenShift Container Platform:

##### PV object definition using VMware vSphere example

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv0001 1
spec:
  capacity:
    storage: 2Gi 2
  accessModes:
    - ReadWriteOnce
  persistentVolumeReclaimPolicy: Retain
  vsphereVolume: 3
    volumePath: "[datastore1] volumes/myDisk" 4
    fsType: ext4 5
```

- 1** The name of the volume. This must be how it is identified by [PV claims](#) or from pods.
- 2** The amount of storage allocated to this volume.
- 3** This defines the volume type being used (**vsphereVolume** plug-in, in this example). The **vsphereVolume** label is used to mount a vSphere VMDK volume into pods. The contents of a volume are preserved when it is unmounted. The volume type supports VMFS and VSAN datastore.
- 4** This VMDK volume must exist, and you must include brackets ([]) in the volume definition.

- 5** The file system type to mount (for example, `ext4`, `xfs`, and other file-systems).



### IMPORTANT

Changing the value of the `fsType` parameter after the volume is formatted and provisioned can result in data loss and pod failure.

To create persistent volumes:

- Save your definition to a file, for example `vsphere-pv.yaml`, and create the PV:

```
$ oc create -f vsphere-pv.yaml
persistentvolume "pv0001" created
```

- Verify that the PV was created:

```
$ oc get pv
NAME      LABELS   CAPACITY  ACCESSMODES  STATUS    CLAIM     REASON
AGE
pv0001   <none>   2Gi       RWO          Available
2s
```

Now you can [request storage using PV claims](#), which can now use your PV.



### IMPORTANT

PV claims only exist in the user's namespace and can only be referenced by a pod within that same namespace. Any attempt to access a PV from a different namespace causes the pod to fail.

#### 24.13.2.2. Formatting VMware vSphere volumes

Before OpenShift Container Platform mounts the volume and passes it to a container, it checks that the volume contains a file system as specified by the `fsType` parameter in the PV definition. If the device is not formatted with the file system, all data from the device is erased and the device is automatically formatted with the given file system.

This allows unformatted vSphere volumes to be used as PVs, because OpenShift Container Platform formats them before the first use.

## 24.14. PERSISTENT STORAGE USING LOCAL VOLUME

### 24.14.1. Overview

OpenShift Container Platform clusters can be provisioned with [persistent storage](#) by using local volumes. Local persistent volume allows you to access local storage devices such as a disk, partition or directory by using the standard PVC interface.

Local volumes can be used without manually scheduling pods to nodes, because the system is aware of the volume's node constraints. However, local volumes are still subject to the availability of the underlying node and are not suitable for all applications.

**NOTE**

Local volumes is an alpha feature and may change in a future release of OpenShift Container Platform. See [Feature Status\(Local Volume\)](#) section for details on known issues and workarounds.

**WARNING**

Local volumes can only be used as a statically created Persistent Volume.

#### 24.14.2. Provisioning

Storage must exist in the underlying infrastructure before it can be mounted as a volume in OpenShift Container Platform. Ensure that OpenShift Container Platform is configured for [Local Volumes](#), before using the **PersistentVolume API**.

#### 24.14.3. Creating Local Persistent Volume Claim

Define the persistent volume claim in an object definition.

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: example-local-claim
spec:
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 5Gi ①
  storageClassName: local-storage ②
```

**①** The required size of storage volume.

**②** The name of storage class, which is used for local PVs.

#### 24.14.4. Feature Status

##### What Works:

- Creating a PV by specifying a directory with node affinity.
- A Pod using the PVC that is bound to the previously mentioned PV always get scheduled to that node.
- External static provisioner daemonset that discovers local directories, creates, cleans up and deletes PVs.

##### What does not work:

- Multiple local PVCs in a single pod.
- PVC binding does not consider pod scheduling requirements and may make sub-optimal or incorrect decisions.
  - Workarounds:
    - Run those pods first, which requires local volume.
    - Give the pods high priority.
    - Run a workaround controller that unbinds PVCs for pods that are stuck pending.
- If mounts are added after the external provisioner is started, then external provisioner cannot detect the correct capacity of mounts.
  - Workarounds:
    - Before adding any new mount points, first stop the daemonset, add the new mount points, and then start the daemonset.
- **fsgroup** conflict occurs if multiple pods using the same PVC specify different **fsgroup**'s.

## 24.15. DYNAMIC PROVISIONING AND CREATING STORAGE CLASSES


### 24.15.1. Overview

The *StorageClass* resource object describes and classifies storage that can be requested, as well as provides a means for passing parameters for **dynamically provisioned storage** on demand.

*StorageClass* objects can also serve as a management mechanism for controlling different levels of storage and access to the storage. Cluster Administrators (**cluster-admin**) or Storage Administrators (**storage-admin**) define and create the *StorageClass* objects that users can request without needing any intimate knowledge about the underlying storage volume sources.

The OpenShift Container Platform [persistent volume](#) framework enables this functionality and allows administrators to provision a cluster with persistent storage. The framework also gives users a way to request those resources without having any knowledge of the underlying infrastructure.

Many storage types are available for use as persistent volumes in OpenShift Container Platform. While all of them can be statically provisioned by an administrator, some types of storage are created dynamically using the built-in provider and plug-in APIs.



#### NOTE

To enable dynamic provisioning, add the **openshift\_master\_dynamic\_provisioning\_enabled** variable to the **[OSEv3:vars]** section of the Ansible inventory file and set its value to **True**.

```
[OSEv3:vars]
```

```
openshift_master_dynamic_provisioning_enabled=True
```

### 24.15.2. Available dynamically provisioned plug-ins

OpenShift Container Platform provides the following *provisioner plug-ins*, which have generic implementations for dynamic provisioning that use the cluster's configured provider's API to create new storage resources:

Storage Type	Provisioner Plug-in Name	Required Configuration	Notes
OpenStack Cinder	<b>kubernetes.io/cinder</b>	<a href="#">Configuring for OpenStack</a>	
AWS Elastic Block Store (EBS)	<b>kubernetes.io/aws-ebs</b>	<a href="#">Configuring for AWS</a>	For dynamic provisioning when using multiple clusters in different zones, tag each node with <b>Key=kubernetes.io/cluster/xxxx,Value=clusterid</b> where <b>xxxx</b> and <b>clusterid</b> are unique per cluster. In versions prior to 3.6, this was <b>Key=KubernetesCluster,Value=clusterid</b> .
GCE Persistent Disk (gcePD)	<b>kubernetes.io/gce-pd</b>	<a href="#">Configuring for GCE</a>	In multi-zone configurations, it is advisable to run one Openshift cluster per GCE project to avoid PVs from getting created in zones where no node from current cluster exists.
GlusterFS	<b>kubernetes.io/glusterfs</b>	<a href="#">Configuring GlusterFS</a>	
Ceph RBD	<b>kubernetes.io/rbd</b>	<a href="#">Configuring Ceph RBD</a>	
Trident from NetApp	<b>netapp.io/trident</b>	<a href="#">Configuring for Trident</a>	Storage orchestrator for NetApp ONTAP, SolidFire, and E-Series storage.
VMWare vSphere	<b>kubernetes.io/vsphere-volume</b>	<a href="#">Getting Started with vSphere and Kubernetes</a>	
Azure Disk	<b>kubernetes.io/azure-disk</b>	<a href="#">Configuring for Azure</a>	

**IMPORTANT**

Any chosen provisioner plug-in also requires configuration for the relevant cloud, host, or third-party provider as per the relevant documentation.

**24.15.3. Defining a StorageClass**

*StorageClass* objects are currently a globally scoped object and need to be created by **cluster-admin** or **storage-admin** users.

**NOTE**

For GCE and AWS, a default StorageClass is created during OpenShift Container Platform installation. You can [change the default StorageClass](#) or delete it.

There are currently six plug-ins that are supported. The following sections describe the basic object definition for a *StorageClass* and specific examples for each of the supported plug-in types.

**24.15.3.1. Basic StorageClass object definition****StorageClass Basic object definition**

```
kind: StorageClass ①
apiVersion: storage.k8s.io/v1 ②
metadata:
  name: foo ③
  annotations: ④
  ...
provisioner: kubernetes.io/plug-in-type ⑤
parameters:
  param1: value
  ...
  paramN: value
```

- ① (required) The API object type.
- ② (required) The current apiVersion.
- ③ (required) The name of the StorageClass.
- ④ (optional) Annotations for the StorageClass
- ⑤ (required) The type of provisioner associated with this storage class.
- ⑥ (optional) The parameters required for the specific provisioner, this will change from plug-in to plug-in.

**24.15.3.2. StorageClass annotations**

To set a *StorageClass* as the cluster-wide default:

```
storageclass.kubernetes.io/is-default-class: "true"
```

This enables any Persistent Volume Claim (PVC) that does not specify a specific volume to automatically be provisioned through the *default* StorageClass



### NOTE

Beta annotation `storageclass.beta.kubernetes.io/is-default-class` is still working. However it will be removed in a future release.

To set a *StorageClass* description:

```
kubernetes.io/description: My StorageClass Description
```

#### 24.15.3.3. OpenStack Cinder object definition

##### cinder-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: gold
provisioner: kubernetes.io/cinder
parameters:
  type: fast ①
  availability: nova ②
  fsType: ext4 ③
```

- ① Volume type created in Cinder. Default is empty.
- ② Availability Zone. If not specified, volumes are generally round-robined across all active zones where the OpenShift Container Platform cluster has a node.
- ③ File system that is created on dynamically provisioned volumes. This value is copied to the `fsType` field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is `ext4`.

#### 24.15.3.4. AWS ElasticBlockStore (EBS) object definition

##### aws-ebs-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow
provisioner: kubernetes.io/aws-ebs
parameters:
  type: io1 ①
  zone: us-east-1d ②
  iopsPerGB: "10" ③
  encrypted: "true" ④
  kmsKeyId: keyvalue ⑤
  fsType: ext4 ⑥
```

- 1 Select from **io1**, **gp2**, **sc1**, **st1**. The default is **gp2**. See [AWS documentation](#) for valid Amazon Resource Name (ARN) values.
- 2 AWS zone. If no zone is specified, volumes are generally round-robined across all active zones where the OpenShift Container Platform cluster has a node. Zone and zones parameters must not be used at the same time.
- 3 Only for **io1** volumes. I/O operations per second per GiB. The AWS volume plug-in multiplies this with the size of the requested volume to compute IOPS of the volume. The value cap is 20,000 IOPS, which is the maximum supported by AWS. See [AWS documentation](#) for further details.
- 4 Denotes whether to encrypt the EBS volume. Valid values are **true** or **false**.
- 5 Optional. The full ARN of the key to use when encrypting the volume. If none is supplied, but **encrypted** is set to **true**, then AWS generates a key. See [AWS documentation](#) for a valid ARN value.
- 6 File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is **ext4**.

#### 24.15.3.5. GCE PersistentDisk (gcePD) object definition

##### `gce-pd-storageclass.yaml`

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow
provisioner: kubernetes.io/gce-pd
parameters:
  type: pd-standard 1
  zone: us-central1-a 2
  zones: us-central1-a, us-central1-b, us-east1-b 3
  fsType: ext4 4
```

- 1 Select either **pd-standard** or **pd-ssd**. The default is **pd-ssd**.
- 2 GCE zone. If no zone is specified, volumes are generally round-robined across all active zones where the OpenShift Container Platform cluster has a node. Zone and zones parameters must not be used at the same time.
- 3 A comma-separated list of GCE zone(s). If no zone is specified, volumes are generally round-robined across all active zones where the OpenShift Container Platform cluster has a node. Zone and zones parameters must not be used at the same time.
- 4 File system that is created on dynamically provisioned volumes. This value is copied to the **fsType** field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is **ext4**.

#### 24.15.3.6. GlusterFS object definition

## glusterfs-storageclass.yaml

```

kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow
provisioner: kubernetes.io/glusterfs
parameters:
  resturl: "http://127.0.0.1:8081" 1
  restuser: "admin" 2
  secretName: "heketi-secret" 3
  secretNamespace: "default" 4
  gidMin: "40000" 5
  gidMax: "50000" 6

```

- 1** heketi (volume management REST service for Gluster) URL that provisions GlusterFS volumes on demand. The general format should be `{http/https}://{IPaddress}:{Port}`. This is a mandatory parameter for the GlusterFS dynamic provisioner. If the heketi service is exposed as a routable service in the OpenShift Container Platform, it will have a resolvable fully qualified domain name (FQDN) and heketi service URL.
- 2** heketi user who has access to create volumes. Usually "admin".
- 3** Identification of a Secret that contains a user password to use when talking to heketi. Optional; an empty password will be used when both `secretNamespace` and `secretName` are omitted. The provided secret must be of type "`kubernetes.io/glusterfs`".
- 4** The namespace of mentioned `secretName`. Optional; an empty password will be used when both `secretNamespace` and `secretName` are omitted. The provided secret must be of type "`kubernetes.io/glusterfs`".
- 5** Optional. The minimum value of the GID range for volumes of this StorageClass.
- 6** Optional. The maximum value of the GID range for volumes of this StorageClass.



### NOTE

When the `gidMin` and `gidMax` values are not specified, their defaults are 2000 and 2147483647, respectively. Each dynamically provisioned volume will be given a GID in this range (`gidMin-gidMax`). This GID is released from the pool when the respective volume is deleted. The GID pool is per StorageClass. If two or more storage classes have GID ranges that overlap there may be duplicate GIDs dispatched by the provisioner.

When heketi authentication is used, a Secret containing the admin key should also exist:

## heketi-secret.yaml

```

apiVersion: v1
kind: Secret
metadata:
  name: heketi-secret
  namespace: default

```

```

data:
  key: bXlwYXNzd29yZA== ①
type: kubernetes.io/glusterfs

```

- ① base64 encoded password, for example: `echo -n "mypassword" | base64`



#### NOTE

When the PVs are dynamically provisioned, the GlusterFS plug-in automatically creates an Endpoints and a headless Service named `gluster-dynamic-<claimname>`. When the PVC is deleted, these dynamic resources are deleted automatically.

#### 24.15.3.7. Ceph RBD object definition

##### `ceph-storageclass.yaml`

```

apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: fast
provisioner: kubernetes.io/rbd
parameters:
  monitors: 10.16.153.105:6789 ①
  adminId: admin ②
  adminSecretName: ceph-secret ③
  adminSecretNamespace: kube-system ④
  pool: kube ⑤
  userId: kube ⑥
  userSecretName: ceph-secret-user ⑦
  fsType: ext4 ⑧

```

- ① Ceph monitors, comma-delimited. It is required.
- ② Ceph client ID that is capable of creating images in the pool. Default is "admin".
- ③ Secret Name for `adminId`. It is required. The provided secret must have type "kubernetes.io/rbd".
- ④ The namespace for `adminSecret`. Default is "default".
- ⑤ Ceph RBD pool. Default is "rbd".
- ⑥ Ceph client ID that is used to map the Ceph RBD image. Default is the same as `adminId`.
- ⑦ The name of Ceph Secret for `userId` to map Ceph RBD image. It must exist in the same namespace as PVCs. It is required.
- ⑧ File system that is created on dynamically provisioned volumes. This value is copied to the `fsType` field of dynamically provisioned persistent volumes and the file system is created when the volume is mounted for the first time. The default value is `ext4`.

#### 24.15.3.8. Trident object definition

## trident.yaml

```

apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
  name: gold
provisioner: netapp.io/trident 1
parameters: 2
  media: "ssd"
  provisioningType: "thin"
  snapshots: "true"

```

Trident uses the parameters as selection criteria for the different pools of storage that are registered with it. Trident itself is configured separately.

- 1** For more information about installing Trident with OpenShift Container Platform, see the [Trident documentation](#).
- 2** For more information about supported parameters, see the [storage attributes](#) section of the Trident documentation.

### 24.15.3.9. VMware vSphere object definition

#### vsphere-storageclass.yaml

```

kind: StorageClass
apiVersion: storage.k8s.io/v1beta1
metadata:
  name: slow
provisioner: kubernetes.io/vsphere-volume 1
parameters:
  diskformat: thin 2

```

- 1** For more information about using VMWare vSphere with OpenShift Container Platform, see the [VMWare vSphere documentation](#).
- 2** **diskformat: thin, zeroedthick and eagerzeroedthick**. See vSphere docs for details.  
Default: **thin**

### 24.15.3.10. Azure Disk object definition

#### azure-advanced-disk-storageclass.yaml

```

kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: slow
provisioner: kubernetes.io/azure-disk
parameters:

```


```
storageAccount: azure_storage_account_name ①
storageaccounttype: Standard_LRS ②
kind: Dedicated ③
```

① Azure storage account name. This must reside in the same resource group as the cluster. If a storage account is specified, the **location** is ignored. If a storage account is not specified, a new storage account gets created in the same resource group as the cluster. If you are specifying a **storageAccount**, the value for **kind** must be **Dedicated**.

② Azure storage account SKU tier. Default is empty. **Note:** Premium VM can attach both *Standard\_LRS* and *Premium\_LRS* disks, Standard VM can only attach *Standard\_LRS* disks, Managed VM can only attach managed disks, and unmanaged VM can only attach unmanaged disks.

③ Possible values are **Shared** (default), **Dedicated**, and **Managed**.

- If **kind** is set to **Shared**, Azure creates all unmanaged disks in a few shared storage accounts in the same resource group as the cluster.
- If **kind** is set to **Managed**, Azure creates new managed disks.
- If **kind** is set to **Dedicated** and a **storageAccount** is specified, Azure uses the specified storage account for the new unmanaged disk in the same resource group as the cluster. For this to work:
  - The specified storage account must be in the same region.
  - Azure Cloud Provider must have a write access to the storage account.
- If **kind** is set to **Dedicated** and a **storageAccount** is not specified, Azure creates a new dedicated storage account for the new unmanaged disk in the same resource group as the cluster.



## IMPORTANT

Azure StorageClass is revised in OpenShift Container Platform version 3.7. If you upgraded from a previous version, either:

- specify the property **kind: dedicated** to continue using the Azure StorageClass created before the upgrade. Or,
- add the location parameter (for example, "**location": "southcentralus",**) in the **azure.conf** file to use the default property **kind: shared**. Doing this creates new storage accounts for future use.

### 24.15.4. Changing the default StorageClass

If you are using GCE and AWS, use the following process to change the default StorageClass:

- List the StorageClass:

```
$ oc get storageclass
```

NAME	TYPE
------	------

gp2 (default)	kubernetes.io/aws-ebs	1
standard	kubernetes.io/gce-pd	

1 (default) denotes the default StorageClass.

2. Change the value of the annotation `storageclass.kubernetes.io/is-default-class` to `false` for the default StorageClass:

```
$ oc patch storageclass gp2 -p '{"metadata": {"annotations": \n    {"storageclass.kubernetes.io/is-default-class": "false"}}}'
```

3. Make another StorageClass the default by adding or modifying the annotation as `storageclass.kubernetes.io/is-default-class=true`.

```
$ oc patch storageclass standard -p '{"metadata": {"annotations": \n    {"storageclass.kubernetes.io/is-default-class": "true"}}}'
```

4. Verify the changes:

```
$ oc get storageclass\n\nNAME          TYPE\ngp2           kubernetes.io/aws-ebs\nstandard (default)  kubernetes.io/gce-pd
```

#### 24.15.5. Additional information and examples

- Examples and uses of StorageClasses for Dynamic Provisioning
- Examples and uses of StorageClasses without Dynamic Provisioning

### 24.16. VOLUME SECURITY

#### 24.16.1. Overview

This topic provides a general guide on pod security as it relates to volume security. For information on pod-level security in general, see [Managing Security Context Constraints \(SCC\)](#) and the [Security Context Constraint](#) concept topic. For information on the OpenShift Container Platform persistent volume (PV) framework in general, see the [Persistent Storage](#) concept topic.

Accessing persistent storage requires coordination between the cluster and/or storage administrator and the end developer. The cluster administrator creates PVs, which abstract the underlying physical storage. The developer creates pods and, optionally, PVCs, which bind to PVs, based on matching criteria, such as capacity.

Multiple persistent volume claims (PVCs) within the same project can bind to the same PV. However, once a PVC binds to a PV, that PV cannot be bound by a claim outside of the first claim's project. If the underlying storage needs to be accessed by multiple projects, then each project needs its own PV, which can point to the same physical storage. In this sense, a bound PV is tied to a project. For a detailed PV and PVC example, see the guide for [WordPress and MySQL using NFS](#).

For the cluster administrator, granting pods access to PVs involves:

- knowing the group ID and/or user ID assigned to the actual storage,
- understanding SELinux considerations, and
- ensuring that these IDs are allowed in the range of legal IDs defined for the project and/or the SCC that matches the requirements of the pod.

Group IDs, the user ID, and SELinux values are defined in the **SecurityContext** section in a pod definition. Group IDs are global to the pod and apply to all containers defined in the pod. User IDs can also be global, or specific to each container. Four sections control access to volumes:

- **supplementalGroups**
- **fsGroup**
- **runAsUser**
- **seLinuxOptions**

## 24.16.2. SCCs, Defaults, and Allowed Ranges

SCCs influence whether or not a pod is given a default user ID, **fsGroup** ID, supplemental group ID, and SELinux label. They also influence whether or not IDs supplied in the pod definition (or in the image) will be validated against a range of allowable IDs. If validation is required and fails, then the pod will also fail.

SCCs define strategies, such as **runAsUser**, **supplementalGroups**, and **fsGroup**. These strategies help decide whether the pod is authorized. Strategy values set to **RunAsAny** are essentially stating that the pod can do what it wants regarding that strategy. Authorization is skipped for that strategy and no OpenShift Container Platform default is produced based on that strategy. Therefore, IDs and SELinux labels in the resulting container are based on container defaults instead of OpenShift Container Platform policies.

For a quick summary of **RunAsAny**:

- Any ID defined in the pod definition (or image) is allowed.
- Absence of an ID in the pod definition (and in the image) results in the container assigning an ID, which is **root** (0) for Docker.
- No SELinux labels are defined, so Docker will assign a unique label.

For these reasons, SCCs with **RunAsAny** for ID-related strategies should be protected so that ordinary developers do not have access to the SCC. On the other hand, SCC strategies set to **MustRunAs** or **MustRunAsRange** trigger ID validation (for ID-related strategies), and cause default values to be supplied by OpenShift Container Platform to the container when those values are not supplied directly in the pod definition or image.

### CAUTION

Allowing access to SCCs with a **RunAsAny FSGroup** strategy can also prevent users from accessing their block devices. Pods need to specify an **fsGroup** in order to take over their block devices. Normally, this is done when the SCC **FSGroup** strategy is set to **MustRunAs**. If a user's pod is assigned an SCC with a **RunAsAny FSGroup** strategy, then the user may face **permission denied** errors until they discover that they need to specify an **fsGroup** themselves.

SCCs may define the range of allowed IDs (user or groups). If range checking is required (for example, using **MustRunAs**) and the allowable range is not defined in the SCC, then the project determines the ID range. Therefore, projects support ranges of allowable ID. However, unlike SCCs, projects do not define strategies, such as **runAsUser**.

Allowable ranges are helpful not only because they define the boundaries for container IDs, but also because the minimum value in the range becomes the default value for the ID in question. For example, if the SCC ID strategy value is **MustRunAs**, the minimum value of an ID range is **100**, and the ID is absent from the pod definition, then 100 is provided as the default for this ID.

As part of pod admission, the SCCs available to a pod are examined (roughly, in priority order followed by most restrictive) to best match the requests of the pod. Setting a SCC's strategy type to **RunAsAny** is less restrictive, whereas a type of **MustRunAs** is more restrictive. All of these strategies are evaluated. To see which SCC was assigned to a pod, use the `oc get pod` command:

```
# oc get pod <pod_name> -o yaml
...
metadata:
  annotations:
    openshift.io/scc: nfs-scc ①
  name: nfs-pod1 ②
  namespace: default ③
...
```

- ① Name of the SCC that the pod used (in this case, a custom SCC).
- ② Name of the pod.
- ③ Name of the project. "Namespace" is interchangeable with "project" in OpenShift Container Platform. See [Projects and Users](#) for details.

It may not be immediately obvious which SCC was matched by a pod, so the command above can be very useful in understanding the UID, supplemental groups, and SELinux relabeling in a live container.

Any SCC with a strategy set to **RunAsAny** allows specific values for that strategy to be defined in the pod definition (and/or image). When this applies to the user ID (**runAsUser**) it is prudent to restrict access to the SCC to prevent a container from being able to run as root.

Because pods often match the **restricted** SCC, it is worth knowing the security this entails. The **restricted** SCC has the following characteristics:

- User IDs are constrained due to the **runAsUser** strategy being set to **MustRunAsRange**. This forces user ID validation.
- Because a range of allowable user IDs is not defined in the SCC (see `oc export scc restricted` for more details), the project's `openshift.io(sa.scc.uid-range)` range will be used for range checking and for a default ID, if needed.
- A default user ID is produced when a user ID is not specified in the pod definition and the matching SCC's **runAsUser** is set to **MustRunAsRange**.
- An SELinux label is required (`seLinuxContext` set to **MustRunAs**), which uses the project's default MCS label.

- **fsGroup** IDs are constrained to a single value due to the **FSGroup** strategy being set to **MustRunAs**, which dictates that the value to use is the minimum value of the first range specified.
- Because a range of allowable **fsGroup** IDs is not defined in the SCC, the minimum value of the project's **openshift.io(sa.scc.supplemental-groups)** range (or the same range used for user IDs) will be used for validation and for a default ID, if needed.
- A default **fsGroup** ID is produced when a **fsGroup** ID is not specified in the pod and the matching SCC's **FSGroup** is set to **MustRunAs**.
- Arbitrary supplemental group IDs are allowed because no range checking is required. This is a result of the **supplementalGroups** strategy being set to **RunAsAny**.
- Default supplemental groups are not produced for the running pod due to **RunAsAny** for the two group strategies above. Therefore, if no groups are defined in the pod definition (or in the image), the container(s) will have no supplemental groups predefined.

The following shows the **default** project and a custom SCC (**my-custom-scc**), which summarizes the interactions of the SCC and the project:

```
$ oc get project default -o yaml ①
...
metadata:
  annotations: ②
    openshift.io/sa.scc.mcs: s0:c1,c0 ③
    openshift.io/sa.scc.supplemental-groups: 1000000000/10000 ④
    openshift.io/sa.scc.uid-range: 1000000000/10000 ⑤

$ oc get scc my-custom-scc -o yaml
...
fsGroup:
  type: MustRunAs ⑥
  ranges:
  - min: 5000
    max: 6000
runAsUser:
  type: MustRunAsRange ⑦
  uidRangeMin: 1000100000
  uidRangeMax: 1000100999
seLinuxContext: ⑧
  type: MustRunAs
  SELinuxOptions: ⑨
    user: <selinux-user-name>
    role: ...
    type: ...
    level: ...
supplementalGroups:
  type: MustRunAs ⑩
  ranges:
  - min: 5000
    max: 6000
```


① **default** is the name of the project.

- 2 Default values are only produced when the corresponding SCC strategy is not **RunAsAny**.
- 3 SELinux default when not defined in the pod definition or in the SCC.
- 4 Range of allowable group IDs. ID validation only occurs when the SCC strategy is **RunAsAny**. There can be more than one range specified, separated by commas. See below for [supported formats](#).
- 5 Same as <4> but for user IDs. Also, only a single range of user IDs is supported.
- 6 10 **MustRunAs** enforces group ID range checking and provides the container's groups default. Based on this SCC definition, the default is 5000 (the minimum ID value). If the range was omitted from the SCC, then the default would be 1000000000 (derived from the project). The other supported type, **RunAsAny**, does not perform range checking, thus allowing any group ID, and produces no default groups.
- 7 **MustRunAsRange** enforces user ID range checking and provides a UID default. Based on this SCC, the default UID is 1000100000 (the minimum value). If the minimum and maximum range were omitted from the SCC, the default user ID would be 1000000000 (derived from the project). **MustRunAsNonRoot** and **RunAsAny** are the other supported types. The range of allowed IDs can be defined to include any user IDs required for the target storage.
- 8 When set to **MustRunAs**, the container is created with the SCC's SELinux options, or the MCS default defined in the project. A type of **RunAsAny** indicates that SELinux context is not required, and, if not defined in the pod, is not set in the container.
- 9 The SELinux user name, role name, type, and labels can be defined here.

Two formats are supported for allowed ranges:

1. **M/N**, where **M** is the starting ID and **N** is the count, so the range becomes **M** through (and including) **M+N-1**.
2. **M-N**, where **M** is again the starting ID and **N** is the ending ID. The default group ID is the starting ID in the first range, which is **1000000000** in this project. If the SCC did not define a minimum group ID, then the project's default ID is applied.

### 24.16.3. Supplemental Groups



#### NOTE

Read [SCCs, Defaults, and Allowed Ranges](#) before working with supplemental groups.

#### TIP

It is generally preferable to use group IDs (supplemental or [fsGroup](#)) to gain access to persistent storage versus using [user IDs](#).

Supplemental groups are regular Linux groups. When a process runs in Linux, it has a UID, a GID, and one or more supplemental groups. These attributes can be set for a container's main process. The **supplementalGroups** IDs are typically used for controlling access to shared storage, such as NFS and GlusterFS, whereas [fsGroup](#) is used for controlling access to block storage, such as Ceph RBD and iSCSI.

The OpenShift Container Platform shared storage plug-ins mount volumes such that the POSIX permissions on the mount match the permissions on the target storage. For example, if the target storage's owner ID is **1234** and its group ID is **5678**, then the mount on the host node and in the container will have those same IDs. Therefore, the container's main process must match one or both of those IDs in order to access the volume.

For example, consider the following NFS export.

On an OpenShift Container Platform node:



### NOTE

**showmount** requires access to the ports used by **rpcbind** and **rpc.mount** on the NFS server

```
# showmount -e <nfs-server-ip-or-hostname>
Export list for f21-nfs.vm:
/opt/nfs *
```

On the NFS server:

```
# cat /etc/exports
/opt/nfs *(rw,sync,root_squash)
...

# ls -lZ /opt/nfs -d
drwx----- 1000100001 5555 unconfined_u:object_r:usr_t:s0 /opt/nfs
```

The **/opt/nfs** export is accessible by UID **1000100001** and the group **5555**. In general, containers should not run as root. So, in this NFS example, containers which are not run as UID **1000100001** and are not members the group **5555** will not have access to the NFS export.

Often, the SCC matching the pod does not allow a specific user ID to be specified, thus using supplemental groups is a more flexible way to grant storage access to a pod. For example, to grant NFS access to the export above, the group **5555** can be defined in the pod definition:

```
apiVersion: v1
kind: Pod
...
spec:
  containers:
    - name: ...
      volumeMounts:
        - name: nfs 1
          mountPath: /usr/share/... 2
      securityContext: 3
        supplementalGroups: [5555] 4
  volumes:
    - name: nfs 5
      nfs:
        server: <nfs_server_ip_or_host>
        path: /opt/nfs 6
```

- 1 Name of the volume mount. Must match the name in the **volumes** section.
- 2 NFS export path as seen in the container.
- 3 Pod global security context. Applies to all containers inside the pod. Each container can also define its **securityContext**, however group IDs are global to the pod and cannot be defined for individual containers.
- 4 Supplemental groups, which is an array of IDs, is set to 5555. This grants group access to the export.
- 5 Name of the volume. Must match the name in the **volumeMounts** section.
- 6 Actual NFS export path on the NFS server.

All containers in the above pod (assuming the matching SCC or project allows the group **5555**) will be members of the group **5555** and have access to the volume, regardless of the container's user ID. However, the assumption above is critical. Sometimes, the SCC does not define a range of allowable group IDs but instead requires group ID validation (a result of **supplementalGroups** set to **MustRunAs**). Note that this is **not** the case for the **restricted** SCC. The project will not likely allow a group ID of **5555**, unless the project has been customized to access this NFS export. So, in this scenario, the above pod will fail because its group ID of **5555** is not within the SCC's or the project's range of allowed group IDs.

### Supplemental Groups and Custom SCCs

To remedy the situation in [the previous example](#), a custom SCC can be created such that:

- a minimum and max group ID are defined,
- ID range checking is enforced, and
- the group ID of **5555** is allowed.

It is often better to create a new SCC rather than modifying a predefined SCC, or changing the range of allowed IDs in the predefined projects.

The easiest way to create a new SCC is to export an existing SCC and customize the YAML file to meet the requirements of the new SCC. For example:

1. Use the **restricted** SCC as a template for the new SCC:

```
$ oc export scc restricted > new-scc.yaml
```

2. Edit the **new-scc.yaml** file to your desired specifications.

3. Create the new SCC:

```
$ oc create -f new-scc.yaml
```



#### NOTE

The **oc edit scc** command can be used to modify an instantiated SCC.

Here is a fragment of a new SCC named **nfs-scc**:

```
$ oc export scc nfs-scc

allowHostDirVolumePlugin: false ①
...
kind: SecurityContextConstraints
metadata:
  ...
    name: nfs-scc ②
priority: 9 ③
...
supplementalGroups:
  type: MustRunAs ④
  ranges:
    - min: 5000 ⑤
      max: 6000
...
...
```

- ① The **allow** booleans are the same as for the **restricted** SCC.
- ② Name of the new SCC.
- ③ Numerically larger numbers have greater priority. Nil or omitted is the lowest priority. Higher priority SCCs sort before lower priority SCCs and thus have a better chance of matching a new pod.
- ④ **supplementalGroups** is a strategy and it is set to **MustRunAs**, which means group ID checking is required.
- ⑤ Multiple ranges are supported. The allowed group ID range here is 5000 through 5999, with the default supplemental group being 5000.

When the same pod shown earlier runs against this new SCC (assuming, of course, the pod matches the new SCC), it will start because the group **5555**, supplied in the pod definition, is now allowed by the custom SCC.

#### 24.16.4. **fsGroup**



##### NOTE

Read [SCCs, Defaults, and Allowed Ranges](#) before working with supplemental groups.

##### TIP

It is generally preferable to use group IDs ([supplemental](#) or **fsGroup**) to gain access to persistent storage versus using [user IDs](#).

**fsGroup** defines a pod's "file system group" ID, which is added to the container's supplemental groups. The **supplementalGroups** ID applies to shared storage, whereas the **fsGroup** ID is used for block storage.

Block storage, such as Ceph RBD, iSCSI, and various cloud storage, is typically dedicated to a single

pod which has requested the block storage volume, either directly or using a PVC. Unlike shared storage, block storage is taken over by a pod, meaning that user and group IDs supplied in the pod definition (or image) are applied to the actual, physical block device. Typically, block storage is not shared.

A **fsGroup** definition is shown below in the following pod definition fragment:

```
kind: Pod
...
spec:
  containers:
    - name: ...
      securityContext: ①
        fsGroup: 5555 ②
      ...

```

- ① As with **supplementalGroups**, **fsGroup** must be defined globally to the pod, not per container.
- ② 5555 will become the group ID for the volume's group permissions and for all new files created in the volume.

As with **supplementalGroups**, all containers in the above pod (assuming the matching SCC or project allows the group **5555**) will be members of the group **5555**, and will have access to the block volume, regardless of the container's user ID. If the pod matches the **restricted** SCC, whose **fsGroup** strategy is **MustRunAs**, then the pod will fail to run. However, if the SCC has its **fsGroup** strategy set to **RunAsAny**, then any **fsGroup** ID (including **5555**) will be accepted. Note that if the SCC has its **fsGroup** strategy set to **RunAsAny** and no **fsGroup** ID is specified, the "taking over" of the block storage does not occur and permissions may be denied to the pod.

### fsGroups and Custom SCCs

To remedy the situation in the previous example, a custom SCC can be created such that:

- a minimum and maximum group ID are defined,
- ID range checking is enforced, and
- the group ID of **5555** is allowed.

It is better to create new SCCs versus modifying a predefined SCC, or changing the range of allowed IDs in the predefined projects.

Consider the following fragment of a new SCC definition:

```
# oc export scc new-scc
...
kind: SecurityContextConstraints
...
fsGroup:
  type: MustRunAs ①
  ranges: ②
    - max: 6000
    min: 5000 ③
  ...

```

- 1 **MustRunAs** triggers group ID range checking, whereas **RunAsAny** does not require range checking.
- 2 The range of allowed group IDs is 5000 through, and including, 5999. Multiple ranges are supported but not used. The allowed group ID range here is 5000 through 5999, with the default **fsGroup** being 5000.
- 3 The minimum value (or the entire range) can be omitted from the SCC, and thus range checking and generating a default value will defer to the project's **openshift.io/sa.scc.supplemental-groups** range. **fsGroup** and **supplementalGroups** use the same group field in the project; there is not a separate range for **fsGroup**.

When the pod shown above runs against this new SCC (assuming, of course, the pod matches the new SCC), it will start because the group **5555**, supplied in the pod definition, is allowed by the custom SCC. Additionally, the pod will "take over" the block device, so when the block storage is viewed by a process outside of the pod, it will actually have **5555** as its group ID.

A list of volumes supporting block ownership include:

- AWS Elastic Block Store
- OpenStack Cinder
- Ceph RBD
- GCE Persistent Disk
- iSCSI
- emptyDir
- gitRepo



#### NOTE

This list is potentially incomplete.

### 24.16.5. User IDs



#### NOTE

Read [SCCs, Defaults, and Allowed Ranges](#) before working with supplemental groups.

#### TIP

It is generally preferable to use group IDs ([supplemental](#) or [fsGroup](#)) to gain access to persistent storage versus using user IDs.

User IDs can be defined in the container image or in the pod definition. In the pod definition, a single user ID can be defined globally to all containers, or specific to individual containers (or both). A user ID is supplied as shown in the pod definition fragment below:

```
spec:  
  containers:
```

```

- name: ...
  securityContext:
    runAsUser: 1000100001

```

ID 1000100001 in the above is container-specific and matches the owner ID on the export. If the NFS export's owner ID was **54321**, then that number would be used in the pod definition. Specifying **securityContext** outside of the container definition makes the ID global to all containers in the pod.

Similar to group IDs, user IDs may be validated according to policies set in the SCC and/or project. If the SCC's **runAsUser** strategy is set to **RunAsAny**, then any user ID defined in the pod definition or in the image is allowed.



### WARNING

This means even a UID of **0** (root) is allowed.

If, instead, the **runAsUser** strategy is set to **MustRunAsRange**, then a supplied user ID will be validated against a range of allowed IDs. If the pod supplies no user ID, then the default ID is set to the minimum value of the range of allowable user IDs.

Returning to the earlier [NFS example](#), the container needs its UID set to **1000100001**, which is shown in the pod fragment above. Assuming the **default** project and the **restricted** SCC, the pod's requested user ID of 1000100001 will not be allowed, and therefore the pod will fail. The pod fails because:

- it requests **1000100001** as its user ID,
- all available SCCs use **MustRunAsRange** for their **runAsUser** strategy, so UID range checking is required, and
- **1000100001** is not included in the SCC or in the project's user ID range.

To remedy this situation, a new SCC can be created with the appropriate user ID range. A new project could also be created with the appropriate user ID range defined. There are also other, less-preferred options:

- The **restricted** SCC could be modified to include **1000100001** within its minimum and maximum user ID range. This is not recommended as you should avoid modifying the predefined SCCs if possible.
- The **restricted** SCC could be modified to use **RunAsAny** for the **runAsUser** value, thus eliminating ID range checking. This is *strongly* not recommended, as containers could run as root.
- The **default** project's UID range could be changed to allow a user ID of **1000100001**. This is not generally advisable because only a single range of user IDs can be specified, and thus other pods may not run if the range is altered.

## User IDs and Custom SCCs

It is good practice to avoid modifying the predefined SCCs if possible. The preferred approach is to create a custom SCC that better fits an organization's security needs, or [create a new project](#) that supports the desired user IDs.

To remedy the situation in the previous example, a custom SCC can be created such that:

- a minimum and maximum user ID is defined,
- UID range checking is still enforced, and
- the UID of **1000100001** is allowed.

For example:

```
$ oc export scc nfs-scc

allowHostDirVolumePlugin: false ①
...
kind: SecurityContextConstraints
metadata:
...
  name: nfs-scc ②
priority: 9 ③
requiredDropCapabilities: null
runAsUser:
  type: MustRunAsRange ④
  uidRangeMax: 1000100001 ⑤
  uidRangeMin: 1000100001
...
```

- ① The **allowXX** bools are the same as for the **restricted** SCC.
- ② The name of this new SCC is **nfs-scc**.
- ③ Numerically larger numbers have greater priority. Nil or omitted is the lowest priority. Higher priority SCCs sort before lower priority SCCs, and thus have a better chance of matching a new pod.
- ④ The **runAsUser** strategy is set to **MustRunAsRange**, which means UID range checking is enforced.
- ⑤ The UID range is 1000100001 through 1000100001 (a range of one value).

Now, with **runAsUser: 1000100001** shown in the previous pod definition fragment, the pod matches the new **nfs-scc** and is able to run with a UID of 1000100001.

## 24.16.6. SELinux Options

All predefined SCCs, except for the **privileged** SCC, set the **seLinuxContext** to **MustRunAs**. So the SCCs most likely to match a pod's requirements will force the pod to use an SELinux policy. The SELinux policy used by the pod can be defined in the pod itself, in the image, in the SCC, or in the project (which provides the default).

SELinux labels can be defined in a pod's **securityContext.seLinuxOptions** section, and supports **user**, **role**, **type**, and **level**:

**NOTE**

Level and MCS label are used interchangeably in this topic.

```
...
  securityContext: 1
    seLinuxOptions:
      level: "s0:c123,c456" 2
...

```

- 1** **level** can be defined globally for the entire pod, or individually for each container.
- 2** SELinux level label.

Here are fragments from an SCC and from the **default** project:

```
$ oc export scc scc-name
...
seLinuxContext:
  type: MustRunAs 1

# oc export project default
...
metadata:
  annotations:
    openshift.io/sa.scc.mcs: s0:c1,c0 2
...

```

- 1** **MustRunAs** causes volume relabeling.
- 2** If the label is not provided in the pod or in the SCC, then the default comes from the project.

All predefined SCCs, except for the **privileged** SCC, set the **seLinuxContext** to **MustRunAs**. This forces pods to use MCS labels, which can be defined in the pod definition, the image, or provided as a default.

The SCC determines whether or not to require an SELinux label and can provide a default label. If the **seLinuxContext** strategy is set to **MustRunAs** and the pod (or image) does not define a label, OpenShift Container Platform defaults to a label chosen from the SCC itself or from the project.

If **seLinuxContext** is set to **RunAsAny**, then no default labels are provided, and the container determines the final label. In the case of Docker, the container will use a unique MCS label, which will not likely match the labeling on existing storage mounts. Volumes which support SELinux management will be relabeled so that they are accessible by the specified label and, depending on how exclusionary the label is, only that label.

This means two things for unprivileged containers:

- The volume will be given a **type** which is accessible by unprivileged containers. This type is usually **container\_file\_t**, which treats volumes as container content. Previously, the label specified was **svirt\_sandbox\_file\_t**. This label is no longer used due to security concerns.
- If a **level** is specified, the volume will be labeled with the given MCS label.

For a volume to be accessible by a pod, the pod must have both categories of the volume. So a pod with **s0:c1,c2** will be able to access a volume with **s0:c1,c2**. A volume with **s0** will be accessible by all pods.

If pods fail authorization, or if the storage mount is failing due to permissions errors, then there is a possibility that SELinux enforcement is interfering. One way to check for this is to run:

```
# ausearch -m avc --start recent
```

This examines the log file for AVC (Access Vector Cache) errors.

## 24.17. SELECTOR-LABEL VOLUME BINDING

### 24.17.1. Overview

This guide provides the steps necessary to enable binding of persistent volume claims (PVCs) to persistent volumes (PVs) via **selector** and **label** attributes. By implementing selectors and labels, regular users are able to target [provisioned storage](#) by identifiers defined by a cluster administrator.

### 24.17.2. Motivation

In cases of statically provisioned storage, developers seeking persistent storage are required to know a handful identifying attributes of a PV in order to deploy and bind a PVC. This creates several problematic situations. Regular users might have to contact a cluster administrator to either deploy the PVC or provide the PV values. PV attributes alone do not convey the intended use of the storage volumes, nor do they provide methods by which volumes can be grouped.

Selector and label attributes can be used to abstract away PV details from the user while providing cluster administrators a way of identifying volumes by a descriptive and customizable tag. Through the selector-label method of binding, users are only required to know which labels are defined by the administrator.



#### NOTE

The selector-label feature is currently only available for *statically* provisioned storage and is currently not implemented for storage provisioned dynamically.

### 24.17.3. Deployment

This section reviews how to define and deploy PVCs.

#### 24.17.3.1. Prerequisites

1. A running OpenShift Container Platform 3.3+ cluster
2. A volume provided by a supported [storage provider](#)
3. A user with a cluster-admin role binding

#### 24.17.3.2. Define the Persistent Volume and Claim

1. As the **cluster-admin** user, define the PV. For this example, we will be using a [GlusterFS](#) volume. See the appropriate [storage provider](#) for your provider's configuration.

##### Example 24.9. Persistent Volume with Labels

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-volume
  labels: ①
    volume-type: ssd
    aws-availability-zone: us-east-1
spec:
  capacity:
    storage: 2Gi
  accessModes:
    - ReadWriteMany
  glusterfs:
    endpoints: glusterfs-cluster
    path: myVol1
    readOnly: false
  persistentVolumeReclaimPolicy: Recycle

```

- ① A PVC whose selectors match *all* of a PV's labels will be bound, assuming a PV is available.

## 2. Define the PVC:

### Example 24.10. Persistent Volume Claim with Selectors

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 1Gi
  selector: ①
    matchLabels: ②
      volume-type: ssd
      aws-availability-zone: us-east-1

```

- ① Begin **selectors** section.
- ② List all labels by which the user is requesting storage. Must match *all* labels of targeted PV.

### 24.17.3.3. Deploy the Persistent Volume and Claim

As the **cluster-admin** user, create the persistent volume:

### Example 24.11. Create the Persistent Volume

```
# oc create -f gluster-pv.yaml
persistentVolume "gluster-volume" created

# oc get pv
NAME          LABELS      CAPACITY   ACCESSMODES   STATUS
CLAIM        REASON     AGE
gluster-volume          map[]    2147483648   RWX
Available                               2s
```

Once the PV is created, any user whose selectors match *all* its labels can create their PVC.

#### Example 24.12. Create the Persistent Volume Claim

```
# oc create -f gluster-pvc.yaml
persistentVolumeClaim "gluster-claim" created
# oc get pvc
NAME          LABELS      STATUS      VOLUME
gluster-claim          Bound      gluster-volume
```

## 24.18. ENABLING CONTROLLER-MANAGED ATTACHMENT AND DETACHMENT

### 24.18.1. Overview

As of OpenShift Container Platform 3.4, administrators can enable the controller running on the cluster's master to manage volume attach and detach operations on behalf of a set of nodes, as opposed to letting them manage their own volume attach and detach operations.

Enabling controller-managed attachment and detachment has the following benefits:

- If a node is lost, volumes that were attached to it can be detached by the controller and reattached elsewhere.
- Credentials for attaching and detaching do not need to be made present on every node, improving security.

As of OpenShift Container Platform 3.6, controller-managed attachment and detachment is the default setting.

### 24.18.2. Determining What Is Managing Attachment and Detachment

If a node has set the annotation `volumes.kubernetes.io/controller-managed-attach-detach` on itself, then its attach and detach operations are being managed by the controller. The controller will automatically inspect all nodes for this annotation and act according to whether it is present or not. Therefore, you may inspect the node for this annotation to determine if it has enabled controller-managed attach and detach.

To further ensure that the node is opting for controller-managed attachment and detachment, its logs can be searched for the following line:

Setting node annotation to enable volume controller attach/detach

If the above line is not found, the logs should instead contain:

```
Controller attach/detach is disabled for this node; Kubelet will attach  
and detach volumes
```

To check from the controller's end that it is managing a particular node's attach and detach operations, the logging level must first be set to at least **4**. Then, the following line should be found:

```
processVolumesInUse for node <node_hostname>
```

For information on how to view logs and configure logging levels, see [Configuring Logging Levels](#).

### 24.18.3. Configuring Nodes to Enable Controller-managed Attachment and Detachment

Enabling controller-managed attachment and detachment is done by configuring individual nodes to opt in and disable their own node-level attachment and detachment management. See [Node Configuration Files](#) for information on what node configuration file to edit and add the following:

```
kubeletArguments:  
  enable-controller-attach-detach:  
    - "true"
```

Once a node is configured, it must be restarted for the setting to take effect.

## 24.19. PERSISTENT VOLUME SNAPSHOTTS

### 24.19.1. Overview



#### IMPORTANT

Persistent Volume Snapshots are a Technology Preview feature. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offering/techpreview/>.

Many storage systems provide the ability to create "snapshots" of a persistent volume (PV) to protect against data loss. The external snapshot controller and provisioner provide means to use the feature in the OpenShift Container Platform cluster and handle volume snapshots through the OpenShift Container Platform API.

This document describes the current state of volume snapshot support in OpenShift Container Platform. Familiarity with [PVs](#), [persistent volume claims \(PVCs\)](#), and [dynamic provisioning](#) is recommended.

### 24.19.2. Features

- Create snapshot of a **PersistentVolume** bound to a **PersistentVolumeClaim**

- List existing **VolumeSnapshots**
- Delete existing **VolumeSnapshot**
- Create a new **PersistentVolume** from an existing **VolumeSnapshot**
- Supported **PersistentVolume** types:
  - AWS Elastic Block Store (EBS)
  - Google Compute Engine (GCE) Persistent Disk (PD)

### 24.19.3. Installation and Setup

The external controller and provisioner are the external components that provide volume snapshotting. These external components run in the cluster. The controller is responsible for creating, deleting, and reporting events on volume snapshots. The provisioner creates new **PersistentVolumes** from the volume snapshots. See [Create Snapshot](#) and [Restore Snapshot](#) for more information.

#### 24.19.3.1. Starting the External Controller and Provisioner

The external controller and provisioner services are distributed as container images and can be run in the OpenShift Container Platform cluster as usual. There are also RPM versions for the controller and provisioner.

To allow the containers managing the API objects, the necessary role-based access control (RBAC) rules need to be configured by the administrator:

1. Create a **ServiceAccount** and **ClusterRole**:

```
apiVersion: v1
kind: ServiceAccount
metadata:
  name: snapshot-controller-runner
  kind: ClusterRole
  apiVersion: rbac.authorization.k8s.io/v1
  metadata:
    name: snapshot-controller-role
  rules:
    - apiGroups: []
      resources: ["persistentvolumes"]
      verbs: ["get", "list", "watch", "create", "delete"]
    - apiGroups: []
      resources: ["persistentvolumeclaims"]
      verbs: ["get", "list", "watch", "update"]
    - apiGroups: ["storage.k8s.io"]
      resources: ["storageclasses"]
      verbs: ["get", "list", "watch"]
    - apiGroups: []
      resources: ["events"]
      verbs: ["list", "watch", "create", "update", "patch"]
    - apiGroups: ["apiextensions.k8s.io"]
      resources: ["customresourcedefinitions"]
      verbs: ["create", "list", "watch", "delete"]
    - apiGroups: ["volumesnapshot.external-storage.k8s.io"]
      resources: ["volumesnapshots"]
```

```

    verbs: ["get", "list", "watch", "create", "update", "patch",
"delete"]
- apiGroups: ["volumesnapshot.external-storage.k8s.io"]
  resources: ["volumesnapshotdatas"]
    verbs: ["get", "list", "watch", "create", "update", "patch",
"delete"]

```

2. Bind the rules via **ClusterRoleBinding**:

```

apiVersion: rbac.authorization.k8s.io/v1beta1
kind: ClusterRoleBinding
metadata:
  name: snapshot-controller
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
  name: snapshot-controller-role
subjects:
- kind: ServiceAccount
  name: snapshot-controller-runner
  namespace: default

```

If the external controller and provisioner are deployed in Amazon Web Services (AWS), they must be able to authenticate using the access key. To provide the credential to the pod, the administrator creates a new secret:

```

apiVersion: v1
kind: Secret
metadata:
  name: awskeys
type: Opaque
data:
  access-key-id: <base64 encoded AWS_ACCESS_KEY_ID>
  secret-access-key: <base64 encoded AWS_SECRET_ACCESS_KEY>

```

The AWS deployment of the external controller and provisioner containers (note that both pod containers use the secret to access the AWS cloud provider API):

```

kind: Deployment
apiVersion: extensions/v1beta1
metadata:
  name: snapshot-controller
spec:
  replicas: 1
  strategy:
    type: Recreate
  template:
    metadata:
      labels:
        app: snapshot-controller
  spec:
    serviceAccountName: snapshot-controller-runner
    containers:
      - name: snapshot-controller
        image: "registry.access.redhat.com/openshift3/snapshot-

```

```

controller:latest"
    imagePullPolicy: "IfNotPresent"
    args: ["-cloudprovider", "aws"]
    env:
      - name: AWS_ACCESS_KEY_ID
        valueFrom:
          secretKeyRef:
            name: awskeys
            key: access-key-id
      - name: AWS_SECRET_ACCESS_KEY
        valueFrom:
          secretKeyRef:
            name: awskeys
            key: secret-access-key
      - name: snapshot-provisioner
        image: "registry.access.redhat.com/openshift3/snapshot-
provisioner:latest"
          imagePullPolicy: "IfNotPresent"
          args: ["-cloudprovider", "aws"]
          env:
            - name: AWS_ACCESS_KEY_ID
              valueFrom:
                secretKeyRef:
                  name: awskeys
                  key: access-key-id
            - name: AWS_SECRET_ACCESS_KEY
              valueFrom:
                secretKeyRef:
                  name: awskeys
                  key: secret-access-key

```

For GCE, there is no need to use secrets to access the GCE cloud provider API. The administrator can proceed with the deployment:

```

kind: Deployment
apiVersion: extensions/v1beta1
metadata:
  name: snapshot-controller
spec:
  replicas: 1
  strategy:
    type: Recreate
  template:
    metadata:
      labels:
        app: snapshot-controller
  spec:
    serviceAccountName: snapshot-controller-runner
    containers:
      - name: snapshot-controller
        image: "registry.access.redhat.com/openshift3/snapshot-
controller:latest"
          imagePullPolicy: "IfNotPresent"
          args: ["-cloudprovider", "gce"]
      - name: snapshot-provisioner
        image: "registry.access.redhat.com/openshift3/snapshot-

```

```

provisioner:latest"
    imagePullPolicy: "IfNotPresent"
    args: ["-cloudprovider", "gce"]

```

### 24.19.3.2. Managing Snapshot Users

Depending on the cluster configuration, it might be necessary to allow non-administrator users to manipulate the **VolumeSnapshot** objects on the API server. This can be done by creating a **ClusterRole** bound to a particular user or group.

For example, assume the user 'alice' needs to work with snapshots in the cluster. The cluster administrator completes the following steps:

1. Define a new **ClusterRole**:

```

apiVersion: v1
kind: ClusterRole
metadata:
  name: volumesnapshot-admin
rules:
- apiGroups:
  - "volumesnapshot.external-storage.k8s.io"
  attributeRestrictions: null
  resources:
  - volumesnapshots
  verbs:
  - create
  - delete
  - deletecollection
  - get
  - list
  - patch
  - update
  - watch

```

2. Bind the cluster role to the user 'alice' by creating a **ClusterRoleBinding** object:

```

apiVersion: rbac.authorization.k8s.io/v1beta1
kind: ClusterRoleBinding
metadata:
  name: volumesnapshot-admin
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
  name: volumesnapshot-admin
subjects:
- kind: User
  name: alice

```



#### NOTE

This is only an example of API access configuration. The **VolumeSnapshot** objects behave similar to other OpenShift Container Platform API objects. See the [API access control documentation](#) for more information on managing the API RBAC.

## 24.19.4. Lifecycle of a Volume Snapshot and Volume Snapshot Data

### 24.19.4.1. Persistent Volume Claim and Persistent Volume

The **PersistentVolumeClaim** is bound to a **PersistentVolume**. The **PersistentVolume** type must be one of the snapshot supported persistent volume types.

#### 24.19.4.1.1. Snapshot Promoter

To create a **StorageClass**:

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: snapshot-promoter
  provisioner: volumesnapshot.external-storage.k8s.io/snapshot-promoter
```

This **StorageClass** is necessary to restore a **PersistentVolume** from a **VolumeSnapshot** that was previously created.

### 24.19.4.2. Create Snapshot

To take a snapshot of a PV, create a new **VolumeSnapshot** object:

```
apiVersion: volumesnapshot.external-storage.k8s.io/v1
kind: VolumeSnapshot
metadata:
  name: snapshot-demo
spec:
  persistentVolumeClaimName: ebs-pvc
```

**persistentVolumeClaimName** is the name of the **PersistentVolumeClaim** bound to a **PersistentVolume**. This particular PV is snapshotted.

A **VolumeSnapshotData** object is then automatically created based on the **VolumeSnapshot**. The relationship between **VolumeSnapshot** and **VolumeSnapshotData** is similar to the relationship between **PersistentVolumeClaim** and **PersistentVolume**.

Depending on the PV type, the operation might go through several phases, which are reflected by the **VolumeSnapshot** status:

1. The new **VolumeSnapshot** object is created.
2. The controller starts the snapshot operation. The snapshotted **PersistentVolume** might need to be frozen and the applications paused.
3. The storage system finishes creating the snapshot (the snapshot is "cut") and the snapshotted **PersistentVolume** might return to normal operation. The snapshot itself is not yet ready. The last status condition is of **Pending** type with status value **True**. A new **VolumeSnapshotData** object is created to represent the actual snapshot.
4. The newly created snapshot is complete and ready to use. The last status condition is of **Ready** type with status value **True**.

**IMPORTANT**

It is the user's responsibility to ensure data consistency (stop the pod/application, flush caches, freeze the file system, and so on).

**NOTE**

In case of error, the **VolumeSnapshot** status is appended with an **Error** condition.

To display the **VolumeSnapshot** status:

```
$ oc get volumesnapshot -o yaml
```

The status is displayed.

```
apiVersion: volumesnapshot.external-storage.k8s.io/v1
kind: VolumeSnapshot
metadata:
  clusterName: ""
  creationTimestamp: 2017-09-19T13:58:28Z
  generation: 0
  labels:
    Timestamp: "1505829508178510973"
  name: snapshot-demo
  namespace: default
  resourceVersion: "780"
  selfLink: /apis/volumesnapshot.external-
storage.k8s.io/v1/namespaces/default/volumesnapshots/snapshot-demo
  uid: 9cc5da57-9d42-11e7-9b25-90b11c132b3f
spec:
  persistentVolumeClaimName: ebs-pvc
  snapshotDataName: k8s-volume-snapshot-9cc8813e-9d42-11e7-8bed-
90b11c132b3f
status:
  conditions:
  - lastTransitionTime: null
    message: Snapshot created successfully
    reason: ""
    status: "True"
    type: Ready
  creationTimestamp: null
```

#### 24.19.4.3. Restore Snapshot

To restore a PV from a **VolumeSnapshot**, create a PVC:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: snapshot-pv-provisioning-demo
  annotations:
    snapshot.alpha.kubernetes.io/snapshot: snapshot-demo
spec:
  storageClassName: snapshot-promoter
```

- **annotations: snapshot.alpha.kubernetes.io/snapshot** is the name of the **VolumeSnapshot** to be restored. **storageClassName: StorageClass** is created by the administrator for restoring **VolumeSnapshots**.

A new **PersistentVolume** is created and bound to the **PersistentVolumeClaim**. The process may take several minutes depending on the PV type.

#### 24.19.4.4. Delete Snapshot

To delete a **snapshot - demo**:

```
$ oc delete volumesnapshot/snapshot-demo
```

The **VolumeSnapshotData** bound to the **VolumeSnapshot** is automatically deleted.

# CHAPTER 25. PERSISTENT STORAGE EXAMPLES

## 25.1. OVERVIEW

The following sections provide detailed, comprehensive instructions on setting up and configuring common storage use cases. These examples cover both the administration of persistent volumes and their security, and how to claim against the volumes as a user of the system.

- [Sharing an NFS PV Across Two Pods](#)
- [Ceph-RBD Block Storage Volume](#)
- [Shared Storage Using a GlusterFS Volume](#)
- [Dynamic Provisioning Storage Using GlusterFS](#)
- [Mounting a PV to Privileged Pods](#)
- [Backing Docker Registry with GlusterFS Storage](#)
- [Binding Persistent Volumes by Labels](#)
- [Using StorageClasses for Dynamic Provisioning](#)
- [Using StorageClasses for Existing Legacy Storage](#)
- [Configuring Azure Blob Storage for Integrated Docker Registry](#)

## 25.2. SHARING AN NFS MOUNT ACROSS TWO PERSISTENT VOLUME CLAIMS

### 25.2.1. Overview

The following use case describes how a cluster administrator wanting to leverage shared storage for use by two separate containers would configure the solution. This example highlights the use of NFS, but can easily be adapted to other shared storage types, such as GlusterFS. In addition, this example will show configuration of pod security as it relates to shared storage.

[Persistent Storage Using NFS](#) provides an explanation of persistent volumes (PVs), persistent volume claims (PVCs), and using NFS as persistent storage. This topic shows an end-to-end example of using an existing NFS cluster and OpenShift Container Platform persistent store, and assumes an existing NFS server and exports exist in your OpenShift Container Platform infrastructure.



#### NOTE

All `oc` commands are executed on the OpenShift Container Platform master host.

### 25.2.2. Creating the Persistent Volume

Before creating the PV object in OpenShift Container Platform, the persistent volume (PV) file is defined:

#### Example 25.1. Persistent Volume Object Definition Using NFS

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: nfs-pv ①
spec:
  capacity:
    storage: 1Gi ②
  accessModes:
    - ReadWriteMany ③
  persistentVolumeReclaimPolicy: Retain ④
  nfs: ⑤
    path: /opt/nfs ⑥
    server: nfs.f22 ⑦
    readOnly: false

```

- ① The name of the PV, which is referenced in pod definitions or displayed in various **oc** volume commands.
- ② The amount of storage allocated to this volume.
- ③ **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control.
- ④ The volume reclaim policy **Retain** indicates that the volume will be preserved after the pods accessing it terminates.
- ⑤ This defines the volume type being used, in this case the **NFS** plug-in.
- ⑥ This is the NFS mount path.
- ⑦ This is the NFS server. This can also be specified by IP address.

Save the PV definition to a file, for example ***nfs-pv.yaml***, and create the persistent volume:

```
# oc create -f nfs-pv.yaml
persistentvolume "nfs-pv" created
```

Verify that the persistent volume was created:

```
# oc get pv
NAME      LABELS      CAPACITY      ACCESSMODES      STATUS      CLAIM
REASON    AGE
nfs-pv    <none>     1Gi          RWX           Available
37s
```

### 25.2.3. Creating the Persistent Volume Claim

A persistent volume claim (PVC) specifies the desired access mode and storage capacity. Currently, based on only these two attributes, a PVC is bound to a single PV. Once a PV is bound to a PVC, that PV is essentially tied to the PVC's project and cannot be bound to by another PVC. There is a one-to-

one mapping of PVs and PVCs. However, multiple pods in the same project can use the same PVC. This is the use case we are highlighting in this example.

### Example 25.2. PVC Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: nfs-pvc ①
spec:
  accessModes:
    - ReadWriteMany ②
  resources:
    requests:
      storage: 1Gi ③
```

- ① The claim name is referenced by the pod under its **volumes** section.
- ② As mentioned above for PVs, the **accessModes** do not enforce access right, but rather act as labels to match a PV to a PVC.
- ③ This claim will look for PVs offering **1Gi** or greater capacity.

Save the PVC definition to a file, for example ***nfs-pvc.yaml***, and create the PVC:

```
# oc create -f nfs-pvc.yaml
persistentvolumeclaim "nfs-pvc" created
```

Verify that the PVC was created and bound to the expected PV:

# oc get pvc	NAME	LABELS	STATUS	VOLUME	CAPACITY	ACCESSMODES
	AGE					
	nfs-pvc	<none>	Bound	nfs-pv	1Gi	RWX
	24s					

①

- ① The claim, **nfs-pvc**, was bound to the **nfs-pv** PV.

#### 25.2.4. Ensuring NFS Volume Access

Access is necessary to a node in the NFS server. On this node, examine the NFS export mount:

```
[root@nfs nfs]# ls -lZ /opt/nfs/
total 8
-rw-r--r--. 1 root 100003 system_u:object_r:usr_t:s0 10 Oct 12 23:27
test2b
```

①

②

- 1 the owner has ID 0.
- 2 the group has ID 100003.

In order to access the NFS mount, the container must match the SELinux label, and either run with a UID of 0, or with 100003 in its supplemental groups range. Gain access to the volume by matching the NFS mount's groups, which will be defined in the pod definition below.

By default, SELinux does not allow writing from a pod to a remote NFS server. To enable writing to NFS volumes with SELinux enforcing on each node, run:

```
# setsebool -P virt_use_nfs on
```

### 25.2.5. Creating the Pod

A pod definition file or a template file can be used to define a pod. Below is a pod specification that creates a single container and mounts the NFS volume for read-write access:

#### Example 25.3. Pod Object Definition

```
apiVersion: v1
kind: Pod
metadata:
  name: nginx-nfs-pod 1
  labels:
    name: nginx-nfs-pod
spec:
  containers:
    - name: nginx-nfs-pod
      image: fedora/nginx 2
      ports:
        - name: web
          containerPort: 80
      volumeMounts:
        - name: nfsvol 3
          mountPath: /usr/share/nginx/html 4
  securityContext:
    supplementalGroups: [100003] 5
    privileged: false
  volumes:
    - name: nfsvol
      persistentVolumeClaim:
        claimName: nfs-pvc 6
```

- 1** The name of this pod as displayed by `oc get pod`.
- 2** The image run by this pod.
- 3** The name of the volume. This name must be the same in both the `containers` and `volumes` sections.
- 4** The mount path as seen in the container.

- 5 The group ID to be assigned to the container.
- 6 The PVC that was created in the previous step.

Save the pod definition to a file, for example ***nfs.yaml***, and create the pod:

```
# oc create -f nfs.yaml
pod "nginx-nfs-pod" created
```

Verify that the pod was created:

```
# oc get pods
NAME           READY   STATUS    RESTARTS   AGE
nginx-nfs-pod  1/1     Running   0          4s
```

More details are shown in the **oc describe pod** command:

```
[root@ose70 nfs]# oc describe pod nginx-nfs-pod
Name:      nginx-nfs-pod
Namespace:  default ①
Image(s):   fedora/nginx
Node:      ose70.rh7/192.168.234.148 ②
Start Time: Mon, 21 Mar 2016 09:59:47 -0400
Labels:     name=nginx-nfs-pod
Status:     Running
Reason:
Message:
IP:       10.1.0.4
Replication Controllers: <none>
Containers:
  nginx-nfs-pod:
    Container ID:
    docker://a3292104d6c28d9cf49f440b2967a0fc5583540fc3b062db598557b93893bc6f
      Image:   fedora/nginx
      Image ID:
    docker://403d268c640894cbd76d84a1de3995d2549a93af51c8e16e89842e4c3ed6a00a
      QoS Tier:
        cpu: BestEffort
        memory: BestEffort
    State:    Running
      Started: Mon, 21 Mar 2016 09:59:49 -0400
    Ready:    True
    Restart Count: 0
    Environment Variables:
Conditions:
  Type  Status
  Ready  True
Volumes:
  nfsvol:
    Type: PersistentVolumeClaim (a reference to a PersistentVolumeClaim in
the same namespace)
    ClaimName: nfs-pvc ③
```

```

    readOnly: false
default-token-a06zb:
  type: Secret (a secret that should populate this volume)
  secretName: default-token-a06zb
Events: ④
  FirstSeen  LastSeen  Count  From           SubobjectPath  Reason  Message
  ---- 4m 4m 1 {scheduler}   Scheduled Successfully assigned nginx-nfs-
pod to ose70.rh7
  4m 4m 1 {kubelet ose70.rh7} implicitly required container POD Pulled
Container image "openshift3/ose-pod:v3.1.0.4" already present on machine
  4m 4m 1 {kubelet ose70.rh7} implicitly required container POD Created
Created with docker id 866a37108041
  4m 4m 1 {kubelet ose70.rh7} implicitly required container POD Started
Started with docker id 866a37108041
  4m 4m 1 {kubelet ose70.rh7} spec.containers{nginx-nfs-pod} Pulled
Container image "fedora/nginx" already present on machine
  4m 4m 1 {kubelet ose70.rh7} spec.containers{nginx-nfs-pod} Created
Created with docker id a3292104d6c2
  4m 4m 1 {kubelet ose70.rh7} spec.containers{nginx-nfs-pod} Started
Started with docker id a3292104d6c2

```

- ① The project (namespace) name.
- ② The IP address of the OpenShift Container Platform node running the pod.
- ③ The PVC name used by the pod.
- ④ The list of events resulting in the pod being launched and the NFS volume being mounted. The container will not start correctly if the volume cannot mount.

There is more internal information, including the SCC used to authorize the pod, the pod's user and group IDs, the SELinux label, and more, shown in the `oc get pod <name> -o yaml` command:

```
[root@ose70 nfs]# oc get pod nginx-nfs-pod -o yaml
apiVersion: v1
kind: Pod
metadata:
  annotations:
    openshift.io/scc: restricted ①
  creationTimestamp: 2016-03-21T13:59:47Z
  labels:
    name: nginx-nfs-pod
    name: nginx-nfs-pod
  namespace: default ②
  resourceVersion: "2814411"
  selflink: /api/v1/namespaces/default/pods/nginx-nfs-pod
  uid: 2c22d2ea-ef6d-11e5-adc7-000c2900f1e3
spec:
  containers:
    - image: fedora/nginx
      imagePullPolicy: IfNotPresent
      name: nginx-nfs-pod
      ports:
        - containerPort: 80
```

```

    name: web
    protocol: TCP
  resources: {}
  securityContext:
    privileged: false
  terminationMessagePath: /dev/termination-log
  volumeMounts:
    - mountPath: /usr/share/nginx/html
      name: nfsvol
    - mountPath: /var/run/secrets/kubernetes.io/serviceaccount
      name: default-token-a06zb
      readOnly: true
  dnsPolicy: ClusterFirst
  host: ose70.rh7
  imagePullSecrets:
    - name: default-dockercfg-xvdew
  nodeName: ose70.rh7
  restartPolicy: Always
  securityContext:
    supplementalGroups:
      - 100003 3
  serviceAccount: default
  serviceAccountName: default
  terminationGracePeriodSeconds: 30
  volumes:
    - name: nfsvol
      persistentVolumeClaim:
        claimName: nfs-pvc 4
    - name: default-token-a06zb
      secret:
        secretName: default-token-a06zb
  status:
    conditions:
      - lastProbeTime: null
        lastTransitionTime: 2016-03-21T13:59:49Z
        status: "True"
        type: Ready
    containerStatuses:
      - containerID:
          docker://a3292104d6c28d9cf49f440b2967a0fc5583540fc3b062db598557b93893bc6f
            image: fedora/nginx
            imageID:
          docker://403d268c640894cbd76d84a1de3995d2549a93af51c8e16e89842e4c3ed6a00a
            lastState: {}
            name: nginx-nfs-pod
            ready: true
            restartCount: 0
            state:
              running:
                startedAt: 2016-03-21T13:59:49Z
          hostIP: 192.168.234.148
          phase: Running
          podIP: 10.1.0.4
          startTime: 2016-03-21T13:59:47Z

```

**1** The SCC used by the pod.

- 2 The project (namespace) name.
- 3 The supplemental group ID for the pod (all containers).
- 4 The PVC name used by the pod.

### 25.2.6. Creating an Additional Pod to Reference the Same PVC

This pod definition, created in the same namespace, uses a different container. However, we can use the same backing storage by specifying the claim name in the volumes section below:

#### Example 25.4. Pod Object Definition

```
apiVersion: v1
kind: Pod
metadata:
  name: busybox-nfs-pod 1
  labels:
    name: busybox-nfs-pod
spec:
  containers:
    - name: busybox-nfs-pod
      image: busybox 2
      command: ["sleep", "60000"]
      volumeMounts:
        - name: nfsvol-2 3
          mountPath: /usr/share/busybox 4
          readOnly: false
  securityContext:
    supplementalGroups: [100003] 5
    privileged: false
  volumes:
    - name: nfsvol-2
      persistentVolumeClaim:
        claimName: nfs-pvc 6
```

- 1 The name of this pod as displayed by `oc get pod`.
- 2 The image run by this pod.
- 3 The name of the volume. This name must be the same in both the `containers` and `volumes` sections.
- 4 The mount path as seen in the container.
- 5 The group ID to be assigned to the container.
- 6 The PVC that was created earlier and is also being used by a different container.

Save the pod definition to a file, for example `nfs-2.yaml`, and create the pod:

```
# oc create -f nfs-2.yaml
```

```
pod "busybox-nfs-pod" created
```

Verify that the pod was created:

```
# oc get pods
NAME          READY   STATUS    RESTARTS   AGE
busybox-nfs-pod  1/1     Running   0          3s
```

More details are shown in the **oc describe pod** command:

```
[root@ose70 nfs]# oc describe pod busybox-nfs-pod
Name:      busybox-nfs-pod
Namespace:  default
Image(s):   busybox
Node:      ose70.rh7/192.168.234.148
Start Time: Mon, 21 Mar 2016 10:19:46 -0400
Labels:     name=busybox-nfs-pod
Status:     Running
Reason:
Message:
IP:        10.1.0.5
Replication Controllers: <none>
Containers:
  busybox-nfs-pod:
    Container ID: docker://346d432e5a4824ebf5a47fceb4247e0568ecc64eadcc160e9bab481aecfb0594
      Image:    busybox
      Image ID: docker://17583c7dd0dae6244203b8029733bdb7d17fccbb2b5d93e2b24cf48b8bfd06e2
      QoS Tier:
        cpu: BestEffort
        memory: BestEffort
      State:  Running
        Started: Mon, 21 Mar 2016 10:19:48 -0400
      Ready:  True
      Restart Count: 0
      Environment Variables:
Conditions:
  Type Status
  Ready True
Volumes:
  nfsvol-2:
    Type: PersistentVolumeClaim (a reference to a PersistentVolumeClaim in
the same namespace)
    ClaimName: nfs-pvc
    ReadOnly: false
  default-token-32d2z:
    Type: Secret (a secret that should populate this volume)
    SecretName: default-token-32d2z
Events:
  FirstSeen LastSeen Count From SubobjectPath Reason Message
  4m 4m 1 {scheduler }       Scheduled Successfully assigned busybox-
nfs-pod to ose70.rh7
  4m 4m 1 {kubelet ose70.rh7} implicitly required container POD Pulled
```

```

Container image "openshift3/ose-pod:v3.1.0.4" already present on machine
 4m 4m 1 {kubelet ose70.rh7} implicitly required container POD Created
Created with docker id 249b7d7519b1
 4m 4m 1 {kubelet ose70.rh7} implicitly required container POD Started
Started with docker id 249b7d7519b1
 4m 4m 1 {kubelet ose70.rh7} spec.containers{busybox-nfs-pod} Pulled
Container image "busybox" already present on machine
 4m 4m 1 {kubelet ose70.rh7} spec.containers{busybox-nfs-pod} Created
Created with docker id 346d432e5a48
 4m 4m 1 {kubelet ose70.rh7} spec.containers{busybox-nfs-pod} Started
Started with docker id 346d432e5a48

```

As you can see, both containers are using the same storage claim that is attached to the same NFS mount on the back end.

## 25.3. COMPLETE EXAMPLE USING CEPH RBD

### 25.3.1. Overview

This topic provides an end-to-end example of using an existing Ceph cluster as an OpenShift Container Platform persistent store. It is assumed that a working Ceph cluster is already set up. If not, consult the [Overview of Red Hat Ceph Storage](#).

[Persistent Storage Using Ceph Rados Block Device](#) provides an explanation of persistent volumes (PVs), persistent volume claims (PVCs), and using Ceph RBD as persistent storage.




#### NOTE

All **oc ...** commands are executed on the OpenShift Container Platform master host.

### 25.3.2. Installing the ceph-common Package

The **ceph-common** library must be installed on **all schedulable** OpenShift Container Platform nodes:



#### NOTE

The OpenShift Container Platform all-in-one host is not often used to run pod workloads and, thus, is not included as a schedulable node.

```
# yum install -y ceph-common
```

### 25.3.3. Creating the Ceph Secret

The **ceph auth get-key** command is run on a Ceph **MON** node to display the key value for the **client.admin** user:

#### Example 25.5. Ceph Secret Definition

```

apiVersion: v1
kind: Secret
metadata:

```

```

name: ceph-secret
data:
  key: QVFBOFF2S1ZheUJQRVJBQWgvS2cwT1laQUhPQno3akZwekxxdGc9PQ== 1

```

- 1** This base64 key is generated on one of the Ceph MON nodes using the **ceph auth get-key client.admin | base64** command, then copying the output and pasting it as the secret key's value.

Save the secret definition to a file, for example **ceph-secret.yaml**, then create the secret:

```
$ oc create -f ceph-secret.yaml
secret "ceph-secret" created
```

Verify that the secret was created:

```
# oc get secret ceph-secret
NAME          TYPE      DATA   AGE
ceph-secret   Opaque    1      23d
```

#### 25.3.4. Creating the Persistent Volume

Next, before creating the PV object in OpenShift Container Platform, define the persistent volume file:

##### Example 25.6. Persistent Volume Object Definition Using Ceph RBD

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: ceph-pv 1
spec:
  capacity:
    storage: 2Gi 2
  accessModes:
    - ReadWriteOnce 3
  rbd:
    monitors: 4
    - 192.168.122.133:6789
    pool: rbd
    image: ceph-image
    user: admin
    secretRef:
      name: ceph-secret 6
    fsType: ext4 7
    readOnly: false
  persistentVolumeReclaimPolicy: Recycle

```

- 1** The name of the PV, which is referenced in pod definitions or displayed in various **oc** volume commands.
- 2** The amount of storage allocated to this volume.

- ③ **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control. All block storage is defined to be single user (non-shared storage).
- ④ This defines the volume type being used. In this case, the **rbd** plug-in is defined.
- ⑤ This is an array of Ceph monitor IP addresses and ports.
- ⑥ This is the Ceph secret, defined above. It is used to create a secure connection from OpenShift Container Platform to the Ceph server.
- ⑦ This is the file system type mounted on the Ceph RBD block device.

Save the PV definition to a file, for example ***ceph-pv.yaml***, and create the persistent volume:

```
# oc create -f ceph-pv.yaml
persistentvolume "ceph-pv" created
```

Verify that the persistent volume was created:

# oc get pv	NAME	LABELS	CAPACITY	ACCESSMODES	STATUS
	CLAIM REASON AGE	<none>	2147483648	RWO	Available
	ceph-pv				2s

### 25.3.5. Creating the Persistent Volume Claim

A persistent volume claim (PVC) specifies the desired access mode and storage capacity. Currently, based on only these two attributes, a PVC is bound to a single PV. Once a PV is bound to a PVC, that PV is essentially tied to the PVC's project and cannot be bound to by another PVC. There is a one-to-one mapping of PVs and PVCs. However, multiple pods in the same project can use the same PVC.

#### Example 25.7. PVC Object Definition

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
  name: ceph-claim
spec:
  accessModes: ①
    - ReadWriteOnce
  resources:
    requests:
      storage: 2Gi ②
```

- ① As mentioned above for PVs, the **accessModes** do not enforce access right, but rather act as labels to match a PV to a PVC.
- ② This claim will look for PVs offering **2Gi** or greater capacity.

Save the PVC definition to a file, for example ***ceph-claim.yaml***, and create the PVC:

```
# oc create -f ceph-claim.yaml
persistentvolumeclaim "ceph-claim" created

#and verify the PVC was created and bound to the expected PV:
# oc get pvc
NAME      LABELS      STATUS      VOLUME      CAPACITY      ACCESSMODES      AGE
ceph-claim  <none>    Bound       ceph-pv     1Gi          RWX           21s
1
```

- 1 the claim was bound to the **ceph-pv** PV.

### 25.3.6. Creating the Pod

A pod definition file or a template file can be used to define a pod. Below is a pod specification that creates a single container and mounts the Ceph RBD volume for read-write access:

#### Example 25.8. Pod Object Definition

```
apiVersion: v1
kind: Pod
metadata:
  name: ceph-pod1
spec:
  containers:
    - name: ceph-busybox
      image: busybox
      command: ["sleep", "60000"]
      volumeMounts:
        - name: ceph-vol1
          mountPath: /usr/share/busybox
          readOnly: false
  volumes:
    - name: ceph-vol1
      persistentVolumeClaim:
        claimName: ceph-claim
```

- 1 The name of this pod as displayed by **oc get pod**.
- 2 The image run by this pod. In this case, we are telling **busybox** to sleep.
- 3, 5 The name of the volume. This name must be the same in both the **containers** and **volumes** sections.
- 4 The mount path as seen in the container.
- 6 The PVC that is bound to the Ceph RBD cluster.

Save the pod definition to a file, for example ***ceph-pod1.yaml***, and create the pod:

```
# oc create -f ceph-pod1.yaml
pod "ceph-pod1" created

#verify pod was created
# oc get pod
NAME      READY   STATUS    RESTARTS   AGE
ceph-pod1  1/1     Running   0          2m
1
```

- 1 After a minute or so, the pod will be in the **Running** state.

### 25.3.7. Defining Group and Owner IDs (Optional)

When using block storage, such as Ceph RBD, the physical block storage is **managed** by the pod. The group ID defined in the pod becomes the group ID of **both** the Ceph RBD mount inside the container, and the group ID of the actual storage itself. Thus, it is usually unnecessary to define a group ID in the pod specification. However, if a group ID is desired, it can be defined using **fsGroup**, as shown in the following pod definition fragment:

#### Example 25.9. Group ID Pod Definition

```
...
spec:
  containers:
    - name:
      ...
  securityContext: 1
    fsGroup: 7777 2
...
1
```

- 1 **securityContext** must be defined at the pod level, not under a specific container.
- 2 All containers in the pod will have the same **fsGroup** ID.

### 25.3.8. Setting `ceph-user-secret` as Default for Projects

If you would like to make the persistent storage available to every project you have to modify the default project template. You can read more on modifying the default project template. Read more on [modifying the default project template](#). Adding this to your default project template allows every user who has access to create a project access to the Ceph cluster.

#### Example 25.10. Default Project Example

```
...
apiVersion: v1
kind: Template
metadata:
  creationTimestamp: null
  name: project-request
objects:
```

```

- apiVersion: v1
  kind: Project
  metadata:
    annotations:
      openshift.io/description: ${PROJECT_DESCRIPTION}
      openshift.io/display-name: ${PROJECT_DISPLAYNAME}
      openshift.io/requester: ${PROJECT_REQUESTING_USER}
    creationTimestamp: null
    name: ${PROJECT_NAME}
  spec: {}
  status: {}
- apiVersion: v1
  kind: Secret
  metadata:
    name: ceph-user-secret
  data:
    key: yoursupersecretbase64keygoeshere ①
  type:
    kubernetes.io/rbd
...

```

- ① Place your super secret Ceph user key here in base64 format. See [Creating the Ceph Secret](#).

## 25.4. USING CEPH RBD FOR DYNAMIC PROVISIONING

### 25.4.1. Overview

This topic provides a complete example of using an existing Ceph cluster for OpenShift Container Platform persistent storage. It is assumed that a working Ceph cluster is already set up. If not, consult the [Overview of Red Hat Ceph Storage](#).

[Persistent Storage Using Ceph Rados Block Device](#) provides an explanation of persistent volumes (PVs), persistent volume claims (PVCs), and how to use Ceph Rados Block Device (RBD) as persistent storage.



#### NOTE

- Run all **oc** commands on the OpenShift Container Platform master host.
- The OpenShift Container Platform all-in-one host is not often used to run pod workloads and, thus, is not included as a schedulable node.

### 25.4.2. Creating a pool for dynamic volumes

1. Install the latest ceph-common package:

```
yum install -y ceph-common
```

**NOTE**

The **ceph-common** library must be installed on **all schedulable** OpenShift Container Platform nodes.

- From an administrator or **MON** node, create a new pool for dynamic volumes, for example:

```
$ ceph osd pool create kube 1024
$ ceph auth get-or-create client.kube mon 'allow r' osd 'allow
class-read object_prefix rbd_children, allow rwx pool=kube' -o
ceph.client.kube.keyring
```

**NOTE**

Using the default pool of RBD is an option, but not recommended.

### 25.4.3. Using an existing Ceph cluster for dynamic persistent storage

To use an existing Ceph cluster for dynamic persistent storage:

- Generate the client.admin base64-encoded key:

```
$ ceph auth get client.admin
```

#### Ceph secret definition example

```
apiVersion: v1
kind: Secret
metadata:
  name: ceph-secret
  namespace: kube-system
data:
  key: QVFB0FF2SlZheUJQRVJBQWgvS2cwT1laQUhPQno3akZwekxxdGc9PQ== 1
type: kubernetes.io/rbd 2
```

- 1** This base64 key is generated on one of the Ceph MON nodes using the **ceph auth get-key client.admin | base64** command, then copying the output and pasting it as the secret key's value.
- 2** This value is required for Ceph RBD to work with dynamic provisioning.

- Create the Ceph secret for the client.admin:

```
$ oc create -f ceph-secret.yaml
secret "ceph-secret" created
```

- Verify that the secret was created:

```
$ oc get secret ceph-secret
NAME          TYPE           DATA   AGE
ceph-secret   kubernetes.io/rbd  1      5d
```

4. Create the storage class:

```
$ oc create -f ceph-storageclass.yaml
storageclass "dynamic" created
```

### Ceph storage class example

```
apiVersion: storage.k8s.io/v1beta1
kind: StorageClass
metadata:
  name: dynamic
  annotations:
    storageclass.beta.kubernetes.io/is-default-class: "true"
provisioner: kubernetes.io/rbd
parameters:
  monitors: 192.168.1.11:6789,192.168.1.12:6789,192.168.1.13:6789 ①
  adminId: admin ②
  adminSecretName: ceph-secret ③
  adminSecretNamespace: kube-system ④
  pool: kube ⑤
  userId: kube ⑥
  userSecretName: ceph-user-secret ⑦
```

- ① A comma-delimited list of IP addresses Ceph monitors. This value is required.
- ② The Ceph client ID that is capable of creating images in the pool. The default is **admin**.
- ③ The secret name for **adminId**. This value is required. The secret that you provide must have **kubernetes.io/rbd**.
- ④ The namespace for **adminSecret**. The default is **default**.
- ⑤ The Ceph RBD pool. The default is **rbd**, but this value is not recommended.
- ⑥ The Ceph client ID used to map the Ceph RBD image. The default is the same as the secret name for **adminId**.
- ⑦ The name of the Ceph secret for **userId** to map the Ceph RBD image. It must exist in the same namespace as the PVCs. Unless you set the Ceph secret as the default in new projects, you must provide this parameter value.

5. Verify that the storage class was created:

```
$ oc get storageclasses
NAME          TYPE
dynamic (default)  kubernetes.io/rbd
```

6. Create the PVC object definition:

### PVC object definition example

```
kind: PersistentVolumeClaim
apiVersion: v1
```

```

metadata:
  name: ceph-claim-dynamic
spec:
  accessModes: 1
    - ReadWriteOnce
  resources:
    requests:
      storage: 2Gi 2

```

- 1** The **accessModes** do not enforce access rights but instead act as labels to match a PV to a PVC.
- 2** This claim looks for PVs that offer **2Gi** or greater capacity.

7. Create the PVC:

```
$ oc create -f ceph-pvc.yaml
persistentvolumeclaim "ceph-claim-dynamic" created
```

8. Verify that the PVC was created and bound to the expected PV:

```
$ oc get pvc
NAME          STATUS  VOLUME
CAPACITY ACCESSMODES AGE
ceph-claim   Bound   pvc-f548d663-3cac-11e7-9937-0024e8650c7a 2Gi
RWO          1m
```

9. Create the pod object definition:

### Pod object definition example

```

apiVersion: v1
kind: Pod
metadata:
  name: ceph-pod1 1
spec:
  containers:
    - name: ceph-busybox
      image: busybox 2
      command: ["sleep", "60000"]
      volumeMounts:
        - name: ceph-vol1 3
          mountPath: /usr/share/busybox 4
          readOnly: false
  volumes:
    - name: ceph-vol1
      persistentVolumeClaim:
        claimName: ceph-claim 5

```

- 1** The name of this pod as displayed by **oc get pod**.
- 2** The image run by this pod. In this case, **busybox** is set to **sleep**.

- 3 The name of the volume. This name must be the same in both the **containers** and **volumes** sections.
- 4 The mount path in the container.
- 5 The PVC that is bound to the Ceph RBD cluster.

10. Create the pod:

```
$ oc create -f ceph-pod1.yaml
pod "ceph-pod1" created
```

11. Verify that the pod was created:

```
$ oc get pod
NAME      READY     STATUS    RESTARTS   AGE
ceph-pod1  1/1      Running   0          2m
```

After a minute or so, the pod status changes to **Running**.

#### 25.4.4. Setting `ceph-user-secret` as the default for projects

To make persistent storage available to every project, you must modify the default project template. Adding this to your default project template allows every user who has access to create a project access to the Ceph cluster. See [modifying the default project template](#) for more information.

##### Default project example

```
...
apiVersion: v1
kind: Template
metadata:
  creationTimestamp: null
  name: project-request
objects:
- apiVersion: v1
  kind: Project
  metadata:
    annotations:
      openshift.io/description: ${PROJECT_DESCRIPTION}
      openshift.io/display-name: ${PROJECT_DISPLAYNAME}
      openshift.io/requester: ${PROJECT_REQUESTING_USER}
    creationTimestamp: null
    name: ${PROJECT_NAME}
  spec: {}
  status: {}
- apiVersion: v1
  kind: Secret
  metadata:
    name: ceph-user-secret
  data:
```

```
key: QVFCbEV40VpmAGJtQ0JBQW55d2Z0NHZtcS96cE42Sw1JVUQvekE9PQ== ①
type:
  kubernetes.io/rbd
...
```


- Place your Ceph user key here in base64 format.

## 25.5. COMPLETE EXAMPLE USING GLUSTERFS

### 25.5.1. Overview

This topic provides an end-to-end example of how to use an existing Container-Native Storage, Container-Ready Storage, or standalone Red Hat Gluster Storage cluster as persistent storage for OpenShift Container Platform. It is assumed that a working Red Hat Gluster Storage cluster is already set up. For help installing Container-Native Storage or Container-Ready Storage, see [Persistent Storage Using Red Hat Gluster Storage](#). For standalone Red Hat Gluster Storage, consult the [Red Hat Gluster Storage Administration Guide](#).

For an end-to-end example of how to dynamically provision GlusterFS volumes, see [Complete Example Using GlusterFS for Dynamic Provisioning](#).



#### NOTE

All `oc` commands are executed on the OpenShift Container Platform master host.

### 25.5.2. Prerequisites

To access GlusterFS volumes, the `mount.glusterfs` command must be available on all schedulable nodes. For RPM-based systems, the `glusterfs-fuse` package must be installed:

```
# yum install glusterfs-fuse
```

This package comes installed on every RHEL system. However, it is recommended to update to the latest available version from Red Hat Gluster Storage. To do this, the following RPM repository must be enabled:

```
# subscription-manager repos --enable=rh-gluster-3-client-for-rhel-7-
server-rpms
```

If `glusterfs-fuse` is already installed on the nodes, ensure that the latest version is installed:

```
# yum update glusterfs-fuse
```

By default, SELinux does not allow writing from a pod to a remote Red Hat Gluster Storage server. To enable writing to Red Hat Gluster Storage volumes with SELinux on, run the following on each node running GlusterFS:

```
$ sudo setsebool -P virt_sandbox_use_fusefs on ①
$ sudo setsebool -P virt_use_fusefs on
```

- The `-P` option makes the boolean persistent between reboots.

**NOTE**

The `virt_sandbox_use_fusefs` boolean is defined by the `docker-selinux` package. If you get an error saying it is not defined, ensure that this package is installed.

**NOTE**

If you use Atomic Host, the SELinux booleans are cleared when you upgrade Atomic Host. When you upgrade Atomic Host, you must set these boolean values again.

### 25.5.3. Static Provisioning

1. To enable static provisioning, first create a GlusterFS volume. See the [Red Hat Gluster Storage Administration Guide](#) for information on how to do this using the `gluster` command-line interface or the [heketi project site](#) for information on how to do this using `heketi-cli`. For this example, the volume will be named `myVol1`.
2. Define the following Service and Endpoints in `gluster-endpoints.yaml`:

```
---
apiVersion: v1
kind: Service
metadata:
  name: glusterfs-cluster ①
spec:
  ports:
  - port: 1
---
apiVersion: v1
kind: Endpoints
metadata:
  name: glusterfs-cluster ②
subsets:
  - addresses:
    - ip: 192.168.122.221 ③
      ports:
      - port: 1 ④
    - addresses:
      - ip: 192.168.122.222 ⑤
        ports:
        - port: 1 ⑥
    - addresses:
      - ip: 192.168.122.223 ⑦
        ports:
        - port: 1 ⑧
```

① ② These names must match.

③ ⑤ ⑦ The `ip` values must be the actual IP addresses of a Red Hat Gluster Storage server, not hostnames.

④ ⑥ ⑧ The port number is ignored.

3. From the OpenShift Container Platform master host, create the Service and Endpoints:

```
$ oc create -f gluster-endpoints.yaml
service "glusterfs-cluster" created
endpoints "glusterfs-cluster" created
```

4. Verify that the Service and Endpoints were created:

```
$ oc get services
NAME           CLUSTER_IP      EXTERNAL_IP    PORT(S)
SELECTOR      AGE
glusterfs-cluster   172.30.205.34  <none>        1/TCP
<none>        44s

$ oc get endpoints
NAME           ENDPOINTS
AGE
docker-registry  10.1.0.3:5000
4h
glusterfs-cluster
192.168.122.221:1,192.168.122.222:1,192.168.122.223:1  11s
kubernetes     172.16.35.3:8443
4d
```



#### NOTE

Endpoints are unique per project. Each project accessing the GlusterFS volume needs its own Endpoints.

5. In order to access the volume, the container must run with either a user ID (UID) or group ID (GID) that has access to the file system on the volume. This information can be discovered in the following manner:

```
$ mkdir -p /mnt/glusterfs/myVol1
$ mount -t glusterfs 192.168.122.221:/myVol1 /mnt/glusterfs/myVol1
$ ls -lnZ /mnt/glusterfs/
drwxrwx---. 592 590 system_u:object_r:fusefs_t:s0    myVol1 ① ②
```

① The UID is 592.

② The GID is 590.

6. Define the following PersistentVolume (PV) in **gluster-pv.yaml**:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-default-volume ①
  annotations:
    pv.beta.kubernetes.io/gid: "590" ②
spec:
```

```

capacity:
  storage: 2Gi 3
accessModes: 4
  - ReadWriteMany
glusterfs:
  endpoints: glusterfs-cluster 5
  path: myVol1 6
  readOnly: false
persistentVolumeReclaimPolicy: Retain

```

- 1** The name of the volume.
- 2** The GID on the root of the GlusterFS volume.
- 3** The amount of storage allocated to this volume.
- 4** **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control.
- 5** The Endpoints resource previously created.
- 6** The GlusterFS volume that will be accessed.

7. From the OpenShift Container Platform master host, create the PV:

```
$ oc create -f gluster-pv.yaml
```

8. Verify that the PV was created:

```
$ oc get pv
NAME                  LABELS      CAPACITY   ACCESSMODES
STATUS    CLAIM     REASON     AGE
gluster-default-volume <none>    2147483648   RWX
Available                                     2s
```

9. Create a PersistentVolumeClaim (PVC) that will bind to the new PV in **gluster-claim.yaml**:

```

apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim 1
spec:
  accessModes:
    - ReadWriteMany 2
  resources:
    requests:
      storage: 1Gi 3

```

- 1** The claim name is referenced by the pod under its **volumes** section.
- 2** Must match the **accessModes** of the PV.
- 3** This claim will look for PVs offering **1Gi** or greater capacity.

- From the OpenShift Container Platform master host, create the PVC:

```
$ oc create -f gluster-claim.yaml
```

- Verify that the PV and PVC are bound:

```
$ oc get pv
NAME          LABELS      CAPACITY   ACCESSMODES   STATUS       CLAIM
REASON AGE
gluster-pv    <none>     1Gi        RWX          Available
gluster-claim            37s

$ oc get pvc
NAME          LABELS      STATUS      VOLUME      CAPACITY
ACCESSMODES AGE
gluster-claim <none>     Bound      gluster-pv  1Gi        RWX
24s
```



#### NOTE

PVCs are unique per project. Each project accessing the GlusterFS volume needs its own PVC. PVs are not bound to a single project, so PVCs across multiple projects may refer to the same PV.

#### 25.5.4. Using the Storage

At this point, you have a dynamically created GlusterFS volume bound to a PVC. You can now utilize this PVC in a pod. In this example, we use a simple NGINX pod.

- Create the pod object definition:

```
apiVersion: v1
kind: Pod
metadata:
  name: nginx-pod
  labels:
    name: nginx-pod
spec:
  containers:
  - name: nginx-pod
    image: nginx
    ports:
    - name: web
      containerPort: 80
    volumeMounts:
    - name: gluster-vol1
      mountPath: /usr/share/nginx/html
      readOnly: false
  volumes:
  - name: gluster-vol1
    persistentVolumeClaim:
      claimName: gluster1 ①
```

① The name of the PVC created in the previous step.

2. From the OpenShift Container Platform master host, create the pod:

```
# oc create -f nginx-pod.yaml
pod "nginx-pod" created
```

3. View the pod. Give it a few minutes, as it might need to download the image if it does not already exist:

NAME	READY	STATUS	RESTARTS
nginx-pod	1/1	Running	0
9m	node1		
AGE	IP	NODE	

4. **oc exec** into the container and create an *index.html* file in the **mountPath** definition of the pod:

```
$ oc exec -ti nginx-pod /bin/sh
$ cd /usr/share/nginx/html
$ echo 'Hello World from GlusterFS!!!' > index.html
$ ls
index.html
$ exit
```

5. Now **curl** the URL of the pod:

```
# curl http://10.38.0.0
Hello World from GlusterFS!!!
```

6. Delete the pod, recreate it, and wait for it to come up:

NAME	READY	STATUS	RESTARTS
nginx-pod	1/1	Running	0
9m	node1		
AGE	IP	NODE	

7. Now **curl** the pod again and it should still have the same data as before. Note that its IP address may have changed:

```
# curl http://10.37.0.0
Hello World from GlusterFS!!!
```

8. Check that the *index.html* file was written to GlusterFS storage by doing the following on any of the nodes:

```
$ mount | grep heketi
/dev/mapper/VolGroup00-LogVol00 on /var/lib/heketi type xfs
(rw,relatime,seclabel,attr2,inode64,noquota)
```

```
/dev/mapper/vg_f92e09091f6b20ab12b02a2513e4ed90-
brick_1e730a5462c352835055018e1874e578 on
/var/lib/heketi-mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_1e7
30a5462c352835055018e1874e578 type xfs
(rw,noatime,seclabel,nouuid,attr2,inode64,logbsize=256k,sunit=512,sw
idth=512,noquota)
/dev/mapper/vg_f92e09091f6b20ab12b02a2513e4ed90-
brick_d8c06e606ff4cc29ccb9d018c73ee292 on
/var/lib/heketi-mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_d8c
06e606ff4cc29ccb9d018c73ee292 type xfs
(rw,noatime,seclabel,nouuid,attr2,inode64,logbsize=256k,sunit=512,sw
idth=512,noquota)

$ cd
/var/lib/heketi-mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_d8c
06e606ff4cc29ccb9d018c73ee292/brick
$ ls
index.html
$ cat index.html
Hello World from GlusterFS!!!
```

## 25.6. COMPLETE EXAMPLE USING GLUSTERFS FOR DYNAMIC PROVISIONING

### 25.6.1. Overview

This topic provides an end-to-end example of how to use an existing Container-Native Storage, Container-Ready Storage, or standalone Red Hat Gluster Storage cluster as dynamic persistent storage for OpenShift Container Platform. It is assumed that a working Red Hat Gluster Storage cluster is already set up. For help installing Container-Native Storage or Container-Ready Storage, see [Persistent Storage Using Red Hat Gluster Storage](#). For standalone Red Hat Gluster Storage, consult the [Red Hat Gluster Storage Administration Guide](#).



#### NOTE

All **oc** commands are executed on the OpenShift Container Platform master host.

### 25.6.2. Prerequisites

To access GlusterFS volumes, the **mount.glusterfs** command must be available on all schedulable nodes. For RPM-based systems, the **glusterfs-fuse** package must be installed:

```
# yum install glusterfs-fuse
```

This package comes installed on every RHEL system. However, it is recommended to update to the latest available version from Red Hat Gluster Storage. To do this, the following RPM repository must be enabled:

```
# subscription-manager repos --enable=rh-gluster-3-client-for-rhel-7-
server-rpms
```


If **glusterfs-fuse** is already installed on the nodes, ensure that the latest version is installed:

```
# yum update glusterfs-fuse
```

By default, SELinux does not allow writing from a pod to a remote Red Hat Gluster Storage server. To enable writing to Red Hat Gluster Storage volumes with SELinux on, run the following on each node running GlusterFS:

```
$ sudo setsebool -P virt_sandbox_use_fusefs on ①
$ sudo setsebool -P virt_use_fusefs on
```

- ① The **-P** option makes the boolean persistent between reboots.



#### NOTE

The **virt\_sandbox\_use\_fusefs** boolean is defined by the **docker-selinux** package. If you get an error saying it is not defined, ensure that this package is installed.



#### NOTE

If you use Atomic Host, the SELinux booleans are cleared when you upgrade Atomic Host. When you upgrade Atomic Host, you must set these boolean values again.

### 25.6.3. Dynamic Provisioning

- To enable dynamic provisioning, first create a **StorageClass** object definition. The definition below is based on the minimum requirements needed for this example to work with OpenShift Container Platform. See [Dynamic Provisioning and Creating Storage Classes](#) for additional parameters and specification definitions.

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: glusterfs
provisioner: kubernetes.io/glusterfs
parameters:
  resturl: "http://10.42.0.0:8080" ①
  restauthenabled: "false" ②
```

- ① The heketi server URL.
- ② Since authentication is not turned on in this example, set to **false**.

- From the OpenShift Container Platform master host, create the StorageClass:

```
# oc create -f gluster-storage-class.yaml
storageclass "glusterfs" created
```

- Create a PVC using the newly-created StorageClass. For example:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
```

```

name: gluster1
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 30Gi
  storageClassName: glusterfs

```

- From the OpenShift Container Platform master host, create the PVC:

```
# oc create -f glusterfs-dyn-pvc.yaml
persistentvolumeclaim "gluster1" created
```

- View the PVC to see that the volume was dynamically created and bound to the PVC:

```
# oc get pvc
NAME           STATUS VOLUME
CAPACITY      ACCESSMODES   STORAGECLASS     AGE
gluster1       Bound        pvc-78852230-d8e2-11e6-a3fa-0800279cf26f
30Gi          RWX          gluster-dyn 42s
```

#### 25.6.4. Using the Storage

At this point, you have a dynamically created GlusterFS volume bound to a PVC. You can now utilize this PVC in a pod. In this example, we use a simple NGINX pod.

- Create the pod object definition:

```

apiVersion: v1
kind: Pod
metadata:
  name: nginx-pod
  labels:
    name: nginx-pod
spec:
  containers:
    - name: nginx-pod
      image: nginx
      ports:
        - name: web
          containerPort: 80
  volumeMounts:
    - name: gluster-vol1
      mountPath: /usr/share/nginx/html
      readOnly: false
  volumes:
    - name: gluster-vol1
      persistentVolumeClaim:
        claimName: gluster1 ①

```

① The name of the PVC created in the previous step.

2. From the OpenShift Container Platform master host, create the pod:

```
# oc create -f nginx-pod.yaml
pod "nginx-pod" created
```

3. View the pod. Give it a few minutes, as it might need to download the image if it does not already exist:

NAME	READY	STATUS	RESTARTS
nginx-pod	1/1	Running	0
9m	node1		
AGE	IP	NODE	

4. **oc exec** into the container and create an ***index.html*** file in the **mountPath** definition of the pod:

```
$ oc exec -ti nginx-pod /bin/sh
$ cd /usr/share/nginx/html
$ echo 'Hello World from GlusterFS!!!' > index.html
$ ls
index.html
$ exit
```

5. Now **curl** the URL of the pod:

```
# curl http://10.38.0.0
Hello World from GlusterFS!!!
```

6. Delete the pod, recreate it, and wait for it to come up:

NAME	READY	STATUS	RESTARTS
nginx-pod	1/1	Running	0
9m	node1		
AGE	IP	NODE	

7. Now **curl** the pod again and it should still have the same data as before. Note that its IP address may have changed:

```
# curl http://10.37.0.0
Hello World from GlusterFS!!!
```

8. Check that the ***index.html*** file was written to GlusterFS storage by doing the following on any of the nodes:

```
$ mount | grep heketi
/dev/mapper/VolGroup00-LogVol00 on /var/lib/heketi type xfs
(rw,relatime,seclabel,attr2,inode64,noquota)
```

```

/dev/mapper/vg_f92e09091f6b20ab12b02a2513e4ed90-
brick_1e730a5462c352835055018e1874e578 on
/var/lib/heketi-mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_1e7
30a5462c352835055018e1874e578 type xfs
(rw,noatime,seclabel,nouuid,attr2,inode64,logbsize=256k,sunit=512,sw
idth=512,noquota)
/dev/mapper/vg_f92e09091f6b20ab12b02a2513e4ed90-
brick_d8c06e606ff4cc29ccb9d018c73ee292 on
/var/lib/heketi-mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_d8c
06e606ff4cc29ccb9d018c73ee292 type xfs
(rw,noatime,seclabel,nouuid,attr2,inode64,logbsize=256k,sunit=512,sw
idth=512,noquota)

$ cd
/var/lib/heketi-mounts/vg_f92e09091f6b20ab12b02a2513e4ed90/brick_d8c
06e606ff4cc29ccb9d018c73ee292/brick
$ ls
index.html
$ cat index.html
Hello World from GlusterFS!!!

```

## 25.7. MOUNTING VOLUMES ON PRIVILEGED PODS

### 25.7.1. Overview

Persistent volumes can be mounted to pods with the **privileged** security context constraint (SCC) attached.



#### NOTE

While this topic uses GlusterFS as a sample use-case for mounting volumes onto privileged pods, it can be adapted to use any [supported storage plug-in](#).

### 25.7.2. Prerequisites

- An existing Gluster volume.
- **glusterfs-fuse** installed on all hosts.
- Definitions for GlusterFS:
  - [Endpoints and services](#): ***gluster-endpoints-service.yaml*** and ***gluster-endpoints.yaml***
  - [Persistent volumes](#): ***gluster-pv.yaml***
  - [Persistent volume claims](#): ***gluster-pvc.yaml***
  - [Privileged pods](#): ***gluster-nginx-pod.yaml***
- A user with the [cluster-admin](#) role binding. For this guide, that user is called **admin**.

### 25.7.3. Creating the Persistent Volume

Creating the **PersistentVolume** makes the storage accessible to users, regardless of projects.

- As the admin, create the service, endpoint object, and persistent volume:

```
$ oc create -f gluster-endpoints-service.yaml
$ oc create -f gluster-endpoints.yaml
$ oc create -f gluster-pv.yaml
```

- Verify that the objects were created:

NAME	CLUSTER_IP	EXTERNAL_IP	PORT(S)	SELECTOR
gluster-cluster	172.30.151.58	<none>	1/TCP	<none>
	24s			

NAME	ENDPOINTS	AGE
gluster-cluster	192.168.59.102:1,192.168.59.103:1	2m

NAME	CLAIM	REASON	AGE	LABELS	CAPACITY	ACCESSMODES	STATUS
gluster-default-volume	Available		2d	<none>	2Gi	RWX	

#### 25.7.4. Creating a Regular User

Adding a [regular user](#) to the **privileged** SCC (or to a group given access to the SCC) allows them to run **privileged** pods:

- As the admin, add a user to the SCC:

```
$ oc adm policy add-scc-to-user privileged <username>
```

- Log in as the regular user:

```
$ oc login -u <username> -p <password>
```

- Then, create a new project:

```
$ oc new-project <project_name>
```

#### 25.7.5. Creating the Persistent Volume Claim

- As a regular user, create the **PersistentVolumeClaim** to access the volume:

```
$ oc create -f gluster-pvc.yaml -n <project_name>
```

- Define your pod to access the claim:

##### Example 25.11. Pod Definition

```
apiVersion: v1
```

```

id: gluster-nginx-pvc
kind: Pod
metadata:
  name: gluster-nginx-priv
spec:
  containers:
    - name: gluster-nginx-priv
      image: fedora/nginx
      volumeMounts:
        - mountPath: /mnt/gluster 1
          name: gluster-volume-claim
  securityContext:
    privileged: true
  volumes:
    - name: gluster-volume-claim
      persistentVolumeClaim:
        claimName: gluster-claim 2

```

**1** Volume mount within the pod.

**2** The **gluster-claim** must reflect the name of the **PersistentVolume**.

- Upon pod creation, the mount directory is created and the volume is attached to that mount point.

As regular user, create a pod from the definition:

```
$ oc create -f gluster-nginx-pod.yaml
```

- Verify that the pod created successfully:

```
$ oc get pods
NAME                  READY     STATUS    RESTARTS   AGE
gluster-nginx-pod    1/1      Running   0          36m
```

It can take several minutes for the pod to create.

## 25.7.6. Verifying the Setup

### 25.7.6.1. Checking the Pod SCC

- Export the pod configuration:

```
$ oc export pod <pod_name>
```

- Examine the output. Check that **openshift.io/scc** has the value of **privileged**:

#### Example 25.12. Export Snippet

```

metadata:
  annotations:
    openshift.io/scc: privileged

```

### 25.7.6.2. Verifying the Mount

- Access the pod and check that the volume is mounted:

```
$ oc rsh <pod_name>
[root@gluster-nginx-pvc /]# mount
```

- Examine the output for the Gluster volume:

#### Example 25.13. Volume Mount

```
192.168.59.102:gv0 on /mnt/gluster type fuse.gluster
(rw,relatime,user_id=0,group_id=0,default_permissions,allow_other,
max_read=131072)
```

## 25.8. SWITCHING AN INTEGRATED OPENSIFT CONTAINER REGISTRY TO GLUSTERFS

### 25.8.1. Overview

This topic reviews how to attach a GlusterFS volume to an integrated OpenShift Container Registry. This can be done with any of Container-Native Storage, Container-Ready Storage, or standalone Red Hat Gluster Storage. It is assumed that the registry has already been started and a volume has been created.

### 25.8.2. Prerequisites

- An existing [registry](#) deployed **without** configuring storage.
- An existing GlusterFS volume
- glusterfs-fuse** installed on all schedulable nodes.
- A user with the **cluster-admin** role binding.
  - For this guide, that user is **admin**.



#### NOTE

All **oc** commands are executed on the master node as the **admin** user.

### 25.8.3. Manually Provision the GlusterFS PersistentVolumeClaim

- To enable static provisioning, first create a GlusterFS volume. See the [Red Hat Gluster Storage Administration Guide](#) for information on how to do this using the **gluster** command-line interface or the [heketi project site](#) for information on how to do this using **heketi-cli**. For this example, the volume will be named **myVol1**.
- Define the following Service and Endpoints in **gluster-endpoints.yaml**:

```
---
apiVersion: v1
```

```

kind: Service
metadata:
  name: glusterfs-cluster 1
spec:
  ports:
    - port: 1
---
apiVersion: v1
kind: Endpoints
metadata:
  name: glusterfs-cluster 2
subsets:
  - addresses:
      - ip: 192.168.122.221 3
    ports:
      - port: 1 4
  - addresses:
      - ip: 192.168.122.222 5
    ports:
      - port: 1 6
  - addresses:
      - ip: 192.168.122.223 7
    ports:
      - port: 1 8

```

**1** **2** These names must match.

**3** **5** **7** The **ip** values must be the actual IP addresses of a Red Hat Gluster Storage server, not hostnames.

**4** **6** **8** The port number is ignored.

3. From the OpenShift Container Platform master host, create the Service and Endpoints:

```
$ oc create -f gluster-endpoints.yaml
service "glusterfs-cluster" created
endpoints "glusterfs-cluster" created
```

4. Verify that the Service and Endpoints were created:

```

$ oc get services
NAME                  CLUSTER_IP        EXTERNAL_IP      PORT(S)
SELECTOR          AGE
glusterfs-cluster   172.30.205.34   <none>           1/TCP
<none>            44s

$ oc get endpoints
NAME                  ENDPOINTS
AGE
docker-registry      10.1.0.3:5000
4h
glusterfs-cluster

```

```
192.168.122.221:1,192.168.122.222:1,192.168.122.223:1    11s
kubernetes           172.16.35.3:8443
4d
```

**NOTE**

Endpoints are unique per project. Each project accessing the GlusterFS volume needs its own Endpoints.

- In order to access the volume, the container must run with either a user ID (UID) or group ID (GID) that has access to the file system on the volume. This information can be discovered in the following manner:

```
$ mkdir -p /mnt/glusterfs/myVol1
$ mount -t glusterfs 192.168.122.221:/myVol1 /mnt/glusterfs/myVol1
$ ls -lnZ /mnt/glusterfs/
drwxrwx---. 592 590 system_u:object_r:fusefs_t:s0      myVol1 ① ②
```

- ① The UID is 592.
- ② The GID is 590.

- Define the following PersistentVolume (PV) in **gluster-pv.yaml**:

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-default-volume ①
  annotations:
    pv.beta.kubernetes.io/gid: "590" ②
spec:
  capacity:
    storage: 2Gi ③
  accessModes: ④
    - ReadWriteMany
  glusterfs:
    endpoints: glusterfs-cluster ⑤
    path: myVol1 ⑥
    readOnly: false
  persistentVolumeReclaimPolicy: Retain
```

- ① The name of the volume.
- ② The GID on the root of the GlusterFS volume.
- ③ The amount of storage allocated to this volume.
- ④ **accessModes** are used as labels to match a PV and a PVC. They currently do not define any form of access control.
- ⑤ The Endpoints resource previously created.

**6** The GlusterFS volume that will be accessed.

7. From the OpenShift Container Platform master host, create the PV:

```
$ oc create -f gluster-pv.yaml
```

8. Verify that the PV was created:

```
$ oc get pv
NAME          LABELS      CAPACITY      ACCESSMODES
STATUS        CLAIM       REASON      AGE
gluster-default-volume <none>    2147483648   RWX
Available                               2s
```

9. Create a PersistentVolumeClaim (PVC) that will bind to the new PV in **gluster-claim.yaml**:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim 1
spec:
  accessModes:
  - ReadWriteMany 2
  resources:
    requests:
      storage: 1Gi 3
```

**1** The claim name is referenced by the pod under its **volumes** section.

**2** Must match the **accessModes** of the PV.

**3** This claim will look for PVs offering **1Gi** or greater capacity.

10. From the OpenShift Container Platform master host, create the PVC:

```
$ oc create -f gluster-claim.yaml
```

11. Verify that the PV and PVC are bound:

```
$ oc get pv
NAME          LABELS      CAPACITY      ACCESSMODES      STATUS      CLAIM
REASON        AGE
gluster-pv    <none>    1Gi           RWX
gluster-claim                      37s           Available

$ oc get pvc
NAME          LABELS      STATUS      VOLUME      CAPACITY
ACCESSMODES    AGE
gluster-claim <none>    Bound      gluster-pv  1Gi           RWX
24s
```

**NOTE**

PVCs are unique per project. Each project accessing the GlusterFS volume needs its own PVC. PVs are not bound to a single project, so PVCs across multiple projects may refer to the same PV.

### 25.8.4. Attach the PersistentVolumeClaim to the Registry

Before moving forward, ensure that the **docker-registry** service is running.

```
$ oc get svc
NAME           CLUSTER_IP      EXTERNAL_IP    PORT(S)
SELECTOR        AGE
docker-registry 172.30.167.194 <none>        5000/TCP
docker-registry=default   18m
```

**NOTE**

If either the **docker-registry** service or its associated pod is not running, refer back to the [registry](#) setup instructions for troubleshooting before continuing.

Then, attach the PVC:

```
$ oc volume deploymentconfigs/docker-registry --add --name=registry-
storage -t pvc \
--claim-name=gluster-claim --overwrite
```

[Setting up the Registry](#) provides more information on using an OpenShift Container Registry.

## 25.9. BINDING PERSISTENT VOLUMES BY LABELS

### 25.9.1. Overview

This topic provides an end-to-end example for binding [persistent volume claims \(PVCs\)](#) to [persistent volumes \(PVs\)](#), by defining labels in the PV and matching selectors in the PVC. This feature is available for all [storage options](#). It is assumed that a OpenShift Container Platform cluster contains persistent storage resources which are available for binding by PVCs.

#### A Note on Labels and Selectors

Labels are an OpenShift Container Platform feature that support user-defined tags (key-value pairs) as part of an object's specification. Their primary purpose is to enable the arbitrary grouping of objects by defining identical labels among them. These labels can then be targeted by selectors to match all objects with specified label values. It is this functionality we will take advantage of to enable our PVC to bind to our PV. For a more in-depth look at labels, see [Pods and Services](#).

**NOTE**

For this example, we will be using modified [GlusterFS](#) PV and PVC specifications. However, implementation of selectors and labels is generic across for all storage options. See the [relevant storage option](#) for your volume provider to learn more about its unique configuration.

### 25.9.1.1. Assumptions

It is assumed that you have:

- An existing OpenShift Container Platform cluster with at least one **master** and one **node**
- At least one supported [storage volume](#)
- A user with **cluster-admin** privileges

### 25.9.2. Defining Specifications



#### NOTE

These specifications are tailored to **GlusterFS**. Consult the [relevant storage option](#) for your volume provider to learn more about its unique configuration.

#### 25.9.2.1. Persistent Volume with Labels

##### Example 25.14. glusterfs-pv.yaml

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: gluster-volume
  labels: ①
    storage-tier: gold
    aws-availability-zone: us-east-1
spec:
  capacity:
    storage: 2Gi
  accessModes:
    - ReadWriteMany
  glusterfs:
    endpoints: glusterfs-cluster ②
    path: myVol1
    readOnly: false
  persistentVolumeReclaimPolicy: Retain
```

- ① Use labels to identify common attributes or characteristics shared among volumes. In this case, we defined the Gluster volume to have a custom attribute (key) named **storage-tier** with a value of **gold** assigned. A claim will be able to select a PV with **storage-tier=gold** to match this PV.
- ② Endpoints define the Gluster trusted pool and are discussed below.

#### 25.9.2.2. Persistent Volume Claim with Selectors

A claim with a **selector** stanza (see example below) attempts to match existing, unclaimed, and non-prebound PVs. The existence of a PVC selector ignores a PV's capacity. However, **accessModes** are still considered in the matching criteria.

It is important to note that a claim must match **all** of the key-value pairs included in its **selector** stanza. If no PV matches the claim, then the PVC will remain unbound (Pending). A PV can subsequently be created and the claim will automatically check for a label match.

#### Example 25.15. glusterfs-pvc.yaml

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: gluster-claim
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 1Gi
  selector: ①
    matchLabels:
      storage-tier: gold
      aws-availability-zone: us-east-1
```

- ① The **selector** stanza defines all labels necessary in a PV in order to match this claim.

#### 25.9.2.3. Volume Endpoints

To attach the PV to the Gluster volume, endpoints should be configured before creating our objects.

#### Example 25.16. glusterfs-ep.yaml

```
apiVersion: v1
kind: Endpoints
metadata:
  name: glusterfs-cluster
subsets:
  - addresses:
      - ip: 192.168.122.221
    ports:
      - port: 1
  - addresses:
      - ip: 192.168.122.222
    ports:
      - port: 1
```

#### 25.9.2.4. Deploy the PV, PVC, and Endpoints


For this example, run the **oc** commands as a **cluster-admin** privileged user. In a production environment, cluster clients might be expected to define and create the PVC.

```
# oc create -f glusterfs-ep.yaml
endpoints "glusterfs-cluster" created
```

```
# oc create -f glusterfs-pv.yaml
persistentvolume "gluster-volume" created
# oc create -f glusterfs-pvc.yaml
persistentvolumeclaim "gluster-claim" created
```

Lastly, confirm that the PV and PVC bound successfully.

# oc get pv,pvc		CAPACITY	ACCESSMODES	STATUS	CLAIM
NAME	REASON	AGE			
gluster-volume	trial/gluster-claim	2Gi	RWX 7s	Bound	gfs-
NAME	STATUS	VOLUME		CAPACITY	ACCESSMODES
gluster-claim	Bound	gluster-volume		2Gi	RWX
		7s			



### NOTE

PVCs are local to a project, whereas PVs are a cluster-wide, global resource. Developers and non-administrator users may not have access to see all (or any) of the available PVs.

## 25.10. USING STORAGE CLASSES FOR DYNAMIC PROVISIONING

### 25.10.1. Overview

In these examples we will walk through a few scenarios of various configurations of [StorageClasses](#) and Dynamic Provisioning using Google Cloud Platform Compute Engine (GCE). These examples assume some familiarity with Kubernetes, GCE and Persistent Disks and OpenShift Container Platform is installed and [properly configured to use GCE](#).

- [Basic Dynamic Provisioning](#)
- [Defaulting Cluster Dynamic Provisioning Behavior](#)

### 25.10.2. Scenario 1: Basic Dynamic Provisioning with Two Types of [StorageClasses](#)

[StorageClasses](#) can be used to differentiate and delineate storage levels and usages. In this case, the **cluster-admin** or **storage-admin** sets up two distinct classes of storage in GCE.

- **slow**: Cheap, efficient, and optimized for sequential data operations (slower reading and writing)
- **fast**: Optimized for higher rates of random IOPS and sustained throughput (faster reading and writing)

By creating these [StorageClasses](#), the **cluster-admin** or **storage-admin** allows users to create claims requesting a particular level or service of [StorageClass](#).

#### Example 25.17. StorageClass Slow Object Definitions

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
```

```

metadata:
  name: slow 1
provisioner: kubernetes.io/gce-pd 2
parameters:
  type: pd-standard 3
  zone: us-east1-d 4

```

- 1** Name of the *StorageClass*.
- 2** The provisioner plug-in to be used. This is a required field for *StorageClasses*.
- 3** PD type. This example uses **pd-standard**, which has a slightly lower cost, rate of sustained IOPS, and throughput versus **pd-ssd**, which carries more sustained IOPS and throughput.
- 4** The zone is required.

#### Example 25.18. StorageClass Fast Object Definition

```

kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: fast
provisioner: kubernetes.io/gce-pd
parameters:
  type: pd-ssd
  zone: us-east1-d

```

As a **cluster-admin** or **storage-admin**, save both definitions as YAML files. For example, **slow-gce.yaml** and **fast-gce.yaml**. Then create the *StorageClasses*.

```

# oc create -f slow-gce.yaml
storageclass "slow" created

# oc create -f fast-gce.yaml
storageclass "fast" created

# oc get storageclass
NAME      TYPE
fast      kubernetes.io/gce-pd
slow      kubernetes.io/gce-pd

```



#### IMPORTANT

**cluster-admin** or **storage-admin** users are responsible for relaying the correct *StorageClass* name to the correct users, groups, and projects.

As a regular user, create a new project:

```
# oc new-project rh-eng
```

Create the claim YAML definition, save it to a file (**pvc-fast.yaml**):

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-engineering
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 10Gi
  storageClassName: fast
```

Add the claim with the **oc create** command:

```
# oc create -f pvc-fast.yaml
persistentvolumeclaim "pvc-engineering" created
```

Check to see if your claim is bound:

```
# oc get pvc
NAME           STATUS   VOLUME
CAPACITY     ACCESSMODES AGE
pvc-engineering Bound   pvc-e9b4fef7-8bf7-11e6-9962-42010af00004
10Gi         RWX        2m
```



### IMPORTANT

Since this claim was created and bound in the *rh-eng* project, it can be shared by any user in the same project.

As a **cluster-admin** or **storage-admin** user, view the recent dynamically provisioned Persistent Volume (PV).

```
# oc get pv
NAME           CAPACITY   ACCESSMODES
RECLAIMPOLICY STATUS     CLAIM          REASON   AGE
pvc-e9b4fef7-8bf7-11e6-9962-42010af00004 10Gi       RWX
Delete        Bound      rh-eng/pvc-engineering          5m
```



### IMPORTANT

Notice the **RECLAIMPOLICY** is *Delete* by default for all dynamically provisioned volumes. This means the volume only lasts as long as the claim still exists in the system. If you delete the claim, the volume is also deleted and all data on the volume is lost.

Finally, check the GCE console. The new disk has been created and is ready for use.

```
kubernetes-dynamic-pvc-e9b4fef7-8bf7-11e6-9962-42010af00004 SSD
persistent disk 10 GB us-east1-d
```

Pods can now reference the persistent volume claim and start using the volume.

### 25.10.3. Scenario 2: How to enable Default *StorageClass* behavior for a Cluster

In this example, a **cluster-admin** or **storage-admin** enables a *default* storage class for all other users and projects that do not implicitly specify a *StorageClass* in their claim. This is useful for a **cluster-admin** or **storage-admin** to provide easy management of a storage volume without having to set up or communicate specialized *StorageClasses* across the cluster.

This example builds upon [Section 25.10.2, “Scenario 1: Basic Dynamic Provisioning with Two Types of StorageClasses”](#). The **cluster-admin** or **storage-admin** will create another *StorageClass* for designation as the *defaultStorageClass*.

#### Example 25.19. Default StorageClass Object Definition

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: generic 1
  annotations:
    storageclass.kubernetes.io/is-default-class: "true" 2
  provisioner: kubernetes.io/gce-pd
parameters:
  type: pd-standard
  zone: us-east1-d
```

- 1** Name of the *StorageClass*, which needs to be unique in the cluster.
- 2** Annotation that marks this *StorageClass* as the default class. You must use **"true"** quoted in this version of the API. Without this annotation, OpenShift Container Platform considers this not the *default StorageClass*.

As a **cluster-admin** or **storage-admin** save the definition to a YAML file (**generic-gce.yaml**), then create the *StorageClasses*:

```
# oc create -f generic-gce.yaml
storageclass "generic" created

# oc get storageclass
NAME      TYPE
generic   kubernetes.io/gce-pd
fast      kubernetes.io/gce-pd
slow      kubernetes.io/gce-pd
```

As a regular user, create a new claim definition without any *StorageClass* requirement and save it to a file (**generic-pvc.yaml**).

#### Example 25.20. *default* Storage Claim Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
```

```

name: pvc-engineering2
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 5Gi

```

Execute it and check the claim is bound:

```

# oc create -f generic-pvc.yaml
persistentvolumeclaim "pvc-engineering2" created
                                         3s

# oc get pvc
NAME           STATUS   VOLUME
CAPACITY     ACCESSMODES AGE
pvc-engineering Bound   pvc-e9b4fef7-8bf7-11e6-9962-42010af00004
10Gi         RWX       41m
pvc-engineering2 Bound   pvc-a9f70544-8bfd-11e6-9962-42010af00004
5Gi          RWX       7s  ①

```

- ① **pvc-engineering2** is bound to a dynamically provisioned Volume by *default*.

As a **cluster-admin** or **storage-admin**, view the Persistent Volumes defined so far:

```

# oc get pv
NAME           CAPACITY   ACCESSMODES
RECLAIMPOLICY STATUS     CLAIM
                REASON     AGE
pvc-a9f70544-8bfd-11e6-9962-42010af00004 5Gi      RWX
Delete        Bound      rh-eng/pvc-engineering2
                                         5m  ①
pvc-ba4612ce-8b4d-11e6-9962-42010af00004 5Gi      RWO
Delete        Bound      mytest/gce-dyn-claim1
                                         21h
pvc-e9b4fef7-8bf7-11e6-9962-42010af00004 10Gi     RWX
Delete        Bound      rh-eng/pvc-engineering
                                         46m  ②

```

- ① This PV was bound to our *default* dynamic volume from the *default StorageClass*.  
 ② This PV was bound to our first PVC from [Section 25.10.2, “Scenario 1: Basic Dynamic Provisioning with Two Types of StorageClasses”](#) with our *fast StorageClass*.

Create a manually provisioned disk using **GCE** (not dynamically provisioned). Then create a **Persistent Volume** that connects to the new GCE disk (**pv-manual-gce.yaml**).

#### Example 25.21. Manual PV Object Definition

```

apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv-manual-gce
spec:
  capacity:

```

```

storage: 35Gi
accessModes:
  - ReadWriteMany
gcePersistentDisk:
  readOnly: false
  pdName: the-newly-created-gce-PD
  fsType: ext4

```

Execute the object definition file:

```
# oc create -f pv-manual-gce.yaml
```

Now view the PVs again. Notice that a **pv-manual-gce** volume is *Available*.

# oc get pv			CAPACITY	ACCESSMODES	
NAME	RECLAIMPOLICY	STATUS	CLAIM	REASON	AGE
pv-manual-gce	Retain	Available		RWX	4s
pvc-a9f70544-8bfd-11e6-9962-42010af00004	Delete	Bound	rh-eng/pvc-engineering2	RWX	12m
pvc-ba4612ce-8b4d-11e6-9962-42010af00004	Delete	Bound	mytest/gce-dyn-claim1	RWO	21h
pvc-e9b4fef7-8bf7-11e6-9962-42010af00004	Delete	Bound	rh-eng/pvc-engineering	RWX	53m

Now create another claim identical to the **generic-pvc.yaml** PVC definition but change the name and do not set a storage class name.

### Example 25.22. Claim Object Definition

```


apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-engineering3
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 15Gi

```

Because *default StorageClass* is enabled in this instance, the manually created PV does not satisfy the claim request. The user receives a new dynamically provisioned Persistent Volume.

NAME	STATUS	VOLUME
CAPACITY	ACCESSMODES	AGE
pvc-engineering	Bound	pvc-e9b4fef7-8bf7-11e6-9962-42010af00004
10Gi	RWX	1h
pvc-engineering2	Bound	pvc-a9f70544-8bfd-11e6-9962-42010af00004

5Gi	RWX	19m
pvc-engineering3	Bound	pvc-6fa8e73b-8c00-11e6-9962-42010af00004
15Gi	RWX	6s

**IMPORTANT**

Since the *default StorageClass* is enabled on this system, for the manually created Persistent Volume to get bound by the above claim and not have a new dynamic provisioned volume be bound, the PV would need to have been created in the *default StorageClass*.

Since the *default StorageClass* is enabled on this system, you would need to create the PV in the *default StorageClass* for the manually created Persistent Volume to get bound to the above claim and not have a new dynamic provisioned volume bound to the claim.

To fix this, the **cluster-admin** or **storage-admin** user simply needs to create another GCE disk or delete the first manual PV and use a PV object definition that assigns a *StorageClass* name (**pv-manual-gce2.yaml**) if necessary:

**Example 25.23. Manual PV Spec with *default StorageClass* name**

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv-manual-gce2
spec:
  capacity:
    storage: 35Gi
  accessModes:
    - ReadWriteMany
  gcePersistentDisk:
    readOnly: false
    pdName: the-newly-created-gce-PD
    fsType: ext4
  storageClassName: generic ①
```

- ① The name for previously created *generic StorageClass*.

Execute the object definition file:

```
# oc create -f pv-manual-gce2.yaml
```

List the PVs:

```
# oc get pv
NAME          STATUS    CLAIM           CAPACITY   ACCESSMODES   REASON   AGE
pv-manual-gce Available            35Gi      RWX
pv-manual-gce2 Retain     rh-eng/pvc-engineering3 35Gi      RWX
Retain        Bound
```

4s ①  
4s ②

pvc-a9f70544-8bfd-11e6-9962-42010af00004	5Gi	RWX	
Delete	Bound	rh-eng/pvc-engineering2	12m
pvc-ba4612ce-8b4d-11e6-9962-42010af00004	5Gi	RWO	
Delete	Bound	mytest/gce-dyn-claim1	21h
pvc-e9b4fef7-8bf7-11e6-9962-42010af00004	10Gi	RWX	
Delete	Bound	rh-eng/pvc-engineering	53m

- ① The original manual PV, still unbound and Available. This is because it was not created in the *default StorageClass*.
- ② The second PVC (other than the name) is bound to the Available manually created PV **pv-manual-gce2**.



### IMPORTANT

Notice that all dynamically provisioned volumes by default have a *RECLAIMPOLICY* of *Delete*. Once the PVC dynamically bound to the PV is deleted, the GCE volume is deleted and all data is lost. However, the manually created PV has a default *RECLAIMPOLICY* of *Retain*.

## 25.11. USING STORAGE CLASSES FOR EXISTING LEGACY STORAGE

### 25.11.1. Overview

In this example, a legacy data volume exists and a **cluster-admin** or **storage-admin** needs to make it available for consumption in a particular project. Using *StorageClasses* decreases the likelihood of other users and projects gaining access to this volume from a claim because the claim would have to have an exact matching value for the *StorageClass* name. This example also disables dynamic provisioning. This example assumes:

- Some familiarity with OpenShift Container Platform, GCE, and Persistent Disks
- OpenShift Container Platform is [properly configured to use GCE](#).

#### 25.11.1.1. Scenario 1: Link StorageClass to existing Persistent Volume with Legacy Data

As a **cluster-admin** or **storage-admin**, define and create the *StorageClass* for historical financial data.

##### Example 25.24. StorageClass finance-history Object Definitions

```
kind: StorageClass
apiVersion: storage.k8s.io/v1
metadata:
  name: finance-history ①
  provisioner: no-provisioning ②
  parameters: ③
```

- ① Name of the StorageClass.
- ② This is a required field, but since there is to be no dynamic provisioning, a value must be put here as long as it is not an actual provisioner plug-in type.

- 3** Parameters can simply be left blank, since these are only used for the dynamic provisioner.

Save the definitions to a YAML file (`finance-history-storageclass.yaml`) and create the `StorageClass`.

```
# oc create -f finance-history-storageclass.yaml
storageclass "finance-history" created

# oc get storageclass
NAME          TYPE
finance-history  no-provisioning
```



### IMPORTANT

`cluster-admin` or `storage-admin` users are responsible for relaying the correct `StorageClass` name to the correct users, groups, and projects.

The `StorageClass` exists. A `cluster-admin` or `storage-admin` can create the Persistent Volume (PV) for use with the `StorageClass`. Create a manually provisioned disk using `GCE` (not dynamically provisioned) and a `Persistent Volume` that connects to the new GCE disk (`gce-pv.yaml`).

#### Example 25.25. Finance History PV Object

```
apiVersion: v1
kind: PersistentVolume
metadata:
  name: pv-finance-history
spec:
  capacity:
    storage: 35Gi
  accessModes:
    - ReadWriteMany
  gcePersistentDisk:
    readOnly: false
    pdName: the-existing-PD-volume-name-that-contains-the-valuable-data
  1   fsType: ext4
  storageClassName: finance-history 2
```

- 2** The `StorageClass` name, that must match exactly.

- 1** The name of the GCE disk that already exists and contains the legacy data.

As a `cluster-admin` or `storage-admin`, create and view the PV.

```
# oc create -f gce-pv.yaml
persistentvolume "pv-finance-history" created
```

```
# oc get pv
NAME CAPACITY ACCESSMODES RECLAIMPOLICY STATUS
CLAIM REASON AGE
pv-finance-history 35Gi RWX Retain Available
2d
```

Notice you have a **pv-finance-history** Available and ready for consumption.

As a user, create a Persistent Volume Claim (PVC) as a YAML file and specify the correct *StorageClass* name:

#### Example 25.26. Claim for finance-history Object Definition

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: pvc-finance-history
spec:
  accessModes:
    - ReadWriteMany
  resources:
    requests:
      storage: 20Gi
  storageClassName: finance-history ①
```

- ① The *StorageClass* name, that must match exactly or the claim will go unbound until it is deleted or another *StorageClass* is created that matches the name.

Create and view the PVC and PV to see if it is bound.

```
# oc create -f pvc-finance-history.yaml
persistentvolumeclaim "pvc-finance-history" created

# oc get pvc
NAME STATUS VOLUME CAPACITY
ACCESSMODES AGE
pvc-finance-history Bound pv-finance-history 35Gi RWX
9m

# oc get pv (cluster/storage-admin)
NAME CAPACITY ACCESSMODES RECLAIMPOLICY STATUS
CLAIM REASON AGE
pv-finance-history 35Gi RWX Retain Bound
default/pvc-finance-history 5m
```



#### IMPORTANT

You can use *StorageClasses* in the same cluster for both legacy data (no dynamic provisioning) and with [dynamic provisioning](#).

## 25.12. CONFIGURING AZURE BLOB STORAGE FOR INTEGRATED DOCKER REGISTRY

### 25.12.1. Overview

This topic reviews how to configure [Microsoft Azure Blob Storage](#) for OpenShift integrated Docker registry.

### 25.12.2. Before You Begin

- Create a storage container using Microsoft Azure Portal, Microsoft Azure CLI, or Microsoft Azure Storage Explorer. Keep a note of the ***storage account name***, ***storage account key*** and ***container name***.
- [Deploy the integrated Docker registry](#) if it is not deployed.

### 25.12.3. Overriding Registry Configuration

To create a new registry pod and replace the old pod automatically:

1. Create a new registry configuration file called ***registryconfig.yaml*** and add the following information:

```
version: 0.1
log:
  level: debug
http:
  addr: :5000
storage:
  cache:
    blobdescriptor: inmemory
  delete:
    enabled: true
  azure: ①
    accountname: azureblobacc
    accountkey: azureblobacckey
    container: azureblobname
    realm: core.windows.net ②
auth:
  openshift:
    realm: openshift
middleware:
  registry:
    - name: openshift
repository:
  - name: openshift
    options:
      acceptschema2: false
      pullthrough: true
      enforcequota: false
      projectcachettl: 1m
      blobrepositorycachettl: 10m
storage:
  - name: openshift
```

- 1 Replace the values for **accountname**, **acountkey**, and **container** with **storage account name**, **storage account key**, and **storage container name** respectively.
- 2 If using Azure regional cloud, set to the desired realm. For example, **core.cloudapi.de** for the Germany regional cloud.

2. Create a new registry configuration:

```
$ oc create secret generic registry-config --from-file=config.yaml=registryconfig.yaml
```

3. Add the secret:

```
$ oc volume dc/docker-registry --add --type=secret \
--secret-name=registry-config -m /etc/docker/registry/
```

4. Set the **REGISTRY\_CONFIGURATION\_PATH** environment variable:

```
$ oc set env dc/docker-registry \
REGISTRY_CONFIGURATION_PATH=/etc/docker/registry/config.yaml
```

5. If you already created a registry configuration:

a. Delete the secret:

```
$ oc delete secret registry-config
```

b. Create a new registry configuration:

```
$ oc create secret generic registry-config --from-file=config.yaml=registryconfig.yaml
```

c. Update the configuration by starting a new rollout:

```
$ oc rollout latest docker-registry
```

# CHAPTER 26. WORKING WITH HTTP PROXIES

## 26.1. OVERVIEW

Production environments can deny direct access to the Internet and instead have an HTTP or HTTPS proxy available. Configuring OpenShift Container Platform to use these proxies can be as simple as setting standard environment variables in configuration or JSON files. This can be done during an [advanced installation](#) or configured after installation.

The proxy configuration must be the same on each host in the cluster. Therefore, when setting up the proxy or modifying it, you must update the files on each OpenShift Container Platform host to the same values. Then, you must restart OpenShift Container Platform services on each host in the cluster.

The **NO\_PROXY**, **HTTP\_PROXY**, and **HTTPS\_PROXY** environment variables are found in each host's `/etc/sysconfig/atomic-openshift-master-api` or `/etc/sysconfig/atomic-openshift-master-controllers` files and `/etc/sysconfig/atomic-openshift-node` file.

## 26.2. CONFIGURING NO\_PROXY

The **NO\_PROXY** environment variable lists all of the OpenShift Container Platform components and all IP addresses that are managed by OpenShift Container Platform.

On the OpenShift service accepting the CIDR, **NO\_PROXY** accepts a comma-separated list of hosts, IP addresses, or IP ranges in CIDR format:

### For master hosts

- Node host name
- Master IP or host name
- IP address of etcd hosts

### For node hosts

- Master IP or host name

### For the Docker service

- Registry service IP and host name
- Registry service URL `docker-registry.default.svc.cluster.local`
- Registry route host name (if created)



### NOTE

When using Docker, Docker accepts a comma-separated list of hosts, domain extensions, or IP addresses, but does not accept IP ranges in CIDR format, which are only accepted by OpenShift services. The `no\_proxy` variable should contain a comma-separated list of domain extensions that the proxy should *not* be used for.

For example, if `no_proxy` is set to `.school.edu`, the proxy will not be used to retrieve documents from the specific school.

**NO\_PROXY** also includes the SDN network and service IP addresses as found in the **master-config.yaml** file.

#### /etc/origin/master/master-config.yaml

```
networkConfig:
  clusterNetworks:
    - cidr: 10.1.0.0/16
      hostSubnetLength: 9
    serviceNetworkCIDR: 172.30.0.0/16
```

OpenShift Container Platform does not accept \* as a wildcard attached to a domain suffix. For example, the following would be accepted:

```
NO_PROXY=.example.com
```

However, the following would not be:

```
NO_PROXY=*.example.com
```

The only wildcard **NO\_PROXY** accepts is a single \* character, which matches all hosts, and effectively disables the proxy.

Each name in this list is matched as either a domain which contains the host name as a suffix, or the host name itself.



#### NOTE

When scaling up nodes, use a domain name rather than a list of hostnames.

For instance, **example.com** would match **example.com**, **example.com:80**, and **www.example.com**.

### 26.3. CONFIGURING HOSTS FOR PROXIES

1. Edit the proxy environment variables in the OpenShift Container Platform control files. Ensure all of the files in the cluster are correct.

```
HTTP_PROXY=http://<user>:<password>@<ip_addr>:<port>/
HTTPS_PROXY=https://<user>:<password>@<ip_addr>:<port>/
NO_PROXY=master.hostname.example.com,10.1.0.0/16,172.30.0.0/16 ①
```

- ① Supports host names and CIDRs. Must include the SDN network and service IP ranges **10.1.0.0/16, 172.30.0.0/16** by default.

2. Restart the master or node host as appropriate:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
# systemctl restart atomic-openshift-node
```

For multi-master installations:

-


```
# systemctl restart atomic-openshift-master-controllers
# systemctl restart atomic-openshift-master-api
```

## 26.4. CONFIGURING HOSTS FOR PROXIES USING ANSIBLE

During [advanced installations](#), the **NO\_PROXY**, **HTTP\_PROXY**, and **HTTPS\_PROXY** environment variables can be configured using the [\*\*openshift\\_no\\_proxy\*\*](#), [\*\*openshift\\_http\\_proxy\*\*](#), and [\*\*openshift\\_https\\_proxy\*\*](#) parameters, which are configurable in the inventory file.

### Example Proxy Configuration with Ansible

```
# Global Proxy Configuration
# These options configure HTTP_PROXY, HTTPS_PROXY, and NOPROXY environment
# variables for docker and master services.
openshift_http_proxy=http://<user>:<password>@<ip_addr>:<port>
openshift_https_proxy=https://<user>:<password>@<ip_addr>:<port>
openshift_no_proxy='hosts.example.com,some-host.com'
#
# Most environments do not require a proxy between OpenShift masters,
# nodes, and
# etcd hosts. So automatically add those host names to the
# openshift_no_proxy list.
# If all of your hosts share a common domain you may wish to disable this
# and
# specify that domain above.
# openshift_generate_no_proxy_hosts=True
```



### NOTE

There are [additional proxy settings](#) that can be [configured for builds](#) using Ansible parameters. For example:

The **openshift\_builddefaults\_git\_http\_proxy** and **openshift\_builddefaults\_git\_https\_proxy** parameters allow you to [use a proxy for Git cloning](#)

The **openshift\_builddefaults\_http\_proxy** and **openshift\_builddefaults\_https\_proxy** parameters can make environment variables available to the [Docker build strategy](#) and [Custom build strategy](#) processes.

## 26.5. PROXYING DOCKER PULL

OpenShift Container Platform node hosts need to perform push and pull operations to Docker registries. If you have a registry that does not need a proxy for nodes to access, include the **NO\_PROXY** parameter with:

- the registry's host name,
- the registry service's IP address, and
- the service name.

This blacklists that registry, leaving the external HTTP proxy as the only option.

1. Retrieve the registry service's IP address `docker_registry_ip` by running:

```
$ oc describe svc/docker-registry -n default

Name: docker-registry
Namespace: default
Labels: docker-registry=default
Selector: docker-registry=default
Type: ClusterIP
IP: 172.30.163.183 ①
Port: 5000-tcp 5000/TCP
Endpoints: 10.1.0.40:5000
Session Affinity: ClientIP
No events.
```

- 1 Registry service IP.

2. Edit the `/etc/sysconfig/docker` file and add the `NO_PROXY` variables in shell format, replacing `<docker_registry_ip>` with the IP address from the previous step.

```
HTTP_PROXY=http://<user>:<password>@<ip_addr>:<port>/
HTTPS_PROXY=https://<user>:<password>@<ip_addr>:<port>/
NO_PROXY=master.hostname.example.com,<docker_registry_ip>,docker-
registry.default.svc.cluster.local
```

3. Restart the Docker service:

```
# systemctl restart docker
```

## 26.6. USING MAVEN BEHIND A PROXY

Using Maven with proxies requires using the `HTTP_PROXY_NONPROXYHOSTS` variable.

See the [Red Hat JBoss Enterprise Application Platform for OpenShift documentation](#) for information about configuring your OpenShift Container Platform environment for Red Hat JBoss Enterprise Application Platform, including the step for setting up Maven behind a proxy.

## 26.7. CONFIGURING S2I BUILDS FOR PROXIES

S2I builds fetch dependencies from various locations. You can [use a `.s2i/environment` file](#) to specify simple shell variables and OpenShift Container Platform will react accordingly when seeing build images.

The following are the supported proxy environment variables with example values:

```
HTTP_PROXY=http://USERNAME:PASSWORD@10.0.1.1:8080/
HTTPS_PROXY=https://USERNAME:PASSWORD@10.0.0.1:8080/
NO_PROXY=master.hostname.example.com
```

## 26.8. CONFIGURING DEFAULT TEMPLATES FOR PROXIES

The [example templates](#) available in OpenShift Container Platform by default do not include settings for HTTP proxies. For existing applications based on these templates, modify the **source** section of the application's build configuration and add proxy settings:

```
...
source:
  type: Git
  git:
    uri: https://github.com/openshift/ruby-hello-world
    httpProxy: http://proxy.example.com
    httpsProxy: https://proxy.example.com
    noProxy: somedomain.com, otherdomain.com
...

```

This is similar to the process for [using proxies for Git cloning](#).

## 26.9. SETTING PROXY ENVIRONMENT VARIABLES IN PODS

You can set the **NO\_PROXY**, **HTTP\_PROXY**, and **HTTPS\_PROXY** environment variables in the **templates.spec.containers** stanza in a deployment configuration to pass proxy connection information. The same can be done for configuring a Pod's proxy at runtime:

```
...
containers:
- env:
  - name: "HTTP_PROXY"
    value: "http://<user>:<password>@<ip_addr>:<port>"
...

```

You can also use the **oc set env** command to update an existing deployment configuration with a new environment variable:

```
$ oc set env dc/frontend HTTP_PROXY=http://<user>:<password>@<ip_addr>:<port>
```

If you have a [ConfigChange trigger](#) set up in your OpenShift Container Platform instance, the changes happen automatically. Otherwise, manually redeploy your application for the changes to take effect.

## 26.10. GIT REPOSITORY ACCESS

If your Git repository can only be accessed using a proxy, you can define the proxy to use in the **source** section of the **BuildConfig**. You can configure both a HTTP and HTTPS proxy to use. Both fields are optional. Domains for which no proxying should be performed can also be specified via the **NoProxy** field.



### NOTE

Your source URI must use the HTTP or HTTPS protocol for this to work.

```
source:
  git:
    uri: "https://github.com/openshift/ruby-hello-world"
```

```
httpProxy: http://proxy.example.com  
httpsProxy: https://proxy.example.com  
noProxy: somedomain.com, otherdomain.com
```

# CHAPTER 27. CONFIGURING GLOBAL BUILD DEFAULTS AND OVERRIDES

## 27.1. OVERVIEW

Developers can define settings in specific build configurations within their projects, such as [configuring a proxy for Git cloning](#). Rather than requiring developers to define certain settings in each build configuration, administrators can use admission control plug-ins to configure global build defaults and overrides that automatically use these settings in any build.

The settings from these plug-ins are used only during the build process but are not set in the build configurations or builds themselves. Configuring the settings through the plug-ins allows administrators to change the global configuration at any time, and any builds that are re-run from existing build configurations or builds are assigned the new settings.

- The **BuildDefaults** admission control plug-in allows administrators to set global defaults for settings such as the Git HTTP and HTTPS proxy, as well as default environment variables. These defaults do not overwrite values that have been configured for a specific build. However, if those values are not present on the build definition, they are set to the default value.
- The **BuildOverrides** admission control plug-in allows administrators to override a setting in a build, regardless of the value stored in the build. The plug-in currently supports [overriding the forcePull flag on a build strategy](#) to force refreshing the local image from the registry during a build. Refreshing ensures that users can build only with images that they are allowed to pull. The plug-in can also be configured to apply a set of image labels to every built image. For information on configuring the **BuildOverrides** admission control plug-in and the values you can override, see [Manually Setting Global Build Overrides](#).

The default node selectors and the **BuildDefaults** or **BuildOverride** admission plug-ins work together as follows:

- The default project node selector, defined in the **projectConfig.defaultNodeSelector** field in the master configuration file, is applied to the pods created in all projects without a specified **nodeSelector** value. These settings are applied to builds with **nodeSelector="null"** on clusters where the **BuildDefaults** or **BuildOverride** nodeselector is not set.
- The cluster-wide default build node selector, **admissionConfig.pluginConfig.BuildDefaults.configuration.nodeSelector**, is applied only if the **nodeSelector="null"** parameter is set in the build configuration. **nodeSelector=null** is the default setting.
- With a default project or cluster-wide node selector, the default setting is added as an AND to the build node selector, which is set by the **BuildDefaults** or **BuildOverride** admission plug-ins. These settings mean that the build will be scheduled only to nodes that satisfy the **BuildOverrides** node selector AND the project default node selector.



### NOTE

You can define a hard limit on how long build pods can run by using the [RunOnceDuration plugin](#).

## 27.2. SETTING GLOBAL BUILD DEFAULTS

You can set global build defaults two ways:

- using Ansible and the advanced installation tool
- manually by modifying the [\*master-config.yaml\*](#) file

### 27.2.1. Configuring Global Build Defaults with Ansible

During [advanced installations](#), the **BuildDefaults** plug-in can be configured using [the following parameters](#), which are configurable in the inventory file:

- `openshift_builddefaults_http_proxy`
- `openshift_builddefaults_https_proxy`
- `openshift_builddefaults_no_proxy`
- `openshift_builddefaults_git_http_proxy`
- `openshift_builddefaults_git_https_proxy`
- `openshift_builddefaults_git_no_proxy`
- `openshift_builddefaults_image_labels`
- `openshift_builddefaults_nodeselectors`
- `openshift_builddefaults_annotations`
- `openshift_builddefaults_resources_requests_cpu`
- `openshift_builddefaults_resources_requests_memory`
- `openshift_builddefaults_resources_limits_cpu`
- `openshift_builddefaults_resources_limits_memory`

#### Example 27.1. Example Build Defaults Configuration with Ansible

```
# These options configure the BuildDefaults admission controller which
# injects
# configuration into Builds. Proxy related values will default to the
# global proxy
# config values. You only need to set these if they differ from the
# global proxy settings.
openshift_builddefaults_http_proxy=http://USER:PASSWORD@HOST:PORT
openshift_builddefaults_https_proxy=https://USER:PASSWORD@HOST:PORT
openshift_builddefaults_no_proxy=mycorp.com
openshift_builddefaults_git_http_proxy=http://USER:PASSWORD@HOST:PORT
openshift_builddefaults_git_https_proxy=https://USER:PASSWORD@HOST:PORT
openshift_builddefaults_git_no_proxy=mycorp.com
openshift_builddefaults_image_labels=
[{'name': 'imagelabelname1', 'value': 'imagelabelvalue1'}]
openshift_builddefaults_nodeselectors={'nodelabel1': 'nodelabelvalue1'}
openshift_builddefaults_annotations=
{'annotationkey1': 'annotationvalue1'}
```

```

openshift_builddefaults_resources_requests_cpu=100m
openshift_builddefaults_resources_requests_memory=256Mi
openshift_builddefaults_resources_limits_cpu=1000m
openshift_builddefaults_resources_limits_memory=512Mi

# Or you may optionally define your own build defaults configuration
# serialized as json
#openshift_builddefaults_json='{"BuildDefaults": {"configuration":
  {"apiVersion": "v1", "env":
    [{"name": "HTTP_PROXY", "value": "http://proxy.example.com.redhat.com:3128"}, {"name": "NO_PROXY", "value": "ose3-master.example.com"}], "gitHTTPProxy": "http://proxy.example.com:3128", "gitNoProxy": "ose3-master.example.com", "kind": "BuildDefaultsConfig"}}'

```

## 27.2.2. Manually Setting Global Build Defaults

To configure the **BuildDefaults** plug-in:

1. Add a configuration for it in the `/etc/origin/master/master-config.yaml` file on the master nodes:

```

admissionConfig:
  pluginConfig:
    BuildDefaults:
      configuration:
        apiVersion: v1
        kind: BuildDefaultsConfig
        gitHTTPProxy: http://my.proxy:8080 1
        gitHTTPSPort: https://my.proxy:8443 2
        gitNoProxy: somedomain.com, otherdomain.com 3
        env:
          - name: HTTP_PROXY 4
            value: http://my.proxy:8080
          - name: HTTPS_PROXY 5
            value: https://my.proxy:8443
          - name: BUILD_LOGLEVEL 6
            value: 4
          - name: CUSTOM_VAR 7
            value: custom_value
        imageLabels:
          - name: url 8
            value: https://containers.example.org
          - name: vendor
            value: ExampleCorp Ltd.
        nodeSelector: 9
          key1: value1
          key2: value2
        annotations: 10
          key1: value1
          key2: value2
        resources: 11
          requests:
            cpu: "100m"

```

```

    memory: "256Mi"
limits:
  cpu: "100m"
  memory: "256Mi"

```

- 1** Sets the HTTP proxy to use when cloning source code from a Git repository.
- 2** Sets the HTTPS proxy to use when cloning source code from a Git repository.
- 3** Sets the list of domains for which proxying should not be performed.
- 4** Default environment variable that sets the HTTP proxy to use during the build. This can be used for downloading dependencies during the assemble and build phases.
- 5** Default environment variable that sets the HTTPS proxy to use during the build. This can be used for downloading dependencies during the assemble and build phases.
- 6** Default environment variable that sets the build log level during the build.
- 7** Additional default environment variable that will be added to every build.
- 8** Labels to be applied to every image built. Users can override these in their **BuildConfig**.
- 9** Build pods will only run on nodes with the **key1=value2** and **key2=value2** labels. Users can define a different set of **nodeSelectors** for their builds in which case these values will be ignored.
- 10** Build pods will have these annotations added to them.
- 11** Sets the default resources to the build pod if the **BuildConfig** does not have related resource defined.

2. Restart the master services for the changes to take effect:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

## 27.3. SETTING GLOBAL BUILD OVERRIDES

You can set global build overrides two ways:

- using [Ansible and the advanced installation tool](#)
- manually by modifying the [\*master-config.yaml\* file](#)

### 27.3.1. Configuring Global Build Overrides with Ansible

During [advanced installations](#), the **BuildOverrides** plug-in can be configured using the following parameters, which are configurable in the inventory file:

- **openshift\_buildoverrides\_force\_pull**
- **openshift\_buildoverrides\_image\_labels**

- `openshift_buildoverrides_nodeselectors`
- `openshift_buildoverrides_annotations`
- `openshift_buildoverrides_tolerations`

### Example 27.2. Example Build Overrides Configuration with Ansible

```
# These options configure the BuildOverrides admission controller which
# injects
# configuration into Builds.
openshift_buildoverrides_force_pull=true
openshift_buildoverrides_image_labels=
[{"name": "imagelabelname1", "value": "imagelabelvalue1"}]
openshift_buildoverrides_nodeselectors={"nodelabel1": "nodelabelvalue1"}
openshift_buildoverrides_annotations=
{"annotationkey1": "annotationvalue1"}
openshift_buildoverrides_tolerations=
[{"key": "mykey1", "value": "myvalue1", "effect": "NoSchedule", "operator": "Equal"}]

# Or you may optionally define your own build overrides configuration
# serialized as json
#openshift_buildoverrides_json='{"BuildOverrides": {"configuration": {
#    "apiVersion": "v1", "kind": "BuildOverridesConfig", "forcePull": "true", "tolerations": [
#        {"key": "mykey1", "value": "myvalue1", "effect": "NoSchedule", "operator": "Equal"}]}}}'
```

### 27.3.2. Manually Setting Global Build Overrides

To configure the `BuildOverrides` plug-in:

1. Add a configuration for it in the `/etc/origin/master/master-config.yaml` file on masters:

```
admissionConfig:
  pluginConfig:
    BuildOverrides:
      configuration:
        apiVersion: v1
        kind: BuildOverridesConfig
        forcePull: true 1
        imageLabels:
          - name: distribution-scope 2
            value: private
        nodeSelector: 3
          key1: value1
          key2: value2
        annotations: 4
          key1: value1
          key2: value2
        tolerations: 5
          - key: mykey1
```

```
value: myvalue1
effect: NoSchedule
operator: Equal
- key: mykey2
  value: myvalue2
  effect: NoExecute
  operator: Equal
```

- 1 Force all builds to pull their builder image and any source images before starting the build.
  - 2 Additional labels to be applied to every image built. Labels defined here take precedence over labels defined in **BuildConfig**.
  - 3 Build pods will only run on nodes with the **key1=value2** and **key2=value2** labels. Users can define additional key/value labels to further constrain the set of nodes a build runs on, but the **node** must have at least these labels.
  - 4 Build pods will have these annotations added to them.
  - 5 Build pods will have any existing tolerations overridden by those listed here.
2. Restart the master services for the changes to take effect:

```
# systemctl restart atomic-openshift-master-api atomic-openshift-
master-controllers
```

# CHAPTER 28. CONFIGURING PIPELINE EXECUTION

## 28.1. OVERVIEW

The first time a user creates a build configuration using the [Pipeline](#) build strategy, OpenShift Container Platform looks for a template named `jenkins-ephemeral` in the `openshift` namespace and instantiates it within the user's project. The `jenkins-ephemeral` template that ships with OpenShift Container Platform creates, upon instantiation:

- a deployment configuration for Jenkins using the official OpenShift Container Platform Jenkins image
- a service and route for accessing the Jenkins deployment
- a new Jenkins service account
- rolebindings to grant the service account edit access to the project

Cluster administrators can control what is created by either modifying the content of the built-in template, or by editing the cluster configuration to direct the cluster to a different template location.

To modify the content of the default template:

```
$ oc edit template jenkins-ephemeral -n openshift
```

To use a different template, such as the `jenkins-persistent` template which uses persistent storage for Jenkins, add the following to your master configuration file:

```
jenkinsPipelineConfig:
  autoProvisionEnabled: true 1
  templateNamespace: openshift 2
  templateName: jenkins-persistent 3
  serviceName: jenkins-persistent-svc 4
  parameters: 5
    key1: value1
    key2: value2
```

- 1** Defaults to `true` if unspecified. If `false`, then no template will be instantiated.
- 2** Namespace containing the template to be instantiated.
- 3** Name of the template to be instantiated.
- 4** Name of the service to be created by the template upon instantiation.
- 5** Optional values to pass to the template during instantiation.

When a Pipeline build configuration is created, OpenShift Container Platform looks for a Service matching `serviceName`. This means `serviceName` must be chosen such that it is unique in the project. If no Service is found, OpenShift Container Platform instantiates the `jenkinsPipelineConfig` template. If this is not desirable (if you would like to use a Jenkins server external to OpenShift Container Platform, for example), there are a few things you can do, depending on who you are.

- If you are a cluster administrator, simply set `autoProvisionEnabled` to `false`. This will disable autopropvisioning across the cluster.
- If you are an unprivileged user, a Service must be created for OpenShift Container Platform to use. The service name must match the cluster configuration value of `serviceName` in the `jenkinsPipelineConfig`. The default value is `jenkins`. If you are disabling autopropvisioning because you are running a Jenkins server outside your project, it is recommended that you point this new service to your existing Jenkins server. See: [Integrating External Services](#)

The latter option could also be used to disable autopropvisioning in select projects only.

## 28.2. OPENSIFT JENKINS CLIENT PLUGIN

The OpenShift Jenkins Client Plugin is a Jenkins plugin which aims to provide a readable, concise, comprehensive, and fluent Jenkins Pipeline syntax for rich interactions with an OpenShift API Server. The plugin leverages the OpenShift command line tool (`oc`) which must be available on the nodes executing the script.

For more information about installing and configuring the plugin, use the links provided below that reference the official documentation.

- [Installing](#)
- [Configuring an OpenShift Cluster](#)
- [Setting up Credentials](#)
- [Setting up Jenkins Nodes](#)



### NOTE

Are you a developer looking for information about using this plugin? If so, see [OpenShift Pipeline Overview](#).

## 28.3. OPENSIFT JENKINS SYNC PLUGIN

This Jenkins plugin keeps OpenShift BuildConfig and Build objects in sync with Jenkins Jobs and Builds.

The OpenShift jenkins Sync Plugin provides the following:

- Dynamic job/run creation in Jenkins.
- Dynamic creation of slave pod templates from ImageStreams, ImageStreamTags, or ConfigMaps.
- Injecting of environment variables.
- Pipeline visualization in the OpenShift web console.
- Integration with the Jenkins git plugin, which passes commit information from OpenShift builds to the Jenkins git plugin.

For more information about this plugin, see:

- [OpenShift Jenkins Sync Plug-in](#)

- OpenShift Container Platform Sync Plug-in

## CHAPTER 29. CONFIGURING ROUTE TIMEOUTS

After installing OpenShift Container Platform and [deploying a router](#), you can configure the default timeouts for an existing route when you have services in need of a low timeout, as required for Service Level Availability (SLA) purposes, or a high timeout, for cases with a slow back end.

Using the **oc annotate** command, add the timeout to the route:

```
# oc annotate route <route_name> \
--overwrite haproxy.router.openshift.io/timeout=<timeout><time_unit>
```

For example, to set a route named **myroute** to a timeout of two seconds:

```
# oc annotate route myroute --overwrite
haproxy.router.openshift.io/timeout=2s
```

Supported time units are microseconds (us), milliseconds (ms), seconds (s), minutes (m), hours (h), or days (d).


# CHAPTER 30. CONFIGURING NATIVE CONTAINER ROUTING

## 30.1. NETWORK OVERVIEW

The following describes a general network setup:

- 11.11.0.0/16 is the container network.
- The 11.11.x.0/24 subnet is reserved for each node and assigned to the Docker Linux bridge.
- Each node has a route to the router for reaching anything in the 11.11.0.0/16 range, except the local subnet.
- The router has routes for each node, so it can be directed to the right node.
- Existing nodes do not need any changes when new nodes are added, unless the network topology is modified.
- IP forwarding is enabled on each node.

The following diagram shows the container networking setup described in this topic. It uses one Linux node with two network interface cards serving as a router, two switches, and three nodes connected to these switches.



## 30.2. CONFIGURE NATIVE CONTAINER ROUTING

You can set up container networking using existing switches and routers, and the kernel networking stack in Linux.

As a network administrator, you must modify, or create a script to modify, the router or routers when new nodes are added to the cluster.

You can adapt this process to use with any type of router.

### 30.3. SETTING UP A NODE FOR CONTAINER NETWORKING

1. Assign an unused 11.11.x.0/24 subnet IP address to the Linux bridge on the node:

```
# brctl addbr lbr0  
# ip addr add 11.11.1.1/24 dev lbr0  
# ip link set dev lbr0 up
```

2. Modify the Docker startup script to use the new bridge. By default, the startup script is the `/etc/sysconfig/docker` file:

```
# docker -d -b lbr0 --other-options
```

3. Add a route to the router for the 11.11.0.0/16 network:

```
# ip route add 11.11.0.0/16 via 192.168.2.2 dev p3p1
```

4. Enable IP forwarding on the node:

```
# sysctl -w net.ipv4.ip_forward=1
```

### 30.4. SETTING UP A ROUTER FOR CONTAINER NETWORKING

The following procedure assumes a Linux box with multiple NICs is used as a router. Modify the steps as required to use the syntax for a particular router:

1. Enable IP forwarding on the router:

```
# sysctl -w net.ipv4.ip_forward=1
```

2. Add a route for each node added to the cluster:

```
# ip route add <node_subnet> via <node_ip_address> dev <interface  
through which node is L2 accessible>  
# ip route add 11.11.1.0/24 via 192.168.2.1 dev p3p1  
# ip route add 11.11.2.0/24 via 192.168.3.3 dev p3p2  
# ip route add 11.11.3.0/24 via 192.168.3.4 dev p3p2
```

# CHAPTER 31. ROUTING FROM EDGE LOAD BALANCERS

## 31.1. OVERVIEW

[Pods](#) inside of an OpenShift Container Platform cluster are only reachable via their IP addresses on the cluster network. An edge load balancer can be used to accept traffic from outside networks and proxy the traffic to pods inside the OpenShift Container Platform cluster. In cases where the load balancer is not part of the cluster network, routing becomes a hurdle as the internal cluster network is not accessible to the edge load balancer.

To solve this problem where the OpenShift Container Platform cluster is using [OpenShift Container Platform SDN](#) as the cluster networking solution, there are two ways to achieve network access to the pods.

## 31.2. INCLUDING THE LOAD BALANCER IN THE SDN

If possible, run an OpenShift Container Platform node instance on the load balancer itself that uses OpenShift SDN as the networking plug-in. This way, the edge machine gets its own Open vSwitch bridge that the SDN automatically configures to provide access to the pods and nodes that reside in the cluster. The *routing table* is dynamically configured by the SDN as pods are created and deleted, and thus the routing software is able to reach the pods.

Mark the load balancer machine as an [unschedulable node](#) so that no pods end up on the load balancer itself:

```
$ oc adm manage-node <load_balancer_hostname> --schedulable=false
```

If the load balancer comes packaged as a container, then it is even easier to integrate with OpenShift Container Platform: Simply run the load balancer as a pod with the host port exposed. The pre-packaged [HAProxy router](#) in OpenShift Container Platform runs in precisely this fashion.

## 31.3. ESTABLISHING A TUNNEL USING A RAMP NODE

In some cases, the previous solution is not possible. For example, an **F5 BIG-IP®** host cannot run an OpenShift Container Platform node instance or the OpenShift Container Platform SDN because **F5®** uses a custom, incompatible Linux kernel and distribution.

Instead, to enable **F5 BIG-IP®** to reach pods, you can choose an existing node within the cluster network as a *ramp node* and establish a tunnel between the **F5 BIG-IP®** host and the designated ramp node. Because it is otherwise an ordinary OpenShift Container Platform node, the ramp node has the necessary configuration to route traffic to any pod on any node in the cluster network. The ramp node thus assumes the role of a gateway through which the **F5 BIG-IP®** host has access to the entire cluster network.

Following is an example of establishing an **ipip** tunnel between an **F5 BIG-IP®** host and a designated ramp node.

### On the F5 BIG-IP® host:

- Set the following variables:

```
# F5_IP=10.3.89.66 ①
# RAMP_IP=10.3.89.89 ②
```

```
# TUNNEL_IP1=10.3.91.216 ③
# CLUSTER_NETWORK=10.128.0.0/14 ④
```

① ② The **F5\_IP** and **RAMP\_IP** variables refer to the **F5 BIG-IP®** host's and the ramp node's IP addresses, respectively, on a shared, internal network.

③ An arbitrary, non-conflicting IP address for the **F5®** host's end of the **ipip** tunnel.

④ The overlay network CIDR that the OpenShift SDN uses to assign addresses to pods.

2. Delete any old route, self, tunnel and SNAT pool:

```
# tmsh delete net route $CLUSTER_NETWORK || true
# tmsh delete net self SDN || true
# tmsh delete net tunnels tunnel SDN || true
# tmsh delete ltm snatpool SDN_snatpool || true
```

3. Create the new tunnel, self, route and SNAT pool and use the SNAT pool in the virtual servers:

```
# tmsh create net tunnels tunnel SDN \
  \{ description "OpenShift SDN" local-address \
    $F5_IP profile ipip remote-address $RAMP_IP \}
# tmsh create net self SDN \{ address \
  ${TUNNEL_IP1}/24 allow-service all vlan SDN \}
# tmsh create net route $CLUSTER_NETWORK interface SDN
# tmsh create ltm snatpool SDN_snatpool members add { $TUNNEL_IP1 }
# tmsh modify ltm virtual ose-vserver source-address-translation {
  type snat pool SDN_snatpool }
# tmsh modify ltm virtual https-ose-vserver source-address-
  translation { type snat pool SDN_snatpool }
```

#### On the ramp node:

1. Set the following variables:

```
# F5_IP=10.3.89.66
# TUNNEL_IP1=10.3.91.216
# TUNNEL_IP2=10.3.91.217 ①
# CLUSTER_NETWORK=10.128.0.0/1 ②
```

① A second, arbitrary IP address for the ramp node's end of the **ipip** tunnel.

② The overlay network CIDR that the OpenShift SDN uses to assign addresses to pods.

2. Delete any old tunnel:

```
# ip tunnel del tun1 || true
```

3. Create the **ipip** tunnel on the ramp node, using a suitable L2-connected interface (e.g., **eth0**):

```
# ip tunnel add tun1 mode ipip \
  remote $F5_IP dev eth0
```

```
# ip addr add $TUNNEL_IP2 dev tun1
# ip link set tun1 up
# ip route add $TUNNEL_IP1 dev tun1
# ping -c 5 $TUNNEL_IP1
```

4. SNAT the tunnel IP with an unused IP from the SDN subnet:

```
# source /run/openshift-sdn/config.env
# tap1=$(ip -o -4 addr list tun0 | awk '{print $4}' | cut -d/ -f1 |
head -n 1)
# subaddr=$(echo ${OPENSHIFT_SDN_TAP1_ADDR}:"$tap1" | cut -d ":" -f
1,2,3)
# export RAMP_SDN_IP=${subaddr}.254
```

5. Assign this **RAMP\_SDN\_IP** as an additional address to **tun0** (the local SDN's gateway):

```
# ip addr add ${RAMP_SDN_IP} dev tun0
```

6. Modify the OVS rules for SNAT:

```
# ipflowopts="cookie=0x999,ip"
# arpflowopts="cookie=0x999, table=0, arp"
#
# ovs-ofctl -O OpenFlow13 add-flow br0 \
"${ipflowopts},nw_src=${TUNNEL_IP1},actions=mod_nw_src:${RAMP_SDN_IP},
},resubmit(,0)"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
"${ipflowopts},nw_dst=${RAMP_SDN_IP},actions=mod_nw_dst:${TUNNEL_IP1},
},resubmit(,0)"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
    "${arpflowopts}, arp_tpa=${RAMP_SDN_IP}, actions=output:2"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
    "${arpflowopts}, priority=200, in_port=2,
arp_spa=${RAMP_SDN_IP}, arp_tpa=${CLUSTER_NETWORK},
actions=goto_table:30"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
    "arp, table=5, priority=300, arp_tpa=${RAMP_SDN_IP},
actions=output:2"
# ovs-ofctl -O OpenFlow13 add-flow br0 \
    "ip,table=5,priority=300,nw_dst=${RAMP_SDN_IP},actions=output:2"
# ovs-ofctl -O OpenFlow13 add-flow br0
"${ipflowopts},nw_dst=${TUNNEL_IP1},actions=output:2"
```

7. Optionally, if you do not plan on configuring the ramp node to be highly available, mark the ramp node as unschedulable. Skip this step if you do plan to follow the next section and plan on creating a highly available ramp node.

```
$ oc adm manage-node <ramp_node_hostname> --schedulable=false
```



### NOTE

The [F5 router plug-in](#) integrates with F5 BIG-IP®.

### 31.3.1. Configuring a Highly-Available Ramp Node

You can use OpenShift Container Platform's **ipfailover** feature, which uses **keepalived** internally, to make the ramp node highly available from **F5 BIG-IP®**'s point of view. To do so, first bring up two nodes, for example called **ramp-node-1** and **ramp-node-2**, on the same L2 subnet.

Then, choose some unassigned IP address from within the same subnet to use for your virtual IP, or **VIP**. This will be set as the **RAMP\_IP** variable with which you will configure your tunnel on **F5 BIG-IP®**.

For example, suppose you are using the **10.20.30.0/24** subnet for your ramp nodes, and you have assigned **10.20.30.2** to **ramp-node-1** and **10.20.30.3** to **ramp-node-2**. For your VIP, choose some unassigned address from the same **10.20.30.0/24** subnet, for example **10.20.30.4**. Then, to configure **ipfailover**, mark both nodes with a label, such as **f5rampnode**:

```
$ oc label node ramp-node-1 f5rampnode=true
$ oc label node ramp-node-2 f5rampnode=true
```

Similar to instructions from the [ipfailover documentation](#), you must now create a service account and add it to the **privileged** SCC. First, create the **f5ipfailover** service account:

```
$ oc create serviceaccount f5ipfailover -n default
```

Next, you can add the **f5ipfailover** service to the **privileged** SCC. To add the **f5ipfailover** in the **default** namespace to the **privileged** SCC, run:

```
$ oc adm policy add-scc-to-user privileged
system:serviceaccount:default:f5ipfailover
```

Finally, configure **ipfailover** using your chosen VIP (the **RAMP\_IP** variable) and the **f5ipfailover** service account, assigning the VIP to your two nodes using the **f5rampnode** label you set earlier:

```
# RAMP_IP=10.20.30.4
# IFNAME=eth0 ①
# oc adm ipfailover <name-tag> \
    --virtual-ips=$RAMP_IP \
    --interface=$IFNAME \
    --watch-port=0 \
    --replicas=2 \
    --service-account=f5ipfailover \
    --selector='f5rampnode=true'
```

- ① The interface where **RAMP\_IP** should be configured.

With the above setup, the VIP (the **RAMP\_IP** variable) is automatically re-assigned when the ramp node host that currently has it assigned fails.

# CHAPTER 32. AGGREGATING CONTAINER LOGS


## 32.1. OVERVIEW

As an OpenShift Container Platform cluster administrator, you can deploy the EFK stack to aggregate logs for a range of OpenShift Container Platform services. Application developers can view the logs of the projects for which they have view access. The EFK stack aggregates logs from hosts and applications, whether coming from multiple containers or even deleted pods.

The EFK stack is a modified version of the [ELK stack](#) and is comprised of:

- [Elasticsearch \(ES\)](#): An object store where all logs are stored.
- [Fluentd](#): Gathers logs from nodes and feeds them to Elasticsearch.
- [Kibana](#): A web UI for Elasticsearch.

Once deployed in a cluster, the stack aggregates logs from all nodes and projects into Elasticsearch, and provides a Kibana UI to view any logs. Cluster administrators can view all logs, but application developers can only view logs for projects they have permission to view. The stack components communicate securely.



### NOTE

[Managing Docker Container Logs](#) discusses the use of `json-file` logging driver options to manage container logs and prevent filling node disks.

## 32.2. PRE-DEPLOYMENT CONFIGURATION

1. An Ansible playbook is available to deploy and upgrade aggregated logging. You should familiarize yourself with the [advanced installation and configuration](#) section. This provides information for preparing to use Ansible and includes information about configuration. Parameters are added to the Ansible inventory file to configure various areas of the EFK stack.
2. Review the [sizing guidelines](#) to determine how best to configure your deployment.
3. Ensure that you have deployed a router for the cluster.
4. Ensure that you have [the necessary storage](#) for Elasticsearch. Note that each Elasticsearch replica requires its own storage volume. See [Elasticsearch](#) for more information.
5. Choose a project. Once deployed, the EFK stack collects logs for every project within your OpenShift Container Platform cluster. The examples in this section use the default project **logging**. The Ansible playbook creates the project for you if it does not already exist. You will only need to create a project if you want to specify a node-selector on it. Otherwise, the **openshift-logging** role will create a project.


```
$ oc adm new-project logging --node-selector=""  
$ oc project logging
```

**NOTE**

Specifying an empty [node selector](#) on the project is recommended, as Fluentd should be deployed throughout the cluster and any selector would restrict where it is deployed. To control component placement, specify node selectors per component to be applied to their deployment configurations.

### 32.3. SPECIFYING LOGGING ANSIBLE VARIABLES

Parameters for the EFK deployment may be specified to the [inventory host file](#) to override the [defaults](#). Read the [Elasticsearch](#) and the [Fluentd](#) sections before choosing parameters:

**NOTE**

By default the Elasticsearch service uses port 9300 for TCP communication between nodes in a cluster.

Parameter	Description
<code>openshift_logging_image_prefix</code>	The prefix for logging component images. For example, setting the prefix to <code>registry.access.redhat.com/openshift3/</code> creates <code>registry.access.redhat.com/openshift3/logging-fluentd:latest</code> .
<code>openshift_logging_image_version</code>	The version for logging component images. For example, setting the version to <code>v3.9</code> creates <code>registry.access.redhat.com/openshift3/logging-fluentd:v3.9</code> .
<code>openshift_logging_use_ops</code>	If set to <code>true</code> , configures a second Elasticsearch cluster and Kibana for operations logs. Fluentd splits logs between the main cluster and a cluster reserved for operations logs, which consists of the logs from the projects <code>default</code> , <code>openshift</code> , and <code>openshift-infra</code> , as well as Docker, OpenShift, and system logs from the journal. This means a second Elasticsearch cluster and Kibana are deployed. The deployments are distinguishable by the <code>-ops</code> suffix included in their names and have parallel deployment options listed below and described in <a href="#">Creating the Curator Configuration</a> .
<code>openshift_logging_master_url</code>	The URL for the Kubernetes master, this does not need to be public facing but should be accessible from within the cluster. For example, <a href="https://&lt;PRIVATE-MASTER-URL&gt;:8443">https://&lt;PRIVATE-MASTER-URL&gt;:8443</a> .
<code>openshift_logging_master_public_url</code>	The public facing URL for the Kubernetes master. This is used for Authentication redirection by the Kibana proxy. For example, <a href="https://&lt;CONSOLE-PUBLIC-URL-MASTER&gt;:8443">https://&lt;CONSOLE-PUBLIC-URL-MASTER&gt;:8443</a> .
<code>openshift_logging_namespace</code>	The namespace where Aggregated Logging is deployed.
<code>openshift_logging_install_logging</code>	Set to <code>true</code> to install logging. Set to <code>false</code> to uninstall logging.

Parameter	Description
<b>openshift_logging_purge_logging</b>	The common uninstall keeps PVC to prevent unwanted data loss during reinstalls. To ensure that the Ansible playbook completely and irreversibly removes all logging persistent data including PVC, set <b>openshift_logging_install_logging</b> to 'false' to trigger uninstallation and <b>openshift_logging_purge_logging</b> to 'true'. The default is set to 'false'.
<b>openshift_logging_install_eventrouter</b>	Coupled with <b>openshift_logging_install_logging</b> . When both are set to 'true', eventrouter will be installed. When both are 'false', eventrouter will be uninstalled.
<b>openshift_logging_eventrouter_image_prefix</b>	The prefix for the eventrouter logging image. The default is set to <b>openshift_logging_image_prefix</b> .
<b>openshift_logging_eventrouter_image_version</b>	The image version for the logging eventrouter. The default is set to 'openshift_logging_image_version'.
<b>openshift_logging_eventrouter_sink</b>	Select a sink for eventrouter, supported <b>stdout</b> and <b>glog</b> . The default is set to <b>stdout</b> .
<b>openshift_logging_eventrouter_nodeselector</b>	A map of labels, such as " <b>node</b> ": "infra", " <b>region</b> ": "west", to select the nodes where the pod will land.
<b>openshift_logging_eventrouter_replicas</b>	The default is set to '1'.
<b>openshift_logging_eventrouter_cpu_limit</b>	The minimum amount of CPU to allocate to eventrouter. The default is set to '100m'.
<b>openshift_logging_eventrouter_memory_limit</b>	The memory limit for eventrouter pods. The default is set to '128Mi'.
<b>openshift_logging_eventrouter_namespace</b>	The namespace where eventrouter is deployed. The default is set to 'default'.
<b>openshift_logging_image_pull_secret</b>	Specify the name of an existing pull secret to be used for pulling component images from an authenticated registry.
<b>openshift_logging_curator_default_days</b>	The default minimum age (in days) Curator uses for deleting log records.

Parameter	Description
<code>openshift_logging_curator_run_hour</code>	The hour of the day Curator will run.
<code>openshift_logging_curator_run_minute</code>	The minute of the hour Curator will run.
<code>openshift_logging_curator_run_timezone</code>	The timezone Curator uses for figuring out its run time. Provide the timezone as a string in the tzselect(8) or timedatectl(1) "Region/Locality" format, for example <b>America/New_York</b> or <b>UTC</b> .
<code>openshift_logging_curator_script_log_level</code>	The script log level for Curator.
<code>openshift_logging_curator_log_level</code>	The log level for the Curator process.
<code>openshift_logging_curator_cpu_limit</code>	The amount of CPU to allocate to Curator.
<code>openshift_logging_curator_memory_limit</code>	The amount of memory to allocate to Curator.
<code>openshift_logging_curator_nodeselector</code>	A node selector that specifies which nodes are eligible targets for deploying Curator instances.
<code>openshift_logging_curator_ops_cpu_limit</code>	Equivalent to <code>openshift_logging_curator_cpu_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_curator_ops_memory_limit</code>	Equivalent to <code>openshift_logging_curator_memory_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_kibana_hostname</code>	The external host name for web clients to reach Kibana.
<code>openshift_logging_kibana_cpu_limit</code>	The amount of CPU to allocate to Kibana.
<code>openshift_logging_kibana_memory_limit</code>	The amount of memory to allocate to Kibana.
<code>openshift_logging_kibana_proxy_debug</code>	When <code>true</code> , set the Kibana Proxy log level to DEBUG.

Parameter	Description
<code>openshift_logging_kibana_proxy_cpu_limit</code>	The amount of CPU to allocate to Kibana proxy.
<code>openshift_logging_kibana_proxy_memory_limit</code>	The amount of memory to allocate to Kibana proxy.
<code>openshift_logging_kibana_replica_count</code>	The number of replicas to which Kibana should be scaled up.
<code>openshift_logging_kibana_nodeselector</code>	A node selector that specifies which nodes are eligible targets for deploying Kibana instances.
<code>openshift_logging_kibana_env_vars</code>	A map of environment variables to add to the Kibana deployment configuration. For example, <code>{"ELASTICSEARCH_REQUESTTIMEOUT":"30000"}</code> .
<code>openshift_logging_kibana_key</code>	The public facing key to use when creating the Kibana route.
<code>openshift_logging_kibana_cert</code>	The cert that matches the key when creating the Kibana route.
<code>openshift_logging_kibana_ca</code>	Optional. The CA to goes with the key and cert used when creating the Kibana route.
<code>openshift_logging_kibana_ops_hostname</code>	Equivalent to <code>openshift_logging_kibana_hostname</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_kibana_ops_cpu_limit</code>	Equivalent to <code>openshift_logging_kibana_cpu_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_kibana_ops_memory_limit</code>	Equivalent to <code>openshift_logging_kibana_memory_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_kibana_ops_proxy_debug</code>	Equivalent to <code>openshift_logging_kibana_proxy_debug</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_kibana_ops_proxy_cpu_limit</code>	Equivalent to <code>openshift_logging_kibana_proxy_cpu_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_kibana_ops_proxy_memory_limit</code>	Equivalent to <code>openshift_logging_kibana_proxy_memory_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .

Parameter	Description
<code>openshift_logging_kibana_ops_replica_count</code>	Equivalent to <code>openshift_logging_kibana_replica_count</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_allow_external</code>	Set to <code>true</code> to expose Elasticsearch as a reencrypt route. Set to <code>false</code> by default.
<code>openshift_logging_es_hostname</code>	<p>The external-facing hostname to use for the route and the TLS server certificate. The default is set to <code>es</code>.</p> <p>For example, if <code>openshift_master_default_subdomain</code> is set to <code>=example.test</code>, then the default value of <code>openshift_logging_es_hostname</code> will be <code>es.example.test</code>.</p>
<code>openshift_logging_es_cert</code>	The location of the certificate Elasticsearch uses for the external TLS server cert. The default is a generated cert.
<code>openshift_logging_es_key</code>	The location of the key Elasticsearch uses for the external TLS server cert. The default is a generated key.
<code>openshift_logging_es_ca_ext</code>	The location of the CA cert Elasticsearch uses for the external TLS server cert. The default is the internal CA.
<code>openshift_logging_es_ops_allow_external</code>	Set to <code>true</code> to expose Elasticsearch as a reencrypt route. Set to <code>false</code> by default.
<code>openshift_logging_es_ops_hostname</code>	<p>The external-facing hostname to use for the route and the TLS server certificate. The default is set to <code>es-ops</code>.</p> <p>For example, if <code>openshift_master_default_subdomain</code> is set to <code>=example.test</code>, then the default value of <code>openshift_logging_es_ops_hostname</code> will be <code>es-ops.example.test</code>.</p>
<code>openshift_logging_es_ops_cert</code>	The location of the certificate Elasticsearch uses for the external TLS server cert. The default is a generated cert.
<code>openshift_logging_es_ops_key</code>	The location of the key Elasticsearch uses for the external TLS server cert. The default is a generated key.
<code>openshift_logging_es_ops_ca_ext</code>	The location of the CA cert Elasticsearch uses for the external TLS server cert. The default is the internal CA.

Parameter	Description
<b>openshift_logging_fluentd_nodeselector</b>	<p>A node selector that specifies which nodes are eligible targets for deploying Fluentd instances. Any node where Fluentd should run (typically, all) must have this label before Fluentd is able to run and collect logs.</p> <p>When scaling up the Aggregated Logging cluster after installation, the <b>openshift_logging</b> role labels nodes provided by <b>openshift_logging_fluentd_hosts</b> with this node selector.</p> <p>As part of the installation, it is recommended that you add the Fluentd node selector label to the list of persisted <a href="#">node labels</a>.</p>
<b>openshift_logging_fluentd_cpu_limit</b>	The CPU limit for Fluentd pods.
<b>openshift_logging_fluentd_memory_limit</b>	The memory limit for Fluentd pods.
<b>openshift_logging_fluentd_journal_read_from_head</b>	Set to <b>true</b> if Fluentd should read from the head of Journal when first starting up, using this may cause a delay in ES receiving current log records.
<b>openshift_logging_fluentd_hosts</b>	List of nodes that should be labeled for Fluentd to be deployed. The default is to label all nodes with ['--all']. The null value is <b>openshift_logging_fluentd_hosts={}</b> . To spin up Fluentd pods update the daemonset's <b>nodeSelector</b> to a valid label. For example, ['host1.example.com', 'host2.example.com'].
<b>openshift_logging_fluentd_audit_container_engine</b>	When <b>openshift_logging_fluentd_audit_container_engine</b> is set to <b>true</b> , the audit log of the container engine is collected and stored in ES. Enabling this variable allows the EFK to watch the specified audit log file or the default <b>/var/log/audit.log</b> file, collects audit information for the container engine for the platform, then puts it into Kibana.
<b>openshift_logging_fluentd_audit_file</b>	Location of audit log file. The default is <b>/var/log/audit/audit.log</b> . Enabling this variable allows the EFK to watch the specified audit log file or the default <b>/var/log/audit.log</b> file, collects audit information for the container engine for the platform, then puts it into Kibana.
<b>openshift_logging_fluentd_audit_pos_file</b>	Location of the Fluentd <b>in_tail</b> position file for the audit log file. The default is <b>/var/log/audit/audit.log.pos</b> . Enabling this variable allows the EFK to watch the specified audit log file or the default <b>/var/log/audit.log</b> file, collects audit information for the container engine for the platform, then puts it into Kibana.
<b>openshift_logging_es_host</b>	The name of the ES service where Fluentd should send logs.

Parameter	Description
<b>openshift_logging_es_port</b>	The port for the ES service where Fluentd should send logs.
<b>openshift_logging_es_ca</b>	The location of the CA Fluentd uses to communicate with <b>openshift_logging_es_host</b> .
<b>openshift_logging_es_client_cert</b>	The location of the client certificate Fluentd uses for <b>openshift_logging_es_host</b> .
<b>openshift_logging_es_client_key</b>	The location of the client key Fluentd uses for <b>openshift_logging_es_host</b> .
<b>openshift_logging_es_cluster_size</b>	Elasticsearch replicas to deploy. Redundancy requires at least three or more.
<b>openshift_logging_es_cpu_limit</b>	The amount of CPU limit for the ES cluster.
<b>openshift_logging_es_memory_limit</b>	Amount of RAM to reserve per Elasticsearch instance. It must be at least 512M. Possible suffixes are G,g,M,m.
<b>openshift_logging_es_number_of_replicas</b>	The number of replica shards per primary shard for every new index. Defaults to '0'. A minimum of <b>1</b> is advisable for production clusters.
<b>openshift_logging_es_number_of_shards</b>	The number of primary shards for every new index created in ES. Defaults to '1'.
<b>openshift_logging_es_pv_selector</b>	A key/value map added to a PVC in order to select specific PVs.
<b>openshift_logging_es_pvc_dynamic</b>	To dynamically provision the backing storage, set the parameter value to <b>true</b> . When set to <b>true</b> , the storageClass spec is omitted from the PVC definition. If you set a <b>openshift_logging_es_pvc_storage_class_name</b> parameter value, its value overrides the value of the the <b>openshift_logging_es_pvc_dynamic</b> parameter.
<b>openshift_logging_es_pvc_storage_class_name</b>	To use a non-default storage class, specify the storage class name, such as <b>glusterprovisioner</b> or <b>cephrbdprovisioner</b> . After you specify the storage class name, dynamic volume provisioning is active regardless of the <b>openshift_logging_es_pvc_dynamic</b> value.
<b>openshift_logging_es_pvc_size</b>	Size of the persistent volume claim to create per Elasticsearch instance. For example, 100G. If omitted, no PVCs are created and ephemeral volumes are used instead.

Parameter	Description
<code>openshift_logging_es_pvc_prefix</code>	<p>Prefix for the names of persistent volume claims to be used as storage for Elasticsearch instances. A number is appended per instance, such as <code>logging-es-1</code>. If they do not already exist, they are created with size <code>es-pvc-size</code>.</p> <p>When <code>openshift_logging_es_pvc_prefix</code> is set, and:</p> <ul style="list-style-type: none"> <li>• <code>openshift_logging_es_pvc_dynamic=true</code>, the value for <code>openshift_logging_es_pvc_size</code> is optional.</li> <li>• <code>openshift_logging_es_pvc_dynamic=false</code>, the value for <code>openshift_logging_es_pvc_size</code> must be set.</li> </ul>
<code>openshift_logging_es_recover_after_time</code>	The amount of time ES will wait before it tries to recover.
<code>openshift_logging_es_storage_group</code>	Number of a supplemental group ID for access to Elasticsearch storage volumes. Backing volumes should allow access by this group ID.
<code>openshift_logging_es_nodeselector</code>	A node selector specified as a map that determines which nodes are eligible targets for deploying Elasticsearch instances. This can be used to place these instances on nodes reserved or optimized for running them. For example, the selector could be <code>{"node-type": "infrastructure"}</code> . At least one active node must have this label before Elasticsearch will deploy.
<code>openshift_logging_es_ops_allow_cluster_reader</code>	Set to <code>true</code> if cluster-reader role is allowed to read operation logs.
<code>openshift_logging_es_ops_host</code>	Equivalent to <code>openshift_logging_es_host</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_port</code>	Equivalent to <code>openshift_logging_es_port</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_ca</code>	Equivalent to <code>openshift_logging_es_ca</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_client_cert</code>	Equivalent to <code>openshift_logging_es_client_cert</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_client_key</code>	Equivalent to <code>openshift_logging_es_client_key</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_cluster_size</code>	Equivalent to <code>openshift_logging_es_cluster_size</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .

Parameter	Description
<code>openshift_logging_es_ops_cpu_limit</code>	Equivalent to <code>openshift_logging_es_cpu_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_memory_limit</code>	Equivalent to <code>openshift_logging_es_memory_limit</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_pv_selector</code>	Equivalent to <code>openshift_logging_es_pv_selector</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_pvc_dynamic</code>	Equivalent to <code>openshift_logging_es_pvc_dynamic</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_pvc_size</code>	Equivalent to <code>openshift_logging_es_pvc_size</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_pvc_prefix</code>	Equivalent to <code>openshift_logging_es_pvc_prefix</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_recover_after_time</code>	Equivalent to <code>openshift_logging_es_recovery_after_time</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_storage_group</code>	Equivalent to <code>openshift_logging_es_storage_group</code> for Ops cluster when <code>openshift_logging_use_ops</code> is set to <code>true</code> .
<code>openshift_logging_es_ops_nodeselector</code>	A node selector that specifies which nodes are eligible targets for deploying Elasticsearch instances. This can be used to place these instances on nodes reserved or optimized for running them. For example, the selector could be <code>node-type=infrastructure</code> . At least one active node must have this label before Elasticsearch will deploy.
<code>openshift_logging_elasticsearch_kibana_index_mode</code>	The default value, <code>unique</code> , allows users to each have their own Kibana index. In this mode, their saved queries, visualizations, and dashboards are not shared.  You may also set the value <code>shared_ops</code> . In this mode, all operations users share a Kibana index which allows each operations user to see the same queries, visualizations, and dashboards.
<code>openshift_logging_kibana_ops_nodeselector</code>	A node selector that specifies which nodes are eligible targets for deploying Kibana instances.
<code>openshift_logging_curator_ops_nodeselector</code>	A node selector that specifies which nodes are eligible targets for deploying Curator instances.

## Custom Certificates

You can specify custom certificates using the following inventory variables instead of relying on those generated during the deployment process. These certificates are used to encrypt and secure communication between a user's browser and Kibana. The security-related files will be generated if they are not supplied.

File Name	Description
<code>openshift_logging_kibana_cert</code>	A browser-facing certificate for the Kibana server.
<code>openshift_logging_kibana_key</code>	A key to be used with the browser-facing Kibana certificate.
<code>openshift_logging_kibana_ca</code>	The absolute path on the control node to the CA file to use for the browser facing Kibana certs.
<code>openshift_logging_kibana_ops_cert</code>	A browser-facing certificate for the Ops Kibana server.
<code>openshift_logging_kibana_ops_key</code>	A key to be used with the browser-facing Ops Kibana certificate.
<code>openshift_logging_kibana_ops_ca</code>	The absolute path on the control node to the CA file to use for the browser facing ops Kibana certs.

## 32.4. DEPLOYING THE EFK STACK

The EFK stack is deployed using an Ansible playbook to the EFK components. Run the playbook from the default OpenShift Ansible location using the default [inventory](#) file.

```
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
logging/config.yml
```

Running the playbook deploys all resources needed to support the stack; such as Secrets, ServiceAccounts, and DeploymentConfigs. The playbook waits to deploy the component pods until the stack is running. If the wait steps fail, the deployment could still be successful; it may be retrieving the component images from the registry which can take up to a few minutes. You can watch the process with:

```
$ oc get pods -w
```

They will eventually enter **Running** status. For additional details about the status of the pods during deployment by retrieving associated events:

```
$ oc describe pods/<pod_name>
```

Check the logs if the pods do not run successfully:

```
$ oc logs -f <pod_name>
```

## 32.5. UNDERSTANDING AND ADJUSTING THE DEPLOYMENT

This section describes adjustments that you can make to deployed components.

### 32.5.1. Ops Cluster



#### NOTE

The logs for the **default**, **openshift**, and **openshift-infra** projects are automatically aggregated and grouped into the **.operations** item in the Kibana interface.

The project where you have deployed the EFK stack (**logging**, as documented here) is *not* aggregated into **.operations** and is found under its ID.

If you set **openshift\_logging\_use\_ops** to **true** in your inventory file, Fluentd is configured to split logs between the main Elasticsearch cluster and another cluster reserved for operations logs, which are defined as node system logs and the projects **default**, **openshift**, and **openshift-infra**. Therefore, a separate Elasticsearch cluster, a separate Kibana, and a separate Curator are deployed to index, access, and manage operations logs. These deployments are set apart with names that include **-ops**. Keep these separate deployments in mind if you enable this option. Most of the following discussion also applies to the operations cluster if present, just with the names changed to include **-ops**.

### 32.5.2. Elasticsearch

A highly-available environment requires at least three replicas of Elasticsearch; each on a different host. Elasticsearch replicas require their own storage, but an OpenShift Container Platform deployment configuration shares storage volumes between all its pods. So, when scaled up, the EFK deployer ensures each replica of Elasticsearch has its own deployment configuration.

It is possible to scale your cluster up after creation by modifying the **openshift\_logging\_es\_cluster\_size** in the inventory file and re-running the logging playbook. Additional clustering parameters can be modified and are described in [Specifying Logging Ansible Variables](#).

Refer to [Elastic's documentation](#) for considerations involved in choosing storage and network location as directed below.

#### Viewing all Elasticsearch Deployments

To view all current Elasticsearch deployments:

```
$ oc get dc --selector logging-infra=elasticsearch
```

#### Node Selector

Because Elasticsearch can use a lot of resources, all members of a cluster should have low latency network connections to each other and to any remote storage. Ensure this by directing the instances to dedicated nodes, or a dedicated region within your cluster, using a [node selector](#).

To configure a node selector, specify the **openshift\_logging\_es\_nodeselector** configuration option in the inventory file. This applies to all Elasticsearch deployments; if you need to individualize the node selectors, you must manually edit each deployment configuration after deployment. The node selector is specified as a python compatible dict. For example, `{"node-type": "infra", "region": "east"}`.

## Persistent Elasticsearch Storage

By default, the `openshift_logging` Ansible role creates an ephemeral deployment in which all of a pod's data is lost upon restart. For production usage, specify a persistent storage volume for each Elasticsearch deployment configuration. You can create the necessary `persistent volume claims` before deploying or have them created for you. The PVCs must be named to match the `openshift_logging_es_pvc_prefix` setting, which defaults to `logging-es`; each PVC name will have a sequence number added to it: `logging-es-0`, `logging-es-1`, `logging-es-2`, and so on. If a PVC needed for the deployment exists already, it is used; if not, and `openshift_logging_es_pvc_size` has been specified, it is created with a request for that size.



### WARNING

Using NFS storage as a volume or a persistent volume is not supported for Elasticsearch storage, as Lucene relies on file system behavior that NFS does not supply. Data corruption and other problems can occur. If NFS storage is a requirement, you can allocate a large file on a volume to serve as a storage device and mount it locally on one host. For example, if your NFS storage volume is mounted at `/nfs/storage`:

```
$ truncate -s 1T /nfs/storage/elasticsearch-1
$ mkfs.xfs /nfs/storage/elasticsearch-1
$ mount -o loop /nfs/storage/elasticsearch-1 /usr/local/es-
storage
$ chown 1000:1000 /usr/local/es-storage
```

Then, use `/usr/local/es-storage` as a host-mount as described below. Use a different backing file as storage for each Elasticsearch replica.

This loopback must be maintained manually outside of OpenShift Container Platform, on the node. You must not maintain it from inside a container.

You can use Red Hat Gluster to enable `gluster-block` Storage as a backend for logging with Elasticsearch. For more information, see [Configuring Red Hat Gluster Persistent Storage](#).

It is possible to use a local disk volume (if available) on each node host as storage for an Elasticsearch replica. Doing so requires some preparation as follows.

1. The relevant service account must be given the privilege to mount and edit a local volume:

```
$ oc adm policy add-scc-to-user privileged \
    system:serviceaccount:logging:aggregated-logging-
elasticsearch ①
```

- 1 Use the project you created earlier (for example, `logging`) when running the logging playbook.

2. Each Elasticsearch replica definition must be patched to claim that privilege, for example (change to `--selector component=es-ops` for Ops cluster):

```
$ for dc in $(oc get deploymentconfig --selector component=es -o name); do
    oc scale $dc --replicas=0
    oc patch $dc \
        -p '{"spec":{"template":{"spec":{"containers": [{"name":"elasticsearch","securityContext":{"privileged":true}}]}}}'
done
```

- The Elasticsearch replicas must be located on the correct nodes to use the local storage, and should not move around even if those nodes are taken down for a period of time. This requires giving each Elasticsearch replica a node selector that is unique to a node where an administrator has allocated storage for it. To configure a node selector, edit each Elasticsearch deployment configuration and add or edit the **nodeSelector** section to specify a unique label that you have applied for each desired node:

```
apiVersion: v1
kind: DeploymentConfig
spec:
  template:
    spec:
      nodeSelector:
        logging-es-node: "1" ①
```

- This label should uniquely identify a replica with a single node that bears that label, in this case **logging-es-node=1**. Use the **oc label** command to apply labels to nodes as needed.

To automate applying the node selector you can instead use the **oc patch** command:

```
$ oc patch dc/logging-es-<suffix> \
  -p '{"spec":{"template":{"spec":{"nodeSelector":{"logging-es-node":"1"}}}}'
```


- Once these steps are taken, a local host mount can be applied to each replica as in this example (where we assume storage is mounted at the same path on each node) (change to **--selector component=es-ops** for Ops cluster):

```
$ for dc in $(oc get deploymentconfig --selector component=es -o name); do
    oc set volume $dc \
        --add --overwrite --name=elasticsearch-storage \
        --type=hostPath --path=/usr/local/es-storage
    oc rollout latest $dc
    oc scale $dc --replicas=1
done
```

## Changing the Scale of Elasticsearch

If you need to scale up the number of Elasticsearch instances your cluster uses, it is not as simple as scaling up an Elasticsearch deployment configuration. This is due to the nature of persistent volumes and how Elasticsearch is configured to store its data and recover the cluster. Instead, scaling up requires creating a deployment configuration for each Elasticsearch cluster node.

The simplest way to change the scale of Elasticsearch is to modify the inventory host file and re-run the logging playbook as described previously. Assuming you have supplied persistent storage for the deployment, this should not be disruptive.



## NOTE

Resizing an Elasticsearch cluster using the logging playbook is only possible when the new `openshift_logging_es_cluster_size` value is higher than the current number of Elasticsearch nodes (scaled up) in the cluster.

If you do not wish to reinstall, for instance because you have made customizations that you would like to preserve, then it is possible to add new Elasticsearch deployment configurations to the cluster using a template supplied by the deployer. This requires a more complicated procedure however.

### Expose Elasticsearch as a Route

By default, Elasticsearch deployed with OpenShift aggregated logging is not accessible from outside the logging cluster. You can enable a route for external access to Elasticsearch for those tools that want to access its data.

You have access to Elasticsearch using your OpenShift token, and you can provide the external Elasticsearch and Elasticsearch Ops hostnames when creating the server certificate (similar to Kibana).

1. To access Elasticsearch as a reencrypt route, define the following variables:

```
openshift_logging_es_allow_external=True
openshift_logging_es_hostname=elasticsearch.example.com
```

2. Run the following Ansible playbook:

```
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
logging/config.yml
```

3. To log in to Elasticsearch remotely, the request must contain three HTTP headers:

```
Authorization: Bearer $token
X-Proxy-Remote-User: $username
X-Forwarded-For: $ip_address
```

4. You must have access to the project in order to be able to access to the logs. For example:

```
$ oc login <user1>
$ oc new-project <user1project>
$ oc new-app <httpd-example>
```

5. You need to get the token of this ServiceAccount to be used in the request:

```
$ token=$(oc whoami -t)
```

6. Using the token previously configured, you should be able access Elasticsearch through the exposed route:

```
$ curl -k -H "Authorization: Bearer $token" -H "X-Proxy-Remote-User: $(oc whoami)" -H "X-Forwarded-For: 127.0.0.1" https://es.example.test/project.my-project.*/_search?q=level:err | python -mjson.tool
```

### 32.5.3. Fluentd

Fluentd is deployed as a DaemonSet that deploys replicas according to a node label selector, which you can specify with the inventory parameter `openshift_logging_fluentd_nodeselector` and the default is `logging-infra-fluentd`. As part of the OpenShift cluster installation, it is recommended that you add the Fluentd node selector to the list of persisted [node labels](#).

Fluentd uses `journald` as the system log source. These are log messages from the operating system, the container runtime, and OpenShift.

Clean installations of OpenShift Container Platform 3.9 use `json-file` as the default log driver, but environments upgraded from OpenShift Container Platform 3.7 will maintain their existing `journald` log driver configuration. It is recommended to use the `json-file` log driver. See [Changing the Aggregated Logging Driver](#) for instructions to change your existing log driver configuration to `json-file`.

#### Configuring Fluentd to Send Logs to an External Log Aggregator

You can configure Fluentd to send a copy of its logs to an external log aggregator, and not the default Elasticsearch, using the `secure-forward` plug-in. From there, you can further process log records after the locally hosted Fluentd has processed them.

The logging deployment provides a `secure-forward.conf` section in the Fluentd configmap for configuring the external aggregator:

```
<store>
@type secure_forward
self_hostname pod-${HOSTNAME}
shared_key thisisasharedkey
secure yes
enable_strict_verification yes
ca_cert_path /etc/fluent/keys/your_ca_cert
ca_private_key_path /etc/fluent/keys/your_private_key
ca_private_key_passphrase passphrase
<server>
  host ose1.example.com
  port 24284
</server>
<server>
  host ose2.example.com
  port 24284
  standby
</server>
<server>
  host ose3.example.com
  port 24284
  standby
</server>
</store>
```

This can be updated using the `oc edit` command:

```
$ oc edit configmap/logging-fluentd
```

Certificates to be used in `secure-forward.conf` can be added to the existing secret that is mounted on the Fluentd pods. The `your_ca_cert` and `your_private_key` values must match what is specified in `secure-forward.conf` in `configmap/logging-fluentd`:

```
$ oc patch secrets/logging-fluentd --type=json \
--patch "[{'op':'add','path':'/data/your_ca_cert','value':'$(base64
/path/to/your_ca_cert.pem)'"}]"
$ oc patch secrets/logging-fluentd --type=json \
--patch "[{'op':'add','path':'/data/your_private_key','value':'$(base64
/path/to/your_private_key.pem)'"}]"
```



### NOTE

Replace `your_private_key` with a generic name. This is a link to the JSON path, not a path on your host system.

When configuring the external aggregator, it must be able to accept messages securely from Fluentd.

If the external aggregator is another Fluentd server, it must have the `fluent-plugin-secure-forward` plug-in installed and make use of the input plug-in it provides:

```
<source>
@type secure_forward


self_hostname ${HOSTNAME}
bind 0.0.0.0
port 24284

shared_key thisisasharedkey

secure yes
cert_path      /path/for/certificate/cert.pem
private_key_path /path/for/certificate/key.pem
private_key_passphrase secret_foo_bar_baz
</source>
```

Further explanation of how to set up the `fluent-plugin-secure-forward` plug-in can be [found here](#).

### Reducing the Number of Connections from Fluentd to the API Server



## IMPORTANT

**mux** is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offering/techpreview/>.

**mux** is a Secure Forward listener service.

Parameter	Description
<b>openshift_logging_use_mux</b>	The default is set to <b>False</b> . If set to <b>True</b> , a service called <b>mux</b> is deployed. This service acts as a Fluentd <b>secure_forward</b> aggregator for the node agent Fluentd daemonsets running in the cluster. Use <b>openshift_logging_use_mux</b> to reduce the number of connections to the OpenShift API server, and configure each node in Fluentd to send raw logs to <b>mux</b> and turn off the Kubernetes metadata plug-in. This requires the use of <b>openshift_logging_mux_client_mode</b> .
<b>openshift_logging_mux_client_mode</b>	Values for <b>openshift_logging_mux_client_mode</b> are <b>minimal</b> and <b>maximal</b> , and there is no default. <b>openshift_logging_mux_client_mode</b> causes the Fluentd node agent to send logs to <b>mux</b> rather than directly to Elasticsearch. The value <b>maximal</b> means that Fluentd does as much processing as possible at the node before sending the records to <b>mux</b> . The <b>maximal</b> value is recommended for using <b>mux</b> . The value <b>minimal</b> means that Fluentd does no processing at all, and sends the raw logs to <b>mux</b> for processing. It is not recommended to use the <b>minimal</b> value.
<b>openshift_logging_mux_allow_external</b>	The default is set to <b>False</b> . If set to <b>True</b> , the <b>mux</b> service is deployed, and it is configured to allow Fluentd clients running outside of the cluster to send logs using <b>secure_forward</b> . This allows OpenShift logging to be used as a central logging service for clients other than OpenShift, or other OpenShift clusters.
<b>openshift_logging_mux_hostname</b>	The default is <b>mux</b> plus <b>openshift_master_default_subdomain</b> . This is the hostname <b>external_clients</b> will use to connect to <b>mux</b> , and is used in the TLS server cert subject.
<b>openshift_logging_mux_port</b>	24284
<b>openshift_logging_mux_cpu_limit</b>	500M
<b>openshift_logging_mux_memory_limit</b>	1Gi

Parameter	Description
<code>openshift_logging_mux_default_namespaces</code>	The default is <code>mux-undefined</code> . The first value in the list is the namespace to use for undefined projects, followed by any additional namespaces to create by default. Usually, you do not need to set this value.
<code>openshift_logging_mux_namespaces</code>	The default value is empty, allowing for additional namespaces to create for external <code>mux</code> clients to associate with their logs. You will need to set this value.

## Throttling logs in Fluentd

For projects that are especially verbose, an administrator can throttle down the rate at which the logs are read in by Fluentd before being processed.



### WARNING

Throttling can contribute to log aggregation falling behind for the configured projects; log entries can be lost if a pod is deleted before Fluentd catches up.



### NOTE

Throttling does not work when using the systemd journal as the log source. The throttling implementation depends on being able to throttle the reading of the individual log files for each project. When reading from the journal, there is only a single log source, no log files, so no file-based throttling is available. There is not a method of restricting the log entries that are read into the Fluentd process.

To tell Fluentd which projects it should be restricting, edit the throttle configuration in its ConfigMap after deployment:

```
$ oc edit configmap/logging-fluentd
```

The format of the `throttle-config.yaml` key is a YAML file that contains project names and the desired rate at which logs are read in on each node. The default is 1000 lines at a time per node. For example:

```
logging:
  read_lines_limit: 500

test-project:
  read_lines_limit: 10

operations:
  read_lines_limit: 100
```

When you make changes to any part of the EFK stack, specifically Elasticsearch or Fluentd, you should first scale Elasticsearch down to zero and scale Fluentd so it does not match any other nodes. Then, make the changes and scale Elasticsearch and Fluentd back.

To scale Elasticsearch to zero:

```
$ oc scale --replicas=0 dc/<ELASTICSEARCH_DC>
```

Change nodeSelector in the daemonset configuration to match zero:

**Get the fluentd node selector:**

```
$ oc get ds logging-fluentd -o yaml |grep -A 1 Selector
nodeSelector:
  logging-infra-fluentd: "true"
```

**Use the `oc patch` command to modify the daemonset nodeSelector:**

```
$ oc patch ds logging-fluentd -p '{"spec":{"template":{"spec":{"nodeSelector":{"nonexistlabel":"true"}}}}}'
```

**Get the fluentd node selector:**

```
$ oc get ds logging-fluentd -o yaml |grep -A 1 Selector
nodeSelector:
  "nonexistlabel: "true"
```

Scale Elasticsearch back up from zero:

```
$ oc scale --replicas=# dc/<ELASTICSEARCH_DC>
```

Change nodeSelector in the daemonset configuration back to logging-infra-fluentd: "true".

Use the `oc patch` command to modify the daemonset nodeSelector:

```
oc patch ds logging-fluentd -p '{"spec":{"template":{"spec":{"nodeSelector":{"logging-infra-fluentd":"true"}}}}}'
```

### 32.5.4. Kibana

To access the Kibana console from the OpenShift Container Platform web console, add the **loggingPublicURL** parameter in the [master webconsole-config configmap file](#), with the URL of the Kibana console (the **kibana-hostname** parameter). The value must be an HTTPS URL:

```
...
clusterInfo:
  ...
    loggingPublicURL: "https://kibana.example.com"
  ...
...
```

Setting the `loggingPublicURL` parameter creates a **View Archive** button on the OpenShift Container Platform web console under the **Browse** → **Pods** → <pod\_name> → **Logs** tab. This links to the Kibana console.

You can scale the Kibana deployment as usual for redundancy:

```
$ oc scale dc/logging-kibana --replicas=2
```



### NOTE

To ensure the scale persists across multiple executions of the logging playbook, make sure to update the `openshift_logging_kibana_replica_count` in the inventory file.

You can see the user interface by visiting the site specified by the `openshift_logging_kibana_hostname` variable.

See the [Kibana documentation](#) for more information on Kibana.

### Kibana Visualize

Kibana Visualize enables you to create visualizations and dashboards for monitoring container and pod logs allows administrator users (`cluster-admin` or `cluster-reader`) to view logs by deployment, namespace, pod, and container.

Kibana Visualize exists inside the Elasticsearch and ES-OPS pod, and must be run inside those pods. To load dashboards and other Kibana UI objects, you must first log into Kibana as the user you want to add the dashboards to, then log out. This will create the necessary per-user configuration that the next step relies on. Then, run:

```
$ oc exec <$espod> -- es_load_kibana_ui_objects <user-name>
```

Where `$espod` is the name of any one of your Elasticsearch pods.

### 32.5.5. Curator

Curator allows administrators to configure scheduled Elasticsearch maintenance operations to be performed automatically on a per-project basis. It is scheduled to perform actions daily based on its configuration. Only one Curator pod is recommended per Elasticsearch cluster. Curator is configured via a YAML configuration file with the following structure:

```
$PROJECT_NAME:  
$ACTION:  
$UNIT: $VALUE  
  
$PROJECT_NAME:  
$ACTION:  
$UNIT: $VALUE  
...
```

The available parameters are:

Variable Name	Description
<b>PROJECT_NAME</b>	The actual name of a project, such as <b>myapp-devel</b> . For OpenShift Container Platform <b>operations</b> logs, use the name <b>.operations</b> as the project name.
<b>ACTION</b>	The action to take, currently only <b>delete</b> is allowed.
<b>UNIT</b>	One of <b>days</b> , <b>weeks</b> , or <b>months</b> .
<b>VALUE</b>	An integer for the number of units.
<b>.defaults</b>	Use <b>.defaults</b> as the <b>\$PROJECT_NAME</b> to set the defaults for projects that are not specified.
<b>runhour</b>	(Number) the hour of the day in 24-hour format at which to run the Curator jobs. For use with <b>.defaults</b> .
<b>runminute</b>	(Number) the minute of the hour at which to run the Curator jobs. For use with <b>.defaults</b> .
<b>timezone</b>	(String) the string in tzselect(8) or timedatectl(1) format. The default timezone is UTC.
<b>.regex</b>	The list of regular expressions that match project names.
<b>pattern</b>	The valid and properly escaped regular expression pattern enclosed by single quotation marks.

For example, to configure Curator to:

- delete indices in the **myapp-dev** project older than **1 day**
- delete indices in the **myapp-qe** project older than **1 week**
- delete **operations** logs older than **8 weeks**
- delete all other projects indices after they are **31 days** old
- run the Curator jobs at midnight every day

Use:

```
config.yaml: |
  myapp-dev:
    delete:
      days: 1

  myapp-qe:
    delete:
      weeks: 1
```

```

.operations:
  delete:
    weeks: 8

.defaults:
  delete:
    days: 31
  runhour: 0
  runminute: 0
  timezone: America/New_York

.regex:
  - pattern: '^project\..+\-dev\..*$'
    delete:
      days: 15
  - pattern: '^project\..+\-test\..*$'
    delete:
      days: 30

```



## IMPORTANT

When you use **month** as the **\$UNIT** for an operation, Curator starts counting at the first day of the current month, not the current day of the current month. For example, if today is April 15, and you want to delete indices that are 2 months older than today (delete: months: 2), Curator does not delete indices that are dated older than February 15; it deletes indices older than February 1. That is, it goes back to the first day of the current month, then goes back two whole months from that date. If you want to be exact with Curator, it is best to use days (for example, **delete: days: 30**).

### 32.5.5.1. Creating the Curator Configuration

The **openshift\_logging** Ansible role provides a ConfigMap from which Curator reads its configuration. You may edit or replace this ConfigMap to reconfigure Curator. Currently the **logging-curator** ConfigMap is used to configure both your ops and non-ops Curator instances. Any **.operations** configurations are in the same location as your application logs configurations.

1. To edit the provided ConfigMap to configure your Curator instances:

```
$ oc edit configmap/logging-curator
```

2. To replace the provided ConfigMap instead:

```
$ create /path/to/mycuratorconfig.yaml
$ oc create configmap logging-curator -o yaml \
--from-file=config.yaml=/path/to/mycuratorconfig.yaml | \
oc replace -f -
```

3. After you make your changes, redeploy Curator:

```
$ oc rollout latest dc/logging-curator
$ oc rollout latest dc/logging-curator-ops
```

## 32.6. CLEANUP

Remove everything generated during the deployment.

```
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
logging/config.yml \
    -e openshift_logging_install_logging=False
```

## 32.7. TROUBLESHOOTING KIBANA

Using the Kibana console with OpenShift Container Platform can cause problems that are easily solved, but are not accompanied with useful error messages. Check the following troubleshooting sections if you are experiencing any problems when deploying Kibana on OpenShift Container Platform:

### Login Loop

The OAuth2 proxy on the Kibana console must share a secret with the master host's OAuth2 server. If the secret is not identical on both servers, it can cause a login loop where you are continuously redirected back to the Kibana login page.

To fix this issue, delete the current OAuthClient, and use **openshift-ansible** to re-run the **openshift\_logging** role:

```
$ oc delete oauthclient/kibana-proxy
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
logging/config.yml
```

### Cryptic Error When Viewing the Console

When attempting to visit the Kibana console, you may receive a browser error instead:

```
{"error":"invalid_request","error_description":"The request is missing a
required parameter,
includes an invalid parameter value, includes a parameter more than once,
or is otherwise malformed."}
```

This can be caused by a mismatch between the OAuth2 client and server. The return address for the client must be in a whitelist so the server can securely redirect back after logging in.

Fix this issue by replacing the OAuthClient entry:

```
$ oc delete oauthclient/kibana-proxy
$ ansible-playbook [-i </path/to/inventory>] \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
logging/config.yml
```

If the problem persists, check that you are accessing Kibana at a URL listed in the OAuth client. This issue can be caused by accessing the URL at a forwarded port, such as 1443 instead of the standard 443 HTTPS port. You can adjust the server whitelist by editing the OAuth client:

```
$ oc edit oauthclient/kibana-proxy
```

## 503 Error When Viewing the Console

If you receive a proxy error when viewing the Kibana console, it could be caused by one of two issues.

First, Kibana may not be recognizing pods. If Elasticsearch is slow in starting up, Kibana may timeout trying to reach it. Check whether the relevant service has any endpoints:

```
$ oc describe service logging-kibana
Name:           logging-kibana
[...]
Endpoints:     <none>
```

If any Kibana pods are live, endpoints are listed. If they are not, check the state of the Kibana pods and deployment. You may need to scale the deployment down and back up again.

The second possible issue may be caused if the route for accessing the Kibana service is masked. This can happen if you perform a test deployment in one project, then deploy in a different project without completely removing the first deployment. When multiple routes are sent to the same destination, the default router will only route to the first created. Check the problematic route to see if it is defined in multiple places:

```
$ oc get route --all-namespaces --selector logging-infra=support
```

## F-5 Load Balancer and X-Forwarded-For Enabled

If you are attempting to use a F-5 load balancer in front of Kibana with **X-Forwarded-For** enabled, this can cause an issue in which the Elasticsearch **Searchguard** plug-in is unable to correctly accept connections from Kibana.

### Example Kibana Error Message

```
Kibana: Unknown error while connecting to Elasticsearch
Error: Unknown error while connecting to Elasticsearch
Error: UnknownHostException[No trusted proxies]
```

To configure Searchguard to ignore the extra header:

1. Scale down all Fluentd pods.
2. Scale down Elasticsearch after the Fluentd pods have terminated.
3. Add **searchguard.http.xforwardedfor.header: DUMMY** to the Elasticsearch configuration section.

```
$ oc edit configmap/logging-elasticsearch ①
```

① This approach requires that Elasticsearch's configurations are within a ConfigMap.

4. Scale Elasticsearch back up.
5. Scale up all Fluentd pods.

## 32.8. SENDING LOGS TO AN EXTERNAL ELASTICSEARCH INSTANCE

Fluentd sends logs to the value of the **ES\_HOST**, **ES\_PORT**, **OPS\_HOST**, and **OPS\_PORT** environment variables of the Elasticsearch deployment configuration. The application logs are directed to the **ES\_HOST** destination, and operations logs to **OPS\_HOST**.



### NOTE

Sending logs directly to an AWS Elasticsearch instance is not supported. Use [Fluentd Secure Forward](#) to direct logs to an instance of Fluentd that you control and that is configured with the **fluent-plugin-aws-elasticsearch-service** plug-in.

To direct logs to a specific Elasticsearch instance, edit the deployment configuration and replace the value of the above variables with the desired instance:

```
$ oc edit dc/<deployment_configuration>
```

For an external Elasticsearch instance to contain both application and operations logs, you can set **ES\_HOST** and **OPS\_HOST** to the same destination, while ensuring that **ES\_PORT** and **OPS\_PORT** also have the same value.

If your externally hosted Elasticsearch instance does not use TLS, update the **\_CLIENT\_CERT**, **\_CLIENT\_KEY**, and **\_CA** variables to be empty. If it does use TLS, but not mutual TLS, update the **\_CLIENT\_CERT** and **\_CLIENT\_KEY** variables to be empty and patch or recreate the **logging-fluentd** secret with the appropriate **\_CA** value for communicating with your Elasticsearch instance. If it uses Mutual TLS as the provided Elasticsearch instance does, patch or recreate the **logging-fluentd** secret with your client key, client cert, and CA.



### NOTE

If you are not using the provided Kibana and Elasticsearch images, you will not have the same multi-tenant capabilities and your data will not be restricted by user access to a particular project.

## 32.9. SENDING LOGS TO AN EXTERNAL SYSLOG SERVER

Use the **fluent-plugin-remote-syslog** plug-in on the host to send logs to an external syslog server.

Set environment variables in the **logging-fluentd** or **logging-mux** deployment configurations:

- ```
- name: REMOTE_SYSLOG_HOST ①
  value: host1
- name: REMOTE_SYSLOG_HOST_BACKUP
  value: host2
- name: REMOTE_SYSLOG_PORT_BACKUP
  value: 5555
```

① The desired remote syslog host. Required for each host.

This will build two destinations. The syslog server on **host1** will be receiving messages on the default port of **514**, while **host2** will be receiving the same messages on port **5555**.

Alternatively, you can configure your own custom `fluent.conf` in the `logging-fluentd` or `logging-mux` ConfigMaps.

## Fluentd Environment Variables

| Parameter                                    | Description                                                                                                                              |
|----------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------|
| <code>USE_REMOTE_SYSLOG</code>               | Defaults to <code>false</code> . Set to <code>true</code> to enable use of the <code>fluent-plugin-remote-syslog</code> gem              |
| <code>REMOTE_SYSLOG_HOST</code>              | (Required) Hostname or IP address of the remote syslog server.                                                                           |
| <code>REMOTE_SYSLOG_PORT</code>              | Port number to connect on. Defaults to <code>514</code> .                                                                                |
| <code>REMOTE_SYSLOG_SEVERITY</code>          | Set the syslog severity level. Defaults to <code>debug</code> .                                                                          |
| <code>REMOTE_SYSLOGFacility</code>           | Set the syslog facility. Defaults to <code>local0</code> .                                                                               |
| <code>REMOTE_SYSLOG_USE_RECORD</code>        | Defaults to <code>false</code> . Set to <code>true</code> to use the record's severity and facility fields to set on the syslog message. |
| <code>REMOTE_SYSLOG_REMOVE_TAG_PREFIX</code> | Removes the prefix from the tag, defaults to '' (empty).                                                                                 |
| <code>REMOTE_SYSLOG_TAG_KEY</code>           | If specified, uses this field as the key to look on the record, to set the tag on the syslog message.                                    |
| <code>REMOTE_SYSLOG_PAYLOAD_KEY</code>       | If specified, uses this field as the key to look on the record, to set the payload on the syslog message.                                |



### WARNING

This implementation is insecure, and should only be used in environments where you can guarantee no snooping on the connection.

## Fluentd Logging Ansible Variables

| Parameter                                            | Description                                                                                                               |
|------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_logging_fluentd_remote_syslog</code> | The default is set to <code>false</code> . Set to <code>true</code> to enable use of the fluent-plugin-remote-syslog gem. |

| Parameter                                                              | Description                                                                                                                            |
|------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_logging_fluentd_remote_syslog_host</code>              | Hostname or IP address of the remote syslog server, this is mandatory.                                                                 |
| <code>openshift_logging_fluentd_remote_syslog_port</code>              | Port number to connect on, defaults to <b>514</b> .                                                                                    |
| <code>openshift_logging_fluentd_remote_syslog_severity</code>          | Set the syslog severity level, defaults to <b>debug</b> .                                                                              |
| <code>openshift_logging_fluentd_remote_syslog_facility</code>          | Set the syslog facility, defaults to <b>local0</b> .                                                                                   |
| <code>openshift_logging_fluentd_remote_syslog_use_record</code>        | The default is set to <b>false</b> . Set to <b>true</b> to use the record's severity and facility fields to set on the syslog message. |
| <code>openshift_logging_fluentd_remote_syslog_remove_tag_prefix</code> | Removes the prefix from the tag, defaults to '' (empty).                                                                               |
| <code>openshift_logging_fluentd_remote_syslog_tag_key</code>           | If string is specified, uses this field as the key to look on the record, to set the tag on the syslog message.                        |
| <code>openshift_logging_fluentd_remote_syslog_payload_key</code>       | If string is specified, uses this field as the key to look on the record, to set the payload on the syslog message.                    |

## Mux Logging Ansible Variables

| Parameter                                             | Description                                                                                                   |
|-------------------------------------------------------|---------------------------------------------------------------------------------------------------------------|
| <code>openshift_logging_mux_remote_syslog</code>      | The default is set to <b>false</b> . Set to <b>true</b> to enable use of the fluent-plugin-remote-syslog gem. |
| <code>openshift_logging_mux_remote_syslog_host</code> | Hostname or IP address of the remote syslog server, this is mandatory.                                        |
| <code>openshift_logging_mux_remote_syslog_port</code> | Port number to connect on, defaults to <b>514</b> .                                                           |

| Parameter                                                                    | Description                                                                                                                            |
|------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_logging_mu<br/>x_remote_syslog_seve<br/>rity</code>          | Set the syslog severity level, defaults to <b>debug</b> .                                                                              |
| <code>openshift_logging_mu<br/>x_remote_syslog_faci<br/>lity</code>          | Set the syslog facility, defaults to <b>local0</b> .                                                                                   |
| <code>openshift_logging_mu<br/>x_remote_syslog_use_<br/>record</code>        | The default is set to <b>false</b> . Set to <b>true</b> to use the record's severity and facility fields to set on the syslog message. |
| <code>openshift_logging_mu<br/>x_remote_syslog_remo<br/>ve_tag_prefix</code> | Removes the prefix from the tag, defaults to '' (empty).                                                                               |
| <code>openshift_logging_mu<br/>x_remote_syslog_tag_<br/>key</code>           | If string is specified, uses this field as the key to look on the record, to set the tag on the syslog message.                        |
| <code>openshift_logging_mu<br/>x_remote_syslog_payl<br/>oad_key</code>       | If string is specified, uses this field as the key to look on the record, to set the payload on the syslog message.                    |

## 32.10. PERFORMING ADMINISTRATIVE ELASTICSEARCH OPERATIONS

As of logging version 3.2.0, an administrator certificate, key, and CA that can be used to communicate with and perform administrative operations on Elasticsearch are provided within the **logging-elasticsearch** secret.



### NOTE

To confirm whether or not your EFK installation provides these, run:

```
$ oc describe secret logging-elasticsearch
```

If they are not available, refer to [Manual Upgrades](#) to ensure you are on the latest version first.

1. Connect to an Elasticsearch pod that is in the cluster on which you are attempting to perform maintenance.
2. To find a pod in a cluster use either:

```
$ oc get pods -l component=es -o name | head -1
$ oc get pods -l component=es-ops -o name | head -1
```

3. Connect to a pod:

```
$ oc rsh <your_Elasticsearch_pod>
```

4. Once connected to an Elasticsearch container, you can use the certificates mounted from the secret to communicate with Elasticsearch per its [Indices APIs documentation](#).

Fluentd sends its logs to Elasticsearch using the index format **project.{project\_name}. {project\_uuid}.YYYY.MM.DD** where YYYY.MM.DD is the date of the log record.

For example, to delete all logs for the **logging** project with uuid **3b3594fa-2ccd-11e6-acb7-0eb6b35eaee3** from June 15, 2016, we can run:

```
$ curl --key /etc/elasticsearch/secret/admin-key \
--cert /etc/elasticsearch/secret/admin-cert \
--cacert /etc/elasticsearch/secret/admin-ca -XDELETE \
"https://localhost:9200/project.logging.3b3594fa-2ccd-11e6-acb7-0eb6b35eaee3.2016.06.15"
```

## 32.11. CHANGING THE AGGREGATED LOGGING DRIVER

For aggregated logging, it is recommended to use the **json-file** log driver.



### IMPORTANT

When using the **json-file** driver, ensure that you are using Docker version **docker-1.12.6-55.gitc4618fb.el7\_4 now** or later.

Fluentd determines the driver Docker is using by checking the **/etc/docker/daemon.json** and **/etc/sysconfig/docker** files.

You can determine which driver Docker is using with the **docker info** command:

```
# docker info | grep Logging
Logging Driver: journald
```

To change to **json-file**:

1. Modify either the **/etc/sysconfig/docker** or **/etc/docker/daemon.json** files.  
For example:

```
# cat /etc/sysconfig/docker
OPTIONS=' --selinux-enabled --log-driver=json-file --log-opt max-size=1M --log-opt max-file=3 --signature-verification=False'

cat /etc/docker/daemon.json
{
  "log-driver": "json-file",
  "log-opt": {
    "max-size": "1M",
    "max-file": "1"
  }
}
```

2. Restart the Docker service:

```
systemctl restart docker
```

3. Restart Fluentd.



### WARNING

Restarting Fluentd on more than a dozen nodes at once will create a large load on the Kubernetes scheduler. Exercise caution when using the following directions to restart Fluentd.

There are two methods for restarting Fluentd. You can restart the Fluentd on one node or a set of nodes, or on all nodes.

- a. The following steps demonstrate how to restart Fluentd on one node or a set of nodes.

- i. List the nodes where Fluentd is running:

```
$ oc get nodes -l logging-infra-fluentd=true
```

- ii. For each node, remove the label and turn off Fluentd:

```
$ oc label node $node logging-infra-fluentd-
```

- iii. Verify Fluentd is off:

```
$ oc get pods -l component=fluentd
```

- iv. For each node, restart Fluentd:

```
$ oc label node $node logging-infra-fluentd=true
```

- b. The following steps demonstrate how to restart the Fluentd on all nodes.

- i. Turn off Fluentd on all nodes:

```
$ oc label node -l logging-infra-fluentd=true --overwrite  
logging-infra-fluentd=false
```

- ii. Verify Fluentd is off:

```
$ oc get pods -l component=fluentd
```

- iii. Restart Fluentd on all nodes:

```
$ oc label node -l logging-infra-fluentd=false --overwrite  
logging-infra-fluentd=true
```

iv. Verify Fluentd is on:

```
$ oc get pods -l component=fluentd
```

## 32.12. MANUAL ELASTICSEARCH ROLLOUTS

As of OpenShift Container Platform 3.7 the Aggregated Logging stack updated the Elasticsearch Deployment Config object so that it no longer has a Config Change Trigger, meaning any changes to the **dc** will not result in an automatic rollout. This was to prevent unintended restarts happening in the ES cluster, which could create excessive shard rebalancing as cluster members restart.

This section presents two restart procedures: [rolling-restart](#) and [full-restart](#). Where a rolling restart applies appropriate changes to the Elasticsearch cluster without down time (provided three masters are configured) and a full restart safely applies major changes without risk to existing data.

### 32.12.1. Performing an Elasticsearch Rolling Cluster Restart

A rolling restart is recommended, when any of the following changes are made:

- nodes on which Elasticsearch pods run require a reboot
- logging-elasticsearch configmap
- logging-es-\* deployment configuration
- new image deployment, or upgrade

This will be the recommended restart policy going forward.



#### NOTE

Any action you do for an ES cluster will need to be repeated for the ops cluster if **openshift\_logging\_use\_ops** was configured to be **True**.

1. Prevent shard balancing when purposely bringing down nodes:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
    curl -s
    --cacert /etc/elasticsearch/secret/admin-ca \
    --cert /etc/elasticsearch/secret/admin-cert \
    --key /etc/elasticsearch/secret/admin-key \
    -XPUT 'https://localhost:9200/_cluster/settings' \
    -d '{ "transient": { "cluster.routing.allocation.enable" :
    "none" } }'
```

2. Once complete, for each **dc** you have for an ES cluster, run **oc rollout latest** to deploy the latest version of the **dc** object:

```
$ oc rollout latest <dc_name>
```

You will see a new pod deployed. Once the pod has two ready containers, you can move on to the next **dc**.

- Once all `dc`s for the cluster have been rolled out, re-enable shard balancing:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
  curl -s
  --cacert /etc/elasticsearch/secret/admin-ca \
  --cert /etc/elasticsearch/secret/admin-cert \
  --key /etc/elasticsearch/secret/admin-key \
  -XPUT 'https://localhost:9200/_cluster/settings' \
  -d '{ "transient": { "cluster.routing.allocation.enable" :
  "all" } }'
```


### 32.12.2. Performing an Elasticsearch Full Cluster Restart

A full restart is recommended when changing major versions of Elasticsearch or other changes which might put data integrity at risk during the change process.



#### NOTE

Any action you do for an ES cluster will need to be repeated for the ops cluster if **openshift\_logging\_use\_ops** was configured to be **True**.



#### NOTE

When making changes to the **logging-es-ops** service use components "es-ops-blocked" and "es-ops" instead in the patch

- Disable all external communications to the ES cluster while it is down. Edit your non-cluster logging service (for example, **logging-es**, **logging-es-ops**) to no longer match the ES pods running:

```
$ oc patch svc/logging-es -p '{"spec": {"selector": {"component": "es-blocked", "provider": "openshift"} }}'
```

- Perform a shard synced flush to ensure there are no pending operations waiting to be written to disk prior to shutting down:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
  curl -s
  --cacert /etc/elasticsearch/secret/admin-ca \
  --cert /etc/elasticsearch/secret/admin-cert \
  --key /etc/elasticsearch/secret/admin-key \
  -XPOST 'https://localhost:9200/_flush/synced'
```

- Prevent shard balancing when purposely bringing down nodes:

```
$ oc exec -c elasticsearch <any_es_pod_in_the_cluster> --
  curl -s
  --cacert /etc/elasticsearch/secret/admin-ca \
  --cert /etc/elasticsearch/secret/admin-cert \
  --key /etc/elasticsearch/secret/admin-key \
  -XPUT 'https://localhost:9200/_cluster/settings' \
  -d '{ "transient": { "cluster.routing.allocation.enable" :
  "none" } }'
```

4. Once complete, for each **dc** you have for an ES cluster, run **oc rollout latest** to deploy the latest version of the **dc** object:

```
$ oc rollout latest <dc_name>
```

You will see a new pod deployed. Once the pod has two ready containers, you can move on to the next **dc**.

5. Once the restart is complete, enable all external communications to the ES cluster. Edit your non-cluster logging service (for example, **logging-es**, **logging-es-ops**) to match the ES pods running again:

```
$ oc patch svc/logging-es -p '{"spec": {"selector": {"component": "es", "provider": "openshift"},}}'
```

# CHAPTER 33. AGGREGATE LOGGING SIZING GUIDELINES

## 33.1. OVERVIEW

The [Elasticsearch, Fluentd, and Kibana](#) (EFK) stack aggregates logs from nodes and applications running inside your OpenShift Container Platform installation. Once deployed it uses [Fluentd](#) to aggregate event logs from all nodes, projects, and pods into [Elasticsearch \(ES\)](#). It also provides a centralized [Kibana](#) web UI where users and administrators can create rich visualizations and dashboards with the aggregated data.

Fluentd [bulk uploads](#) logs to an index, in JSON format, then Elasticsearch routes your search requests to the appropriate shards.

## 33.2. INSTALLATION

The general procedure for installing an aggregate logging stack in OpenShift Container Platform is described in [Aggregating Container Logs](#). There are some important things to keep in mind while going through the installation guide:

In order for the logging pods to spread evenly across your cluster, an empty [node selector](#) should be used.

```
$ oc adm new-project logging --node-selector=""
```

In conjunction with node labeling, which is done later, this controls pod placement across the logging project. You can now create the logging project.

```
$ oc project logging
```

Elasticsearch (ES) should be deployed with a cluster size of at least three for resiliency to node failures. This is specified by setting the `openshift_logging_es_cluster_size` parameter in the inventory host file.

Refer to [Ansible Variables](#) for a full list of parameters.

If you do not have an existing Kibana installation, you can use `kibana.example.com` as a value to `openshift_logging_kibana_hostname`.

Installation can take some time depending on whether the images were already retrieved from the registry or not, and on the size of your cluster.

Inside the `logging` namespace, you can check your deployment with `oc get all`.

```
$ oc get all
```

| NAME                | REVISION | REPLICAS |
|---------------------|----------|----------|
| TRIGGERED BY        |          |          |
| logging-curator     | 1        | 1        |
| logging-es-6cvk237t | 1        | 1        |
| logging-es-e5x4t4ai | 1        | 1        |
| logging-es-xmwvnorv | 1        | 1        |
| logging-kibana      | 1        | 1        |
| NAME                | DESIRED  | CURRENT  |
| AGE                 |          |          |

|                             |             |                                                            |        |  |
|-----------------------------|-------------|------------------------------------------------------------|--------|--|
| logging-curatore-1          | 1           | 1                                                          | 3d     |  |
| logging-es-6cvk237t-1       | 1           | 1                                                          | 3d     |  |
| logging-es-e5x4t4ai-1       | 1           | 1                                                          | 3d     |  |
| logging-es-xmwvnorv-1       | 1           | 1                                                          | 3d     |  |
| logging-kibana-1            | 1           | 1                                                          | 3d     |  |
| NAME                        | HOST/PORT   | PATH                                                       |        |  |
| SERVICE                     | TERMINATION | LABELS                                                     |        |  |
| logging-kibana              |             | kibana.example.com                                         |        |  |
| logging-kibana              | reencrypt   | component=support,logging-infra=support,provider=openshift |        |  |
| logging-kibana-ops          |             | kibana-ops.example.com                                     |        |  |
| logging-kibana-ops          | reencrypt   | component=support,logging-infra=support,provider=openshift |        |  |
| NAME                        | CLUSTER-IP  | EXTERNAL-IP                                                |        |  |
| PORT(S)                     | AGE         |                                                            |        |  |
| logging-es                  |             | 172.24.155.177                                             | <none> |  |
| 9200/TCP                    | 3d          | None                                                       | <none> |  |
| logging-es-cluster          |             |                                                            |        |  |
| 9300/TCP                    | 3d          |                                                            |        |  |
| logging-es-ops              |             | 172.27.197.57                                              | <none> |  |
| 9200/TCP                    | 3d          | None                                                       | <none> |  |
| logging-es-ops-cluster      |             |                                                            |        |  |
| 9300/TCP                    | 3d          |                                                            |        |  |
| logging-kibana              |             | 172.27.224.55                                              | <none> |  |
| 443/TCP                     | 3d          | 172.25.117.77                                              | <none> |  |
| logging-kibana-ops          |             |                                                            |        |  |
| 443/TCP                     | 3d          |                                                            |        |  |
| NAME                        | READY       | STATUS                                                     |        |  |
| RESTARTS                    | AGE         |                                                            |        |  |
| logging-curatore-1-6s7wy    | 1/1         | Running                                                    | 0      |  |
| 3d                          |             |                                                            |        |  |
| logging-deployer-un6ut      | 0/1         | Completed                                                  | 0      |  |
| 3d                          |             |                                                            |        |  |
| logging-es-6cvk237t-1-cnpw3 | 1/1         | Running                                                    | 0      |  |
| 3d                          |             |                                                            |        |  |
| logging-es-e5x4t4ai-1-v933h | 1/1         | Running                                                    | 0      |  |
| 3d                          |             |                                                            |        |  |
| logging-es-xmwvnorv-1-adr5x | 1/1         | Running                                                    | 0      |  |
| 3d                          |             |                                                            |        |  |
| logging-fluentd-156xn       | 1/1         | Running                                                    | 0      |  |
| 3d                          |             |                                                            |        |  |
| logging-fluentd-40biz       | 1/1         | Running                                                    | 0      |  |
| 3d                          |             |                                                            |        |  |
| logging-fluentd-8k847       | 1/1         | Running                                                    | 0      |  |
| 3d                          |             |                                                            |        |  |

You should end up with a similar setup to the following.

|                                             |       |           |          |     |
|---------------------------------------------|-------|-----------|----------|-----|
| \$ oc get pods -o wide                      |       |           |          |     |
| NAME                                        | READY | STATUS    | RESTARTS | AGE |
| NODE                                        |       |           |          |     |
| logging-curatore-1-6s7wy                    | 1/1   | Running   | 0        | 3d  |
| ip-172-31-24-239.us-west-2.compute.internal |       |           |          |     |
| logging-deployer-un6ut                      | 0/1   | Completed | 0        | 3d  |
| ip-172-31-6-152.us-west-2.compute.internal  |       |           |          |     |

|                                             |     |         |   |    |
|---------------------------------------------|-----|---------|---|----|
| logging-es-6cvk237t-1-cnpw3                 | 1/1 | Running | 0 | 3d |
| ip-172-31-24-238.us-west-2.compute.internal |     |         |   |    |
| logging-es-e5x4t4ai-1-v933h                 | 1/1 | Running | 0 | 3d |
| ip-172-31-24-235.us-west-2.compute.internal |     |         |   |    |
| logging-es-xmwvnorv-1-adr5x                 | 1/1 | Running | 0 | 3d |
| ip-172-31-24-233.us-west-2.compute.internal |     |         |   |    |
| logging-fluentd-156xn                       | 1/1 | Running | 0 | 3d |
| ip-172-31-24-241.us-west-2.compute.internal |     |         |   |    |
| logging-fluentd-40biz                       | 1/1 | Running | 0 | 3d |
| ip-172-31-24-236.us-west-2.compute.internal |     |         |   |    |
| logging-fluentd-8k847                       | 1/1 | Running | 0 | 3d |
| ip-172-31-24-237.us-west-2.compute.internal |     |         |   |    |
| logging-fluentd-9a3qx                       | 1/1 | Running | 0 | 3d |
| ip-172-31-24-231.us-west-2.compute.internal |     |         |   |    |
| logging-fluentd-abvgj                       | 1/1 | Running | 0 | 3d |
| ip-172-31-24-228.us-west-2.compute.internal |     |         |   |    |
| logging-fluentd-bh74n                       | 1/1 | Running | 0 | 3d |
| ip-172-31-24-238.us-west-2.compute.internal |     |         |   |    |
| ...                                         |     |         |   |    |
| ...                                         |     |         |   |    |

By default the amount of RAM allocated to each ES instance is 8GB.

**openshift\_logging\_es\_memory\_limit** is the parameter used in the **openshift-ansible** host inventory file. Keep in mind that **half** of this value will be passed to the individual elasticsearch pods java processes **heap size**.

[Learn more about installing EFK.](#)

### 33.2.1. Large Clusters

At 100 nodes or more, it is recommended to first pre-pull the logging images from **docker pull registry.access.redhat.com/openshift3/logging-fluentd:v3.9**. After deploying the logging infrastructure pods (Elasticsearch, Kibana, and Curator), node labeling should be done in steps of 20 nodes at a time. For example:

Using a simple loop:

```
$ while read node; do oc label nodes $node logging-infra-fluentd=true;
done < 20_fluentd.lst
```

The following also works:

```
$ oc label nodes 10.10.0.{100..119} logging-infra-fluentd=true
```

Labeling nodes in groups paces the DaemonSets used by OpenShift logging, helping to avoid contention on shared resources such as the image registry.



#### NOTE

Check for the occurrence of any "CrashLoopBackOff | ImagePullFailed | Error" issues. **oc logs <pod>**, **oc describe pod <pod>** and **oc get event** are helpful diagnostic commands.

## 33.3. SYSTEMD-JOURNALD AND RSYSLOG

## Rate-limiting

In Red Hat Enterprise Linux (RHEL) 7 the **systemd-journald.socket** unit creates **/dev/log** during the boot process, and then passes input to **systemd-journald.service**. Every **syslog()** call goes to the journal.

Rsyslog uses the **imjournal** module as a default input mode for journal files. Refer to [Interaction of rsyslog and journal](#) for detailed information about this topic.

A simple test harness was developed, which uses **logger** across the cluster nodes to make entries of different sizes at different rates in the system log. During testing simulations under a default Red Hat Enterprise Linux (RHEL) 7 installation with **systemd-219-19.el7.x86\_64** at certain logging rates (approximately 40 log lines per second), we encountered the default rate limit of **rsyslogd**. After adjusting these limits, entries stopped being written to journald due to local journal file corruption. [This issue is resolved in later versions of systemd](#).

## Scaling up

As you scale up your project, the default logging environment might need some adjustments. After updating to **systemd-219-22.el7.x86\_64**, we added:

```
$IMUXSockRateLimitInterval 0
$IMJournalRateLimitInterval 0
```

to **/etc/rsyslog.conf** and:

```
# Disable rate limiting
RateLimitInterval=1s
RateLimitBurst=10000
Storage=volatile
Compress=no
MaxRetentionSec=30s
```

to **/etc/systemd/journald.conf**.

Now, restart the services.

```
$ systemctl restart systemd-journald.service
$ systemctl restart rsyslog.service
```

These settings account for the bursty nature of uploading in bulk.

After removing the rate limit, you may see increased CPU utilization on the system logging daemons as it processes any messages that would have previously been throttled.

Rsyslog is configured (see **ratelimit.interval**, **ratelimit.burst**) to rate-limit entries read from the journal at 10,000 messages in 300 seconds. A good rule of thumb is to ensure that the rsyslog rate-limits account for the **systemd-journald** rate-limits.

## 33.4. SCALING UP EFK LOGGING

If you do not indicate the desired scale at first deployment, the least disruptive way of adjusting your cluster is by re-running the Ansible logging playbook after updating the inventory file with an updated **openshift\_logging\_es\_cluster\_size** value. parameter. Refer to the [Performing Administrative Elasticsearch Operations](#) section for more in-depth information.

## 33.5. STORAGE CONSIDERATIONS

An Elasticsearch index is a collection of shards and its corresponding replica shards. This is how ES implements high availability internally, therefore there is little need to use hardware based mirroring RAID variants. RAID 0 can still be used to increase overall disk performance.

Every search request needs to hit a copy of every shard in the index. Each ES instance requires its own individual storage, but an OpenShift Container Platform deployment can only provide volumes shared by all of its pods, which again means that Elasticsearch shouldn't be implemented with a single node.

A [persistent volume](#) should be added to each Elasticsearch deployment configuration so that we have one volume per [replica shard](#). On OpenShift Container Platform this is often achieved through [Persistent Volume Claims](#)

- 1 volume per shard
- 1 volume per replica shard

The PVCs must be named based on the `openshift_logging_es_pvc_prefix` setting. Refer to [Persistent Elasticsearch Storage](#) for more details.

Below are capacity planning guidelines for OpenShift Container Platform aggregate logging. [Example scenario](#)

Assumptions:

1. Which application: Apache
2. Bytes per line: 256
3. Lines per second load on application: 1
4. Raw text data → JSON

Baseline (256 characters per minute → 15KB/min)

| Logging Infra Pods                 | Storage Throughput                                         |
|------------------------------------|------------------------------------------------------------|
| 3 es 1 kibana 1 curator 1 fluentd  | 6 pods total: $90000 \times 86400 = 7,7 \text{ GB/day}$    |
| 3 es 1 kibana 1 curator 11 fluentd | 16 pods total: $225000 \times 86400 = 24,0 \text{ GB/day}$ |
| 3 es 1 kibana 1 curator 20 fluentd | 25 pods total: $225000 \times 86400 = 32,4 \text{ GB/day}$ |

Calculating total logging throughput and disk space required for your logging environment requires knowledge of your application. For example, if one of your applications on average logs 10 lines-per-second, each 256 bytes-per-line, calculate per-application throughput and disk space as follows:

```
(bytes-per-line * (lines-per-second) = 2560 bytes per app per second
(2560) * (number-of-pods-per-node,100) = 256,000 bytes per second per node
256k * (number-of-nodes) = total logging throughput per cluster
```

Fluentd ships any logs from `systemd journal` and `/var/lib/docker/containers/` to Elasticsearch. [Learn more](#).

Local SSD drives are recommended in order to achieve the best performance. In Red Hat Enterprise Linux (RHEL) 7, the [deadline](#) IO scheduler is the default for all block devices except SATA disks. For SATA disks, the default IO scheduler is [cfq](#).

Sizing storage for ES is greatly dependent on how you optimize your indices. Therefore, consider how much data you need in advance and that you are aggregating application log data. Some Elasticsearch users have found that it is necessary to [keep absolute storage consumption around 50% and below 70% at all times](#). This helps to avoid Elasticsearch becoming unresponsive during large merge operations.

# CHAPTER 34. ENABLING CLUSTER METRICS

## 34.1. OVERVIEW

The [kubelet](#) exposes metrics that can be collected and stored in back-ends by [Heapster](#).

As an OpenShift Container Platform administrator, you can view a cluster's metrics from all containers and components in one user interface. These metrics are also used by [horizontal pod autoscalers](#) in order to determine when and how to scale.

This topic describes using [Hawkular Metrics](#) as a metrics engine which stores the data persistently in a [Cassandra](#) database. When this is configured, CPU, memory and network-based metrics are viewable from the OpenShift Container Platform web console and are available for use by [horizontal pod autoscalers](#).

Heapster retrieves a list of all nodes from the master server, then contacts each node individually through the `/stats` endpoint. From there, Heapster scrapes the metrics for CPU, memory and network usage, then exports them into Hawkular Metrics.

The storage volume metrics available on the kubelet are not available through the `/stats` endpoint, but are available through the `/metrics` endpoint. See OpenShift Container Platform via Prometheus for detailed information.

Browsing individual pods in the web console displays separate sparkline charts for memory and CPU. The time range displayed is selectable, and these charts automatically update every 30 seconds. If there are multiple containers on the pod, then you can select a specific container to display its metrics.

If [resource limits](#) are defined for your project, then you can also see a donut chart for each pod. The donut chart displays usage against the resource limit. For example: **145 Available of 200 MiB**, with the donut chart showing **55 MiB Used**.

## 34.2. BEFORE YOU BEGIN

An Ansible playbook is available to deploy and upgrade cluster metrics. You should familiarize yourself with the [Advanced Installation](#) section. This provides information for preparing to use Ansible and includes information about configuration. Parameters are added to the Ansible inventory file to configure various areas of cluster metrics.

The following describe the various areas and the parameters that can be added to the Ansible inventory file in order to modify the defaults:

- [Metrics Project](#)
- [Metrics Data Storage](#)

## 34.3. METRICS PROJECT

The components for cluster metrics must be deployed to the [openshift-infra](#) project in order for autoscaling to work. [Horizontal pod autoscalers](#) specifically use this project to discover the Heapster service and use it to retrieve metrics. The metrics project can be changed by adding [openshift\\_metrics\\_project](#) to the inventory file.

## 34.4. METRICS DATA STORAGE

You can store the metrics data to either [persistent storage](#) or to a temporary [pod volume](#).

### 34.4.1. Persistent Storage

Running OpenShift Container Platform cluster metrics with persistent storage means that your metrics are stored to a [persistent volume](#) and are able to survive a pod being restarted or recreated. This is ideal if you require your metrics data to be guarded from data loss. For production environments it is highly recommended to configure persistent storage for your metrics pods.

The size requirement of the Cassandra storage is dependent on the number of pods. It is the administrator's responsibility to ensure that the size requirements are sufficient for their setup and to monitor usage to ensure that the disk does not become full. The size of the persisted volume claim is specified with the `openshift_metrics_cassandra_pvc_size`[ansible variable](#) which is set to 10 GB by default.

If you would like to use [dynamically provisioned persistent volumes](#) set the `openshift_metrics_cassandra_storage_type`[variable](#) to `dynamic` in the inventory file.

You can use Red Hat Gluster to enable `gluster-block` Storage as a backend for metrics with Elasticsearch. For more information, see [Configuring Red Hat Gluster Persistent Storage](#).

### 34.4.2. Capacity Planning for Cluster Metrics

After running the `openshift_metrics` Ansible role, the output of `oc get pods` should resemble the following:

| # oc get pods -n openshift-infra |     | READY | STATUS    |
|----------------------------------|-----|-------|-----------|
| NAME                             | AGE |       |           |
| RESTARTS                         |     |       |           |
| hawkular-cassandra-1-15y4g       | 17h | 1/1   | Running 0 |
| hawkular-metrics-1t9so           | 17h | 1/1   | Running 0 |
| heapster-febru                   | 17h | 1/1   | Running 0 |

OpenShift Container Platform metrics are stored using the Cassandra database, which is deployed with settings of `openshift_metrics_cassandra_limits_memory: 2G`; this value could be adjusted further based upon the available memory as determined by the Cassandra start script. This value should cover most OpenShift Container Platform metrics installations, but using environment variables you can modify the `MAX_HEAP_SIZE` along with heap new generation size, `HEAP_NEWSIZE`, in the Cassandra Dockerfile prior to deploying cluster metrics.

By default, metrics data is stored for seven days. After seven days, Cassandra begins to purge the oldest metrics data. Metrics data for deleted pods and projects is not automatically purged; it is only removed once the data is more than seven days old.

#### Example 34.1. Data Accumulated by 10 Nodes and 1000 Pods

In a test scenario including 10 nodes and 1000 pods, a 24 hour period accumulated 2.5 GB of metrics data. Therefore, the capacity planning formula for metrics data in this scenario is:

$$((2.5 \times 10^9) \div 1000) \div 24) \div 10^6 = \sim 0.125 \text{ MB/hour per pod.}$$

### Example 34.2. Data Accumulated by 120 Nodes and 10000 Pods

In a test scenario including 120 nodes and 10000 pods, a 24 hour period accumulated 25 GB of metrics data. Therefore, the capacity planning formula for metrics data in this scenario is:

$$(((11.410 \times 10^9) \div 1000) \div 24) \div 10^6 = 0.475 \text{ MB/hour}$$

|                                                                               | 1000 pods | 10000 pods |
|-------------------------------------------------------------------------------|-----------|------------|
| Cassandra storage data accumulated over 24 hours (default metrics parameters) | 2.5 GB    | 11.4 GB    |

If the default value of 7 days for `openshift_metrics_duration` and 30 seconds for `openshift_metrics_resolution` are preserved, then weekly storage requirements for the Cassandra pod would be:

|                                                                                 | 1000 pods | 10000 pods |
|---------------------------------------------------------------------------------|-----------|------------|
| Cassandra storage data accumulated over seven days (default metrics parameters) | 20 GB     | 90 GB      |

In the previous table, an additional 10 percent was added to the expected storage space as a buffer for unexpected monitored pod usage.



#### WARNING

If the Cassandra persisted volume runs out of sufficient space, then data loss occurs.

For cluster metrics to work with persistent storage, ensure that the persistent volume has the `ReadWriteOnce` access mode. If this mode is not active, then the persistent volume claim cannot locate the persistent volume, and Cassandra fails to start.

To use persistent storage with the metric components, ensure that a `persistent volume` of sufficient size is available. The creation of `persistent volume claims` is handled by the OpenShift Ansible `openshift_metrics` role.

OpenShift Container Platform metrics also supports dynamically-provisioned persistent volumes. To use this feature with OpenShift Container Platform metrics, it is necessary to set the value of `openshift_metrics_cassandra_storage_type` to `dynamic`. You can use EBS, GCE, and Cinder storage back-ends to `dynamically provision persistent volumes`.

For information on configuring the performance and scaling the cluster metrics pods, see the [Scaling Cluster Metrics](#) topic.

**Table 34.1. Cassandra Database storage requirements based on number of nodes/pods in the cluster**

| Number of Nodes | Number of Pods | Cassandra Storage growth speed | Cassandra storage growth per day | Cassandra storage growth per week |
|-----------------|----------------|--------------------------------|----------------------------------|-----------------------------------|
| 210             | 10500          | 500 MB per hour                | 15 GB                            | 75 GB                             |
| 990             | 11000          | 1 GB per hour                  | 30 GB                            | 210 GB                            |

In the above calculation, approximately 20 percent of the expected size was added as overhead to ensure that the storage requirements do not exceed calculated value.

If the **METRICS\_DURATION** and **METRICS\_RESOLUTION** values are kept at the default (7 days and 15 seconds respectively), it is safe to plan Cassandra storage size requirements for week, as in the values above.



### WARNING

Because OpenShift Container Platform metrics uses the Cassandra database as a datastore for metrics data, if **USE\_PERSISTANT\_STORAGE=true** is set during the metrics set up process, **PV** will be on top in the network storage, with NFS as the default. However, using network storage in combination with Cassandra is not recommended, as per the [Cassandra documentation](#).

### Known Issues and Limitations

Testing found that the **heapster** metrics component is capable of handling up to 25,000 pods. If the amount of pods exceed that number, Heapster begins to fall behind in metrics processing, resulting in the possibility of metrics graphs no longer appearing. Work is ongoing to increase the number of pods that Heapster can gather metrics on, as well as upstream development of alternate metrics-gathering solutions.

### 34.4.3. Non-Persistent Storage

Running OpenShift Container Platform cluster metrics with non-persistent storage means that any stored metrics are deleted when the pod is deleted. While it is much easier to run cluster metrics with non-persistent data, running with non-persistent data does come with the risk of permanent data loss. However, metrics can still survive a container being restarted.

In order to use non-persistent storage, you must set the **openshift\_metrics\_cassandra\_storage\_type** variable to **emptydir** in the inventory file.



### NOTE

When using non-persistent storage, metrics data is written to **/var/lib/origin/openshift.local.volumes/pods** on the node where the Cassandra pod runs. Ensure **/var** has enough free space to accommodate metrics storage.

## 34.5. METRICS ANSIBLE ROLE

The OpenShift Container Platform Ansible `openshift_metrics` role configures and deploys all of the metrics components using the variables from the [Configuring Ansible inventory file](#).

### 34.5.1. Specifying Metrics Ansible Variables

The `openshift_metrics` role included with OpenShift Ansible defines the tasks to deploy cluster metrics. The following is a list of role variables that can be added to your inventory file if it is necessary to override them.

**Table 34.2. Ansible Variables**

| Variable                                                    | Description                                                                                                                                                                                                          |
|-------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_metrics_install_metrics</code>              | Deploy metrics if <code>true</code> . Otherwise, undeploy.                                                                                                                                                           |
| <code>openshift_metrics_start_cluster</code>                | Start the metrics cluster after deploying the components.                                                                                                                                                            |
| <code>openshift_metrics_image_prefix</code>                 | The prefix for the component images. With <code>openshift3/ose-metrics-cassandra:v3.9</code> , set prefix <code>openshift/ose-</code> .                                                                              |
| <code>openshift_metrics_image_version</code>                | The version for the component images. For example, with <code>openshift3/ose-metrics-cassandra:v3.9.11</code> , set version as <code>v3.9.11</code> , or to always get the latest 3.9 image, set <code>v3.9</code> . |
| <code>openshift_metrics_startup_timeout</code>              | The time, in seconds, to wait until Hawkular Metrics and Heapster start up before attempting a restart.                                                                                                              |
| <code>openshift_metrics_duration</code>                     | The number of days to store metrics before they are purged.                                                                                                                                                          |
| <code>openshift_metrics_resolution</code>                   | The frequency that metrics are gathered. Defined as a number and time identifier: seconds (s), minutes (m), hours (h).                                                                                               |
| <code>openshift_metrics_cassandra_pvc_prefix</code>         | The persistent volume claim prefix created for Cassandra. A serial number is appended to the prefix starting from 1.                                                                                                 |
| <code>openshift_metrics_cassandra_pvc_size</code>           | The persistent volume claim size for each of the Cassandra nodes.                                                                                                                                                    |
| <code>openshift_metrics_cassandra_storage_class_name</code> | If you want to explicitly set the storage class, you must not set <code>openshift_metrics_cassandra_storage_type</code> to <code>emptydir</code> or <code>dynamic</code> .                                           |

| Variable                                                 | Description                                                                                                                                                                                                                                  |
|----------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_metrics_cassandra_storage_type</code>    | Use <b>emptydir</b> for ephemeral storage (for testing); <b>pv</b> for persistent volumes, which need to be created before the installation; or <b>dynamic</b> for dynamic persistent volumes.                                               |
| <code>openshift_metrics_cassandra_replicas</code>        | The number of Cassandra nodes for the metrics stack. This value dictates the number of Cassandra replication controllers.                                                                                                                    |
| <code>openshift_metrics_cassandra_limits_memory</code>   | The memory limit for the Cassandra pod. For example, a value of <b>2Gi</b> would limit Cassandra to 2 GB of memory. This value could be further adjusted by the start script based on available memory of the node on which it is scheduled. |
| <code>openshift_metrics_cassandra_limits_cpu</code>      | The CPU limit for the Cassandra pod. For example, a value of <b>4000m</b> (4000 millicores) would limit Cassandra to 4 CPUs.                                                                                                                 |
| <code>openshift_metrics_cassandra_requests_memory</code> | The amount of memory to request for Cassandra pod. For example, a value of <b>2Gi</b> would request 2 GB of memory.                                                                                                                          |
| <code>openshift_metrics_cassandra_requests_cpu</code>    | The CPU request for the Cassandra pod. For example, a value of <b>4000m</b> (4000 millicores) would request 4 CPUs.                                                                                                                          |
| <code>openshift_metrics_cassandra_storage_group</code>   | The supplemental storage group to use for Cassandra.                                                                                                                                                                                         |
| <code>openshift_metrics_cassandra_nodeselector</code>    | Set to the desired, existing <a href="#">node selector</a> to ensure that pods are placed onto nodes with specific labels. For example, <code>{"region": "infra"}</code> .                                                                   |
| <code>openshift_metrics_hawkular_ca</code>               | An optional certificate authority (CA) file used to sign the Hawkular certificate.                                                                                                                                                           |
| <code>openshift_metrics_hawkular_cert</code>             | The certificate file used for re-encrypting the route to Hawkular metrics. The certificate must contain the host name used by the route. If unspecified, the default router certificate is used.                                             |
| <code>openshift_metrics_hawkular_key</code>              | The key file used with the Hawkular certificate.                                                                                                                                                                                             |

| Variable                                                | Description                                                                                                                                                                                                                                                    |
|---------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_metrics_hawkular_limits_memory</code>   | The amount of memory to limit the Hawkular pod. For example, a value of <b>2Gi</b> would limit the Hawkular pod to 2 GB of memory. This value could be further adjusted by the start script based on available memory of the node on which it is scheduled.    |
| <code>openshift_metrics_hawkular_limits_cpu</code>      | The CPU limit for the Hawkular pod. For example, a value of <b>4000m</b> (4000 millicores) would limit the Hawkular pod to 4 CPUs.                                                                                                                             |
| <code>openshift_metrics_hawkular_replicas</code>        | The number of replicas for Hawkular metrics.                                                                                                                                                                                                                   |
| <code>openshift_metrics_hawkular_requests_memory</code> | The amount of memory to request for the Hawkular pod. For example, a value of <b>2Gi</b> would request 2 GB of memory.                                                                                                                                         |
| <code>openshift_metrics_hawkular_requests_cpu</code>    | The CPU request for the Hawkular pod. For example, a value of <b>4000m</b> (4000 millicores) would request 4 CPUs.                                                                                                                                             |
| <code>openshift_metrics_hawkular_nodeselector</code>    | Set to the desired, existing <a href="#">node selector</a> to ensure that pods are placed onto nodes with specific labels. For example, <code>{"region": "infra"}</code> .                                                                                     |
| <code>openshift_metrics_heapster_allowed_users</code>   | A comma-separated list of CN to accept. By default, this is set to allow the OpenShift service proxy to connect. Add <b>system:master-proxy</b> to the list when overriding in order to allow <a href="#">horizontal pod autoscaling</a> to function properly. |
| <code>openshift_metrics_heapster_limits_memory</code>   | The amount of memory to limit the Heapster pod. For example, a value of <b>2Gi</b> would limit the Heapster pod to 2 GB of memory.                                                                                                                             |
| <code>openshift_metrics_heapster_limits_cpu</code>      | The CPU limit for the Heapster pod. For example, a value of <b>4000m</b> (4000 millicores) would limit the Heapster pod to 4 CPUs.                                                                                                                             |
| <code>openshift_metrics_heapster_requests_memory</code> | The amount of memory to request for Heapster pod. For example, a value of <b>2Gi</b> would request 2 GB of memory.                                                                                                                                             |
| <code>openshift_metrics_heapster_requests_cpu</code>    | The CPU request for the Heapster pod. For example, a value of <b>4000m</b> (4000 millicores) would request 4 CPUs.                                                                                                                                             |
| <code>openshift_metrics_heapster_standalone</code>      | Deploy only Heapster, without the Hawkular Metrics and Cassandra components.                                                                                                                                                                                   |

| Variable                                              | Description                                                                                                                                                                                                                                                                               |
|-------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_metrics_heapster_nodeselector</code>  | Set to the desired, existing <code>node selector</code> to ensure that pods are placed onto nodes with specific labels. For example, <code>{"region": "infra"}</code> .                                                                                                                   |
| <code>openshift_metrics_install_hawkular_agent</code> | Set to <code>true</code> to install the Hawkular OpenShift Agent (HOSA). Set to <code>false</code> to remove the HOSA from an installation. HOSA can be used to collect custom metrics from your pods. This component is currently in Technology Preview and is not installed by default. |
| <code>openshift_metrics_hawkular_hostname</code>      | Set when executing the <code>openshift_metrics</code> Ansible role, since it uses the host name for the Hawkular Metrics <code>route</code> . This value should correspond to a fully qualified domain name.                                                                              |



## NOTE

The Hawkular OpenShift Container Platform Agent on OpenShift Container Platform is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offering/techpreview/>.

See [Compute Resources](#) for further discussion on how to specify requests and limits.

If you are using [persistent storage](#) with Cassandra, it is the administrator's responsibility to set a sufficient disk size for the cluster using the `openshift_metrics_cassandra_pvc_size` variable. It is also the administrator's responsibility to monitor disk usage to make sure that it does not become full.



## WARNING

Data loss results if the Cassandra persisted volume runs out of sufficient space.

All of the other variables are optional and allow for greater customization. For instance, if you have a custom install in which the Kubernetes master is not available under <https://kubernetes.default.svc:443> you can specify the value to use instead with the `openshift_metrics_master_url` parameter. To deploy a specific version of the metrics components, modify the `openshift_metrics_image_version` variable.

**WARNING**

It is highly recommended to not use `latest` for the `openshift_metrics_image_version`. The `latest` version corresponds to the very latest version available and can cause issues if it brings in a newer version not meant to function on the version of OpenShift Container Platform you are currently running.

### 34.5.2. Using Secrets

The OpenShift Container Platform Ansible `openshift_metrics` role auto-generates self-signed certificates for use between its components and generates a [re-encrypting route](#) to expose the Hawkular Metrics service. This route is what allows the web console to access the Hawkular Metrics service.

In order for the browser running the web console to trust the connection through this route, it must trust the route's certificate. This can be accomplished by [providing your own certificates](#) signed by a trusted Certificate Authority. The `openshift_metrics` role allows you to specify your own certificates, which it then uses when creating the route.

The router's default certificate are used if you do not provide your own.

#### 34.5.2.1. Providing Your Own Certificates

To provide your own certificate, which is used by the [re-encrypting route](#), you can set the `openshift_metrics_hawkular_cert`, `openshift_metrics_hawkular_key`, and `openshift_metrics_hawkular_cavariables` in your inventory file.

The `hawkular-metrics.pem` value needs to contain the certificate in its `.pem` format. You may also need to provide the certificate for the Certificate Authority which signed this `pem` file via the `hawkular-metrics-ca.cert` secret.

For more information, see the [re-encryption route documentation](#).

## 34.6. DEPLOYING THE METRIC COMPONENTS

Because deploying and configuring all the metric components is handled with OpenShift Container Platform Ansible, you can deploy everything in one step.

The following examples show you how to deploy metrics with and without persistent storage using the default parameters.

**IMPORTANT**

The host that you run the Ansible playbook on must have at least 75MiB of free memory per host in the inventory.

**IMPORTANT**

In accordance with upstream Kubernetes rules, metrics can be collected only on the default interface of `eth0`.

### Example 34.3. Deploying with Persistent Storage

The following command sets the Hawkular Metrics route to use **hawkular-metrics.example.com** and is deployed using persistent storage.

You must have a persistent volume of sufficient size available.

```
$ ansible-playbook [-i </path/to/inventory>]
<OPENSHIFT_ANSIBLE_DIR>/playbooks/openshift-metrics/config.yml \
-e openshift_metrics_install_metrics=True \
-e openshift_metrics_hawkular_hostname=hawkular-metrics.example.com \
-e openshift_metrics_cassandra_storage_type=pv
```

### Example 34.4. Deploying without Persistent Storage

The following command sets the Hawkular Metrics route to use **hawkular-metrics.example.com** and deploy without persistent storage.

```
$ ansible-playbook [-i </path/to/inventory>]
<OPENSHIFT_ANSIBLE_DIR>/playbooks/openshift-metrics/config.yml \
-e openshift_metrics_install_metrics=True \
-e openshift_metrics_hawkular_hostname=hawkular-metrics.example.com
```



#### WARNING

Because this is being deployed without persistent storage, metric data loss can occur.

### 34.6.1. Metrics Diagnostics

There are some diagnostics for metrics to assist in evaluating the state of the metrics stack. To execute diagnostics for metrics:

```
$ oc adm diagnostics MetricsApiProxy
```

## 34.7. SETTING THE METRICS PUBLIC URL

The OpenShift Container Platform web console uses the data coming from the Hawkular Metrics service to display its graphs. The URL for accessing the Hawkular Metrics service must be configured with the **metricsPublicURL** option in the [master webconsole-config configmap file](#). This URL corresponds to the route created with the **openshift\_metrics\_hawkular\_hostname** inventory variable used during the [deployment](#) of the metrics components.

**NOTE**

You must be able to resolve the `openshift_metrics_hawkular_hostname` from the browser accessing the console.

For example, if your `openshift_metrics_hawkular_hostname` corresponds to `hawkular-metrics.example.com`, then you must make the following change in the `webconsole-config` configmap file:

```
clusterInfo:
  ...
  metricsPublicURL: "https://hawkular-
  metrics.example.com/hawkular/metrics"
```

Once you have updated and saved the `webconsole-config` configmap file, you must restart your OpenShift Container Platform instance.

When your OpenShift Container Platform server is back up and running, metrics are displayed on the pod overview pages.

**CAUTION**

If you are using self-signed certificates, remember that the Hawkular Metrics service is hosted under a different host name and uses different certificates than the console. You may need to explicitly open a browser tab to the value specified in `metricsPublicURL` and accept that certificate.

To avoid this issue, use certificates which are configured to be acceptable by your browser.

## 34.8. ACCESSING HAWKULAR METRICS DIRECTLY

To access and manage metrics more directly, use the [Hawkular Metrics API](#).

**NOTE**

When accessing Hawkular Metrics from the API, you are only able to perform reads. Writing metrics is disabled by default. If you want individual users to also be able to write metrics, you must set the `openshift_metrics_hawkular_user_write_accessvariable` to `true`.

However, it is recommended to use the default configuration and only have metrics enter the system via Heapster. If write access is enabled, any user can write metrics to the system, which can affect performance and cause Cassandra disk usage to unpredictably increase.

The [Hawkular Metrics documentation](#) covers how to use the API, but there are a few differences when dealing with the version of Hawkular Metrics configured for use on OpenShift Container Platform:

### 34.8.1. OpenShift Container Platform Projects and Hawkular Tenants

Hawkular Metrics is a multi-tenanted application. It is configured so that a project in OpenShift Container Platform corresponds to a tenant in Hawkular Metrics.

As such, when accessing metrics for a project named **MyProject** you must set the **Hawkular-Tenant** header to **MyProject**.

There is also a special tenant named **\_system** which contains system level metrics. This requires either a **cluster-reader** or **cluster-admin** level privileges to access.

### 34.8.2. Authorization

The Hawkular Metrics service authenticates the user against OpenShift Container Platform to determine if the user has access to the project it is trying to access.

Hawkular Metrics accepts a bearer token from the client and verifies that token with the OpenShift Container Platform server using a **SubjectAccessReview**. If the user has proper read privileges for the project, they are allowed to read the metrics for that project. For the **\_system** tenant, the user requesting to read from this tenant must have **cluster-reader** permission.

When accessing the Hawkular Metrics API, you must pass a bearer token in the **Authorization** header.

## 34.9. SCALING OPENSHIFT CONTAINER PLATFORM CLUSTER METRICS PODS

Information about scaling cluster metrics capabilities is available in the [Scaling and Performance Guide](#).

## 34.10. INTEGRATION WITH AGGREGATED LOGGING

Hawkular Alerts must be connected to the Aggregated Logging's Elasticsearch to react on log events. By default, Hawkular tries to find Elasticsearch on its default place (namespace **logging**, pod **logging-es**) at every boot. If Aggregated Logging is installed after Hawkular, the Hawkular Metrics pod might need to be restarted in order to recognize the new Elasticsearch server. The Hawkular boot log provides a clear indication if the integration could not be properly configured, with messages like:

Failed to import the logging certificate into the store. Continuing, but the  
logging integration might fail.

or

Could not get the logging secret! Status code: 000. The Hawkular Alerts  
integration with Logging might not work properly.

This feature is available from version 3.7.0. You can confirm if logging is available by checking the log for an entry like:

Retrieving the Logging's CA and adding to the trust store, if Logging is  
available.

## 34.11. CLEANUP

You can remove everything deployed by the OpenShift Container Platform Ansible **openshift\_metrics** role by performing the following steps:

```
$ ansible-playbook [-i </path/to/inventory>]
<OPENSHIFT_ANSIBLE_DIR>/playbooks/openshift-metrics/config.yml \
-e openshift_metrics_install_metrics=False
```

## 34.12. PROMETHEUS ON OPENSHIFT CONTAINER PLATFORM

Prometheus is a stand-alone, open source systems monitoring and alerting toolkit. You can use Prometheus to visualize metrics and alerts for OpenShift Container Platform system resources.



### IMPORTANT

Prometheus on OpenShift Container Platform is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs), might not be functionally complete, and Red Hat does not recommend to use them for production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information on Red Hat Technology Preview features support scope, see <https://access.redhat.com/support/offering/techpreview/>.

### 34.12.1. Setting Prometheus Role Variables

The Prometheus role creates:

- The **openshift-metrics** namespace.
- Prometheus **clusterrolebinding** and service account.
- Prometheus pod with Prometheus behind OAuth proxy, Alertmanager, and Alert Buffer as a stateful set.
- Prometheus and **prometheus-alerts** ConfigMaps.
- Prometheus and Prometheus Alerts services and direct routes.

Prometheus deployment is disabled by default, enable it by setting **openshift\_hosted\_prometheus\_deploy** to **true**. For example:

```
# openshift_hosted_prometheus_deploy=true
```

Set the following role variables to install and configure Prometheus.

**Table 34.3. Prometheus Variables**

| Variable                              | Description                                                                                                                                                          |
|---------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>openshift_prometheus_namespace</b> | Project namespace where the components are deployed. Default set to <b>openshift-metrics</b> . For example, <b>openshift_prometheus_namespace=\${USER_PROJECT}</b> . |

| Variable                                                    | Description                                                                                                        |
|-------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------|
| <code>openshift_prometheus_node_selector</code>             | Selector for the nodes on which Prometheus is deployed.                                                            |
| <code>openshift_prometheus_storage_kind</code>              | Set to create PV for Prometheus. For example, <code>openshift_prometheus_storage_kind=nfs</code> .                 |
| <code>openshift_prometheus_alertmanager_storage_kind</code> | Set to create PV for Alertmanager. For example, <code>openshift_prometheus_alertmanager_storage_kind=nfs</code> .  |
| <code>openshift_prometheus_alertbuffer_storage_kind</code>  | Set to create PV for Alert Buffer. For example, <code>openshift_prometheus_alertbuffer_storage_kind=nfs</code> .   |
| <code>openshift_prometheus_storage_type</code>              | Set to create PVC for Prometheus. For example, <code>openshift_prometheus_storage_type=pvc</code> .                |
| <code>openshift_prometheus_alertmanager_storage_type</code> | Set to create PVC for Alertmanager. For example, <code>openshift_prometheus_alertmanager_storage_type=pvc</code> . |
| <code>openshift_prometheus_alertbuffer_storage_type</code>  | Set to create PVC for Alert Buffer. For example, <code>openshift_prometheus_alertbuffer_storage_type=pvc</code> .  |
| <code>openshift_prometheus_additional_rules_file</code>     | Additional Prometheus rules file. Set to <code>null</code> by default.                                             |

### 34.12.2. Deploying Prometheus Using Ansible Installer



#### IMPORTANT

The host that you run the Ansible playbook on must have at least 75MiB of free memory per host in the inventory.

The Ansible Installer is the default method of deploying Prometheus.

Add label to your node:

```
# Inventory file
openshift_prometheus_namespace=openshift-metrics

openshift_prometheus_node_selector={"region":"infra"}
```

Run the playbook:

```
$ ansible-playbook -vvv -i ${INVENTORY_FILE} playbooks/openshift-prometheus/config.yml
```

### 34.12.2.1. Additional Methods for Deploying Prometheus

#### Deploy Using Node-Selector

Label the node on which you want to deploy Prometheus:

```
# oc adm label node/$NODE ${KEY}=${VALUE}
```

Deploy Prometheus with Ansible and container resources:

```
# Inventory file
openshift_prometheus_namespace=openshift-metrics

# Set node selector for prometheus
openshift_prometheus_node_selector={"${KEY}":"${VALUE}"}
```

Run the playbook:

```
$ ansible-playbook -vvv -i ${INVENTORY_FILE} playbooks/openshift-prometheus/config.yml
```

#### Deploy Using a Non-default Namespace

Identify your namespace:

```
# Inventory file
openshift_prometheus_node_selector={"region":"infra"}

# Set non-default openshift_prometheus_namespace
openshift_prometheus_namespace=${USER_PROJECT}
```

Run the playbook:

```
$ ansible-playbook -vvv -i ${INVENTORY_FILE} playbooks/openshift-prometheus/config.yml
```

### 34.12.2.2. Accessing the Prometheus Web UI

The Prometheus server automatically exposes a Web UI at **localhost:9090**. You can access the Prometheus Web UI with the **view** role.

### 34.12.2.3. Configuring Prometheus for OpenShift Container Platform

#### Prometheus Storage Related Variables

With each Prometheus component (including Prometheus, Alertmanager, Alert Buffer, and OAuth proxy) you can set the PV claim by setting corresponding role variable, for example:

```
openshift_prometheus_storage_type: pvc
```

```
openshift_prometheus_alertmanager_pvc_name: alertmanager
openshift_prometheus_alertbuffer_pvc_size: 10G
openshift_prometheus_pvc_access_modes: [ReadWriteOnce]
```

## Prometheus Alert Rules File Variable

You can add an external file with alert rules by setting the path to an additional rules variable:

```
openshift_prometheus_additional_rules_file: <PATH>
```

The file must follow [the Prometheus Alert rules format](#). The following example sets a rule to send an alert when one of the cluster nodes is down:

```
groups:
- name: example-rules
  interval: 30s # defaults to global interval
  rules:
    - alert: Node Down
      expr: up{job="kubernetes-nodes"} == 0
      for: 10m 1
      annotations:
        miqTarget: "ContainerNode"
        severity: "HIGH"
        message: "{{'{{'}}{$labels.instance}'}}{{'}}' }} is down"
```

- 1** The optional **for** value specifies the amount of time Prometheus waits before it sends an alert for this element. For example, if you set **10m**, Prometheus waits 10 minutes after it encounters this issue before sending an alert.

## Prometheus Variables to Control Resource Limits

With each Prometheus component (including Prometheus, Alertmanager, Alert Buffer, and OAuth proxy) you can specify CPU, memory limits, and requests by setting the corresponding role variable, for example:

```
openshift_prometheus_alertmanager_limits_memory: 1Gi
openshift_prometheus_oauth_proxy_cpu_requests: 100m
```

For more detailed information, see [OpenShift Prometheus](#).



### NOTE

Once `openshift_metrics_project: openshift-infra` is installed, metrics can be gathered from the `http://${POD_IP}:7575/metrics` endpoint.

## 34.12.3. OpenShift Container Platform Metrics via Prometheus

The state of a system can be gauged by the metrics that it emits. This section describes current and proposed metrics that identify the health of the storage subsystem and cluster.

### 34.12.3.1. Current Metrics

This section describes the metrics currently emitted from Kubernetes's storage subsystem.

## Cloud Provider API Call Metrics

This metric reports the time and count of success and failures of all cloudprovider API calls. These metrics include `aws_attach_time` and `aws_detach_time`. The type of emitted metrics is a histogram, and hence, Prometheus also generates sum, count, and bucket metrics for these metrics.

### Example summary of cloudprovider metrics from GCE:

```
cloudprovider_gce_api_request_duration_seconds { request =
"instance_list"}
cloudprovider_gce_api_request_duration_seconds { request = "disk_insert"}
cloudprovider_gce_api_request_duration_seconds { request = "disk_delete"}
cloudprovider_gce_api_request_duration_seconds { request = "attach_disk"}
cloudprovider_gce_api_request_duration_seconds { request = "detach_disk"}
cloudprovider_gce_api_request_duration_seconds { request = "list_disk"}
```

### Example summary of cloudprovider metrics from AWS:

```
cloudprovider_aws_api_request_duration_seconds { request =
"attach_volume"}
cloudprovider_aws_api_request_duration_seconds { request =
"detach_volume"}
cloudprovider_aws_api_request_duration_seconds { request = "create_tags"}
cloudprovider_aws_api_request_duration_seconds { request =
"create_volume"}
cloudprovider_aws_api_request_duration_seconds { request =
"delete_volume"}
cloudprovider_aws_api_request_duration_seconds { request =
"describe_instance"}
cloudprovider_aws_api_request_duration_seconds { request =
"describe_volume"}
```

See [Cloud Provider \(specifically GCE and AWS\) metrics for Storage API calls](#) for more information.

## Volume Operation Metrics

These metrics report time taken by a storage operation once started. These metrics keep track of operation time at the plug-in level, but do not include time taken by `goroutine` to run or operation to be picked up from the internal queue. These metrics are a type of histogram.

### Example summary of available volume operation metrics

```
storage_operation_duration_seconds { volume_plugin = "aws-ebs",
operation_name = "volume_attach" }
storage_operation_duration_seconds { volume_plugin = "aws-ebs",
operation_name = "volume_detach" }
storage_operation_duration_seconds { volume_plugin = "glusterfs",
operation_name = "volume_provision" }
storage_operation_duration_seconds { volume_plugin = "gce-pd",
operation_name = "volume_delete" }
storage_operation_duration_seconds { volume_plugin = "vsphere",
operation_name = "volume_mount" }
storage_operation_duration_seconds { volume_plugin = "iscsi" ,
operation_name = "volume_unmount" }
storage_operation_duration_seconds { volume_plugin = "aws-ebs",
```

```

operation_name = "unmount_device" }
storage_operation_duration_seconds { volume_plugin = "cinder" ,
operation_name = "verify_volumes_areAttached" }
storage_operation_duration_seconds { volume_plugin = "<n/a>" ,
operation_name = "verify_volumes_areAttached_per_node" }

```

See [Volume operation metrics](#) for more information.

## Volume Stats Metrics

These metrics typically report usage stats of PVC (such as used space versus available space). The type of metrics emitted is gauge.

**Table 34.4. Volume Stats Metrics**

| Metric                      | Type  | Labels/tags                                                                                                                             |
|-----------------------------|-------|-----------------------------------------------------------------------------------------------------------------------------------------|
| volume_stats_capacityBytes  | Gauge | namespace,persistentvolumeclaim,persistentvolume=                                                                                       |
| volume_stats_usedBytes      | Gauge | namespace=<persistentvolumeclaim-namespace> persistentvolumeclaim=<persistentvolumeclaim-name> persistentvolume=<persistentvolume-name> |
| volume_stats_availableBytes | Gauge | namespace=<persistentvolumeclaim-namespace> persistentvolumeclaim=<persistentvolumeclaim-name> persistentvolume=                        |
| volume_stats_inodesFree     | Gauge | namespace=<persistentvolumeclaim-namespace> persistentvolumeclaim=<persistentvolumeclaim-name> persistentvolume=<persistentvolume-name> |
| volume_stats_inodes         | Gauge | namespace=<persistentvolumeclaim-namespace> persistentvolumeclaim=<persistentvolumeclaim-name> persistentvolume=<persistentvolume-name> |

| Metric                  | Type  | Labels/tags                                                                                                                                   |
|-------------------------|-------|-----------------------------------------------------------------------------------------------------------------------------------------------|
| volume_stats_inodesUsed | Gauge | namespace=<persistentvolumeclaim-namespace><br>persistentvolumeclaim=<persistentvolumeclaim-name><br>persistentvolume=<persistentvolume-name> |

#### 34.12.4. Undeploying Prometheus

To undeploy Prometheus, run:

```
$ ansible-playbook -vvv -i ${INVENTORY_FILE} playbooks/openshift-prometheus/config.yml -e openshift_prometheus_state=absent
```

# CHAPTER 35. CUSTOMIZING THE WEB CONSOLE

## 35.1. OVERVIEW

Administrators can customize the [web console](#) using extensions, which let you run scripts and load custom stylesheets when the web console loads. Extension scripts allow you to override the default behavior of the web console and customize it for your needs.

For example, extension scripts can be used to add your own company's branding or to add company-specific capabilities. A common use case for this is rebranding or white-labeling for different environments. You can use the same extension code, but provide settings that change the web console.

### CAUTION

Take caution making extensive changes to the web console styles or behavior that are not documented below. While you add any scripts or stylesheets, significant customizations might need to be reworked on upgrades as the web console markup and behavior change in future versions.

## 35.2. LOADING EXTENSION SCRIPTS AND STYLESHEETS

As of OpenShift Container Platform 3.9, extension scripts and stylesheets can be hosted at any <https://> URL as long as the URL is accessible from the browser. The files might be hosted from a pod on the platform using a publicly accessible route, or on another server outside of OpenShift Container Platform.

To add scripts and stylesheets, edit the `webconsole-config` ConfigMap in the `openshift-web-console` namespace. The web console configuration is available in the `webconsole-config.yaml` key of the ConfigMap.

```
$ oc edit configmap/webconsole-config -n openshift-web-console
```


To add scripts, update the `extensions.scriptURLs` property. The value is an array of URLs.

To add stylesheets, update the `extensions.stylesheetURLs` property. The value is an array of URLs.

### Example `extensions.stylesheetURLs` Setting

```
apiVersion: v1
kind: ConfigMap
data:
  webconsole-config.yaml: |
    apiVersion: webconsole.config.openshift.io/v1
    extensions:
      scriptURLs:
        - https://example.com/scripts/menu-customization.js
        - https://example.com/scripts/nav-customization.js
      stylesheetURLs:
        - https://example.com/styles/logo.css
        - https://example.com/styles/custom-styles.css
    [...]
```

After saving the ConfigMap, the web console containers will be updated automatically for the new extension files within a few minutes.



### NOTE

Scripts and stylesheets must be served with the correct content type or they will not be run by the browser. Scripts must be served with **Content-Type**: **application/javascript** and stylesheets with **Content-Type**: **text/css**.

It is a best practice to wrap extension scripts in an Immediately Invoked Function Expression (IIFE). This ensures that you do not create global variables that conflict with the names used by the web console or by other extensions. For example:

```
(function() {
    // Put your extension code here...
})();
```

The examples in the following sections show common ways you can customize the web console.



### NOTE

Additional extension examples are available in the [OpenShift Origin](#) repository on GitHub.

#### 35.2.1. Setting Extension Properties

If you have a specific extension, but want to use different text in it for each of the environments, you can define the environment in the web console configuration, and use the same extension script across environments.

To add extension properties, edit the **webconsole-config** ConfigMap in the **openshift-web-console** namespace. The web console configuration is available in the **webconsole-config.yaml** key of the ConfigMap.

```
$ oc edit configmap/webconsole-config -n openshift-web-console
```

Update the **extensions.properties** value, which is a map of key-value pairs.

```
apiVersion: v1
kind: ConfigMap
data:
  webconsole-config.yaml: |
    apiVersion: webconsole.config.openshift.io/v1
    extensions:
      [...]
      properties:
        doc_url: https://docs.openshift.com
        key1: value1
        key2: value2
      [...]
```

This results in a global variable that can be accessed by the extension, as if the following code was executed:

```
window.OPENSIGHT_EXTENSION_PROPERTIES = {
  doc_url: "https://docs.openshift.com",
  key1: "value1",
  key2: "value2"
}
```

### 35.3. EXTENSION OPTION FOR EXTERNAL LOGGING SOLUTIONS

As of OpenShift Container Platform 3.6, there is an extension option to link to external logging solutions instead of using OpenShift Container Platform's EFK logging stack:

```
'use strict';
angular.module("mylinkextensions", ['openshiftConsole'])
  .run(function(extensionRegistry) {
    extensionRegistry.add('log-links', _.spread(function(resource,
options) {
      return {
        type: 'dom',
        node: '<span><a href="https://extension-
point.example.com">' + resource.metadata.name + '</a><span class="action-
divider">|</span></span>'
      };
    });
  });
hawtioPluginLoader.addModule("mylinkextensions");
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

### 35.4. CUSTOMIZING AND DISABLING THE GUIDED TOUR

A guided tour will pop up the first time a user logs in on a particular browser. You can enable the `auto_launch` for new users:

```
window.OPENSIGHT_CONSTANTS.GUIDED TOURS.landing_page_tour.auto_launch =
true;
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

### 35.5. CUSTOMIZING DOCUMENTATION LINKS

Documentation links on the landing page are customizable.

`window.OPENSIGHT_CONSTANTS.CATALOG_HELP_RESOURCES` is an array of objects containing a title and an `href`. These will be turned into links. You can completely override the array, push or pop additional links, or modify the attributes of existing links. For example:

```
window.OPENSIGHT_CONSTANTS.CATALOG_HELP_RESOURCES.push({
  title: 'Blog',
  href: 'https://blog.openshift.com'
});
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

## 35.6. CUSTOMIZING THE LOGO

The following style changes the logo in the web console header:

```
#header-logo {
    background-image: url("https://www.example.com/images/logo.png");
    width: 190px;
    height: 20px;
}
```

Replace the **example.com** URL with a URL to an actual image, and adjust the width and height. The ideal height is **20px**.

Add the stylesheet as described in [Loading Extension Scripts and Stylesheets](#).

## 35.7. CHANGING LINKS TO DOCUMENTATION

Links to external documentation are shown in various sections of the web console. The following example changes the URL for two given links to the documentation:

```
window.OPENSIGHT_CONSTANTS.HELP['get_started_cli']      =
"https://example.com/doc1.html";
window.OPENSIGHT_CONSTANTS.HELP['basic_cli_operations'] =
"https://example.com/doc2.html";
```

Alternatively, you can change the base URL for all documentation links.

This example would result in the default help URL  
<https://example.com/docs/welcome/index.html>:

```
window.OPENSIGHT_CONSTANTS.HELP_BASE_URL = "https://example.com/docs/";
```

**1** The path must end in a /.

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

## 35.8. ADDING OR CHANGING LINKS TO DOWNLOAD THE CLI

The **About** page in the web console provides download links for the [command line interface \(CLI\)](#) tools. These links can be configured by providing both the link text and URL, so that you can choose to point them directly to file packages, or to an external page that points to the actual packages.

For example, to point directly to packages that can be downloaded, where the link text is the package platform:

```
window.OPENSIGHT_CONSTANTS.CLI = {
    "Linux (32 bits)": "https://<cdn>/openshift-client-tools-linux-32bit.tar.gz",
    "Linux (64 bits)": "https://<cdn>/openshift-client-tools-linux-64bit.tar.gz",
    "Windows":           "https://<cdn>/openshift-client-tools-windows.zip",
    "Mac OS X":          "https://<cdn>/openshift-client-tools-mac.zip"
};
```

- Alternatively, to point to a page that links the actual download packages, with the **Latest Release** link text:

```
window.OPENSIGHT_CONSTANTS.CLI = {
  "Latest Release": "https://<cdn>/openshift-client-tools/latest.html"
};
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

### 35.8.1. Customizing the About Page

To provide a custom **About** page for the web console:

1. Write an extension that looks like:

```
angular
  .module('aboutPageExtension', ['openshiftConsole'])
  .config(function($routeProvider) {
    $routeProvider
      .when('/about', {
        templateUrl:
          'https://example.com/extensions/about/about.html',
        controller: 'AboutController'
      });
  })
  .addModule('aboutPageExtension');
```

2. Write a customized template.

Start from the version of [about.html](#) from the OpenShift Container Platform [release](#) you are using. Within the template, there are two angular scope variables available: **version.master.openshift** and **version.master.kubernetes**.

3. Host the template at a URL with the correct Cross-Origin Resource Sharing (CORS) response headers for the web console.
  - a. Set **Access-Control-Allow-Origin** response to allow requests from the web console domain.
  - b. Set **Access-Control-Allow-Methods** to include **GET**.
  - c. Set **Access-Control-Allow-Headers** to include **Content-Type**.

Alternatively, you can include the template directly in your JavaScript using AngularJS [\\$templateCache](#).

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

## 35.9. CONFIGURING NAVIGATION MENUS

### 35.9.1. Top Navigation Dropdown Menus

The top navigation bar of the web console contains the help icon and the user dropdown menus. You can add additional menu items to these using the [angular-extension-registry](#).

The available extension points are:

- **nav-help-dropdown** - the help icon dropdown menu, visible at desktop screen widths
- **nav-user-dropdown** - the user dropdown menu, visible at desktop screen widths
- **nav-dropdown-mobile** - the single menu for top navigation items at mobile screen widths

The following example extends the **nav-help-dropdown** menu, with a name of `<myExtensionModule>`:



### NOTE

`<myExtensionModule>` is a placeholder name. Each dropdown menu extension must be unique enough so that it does not clash with any future angular modules.

```
angular
  .module('<myExtensionModule>', ['openshiftConsole'])
  .run([
    'extensionRegistry',
    function(extensionRegistry) {
      extensionRegistry
        .add('nav-help-dropdown', function() {
          return [
            {
              type: 'dom',
              node: '<li><a href="http://www.example.com/report" target="_blank">Report a Bug</a></li>'
            },
            {
              type: 'dom',
              node: '<li class="divider"></li>' // If you want a horizontal divider to appear in the menu
            },
            {
              type: 'dom',
              node: '<li><a href="http://www.example.com/status" target="_blank">System Status</a></li>'
            }
          ];
        });
    }
  ]);

  hawtioPluginLoader.addModule('<myExtensionModule>');
}
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

### 35.9.2. Application Launcher

The top navigation bar also contains an optional application launcher for linking to other web applications. This dropdown menu is empty by default, but when links are added, appears to the left of the help menu in the masthead.

```
// Add items to the application launcher dropdown menu.
window.OPENSHIFT_CONSTANTS.APP_LAUNCHER_NAVIGATION = [
  {
    title: "Dashboard", // The text label
    iconClass: "fa fa-dashboard", // The icon you want to appear
    href: "http://example.com/dashboard", // Where to go when this item is
    clicked
    tooltip: 'View dashboard' // Optional tooltip to display
    on hover
  },
  {
    title: "Manage Account",
    iconClass: "pficon pficon-user",
    href: "http://example.com/account",
    tooltip: "Update email address or password."
  }];
]
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

### 35.9.3. System Status Badge

The top navigation bar can also include an optional system status badge in order to notify users of system-wide events such as maintenance windows. To make use of the existing styles using a yellow warning icon for the badge, follow the example below.

```
'use strict';

angular
  .module('mysystemstatusbadgeextension', ['openshiftConsole'])
  .run([
    'extensionRegistry',
    function(extensionRegistry) {
      // Replace http://status.example.com/ with your domain
      var system_status_elem = $('<a href="http://status.example.com/"' +
        'target="_blank" class="nav-item-iconic system-status"><span
title="' +
        'System Status" class="fa status-icon pficon-warning-triangle-o">' +
        '</span></a>');

      // Add the extension point to the registry so the badge appears
      // To disable the badge, comment this block out
      extensionRegistry
        .add('nav-system-status', function() {
          return [
            type: 'dom',
            node: system_status_elem
          ];
        });
    }
  ]);

hawtioPluginLoader.addModule('mysystemstatusbadgeextension');
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

### 35.9.4. Project Left Navigation

When navigating within a project, a menu appears on the left with primary and secondary navigation. This menu structure is defined as a constant and can be overridden or modified.



## NOTE

Significant customizations to the project navigation may affect the user experience and should be done with careful consideration. You may need to update this customization in future upgrades if you modify existing navigation items.

```
// Append a new primary nav item. This is a simple direct navigation item
// with no secondary menu.
window.OPENSHIFT_CONSTANTS.PROJECT_NAVIGATION.push({
  label: "Dashboard",           // The text label
  iconClass: "fa fa-dashboard", // The icon you want to appear
  href: "/dashboard"           // Where to go when this nav item is
                                // clicked.
                                // Relative URLs are pre-pended with the
path
                                // '/project/<project-name>'

});

// Splice a primary nav item to a specific spot in the list. This primary
// item has
// a secondary menu.
window.OPENSHIFT_CONSTANTS.PROJECT_NAVIGATION.splice(2, 0, { // Insert at
the third spot
  label: "Git",
  iconClass: "fa fa-code",
  secondaryNavSections: [      // Instead of an href, a sub-menu can be
defined
  {
    items: [
      {
        label: "Branches",
        href: "/git/branches",
        prefixes: [
          "/git/branches/"       // Defines prefix URL patterns that will
cause
                                // this nav item to show the active
state, so
                                // tertiary or lower pages show the
right context
        ]
      }
    ]
  },
  {
    header: "Collaboration",   // Sections within a sub-menu can have an
optional header
    items: [
      {
        label: "Pull Requests",
        href: "/git/pull-requests",
        prefixes: [
          "/git/pull-requests/"
        ]
      }
    ]
  }
}]
```

```

        ]
    }
}
});

// Add a primary item to the top of the list. This primary item is shown
// conditionally.
window.OPENSIFT_CONSTANTS.PROJECT_NAVIGATION.unshift({
    label: "Getting Started",
    iconClass: "pficon pficon-screen",
    href: "/getting-started",
    prefixes: [ // Primary nav items can also specify
prefixes to trigger
        "/getting-started/" // active state
    ],
    isValid: function() { // Primary or secondary items can define
an isValid
        return isNewUser; // function. If present it will be called
to test whether // the item should be shown, it should
return a boolean
    }
});

// Modify an existing menu item
var applicationsMenu =
_.find(window.OPENSIFT_CONSTANTS.PROJECT_NAVIGATION, { label:
'Applications' });
applicationsMenu.secondaryNavSections.push({ // Add a new secondary nav
section to the Applications menu
    // my secondary nav section
});

```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

## 35.10. CONFIGURING FEATURED APPLICATIONS

The web console has an optional list of featured application links in its landing page catalog. These appear near the top of the page and can have an icon, a title, a short description, and a link.



```
// Add featured applications to the top of the catalog.
```

```

window.OPENSIGHT_CONSTANTS.SAAS_OFFERINGS = [
    {
        title: "Dashboard",                                // The text label
        icon: "fa fa-dashboard",                          // The icon you want to
        appear
        url: "http://example.com/dashboard",           // Where to go when this
        item is clicked
        description: "Open application dashboard." // Short description
    },
    {
        title: "System Status",
        icon: "fa fa-heartbeat",
        url: "http://example.com/status",
        description: "View system alerts and outages."
    },
    {
        title: "Manage Account",
        icon: "pficon pficon-user",
        url: "http://example.com/account",
        description: "Update email address or password."
    }
];

```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

## 35.11. CONFIGURING CATALOG CATEGORIES

Catalog categories organize the display of items in the web console catalog landing page. Each category has one or more subcategories. A builder image, template, or service is grouped in a subcategory if it includes a tag listed in the matching subcategory tags, and an item can appear in more than one subcategory. Categories and subcategories only display if they contain at least one item.



### NOTE

Significant customizations to the catalog categories may affect the user experience and should be done with careful consideration. You may need to update this customization in future upgrades if you modify existing category items.

```

// Find the Languages category.
var category =
_.find(window.OPENSIGHT_CONSTANTS.SERVICE_CATALOG_CATEGORIES,
    { id: 'languages' });
// Add Go as a new subcategory under Languages.
category.subCategories.splice(2,0,{ // Insert at the third spot.
    // Required. Must be unique.
    id: "go",
    // Required.
    label: "Go",
    // Optional. If specified, defines a unique icon for this item.
    icon: "icon-go-gopher",
    // Required. Items matching any tag will appear in this subcategory.
    tags: [
        "go",
        "golang"
    ]
});

// Add a Featured category as the first category tab.
window.OPENSIGHT_CONSTANTS.SERVICE_CATALOG_CATEGORIES.unshift({

```

```
// Required. Must be unique.
id: "featured",
// Required
label: "Featured",
subCategories: [
  {
    // Required. Must be unique.
    id: "go",
    // Required.
    label: "Go",
    // Optional. If specified, defines a unique icon for this item.
    icon: "icon-go-gopher",
    // Required. Items matching any tag will appear in this subcategory.
    tags: [
      "go",
      "golang"
    ]
  },
  {
    // Required. Must be unique.
    id: "jenkins",
    // Required.
    label: "Jenkins",
    // Optional. If specified, defines a unique icon for this item.
    icon: "icon-jenkins",
    // Required. Items matching any tag will appear in this subcategory.
    tags: [
      "jenkins"
    ]
  }
]
});
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

## 35.12. CONFIGURING QUOTA NOTIFICATION MESSAGES

Whenever a user reaches a quota, a quota notification is put into the notification drawer. A custom quota notification message, per [quota resource type](#), can be added to the notification. For example:

Your project is over quota. It is using 200% of 2 cores CPU (Limit).  
 Upgrade  
 to <a href='https://www.openshift.com'>OpenShift Online Pro</a> if you  
 need  
 additional resources.

The "Upgrade to..." part of the notification is the custom message and may contain HTML such as links to additional resources.



### NOTE

Since the quota message is HTML markup, any special characters need to be properly escaped for HTML.

Set the `window.OPENSIGHT_CONSTANTS.QUOTA_NOTIFICATION_MESSAGE` property in an extension script to customize the message for each resource.

```
// Set custom notification messages per quota type/key
window.OPENSIGHT_CONSTANTS.QUOTA_NOTIFICATION_MESSAGE = {
  'pods': 'Upgrade to <a href="https://www.openshift.com">OpenShift Online Pro</a> if you need additional resources.',
  'limits.memory': 'Upgrade to <a href="https://www.openshift.com">OpenShift Online Pro</a> if you need additional resources.'
};
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

## 35.13. CONFIGURING THE CREATE FROM URL NAMESPACE WHITELIST

[Create from URL](#) only works with image streams or templates from namespaces that have been explicitly specified in `OPENSIGHT_CONSTANTS.CREATE_FROM_URL_WHITELIST`. To add namespaces to the whitelist, follow these steps:



### NOTE

`openshift` is included in the whitelist by default. Do not remove it.

```
// Add a namespace containing the image streams and/or templates
window.OPENSIGHT_CONSTANTS.CREATE_FROM_URL_WHITELIST.push(
  'shared-stuff'
);
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

## 35.14. DISABLING THE COPY LOGIN COMMAND

The web console allows users to copy a login command, including the current access token, to the clipboard from the user menu and the Command Line Tools page. This function can be changed so that the user's access token is not included in the copied command.

```
// Do not copy the user's access token in the copy login command.
window.OPENSIGHT_CONSTANTS.DISABLE_COPY_LOGIN_COMMAND = true;
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

### 35.14.1. Enabling Wildcard Routes

If you enabled wildcard routes for a router, you can also enable wildcard routes in the web console. This lets users enter hostnames starting with an asterisk like `*.example.com` when creating a route. To enable wildcard routes:

```
window.OPENSIGHT_CONSTANTS.DISABLE_WILDCARD_ROUTES = false;
```

Add the script as described in [Loading Extension Scripts and Stylesheets](#).

[Learn how to configure HAProxy routers to allow wildcard routes.](#)

## 35.15. CUSTOMIZING THE LOGIN PAGE

You can also change the login page, and the login provider selection page for the web console. Run the following commands to create templates you can modify:

```
$ oc adm create-login-template > login-template.html  
$ oc adm create-provider-selection-template > provider-selection-template.html
```

Edit the file to change the styles or add content, but be careful not to remove any required parameters inside the curly brackets.

To use your custom login page or provider selection page, set the following options in the master configuration file:

```
oauthConfig:  
...  
templates:  
  login: /path/to/login-template.html  
  providerSelection: /path/to/provider-selection-template.html
```

Relative paths are resolved relative to the master configuration file. You must restart the server after changing this configuration.

When there are multiple login providers configured or when the [alwaysShowProviderSelection](#) option in the [\*master-config.yaml\*](#) file is set to **true**, each time a user's token to OpenShift Container Platform expires, the user is presented with this custom page before they can proceed with other tasks.

### 35.15.1. Example Usage

Custom login pages can be used to create Terms of Service information. They can also be helpful if you use a third-party login provider, like GitHub or Google, to show users a branded page that they trust and expect before being redirected to the authentication provider.

## 35.16. CUSTOMIZING THE OAUTH ERROR PAGE

When errors occur during authentication, you can change the page shown.

1. Run the following command to create a template you can modify:

```
$ oc adm create-error-template > error-template.html
```

2. Edit the file to change the styles or add content.

You can use the **Error** and **ErrorCode** variables in the template. To use your custom error page, set the following option in the master configuration file:

```
oauthConfig:  
...  
templates:
```

```
error: /path/to/error-template.html
```

Relative paths are resolved relative to the master configuration file.

3. You must restart the server after changing this configuration.

## 35.17. CHANGING THE LOGOUT URL

You can change the location a console user is sent to when logging out of the console by modifying the `clusterInfo.logoutPublicURL` parameter in the `webconsole-config` ConfigMap.

```
$ oc edit configmap/webconsole-config -n openshift-web-console
```

Here is an example that changes the logout URL to <https://www.example.com/logout>:

```
apiVersion: v1
kind: ConfigMap
data:
  webconsole-config.yaml: |
    apiVersion: webconsole.config.openshift.io/v1
    clusterInfo:
      [...]
      logoutPublicURL: "https://www.example.com/logout"
      [...]
```

This can be useful when authenticating with [Request Header](#) and OAuth or [OpenID](#) identity providers, which require visiting an external URL to destroy single sign-on sessions.

## 35.18. CONFIGURING WEB CONSOLE CUSTOMIZATIONS WITH ANSIBLE

During [advanced installations](#), many modifications to the web console can be configured using [the following parameters](#), which are configurable in the inventory file:

- [openshift\\_master\\_logout\\_url](#)
- [openshift\\_web\\_console\\_extension\\_script\\_urls](#)
- [openshift\\_web\\_console\\_extension\\_stylesheet\\_urls](#)
- [openshift\\_master\\_oauth\\_templates](#)
- [openshift\\_master\\_metrics\\_public\\_url](#)
- [openshift\\_master\\_logging\\_public\\_url](#)

### Example Web Console Customization with Ansible

```
# Configure `clusterInfo.logoutPublicURL` in the web console configuration
# See:
https://docs.openshift.com/enterprise/latest/install\_config/web\_console\_customization.html#changing-the-logout-url
#openshift_master_logout_url=https://example.com/logout
```

```
# Configure extension scripts for web console customization
# See:
https://docs.openshift.com/enterprise/latest/install\_config/web\_console\_customization.html#loading-custom-scripts-and-stylesheets
#openshift_web_console_extension_script_urls=
['https://example.com/scripts/menu-customization.js', 'https://example.com/scripts/nav-customization.js']

# Configure extension stylesheets for web console customization
# See:
https://docs.openshift.com/enterprise/latest/install\_config/web\_console\_customization.html#loading-custom-scripts-and-stylesheets
#openshift_web_console_extension_stylesheet_urls=
['https://example.com/styles/logo.css', 'https://example.com/styles/custom-styles.css']

# Configure a custom login template in the master config
# See:
https://docs.openshift.com/enterprise/latest/install\_config/web\_console\_customization.html#customizing-the-login-page
#openshift_master_oauth_templates={'login': '/path/to/login-template.html'}

# Configure `clusterInfo.metricsPublicURL` in the web console configuration for cluster metrics. Ansible is also able to configure metrics for you.
# See:
https://docs.openshift.com/enterprise/latest/install\_config/cluster\_metrics.html
#openshift_master_metrics_public_url=https://hawkular-metrics.example.com/hawkular/metrics

# Configure `clusterInfo.loggingPublicURL` in the web console configuration for aggregate logging. Ansible is also able to install logging for you.
# See:
https://docs.openshift.com/enterprise/latest/install\_config/aggregate\_logging.html
#openshift_master_logging_public_url=https://kibana.example.com
```

# CHAPTER 36. DEPLOYING EXTERNAL PERSISTENT VOLUME PROVISIONERS

## 36.1. OVERVIEW

An external provisioner is an application that enables dynamic provisioning for a particular storage provider. External provisioners can run alongside the provisioner plug-ins provided by OpenShift Container Platform and are configured in a similar way as the ***StorageClass*** objects are configured, as described in the [Dynamic Provisioning and Creating Storage Classes](#) section. Since these provisioners are external, you can deploy and update them independently of OpenShift Container Platform.

## 36.2. BEFORE YOU BEGIN

An [Ansible Playbook](#) is also available to deploy and upgrade external provisioners.



### NOTE

Before proceeding, familiarize yourself with the [Configuring Cluster Metrics](#) and the [Configuring Cluster Logging](#) sections.

### 36.2.1. External Provisioners Ansible Role

The OpenShift Ansible `openshift_provisioners` role configures and deploys external provisioners using the variables from the [Ansible](#) inventory file. You must specify which provisioners to install by overriding their respective `install` variables to `true`.

### 36.2.2. External Provisioners Ansible Variables

Following is a list of role variables that apply to all provisioners for which the `install` variable is `true`.

**Table 36.1. Ansible Variables**

| Variable                                                 | Description                                                                                                                                                 |
|----------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_provisioners_install_provisioners</code> | If <code>true</code> , deploy all provisioners that have their respective <code>install</code> variables set as <code>true</code> , otherwise, remove them. |
| <code>openshift_provisioners_image_prefix</code>         | The prefix for the component images. For example, with <code>openshift3/efs-provisioner:v3.6</code> , set prefix <code>openshift3/</code> .                 |
| <code>openshift_provisioners_image_version</code>        | The version for the component images. For example, with <code>openshift3/efs-provisioner:v3.6</code> , set version as <code>v3.6</code> .                   |
| <code>openshift_provisioners_project</code>              | The project to deploy provisioners in. Defaults to <code>openshift-infra</code> .                                                                           |

### 36.2.3. AWS EFS Provisioner Ansible Variables

The AWS EFS provisioner dynamically provisions [NFS PVs](#) backed by dynamically created directories in a given EFS file system's directory. You must satisfy the following requirements before the AWS EFS Provisioner Ansible variables can be configured:

- An IAM user assigned with the ***AmazonElasticFileSystemReadOnlyAccess*** policy (or better).
- An EFS file system in your cluster's region.
- [Mount targets](#) and [security groups](#) such that any node (in any zone in the cluster's region) can mount the EFS file system by its [File system DNS name](#).

**Table 36.2. Required EFS Ansible Variables**

| Variable                                                      | Description                                                                                     |
|---------------------------------------------------------------|-------------------------------------------------------------------------------------------------|
| <code>openshift_provisioners_efs_fsid</code>                  | The <a href="#">File system ID</a> of the EFS file system, for example: <b>fs-47a2c22e</b>      |
| <code>openshift_provisioners_efs_region</code>                | The Amazon EC2 region for the EFS file system.                                                  |
| <code>openshift_provisioners_efs_aws_access_key_id</code>     | The AWS access key of the IAM user (to check that the specified EFS file system exists).        |
| <code>openshift_provisioners_efs_aws_secret_access_key</code> | The AWS secret access key of the IAM user (to check that the specified EFS file system exists). |

**Table 36.3. Optional EFS Ansible Variables**

| Variable                                             | Description                                                                                                                                                                                                                       |
|------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_provisioners_efs</code>              | If <b>true</b> , the AWS EFS provisioner is installed or uninstalled according to whether <code>openshift_provisioners_install_provisioners</code> is <b>true</b> or <b>false</b> , respectively. Defaults to <b>false</b> .      |
| <code>openshift_provisioners_efs_path</code>         | The path of the directory in the EFS file system, in which the EFS provisioner will create a directory to back each PV it creates. It must exist and be mountable by the EFS provisioner. Defaults to <b>/persistentvolumes</b> . |
| <code>openshift_provisioners_efs_name</code>         | The <b>provisioner</b> name that <b>StorageClasses</b> specify. Defaults to <b>openshift.org/aws-efs</b> .                                                                                                                        |
| <code>openshift_provisioners_efs_nodeselector</code> | A map of labels to select the nodes where the pod will land. For example:<br><code>{"node": "infra", "region": "west"}</code> .                                                                                                   |

| Variable                                                  | Description                                                                                                                             |
|-----------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| <code>openshift_provisioners_efs_supplementalgroup</code> | The supplemental group to give the pod, in case it is needed for permission to write to the EFS file system. Defaults to <b>65534</b> . |

## 36.3. DEPLOYING THE PROVISIONERS

You can deploy all provisioners at once or one provisioner at a time according to the configuration specified in the OpenShift Ansible variables. The following example shows you how to deploy a given provisioner and then create and configure a corresponding *StorageClass*.

### 36.3.1. Deploying the AWS EFS Provisioner

The following command sets the directory in the EFS volume to `/data/persistentvolumes`. This directory must exist in the file system and must be mountable and writeable by the provisioner pod.

```
$ ansible-playbook -v -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
provisioners/config.yml \
    -e openshift_provisioners_install_provisioners=True \
    -e openshift_provisioners_efs=True \
    -e openshift_provisioners_efs_fsid=fs-47a2c22e \
    -e openshift_provisioners_efs_region=us-west-2 \
    -e openshift_provisioners_efs_aws_access_key_id=AKIAIOSFODNN7EXAMPLE \
    -e
    openshift_provisioners_efs_aws_secret_access_key=wJalrXUtnFEMI/K7MDENG/bPx
    RfiCYEXAMPLEKEY \
    -e openshift_provisioners_efs_path=/data/persistentvolumes
```

#### 36.3.1.1. AWS EFS Object Definition

##### aws-efs-storageclass.yaml

```
kind: StorageClass
apiVersion: storage.k8s.io/v1beta1
metadata:
  name: slow
provisioner: openshift.org/aws-efs 1
parameters:
  gidMin: "40000" 2
  gidMax: "50000" 3
```

- 1** Set this value same as the value of `openshift_provisioners_efs_name` variable, which defaults to `openshift.org/aws-efs`.
- 2** The minimum value of GID range for the *StorageClass*. (Optional)
- 3** The maximum value of GID range for the *StorageClass*. (Optional)

Each dynamically provisioned volume's corresponding NFS directory is assigned a unique GID owner

from the range **gidMin-gidMax**. If it is not specified, **gidMin** defaults to **2000** and **gidMax** defaults to **2147483647**. Any pod that consumes a provisioned volume via a claim automatically runs with the needed GID as a supplemental group and is able to read & write to the volume. Other mounters that do not have the supplemental group (and are not running as root) will not be able to read or write to the volume. For more information on using the supplemental groups to manage NFS access, see the [Group IDs](#) section of NFS Volume Security topic.

## 36.4. CLEANUP

You can remove everything deployed by the OpenShift Ansible **openshift\_provisioners** role by running the following command:

```
$ ansible-playbook -v -i <inventory_file> \
    /usr/share/ansible/openshift-ansible/playbooks/openshift-
provisioners/config.yml \
    -e openshift_provisioners_install_provisioners=False
```