Outline	M	I
Lecture 13: Linear Filters III: Detection of Edges and Corners	1 3	2
Contents	5	6
1. Why are Edges Important?	7	8
2. A Baseline Edge Detector	9	10
3. The Canny Edge Detector	11	12
4. Why are Corners Important?	13	14
5. Basics From Linear Algebra	15	16
6. The Structure Tensor		
7. Corner Detection	17	18
	19	20
	21	22
	23	24
© 2020 – 2023 Joachim Weickert, Pascal Peter	25	

#### Recently on IPCV ... Recently on IPCV ... 3 Image derivatives are useful for detecting features such as edges. 5 6 ◆ Differentiation is dangerous. It can be stabilised with a lowpass filter. 7 8 ◆ The weights of the discrete derivative approximations can be computed via a Taylor expansion with subsequent comparision of coefficients. 9 10 The order of consistency can be increased by larger stencils. 11 12 ◆ The continuous Fourier transform allows to analyse the frequency-dependent 13 14 approximation quality. 2D derivative operators should have good rotation invariance. 15 16 Example: Sobel operators. 17 18 19 20 21 22 23 24

Image Processing and Computer Vision 2023	M I
Lecture 13: Linear Filters III: Detection of Edges and Corners	1 2 3 4
Contents	5 6
1. Why are Edges Important?	7 8
2. A Baseline Edge Detector	9 10
3. The Canny Edge Detector	11 12
4. Why are Corners Important?	13 14
5. Basics From Linear Algebra	15 16
6. The Structure Tensor	
7. Corner Detection	17 18
	19 20
	21 22
	23 24
© 2020 – 2023 Joachim Weickert, Pascal Peter	25

#### Why are Edges Important? Why are Edges Important? 3 ◆ A strong change in the grey values within a neighbourhood indicates an edge. 5 For the human visual system, edges 7 8 • provide some of the most relevant image information. This is why we can understand cartoons and use line drawings. 9 10 In computer vision, edges 11 12 belong to the most important image features. 13 14 are assumed to comprise the object boundaries. 15 16 • give a much sparser image representation than the grey values of all pixels. 17 18 • are a first step from a pixel-based image description (low-level vision) to an automised understanding of the image content (high-level vision). 19 20 Edges can be detected with the gradient magnitude. 21 22 23 | 24

	M	
Outline		Α
Lecture 13:	1	2
Linear Filters III: Detection of Edges and Corners	3	4
Contents	5	6
1. Why are Edges Important?	7	8
2. A Baseline Edge Detector	9	10
3. The Canny Edge Detector	11	12
4. Why are Corners Important?	13	14
5. Basics From Linear Algebra	15	16
6. The Structure Tensor		
7. Corner Detection	17	18
	19	20
	21	22
	23	24
© 2020 – 2023 Joachim Weickert, Pascal Peter	25	
	1	

# A Baseline Edge Detector (1)

# A Baseline Edge Detector

• Convolve the initial image f with a Gaussian  $K_{\sigma}$ :

$$u = K_{\sigma} * f$$
.

This stabilises differentiation and makes it more robust under noise.

◆ Compute the gradient magnitude

$$|\nabla u| = \sqrt{(\partial_x u)^2 + (\partial_y u)^2}$$

by approximating the derivatives with Sobel operators (see previous lecture).


• Extract image edges as regions where  $|\nabla u|$  exceeds a certain threshold T.


₩ ₩	A
1	2
3	4
5	6
7	8
9	10
11	12
13	14
15	16
17	18
19	20
21	22
23	24
25	

#### A Baseline Edge Detector (2)









**Top left:** Original image,  $256 \times 256$  pixels. **Top right:** Gradient magnitude of the Gaussian-smoothed image ( $\sigma=1$ ). **Bottom left:** After thresholding with T=10. For better visualisation, values larger or equal than T are depicted in black. **Bottom right:** Same with T=20. Author: J. Weickert.

## A Baseline Edge Detector (3)

#### **Advantage**

◆ The Gaussian convolution offers reasonable robustness against noise.

## Disadvantages

- lacktriangle two parameters: Gaussian standard deviation  $\sigma$ , threshold T
- Some edges may be too thick. Others may be below the threshold.

#### **Remarks**

- A suitable value for T strongly depends on the value of  $\sigma$ : Larger  $\sigma$ -values require smaller T-values.
- Thus, it is convenient to select T as a certain quantile of the histogram of  $|\nabla u|$ .
- Example:

The 0.8 quantile is the smallest number T with  $|\nabla u| \leq T$  for 80 % of all pixels.

3	4
5	6
7	8
9	10
11	12
13	14
15	16
17	18
19	20
21	22
23	24
25	
M	
M 1	Δ
SERE	
1	
3	4
5	6
7	8
9	10
11	12
	14
15	16
17	18
19	20
21	22
23	24
25	

Outline	N	   A
Lecture 13: Linear Filters III: Detection of Edges and Corners	3	2 4
Contents	5	6
1. Why are Edges Important?	7	8
2. A Baseline Edge Detector	9	10
3. The Canny Edge Detector	11	12
4. Why are Corners Important?	13	<b>14</b>
5. Basics From Linear Algebra	15	16
6. The Structure Tensor		+-
7. Corner Detection	1 4	18
	19	20
	21	22
	23	24
© 2020 – 2023 Joachim Weickert, Pascal Peter	25	

The Canny Edge Detector (1)	N	/	I A
The Canny Edge Detector	1	L	2
<ul> <li>popular edge detector with sophisticated postprocessing</li> </ul>	3	3	4
• better than our baseline edge detector	5	5	6
<ul><li>proposed by John Canny in 1986</li></ul>	7	7	8
<ul> <li>still a prototype of a well-performing edge detector</li> </ul>	9	)	10
proceeds in three steps and requires three parameters:	1	1	12
$ullet$ Gaussian standard deviation $\sigma$	1	3	14
$ullet$ two thresholds $T_1$ , $T_2$ (found via two quantiles $q_1$ , $q_2$ )	1	5	16
	1	7	18
	1	9	20
	2	1	22
	2	3	24
	2	5	


## The Canny Edge Detector (2)


#### How Does the Canny Edge Detector Work?

- Gradient Approximation with Gaussian Derivatives:
  - For Gaussian-smoothed image u, compute magnitude  $|\nabla u|$  and orientation angle  $\phi = \arg(\nabla u)$  of  $\nabla u$  (cf. also Lecture 4, polar coordinates).
  - Choose quantiles  $q_1 < q_2$  for  $|\nabla u|$ , find corresponding thresholds  $T_1 < T_2$ . Pixels with  $T_1 \leq |\nabla u| < T_2$  are potential edge pixels. Pixels with  $|\nabla u| > T_2$  are guaranteed edge pixels.
- Nonmaxima Suppression:
  - Goal: thinning of edges to a width of 1 pixel
  - In every pixel with nonzero gradient, consider the grid direction (out of 4 directions) that is "most orthogonal" to the edge.
  - If one of the two neighbours in this direction has a larger gradient magnitude, mark the central pixel for removal.
  - After passing through all candidates, remove marked pixels from edge map.
- ◆ Hysteresis Thresholding (Double Thresholding):
  - Goal: extract relevant edges with long edge contours
  - ullet Use pixels above the upper threshold  $T_2$  as seed points for relevant edges.
  - ullet Add neighbours exceeding lower threshold  $T_1$ . Iterate step for added pixels.


## The Canny Edge Detector (3)

greyscale image









after hysteresis thresholding

Visualisation of the three steps in the Canny edge detection algorithm. From https://en.wikipedia.org/wiki/Canny\_edge\_detector.

3

5

7 8

9 10

11|12

13 14

15|16

17 18

19|20

21|22

23 | 24


## The Canny Edge Detector (4)


original,  $256 \times 256$ 











 $\sigma = 2.5$ 


Influence of the Gaussian standard deviation  $\sigma$ . Larger  $\sigma$ -values give less details and more delocalisations. The thresholds  $T_1$  and  $T_2$  are set to the 0.70 resp. 0.85 quantiles of  $|\nabla u|$ . Author: J. Weickert.


# The Canny Edge Detector (5)

original,  $256 \times 256$ 



0.95 quantile





0.85 quantile



0.75 quantile

Influence of the upper threshold  $T_2$  ( $\sigma=1$ , lower threshold  $T_1$  at 0.7 quantile). With a good value of  $T_2$ , all relevant edges are detected, and irrelevant ones are suppressed. Author: J. Weickert.

M I A 1 2

5

9 10

11|12

13 14

15 16

17 18

19|20

21 | 22

23 24

25

5 6

7 8

11 12

10

13 14

15 16

17 18

19 20


21 22

23 24

# The Canny Edge Detector (6)

original,  $256 \times 256$ 





10

11 12

13 14

15 16


17 18


19 20

21 | 22

23 24

25





 $0.7\ \mathrm{quantile}$ 

 $0.5 \; {\rm quantile}$ 

Influence of the lower threshold  $T_1$  ( $\sigma=1$ , upper threshold  $T_2$  at 0.85 quantile). With a good value for  $T_1$ , edges are neither too short nor too long. Author: J. Weickert.

Outline	M	L
Lecture 13:	1	2
Linear Filters III: Detection of Edges and Corners	3	4
Contents	5	6
1. Why are Edges Important?	7	8
2. A Baseline Edge Detector	9	10
3. The Canny Edge Detector	11	1
4. Why are Corners Important?	13	1
5. Basics From Linear Algebra	 15	10
6. The Structure Tensor		H
7. Corner Detection	17	13
	19	2
	21	2
	23	24
© 2020 – 2023 Joachim Weickert, Pascal Peter	25	

Why are Corners Important ?	M	I A
Why are Corners Important ?	1	2
<ul> <li>Corners are sparser features than edges.</li> </ul>	3	4
They are useful whenever point-like features are preferred over line-like features.	5	6
Corners can help solving correspondence problems in computer vision:	7	8
<ul> <li>finding correspondences in stereo image pairs</li> </ul>	9	10
<ul> <li>matching medical images (so-called registration)</li> </ul>	11	12
Edges would be ambiguous in this context.	13	14
<ul> <li>However, to be able to detect corners, we first</li> </ul>		-
<ul> <li>have to remember some basics from linear algebra,</li> </ul>	15 —	16
• and use them to construct a good detector of the local image structure.	17	18
	19	20
	21	22

Outline	M	I A
Lecture 13:	1	2
Linear Filters III: Detection of Edges and Corners	3	4
Contents	5	6
1. Why are Edges Important?	7	8
2. A Baseline Edge Detector	9	10
3. The Canny Edge Detector	11	12
4. Why are Corners Important?	13	14
5. Basics From Linear Algebra	 15	16
6. The Structure Tensor		
7. Corner Detection	<b>17</b>	18
	19	20
	21	22
	23	24
© 2020 – 2023 Joachim Weickert, Pascal Peter	25	

Basics From Linear Algebra (1)	M I
Basics From Linear Algebra	1 2
What are eigenvalues and eigenvectors?	3 4
• Consider some $n \times n$ matrix $\mathbf{A} \in \mathbb{R}^{n \times n}$ .	5 6
Idea: Find characteristic directions where $m{A}$ acts like a simple rescaling.	7 8
$ullet$ Assume there is a number $\lambda\in\mathbb{C}$ and a vector $m{v}\in\mathbb{R}^n$ , $m{v} eq m{0}$ with $m{A}m{v}=\lambdam{v}$ .	9 10
• Then the scaling factor $\lambda$ is called an <i>eigenvalue</i> ( <i>Eigenwert</i> ) of $\boldsymbol{A}$ .	11 12
ullet The characteristic direction $v$ is its associated eigenvector (Eigenvektor).	13 14
We have to exclude $oldsymbol{v}=oldsymbol{0}$ , since $oldsymbol{A}oldsymbol{0}=\lambdaoldsymbol{0}$ trivially holds for any $\lambda$ .	15 16
◆ A simple way to obtain the sum and product of all eigenvalues.	17 18
<ul> <li>trace (sum of diagonal elements) of a matrix: sum of its eigenvalues</li> </ul>	19 20
• The determinant of a matrix is the product of its eigenvalues.	21 22
	23 24
	25

Basics From Linear Algebra (2)	A
◆ How can we compute eigenvalues?	1 2
• The basic equation $m{A}m{v}=\lambdam{v}$ can be rewritten as $(m{A}-\lambdam{I})m{v}=m{0}.$ Here $m{I}\in\mathbb{R}^{n imes n}$ denotes the unit matrix.	<ul><li>3 4</li><li>5 6</li></ul>
• Eigenvectors are nontrivial solutions $(v \neq 0)$ of $(A - \lambda I) v = 0$ . Thus, the matrix $A - \lambda I$ must be singular. Therefore, its determinant $\det(A - \lambda I)$ must vanish.	<ul><li>5   6</li><li>7   8</li><li>9   10</li></ul>
• This shows how we can find the eigenvalues: Eigenvalues are zeroes of the <i>characteristic polynomial</i> $p(\lambda) := \det(\boldsymbol{A} - \lambda \boldsymbol{I}).$	11 12 13 14
• For $n=2$ , we solve a quadratic equation in $\lambda$ . This case is relevant for us. For $n\geq 3$ , usually numerical algorithms are used. Many methods exist.	15 16
♦ How can we compute eigenvectors?	<ul><li>17 18</li><li>19 20</li></ul>
<ul> <li>Assume we have computed an eigenvalue \(\lambda\).</li> <li>Then we find its eigenvector \(v\) as a nontrivial solution of \((A - \lambda I\)\(v = 0\).</li> </ul>	21 22

• Thus, eigenvectors are only defined up to a nonzero scaling factor.

ullet Often one restricts their norm  $|{m v}|$  to 1 (as we always do in our class).

Basics From Linear Algebra (3)	M	I A
♦ Is there a particularly nice scenario?	1	2
$ullet$ Yes, if $oldsymbol{A} \in \mathbb{R}^{n  imes n}$ is symmetric.	3	4
$ullet$ Then all $n$ eigenvalues of $oldsymbol{A}$ are real-valued.	5	6
$ullet$ One can also find $n$ eigenvectors that create an orthonormal basis of $\mathbb{R}^n$ .	7	8
◆ A frequently used definition.	9	10
• Let a symmetric matrix have only positive (resp. nonnegative) eigenvalues.		
• Then it is called <i>positive definite</i> (resp. <i>positive semidefinite</i> ).	11	
♦ We will need the following result many times:	13	14
• Let $m{A} \in \mathbb{R}^{n  imes n}$ be symmetric. Then $q(m{x}) := m{x}^{ op} m{A} m{x}$ is called its <i>quadratic</i> form.	15 17	
$ullet$ Among all vectors $oldsymbol{x} \in \mathbb{R}^n$ with norm $1$ , $q(oldsymbol{x})$ is maximised (minimised)		
by the eigenvector with the largest (smallest) eigenvalue:	19	20
$\lambda_{min} \; oldsymbol{v}_{min}^{ op} oldsymbol{v}_{min} \; \leq \; oldsymbol{x}^{ op} oldsymbol{A} oldsymbol{x} \; \leq \; \lambda_{max}  oldsymbol{v}_{max}^{ op} oldsymbol{v}_{max} \; .$	21	22

Outline	MI
Lecture 13: Linear Filters III: Detection of Edges and Corners	1 2 3 4
Contents	5 6
1. Why are Edges Important?	7 8
2. A Baseline Edge Detector	9 10
3. The Canny Edge Detector	11 12
4. Why are Corners Important?	13 14
5. Basics From Linear Algebra	15 16
6. The Structure Tensor	
7. Corner Detection	17 18
	19 20
	21 22
	23 24
© 2020 – 2023 Joachim Weickert, Pascal Peter	25

# The Structure Tensor (1) The Structure Tensor 3 **Motivation** 5 6 So far we have analysed edges. 7 8 The gradient information was sufficient to give the local structure information. Now we would like to analyse corners. 9 10 The maximal contrast direction changes strongly in the vicinity around a corner. 11 12 Thus, we need a concept to measure average contrast along a specified direction. 13 14 The averaging should be done over a user-specified scale. 15 16 17 18 19|20 21 | 22

# The Structure Tensor (2)

#### How can We Model This?

- Let us specify a direction by a unit vector n.
- We model *local contrast along* n by the squared directional derivative  $(n^{\top}\nabla u)^2$ . The square guarantees that the sign of the directional derivative does not matter.
- We want a weighted average of this directional contrast in a vicinity of scale  $\rho$ . To this end, we convolve with a Gaussian  $K_{\rho}$  with standard deviation  $\rho$ .
- lacktriangle Thus, the average local contrast in direction n is measured by

$$E(\boldsymbol{n}) = K_{\rho} * ((\boldsymbol{n}^{\top} \nabla u)^{2})$$

$$= K_{\rho} * (\boldsymbol{n}^{\top} \nabla u \nabla u^{\top} \boldsymbol{n})$$

$$= \boldsymbol{n}^{\top} \underbrace{K_{\rho} * (\nabla u \nabla u^{\top})}_{\boldsymbol{n} \times \boldsymbol{n} \text{ matrix}} \boldsymbol{n}.$$

		Ā
	1	2
	3	4
$(\mu)^2$ . ter.	5	6
0.	7	8
	9	10
	11	12
	13	14
	15	16
	17	18
	19	20
	21	22
	23	24
	25	

23 24

# The Structure Tensor (3)

This is a quadratic form with the symmetric matrix

$$\boldsymbol{J}_{\rho}(\boldsymbol{\nabla}\boldsymbol{u}) \; := \; K_{\rho} * (\boldsymbol{\nabla}\boldsymbol{u} \, \boldsymbol{\nabla}\boldsymbol{u}^{\top}) \; = \; \begin{pmatrix} K_{\rho} * (u_{x}^{2}) & K_{\rho} * (u_{x}u_{y}) \\ K_{\rho} * (u_{x}u_{y}) & K_{\rho} * (u_{y}^{2}) \end{pmatrix}.$$

- $J_{\rho}$  is called structure tensor (Strukturtensor) (Förstner/Gülch 1987).
- The standard deviation  $\rho$  of the Gaussian  $K_{\rho}$  determines its locality. It is the scale over which directional information is integrated. Therefore one calls it *integration scale*.

# 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25

3

5

7 | 8

9 10

11|12

13 | 14

15 16

17|18

19 20

21 22

23|24

# The Structure Tensor (4)

#### What Does the Structure Tensor Tell Us?

- We have seen that  $J_{\rho}$  is symmetric. Thus, it has orthonormal eigenvectors  $v_1$ ,  $v_2$  and real-valued eigenvalues  $\lambda_1$ ,  $\lambda_2$ .
- One can even show that  $J_{\rho}$  is positive semidefinite. Let w.l.o.g.  $\lambda_1 \geq \lambda_2 \geq 0$ .
- Our quadratic form  $E(n) = n^{\top} J_{\rho} n$  models the average local contrast along n. Thus, eigenvectors  $v_1$ ,  $v_2$  of  $J_{\rho}$  are directions of largest/smallest local contrast.
- ◆ For these normalised eigenvectors we obtain

$$E(\boldsymbol{v}_i) = \boldsymbol{v}_i^{\top} \boldsymbol{J}_o \boldsymbol{v}_i = \lambda_i \boldsymbol{v}_i^{\top} \boldsymbol{v}_i = \lambda_i.$$

Therefore, eigenvalues  $\lambda_1$ ,  $\lambda_2$  measure average local contrast along  $v_1$ ,  $v_2$ .

◆ The eigenvalues allow to interpret the local image structure:

constant areas:	$\lambda_1 = \lambda_2 = 0$	(no large eigenvalues)
straight edges:	$\lambda_1 \gg \lambda_2 = 0$	(one large eigenvalue)
corners:	$\lambda_1 \geq \lambda_2 \gg 0$	(two large eigenvalues)

Outline	M		
Lecture 13: Linear Filters III: Detection of Edges and Corners	1 3	2	
Contents	5	6	
1. Why are Edges Important?	7	8	;
2. A Baseline Edge Detector	9	10	0
3. The Canny Edge Detector	11	12	2
4. Why are Corners Important?	13	B 14	4
5. Basics From Linear Algebra	15	10	_ 6
6. The Structure Tensor		+	
7. Corner Detection	17	1 18	5
	19	20	0
	21	22	2
	23	3 24	4
© 2020 – 2023 Joachim Weickert, Pascal Peter	25		
	N.		

# Corner Detection (1)

# **Corner Detection**

• Consider a Gaussian-smoothed version  $u = K_{\sigma} * f$  of the original image f. This makes corner detection robust w.r.t. noise/irrelevant small scale features. 3

5

7 | 8

9 10

11|12

13 | 14

15|16

17 18

19 20


21 | 22

23|24

- Compute the structure tensor  $J_{\rho}(\nabla u) = K_{\rho} * (\nabla u \nabla u^{\top})$ . Convolving with  $K_{\rho}$  averages directional information in neighbourhood of scale  $\rho$ .
- Make sure that the integration scale  $\rho$  is larger than the noise scale  $\sigma$ .
- Corners are locations where the structure tensor has two large eigenvalues.
   There are different ways how to detect this.
- ◆ The corner detector of Rohr (1987) is particularly elegant and works well:
  - ullet idea: measure cornerness with  $\det oldsymbol{J}_{
    ho} = j_{1,1} \, j_{2,2} j_{1,2}^2$
  - effective: involves both eigenvalues  $\lambda_1$  and  $\lambda_2$ , since  $\det \boldsymbol{J}_{\rho} = \lambda_1 \lambda_2$ ; only large when both are large (zero at edges where  $\lambda_2 = 0$ )
  - simple: does not even require to compute the eigenvalues explicitly
  - ullet criterion:  $\det oldsymbol{J}_{
    ho}$  must be locally maximal and exceed some threshold T.

#### **Corner Detection (2)**





**Left:** Original image,  $256\times256$  pixels. **Right:** Corners detected with the method of Rohr, using the structure tensor with  $\sigma=2$ ,  $\rho=4$ , and a cornerness threshold of T=100. By adjusting T, one can steer the number of corners. Author: J. Weickert.

# **Corner Detection (3)**

#### **Extensions**

- Besides corners, many other local feature descriptors have been advocated, e.g.
  - SIFT: Scale-Invariant Feature Transform (Lowe 2004)
  - SURF: Speeded Up Robust Features (Bay et al. 2008)
- ◆ They are substantially more advanced and offer higher robustness.
- ◆ These are discussed in more detail in the course Advanced Image Analysis.

21	22
23	24
25	
M	
	A
1	2
3	4
5	6
7	8
9	10
11	12
13	14
15	16
17	18
19	20
21	22
23	24
25	

3

5 | 6

7 | 8

9 10

11 | 12

13 14

15 16

17 18

Summary	M	I A
Summary	1	2
<ul> <li>Gaussian-smoothed derivatives can be used for detecting edges and corners.</li> </ul>	3	4
Edges are locations with large gradient magnitude.	5	6
The Canny filter is one of the best methods for edge detection. It uses nonmaxima suppression and hysteresis thresholding as postprocessing steps.	7	8 10
<ul> <li>The structure tensor allows a robust description of local image structure:</li> <li>Its eigenvectors specify the local structure directions.</li> <li>The eigenvalues give the average contrast in these directions.</li> </ul>	11 13 15	14
<ul> <li>Corners are locations where both eigenvalues of the structure tensor are large.         The determinant of the structure tensor is a simple measure for this.     </li> </ul>	17 19 21 23	22

## References (1)

3

5

7 8

9 10

11 12

13 14

15 16

17 18

19 20

21 | 22

23 24

6

# **References**

- O. Faugeras: Three-Dimensional Computer Vision: A Geometric Viewpoint. MIT Press, Cambridge, MA, 1993.
   (Chapter 4 gives a good and detailed description of edge detection methods.)
- ◆ J. Canny: A computational approach to edge detection. *IEEE Transactions on Pattern Analysis and Machine Intelligence*, Vol. 8, No. 6, pp. 679–698, Nov. 1986. (Canny's original paper)
- H. Anton, C. Rorres, A. Kaul: Elementary Linear Algebra. Applications Version. 12th Edition, Wiley, 2019.
   (thick, but very well readable; also available in German: H. Anton: Lineare Algebra. Spektrum, Heidelberg, 1998.)
- ◆ G. Strang: Introduction to Linear Algebra. Fifth Edition, Wellesley-Cambridge Press, 2016. (excellent linear algebra book; see Section 6.1 for eigenvalues and eigenvectors)
- ◆ W. Förstner, E. Gülch: A fast operator for detection and precise location of distinct points, corners and centres of circular features. *Proc. ISPRS Intercommission Conference on Fast Processing of Photogrammetric Data* (Interlaken, Switzerland, June 1987), pp. 281–305, 1987. (one of the early papers on the structure tensor)
- K. Rohr: Localization properties of direct corner detectors. Journal of Mathematical Imaging and Vision, Vol. 4, 139–150, 1994.
   (compares various corner detectors)

### References (2)

- ◆ E. Trucco, A. Verri: *Introductory Techniques for 3-D Computer Vision*. Prentice Hall, Englewood Cliffs, 1998.
  - (computer vision book dealing also with corner detection)
- ◆ D. G. Lowe: Distinctive image features from scale-invariant keypoints. *International Journal of Computer Vision*, Vol. 60, No. 2, pp. 91-110, 2004. (detailed description of SIFT features)
- H. Bay, A. Ess, T. Tuytelaars, L. Van Gool: SURF: Speeded up robust features. Computer Vision and Image Understanding, Vol. 110, No. 3, pp. 346–359, 2008. (faster alternative to SIFT)

M	I A
1	2
3	4
5	6
7	8
9	10
11	12
13	14
15	16
17	18
19	20
21	22
23	24
25	