

Tutorial 3 Command Line Tools

Htop

An interactive Linux command-line tool that shows running processes in real time.

After using the command “htop” we can see the results as this:

The screenshot shows the htop command-line interface. At the top, there are four small bar charts for CPU cores 0, 1, 2, and 3, each showing 0.0% usage. Below these are memory and swap usage statistics: Mem[|||||] 323M/3.56G and Swp[] 0K/1.00G. The system tasks section shows 6 total processes, 2 threads, and 1 running process. The load average is 0.04 over 1, 0.01 over 5, and 0.00 over 15 minutes. The uptime is 00:00:42. The main table lists 11 processes with columns: PID, USER, PRI, NI, VIRT, RES, SHR, S, CPU%, △MEM%, TIME+, and Command. The processes listed are: 1 root (init), 5 root (plan9 --control-socket), 6 root (plan9 --control-socket), 7 root (init), 8 root (init), 9 root (init), 10 code (-bash), and 21 code (htop). At the bottom, there is a blue footer bar with function keys: F1Help, F2Setup, F3Search, F4Filter, F5Tree, F6SortBy, F7Nice -, F8Nice +, F9Kill, and F10Quit.

Just for your knowledge each terms means:

Field	Meaning
0,1,2,3,..	CPU cores usage (each bar shows activity per core)
Mem	Memory usage (used / total RAM)
Swp	Swap memory usage (used / total swap)
Tasks	Number of processes: total, threads, and how many are running
Load average	System load (last 1, 5, 15 minutes)
Uptime	Time since system boot

Column	Meaning
PID	Process ID (unique number for each process)
USER	The owner of the process

PRI	Priority of the process (lower = higher priority)
NI	Niceness value (affects priority)
VIRT	Virtual memory used by process (total address space)
RES	Resident memory (RAM actually used)
SHR	Shared memory used with other processes
S	Process state (R=Running, S=Sleeping, Z=Zombie, etc.)
CPU%	Percentage of CPU being used by the process
MEM%	Percentage of RAM being used
TIME+	Total CPU time consumed since process started
Command	The command/program that started the process

You can also use the “[top](#)” command to view running processes, but “[htop](#)” is preferred because it provides a clearer interface, easier navigation, and better visualization, making process management more user-friendly.

After running the [top](#) command

```

code@LAPTOP-2ASCEIQV:/m + ~ - □ ×
top - 11:54:17 up 15 min, 0 users, load average: 0.00, 0.00, 0.00
Tasks: 7 total, 1 running, 5 sleeping, 1 stopped, 0 zombie
%Cpu(s): 0.0 us, 0.0 sy, 0.0 ni, 100.0 id, 0.0 wa, 0.0 hi, 0.0 si, 0.0 st
MiB Mem : 3641.9 total, 3190.7 free, 346.1 used, 105.2 buff/cache
MiB Swap: 1024.0 total, 1024.0 free, 0.0 used. 3162.2 avail Mem

PID USER PR NI VIRT RES SHR S %CPU %MEM TIME+ COMMAND
 1 root 20 0 2776 1952 1828 S 0.0 0.1 0:00.01 init(Ubuntu)
 5 root 20 0 2776 4 0 S 0.0 0.0 0:00.00 init
 8 root 20 0 2780 208 80 S 0.0 0.0 0:00.00 SessionLeader
 9 root 20 0 2780 212 80 S 0.0 0.0 0:00.13 Relay(10)
10 code 20 0 6208 5108 3328 S 0.0 0.1 0:00.08 bash
21 code 20 0 5436 4092 3200 T 0.0 0.1 0:01.14 htop
22 code 20 0 7784 3164 2800 R 0.0 0.1 0:00.04 top

```

Some HTOP Commands


(<https://www.geeksforgeeks.org/linux-unix/htop-command-in-linux-with-examples>) :

Option	Description
-d <delay>	Sets the delay between updates (in seconds).
-u <user>	Displays only the processes owned by the specified user.
-p <pid>	Shows only the process with the given process ID(s).
-s <column>	Sorts the process list by the specified column.
-t	Displays processes in a tree view under the commands column.
--no-color	Runs htop in monochrome mode, disabling colors.

1. **-u <user>** : In htop, using -u filters processes by the user name, so only processes owned by that user are displayed.


eg

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar/Downloads/OS$ htop -u code
```



2. **-p <PID>** : used to show only the given PIDs.

Eg. My VIM process has a PID of 45. If I use the command “htop -p 45”, it will display information only about that specific process.



nice/renice

Commands:

- nice [OPTION] [COMMAND [ARG]...]
- renice [-n] priority [-g|-p|-u] identifier..

1. Nice :

E.g.: `nice -10 vim` or `nice -n 10 vim`

Explanation: When you use the `nice` command, the process you start will run with the priority you assign. In this case, we used a nice value of **10**, so the `vim` process will run with Lower priority.

If you want to give a higher priority, you need to write the command as:

`nice -n -10 vim`

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ ps -l
F S   UID    PID   PPID   C PRI   NI ADDR SZ WCHAN TTY          TIME CMD
4 S  1000     10      9  0 80    0 - 1552 do_wai pts/0    00:00:00 bash
0 R  1000     23      10  0 80    0 - 1870 -          pts/0    00:00:00 ps
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ nice -10 vim

[1]+  Stopped                  nice -10 vim
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ ps -l
F S   UID    PID   PPID   C PRI   NI ADDR SZ WCHAN TTY          TIME CMD
4 S  1000     10      9  0 80    0 - 1552 do_wai pts/0    00:00:00 bash
0 T  1000     24      10  1 90  10 - 4580 do_sig pts/0    00:00:00 vim
0 R  1000     25      10  0 80    0 - 1870 -          pts/0    00:00:00 ps
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$
```

2. Renice:

E.g.: `renice 10 -p 47`

Explanation: When you use the `renice` command, you can change the priority (nice value) of an already running process. In this case, we set the nice value to **10** for the process with PID (-p) **47**, so it will run with **lower priority**.

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ ps -l
F S   UID    PID   PPID   C PRI   NI ADDR SZ WCHAN TTY          TIME CMD
4 S  1000     36      35  0 80    0 - 1552 do_wai pts/0    00:00:00 bash
0 T  1000     47      36  3 80  0 - 4580 do_sig pts/0    00:00:00 vim
0 R  1000     49      36  0 80    0 - 1870 -          pts/0    00:00:00 ps
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ exit
logout
There are stopped jobs.
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ renice 10 -p 47
47 (process ID) old priority 0, new priority 10
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ ps -l
F S   UID    PID   PPID   C PRI   NI ADDR SZ WCHAN TTY          TIME CMD
4 S  1000     36      35  0 80    0 - 1552 do_wai pts/0    00:00:00 bash
0 T  1000     47      36  0 90  10 - 4580 do_sig pts/0    00:00:00 vim
0 R  1000     51      36  0 80    0 - 1870 -          pts/0    00:00:00 ps
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$
```

If you want to give a higher priority, you need to write the command as:

```
sudo renice -10 -p 47
```

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ renice -10 -p 47
renice: failed to set priority for 47 (process ID): Permission denied
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ sudo renice -10 -p 47
[sudo] password for code:
47 (process ID) old priority 10, new priority -10
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ ps -l
F S   UID   PID  PPID  C PRI  NI ADDR SZ WCHAN TTY          TIME CMD
4 S  1000    36    35  0 80   0 - 1552 do_wai pts/0    00:00:00 bash
0 T  1000    47    36  0 70 -10 - 4580 do_sig pts/0    00:00:00 vim
0 R  1000    56    36  0 80   0 - 1870 -           pts/0    00:00:00 ps
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$
```

Note: `nice` is used when starting a process, while `renice` is used to change the priority of an already running process. And we use `sudo` to change a process to a higher priority because lowering the nice value, e.g., `-10`, requires superuser privileges.

Chrt

(<https://www.geeksforgeeks.org/linux-unix/chrt-command-in-linux-with-examples/>)

- `chrt [options] priority` command argument ...
- `chrt [options] -p [priority] PID`

1. To see the maximum and minimum priority of a scheduling policy, we use:

```
chrt -m
```

You can see that the priorities of `SCHED_FIFO` and `SCHED_RR` are

available in the range 1–99, while the others show `0/0`, which means they do not use priority values.

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ chrt -m
SCHED_OTHER min/max priority : 0/0
SCHED_FIFO min/max priority  : 1/99
SCHED_RR min/max priority   : 1/99
SCHED_BATCH min/max priority : 0/0
SCHED_IDLE min/max priority : 0/0
SCHED_DEADLINE min/max priority : 0/0
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$
```

2. **chrt -p <PID of the process>** To see the scheduling policy of a process eg:

```
chrt -p 47
```

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ ps -l
F S   UID   PID  PPID  C PRI  NI ADDR SZ WCHAN TTY          TIME CMD
4 S  1000    36    35  0 80   0 - 1552 do_wai pts/0    00:00:00 bash
0 T  1000    47    36  0 70 -10 - 4580 do_sig pts/0    00:00:00 vim
0 R  1000    71    36  0 80   0 - 1870 -           pts/0    00:00:00 ps
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ chrt -p 47
pid 47's current scheduling policy: SCHED_OTHER
pid 47's current scheduling priority: 0
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ chrt -p 36
pid 36's current scheduling policy: SCHED_OTHER
pid 36's current scheduling priority: 0
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$
```

chrt -p 36

3. To change the scheduling policy or priority of a process, we use:

`sudo chrt -<policy> -p <priority> <PID>` (for only FIFO and RR priority is 1/99)

Here are various scheduling policies, and we use the following options with `chrt` to set them:

- `-f` : **SCHED_FIFO** (First-In-First-Out)
- `-b` : **SCHED_BATCH**
- `-i` : **SCHED_IDLE**
- `-r` : **SCHED_RR** (Round Robin)
- `-o` : **SCHED_OTHER** (default policy)

Eg 1. `sudo chrt -b -p 0 122`

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ ps -l
F S   UID    PID  PPID   C PRI  NI ADDR SZ WCHAN TTY          TIME CMD
4 S  1000    111  110  0  80  0 - 1552 do_wai pts/0    00:00:00 bash
0 T  1000  122  111  0  80  0 - 4580 do_sig pts/0    00:00:00 vim
0 R  1000    125  111  0  80  0 - 1870 -      pts/0    00:00:00 ps
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ chrt -p 122
pid 122's current scheduling policy: SCHED_OTHER
pid 122's current scheduling priority: 0
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ sudo chrt -b -p 0 122
[sudo] password for code:
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ chrt -p 122
pid 122's current scheduling policy: SCHED_BATCH
pid 122's current scheduling priority: 0
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$
```

Eg 2. `sudo chrt -f -p 3 122` (Note: Since the scheduling policy is **FIFO**, the priority must be set between **1 and 99**.)

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ chrt -p 122
pid 122's current scheduling policy: SCHED_BATCH
pid 122's current scheduling priority: 0
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ sudo chrt -f -p 3 122
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$ chrt -p 122
pid 122's current scheduling policy: SCHED_FIFO
pid 122's current scheduling priority: 3
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar$
```

C Library Functions:

The C program demonstrates Linux process scheduling functions. It retrieves a process's scheduling policy and priority using `sched_getscheduler` and `sched_getparam`. Then, it attempts to change the process's priority (`sched_setparam`) and scheduling policy to real-time FIFO (`sched_setscheduler`). By default, processes run under `SCHED_OTHER` with priority 0. Changing to real-time policies requires root privileges, while priority changes only apply to FIFO or RR policies.

```
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar/Downloads/OS$ gcc sched_setscheduler.c -o sched_setscheduler
code@LAPTOP-2ASCEIQV:/mnt/c/Users/Gautam Kumar/Downloads/OS$ sudo ./sched_setscheduler
[sudo] password for code:
No PID given, using self (PID=79)
Current policy: SCHED_OTHER
Current priority: 0
sched_setparam failed: Invalid argument
Policy changed to: SCHED_FIFO
After changes → Policy: SCHED_FIFO, Priority: 1
```