
vCloud Director 5.5

This document supports the version of each product listed and supports all subsequent versions until the document is replaced by a new edition. To check for more recent editions of this document, see http://www.vmware.com/support/pubs.

EN-001257-01





VMware, Inc. 3401 Hillview Ave. Palo Alto, CA 94304 www.vmware.com

Contents

	vCloud Director User's Guide 7
	Updated Information 9
1	Getting Started with vCloud Director 11
	Understanding VMware vCloud Director 11
	Log In to the Web Console 12
	Using vCloud Director 12
	Set Mozilla Firefox Options 13
	Set Microsoft Internet Explorer Options 14
	Set User Preferences 15
	Change Your Password 16
2	Managing Cloud Resources 17
	Managing Virtual Datacenters 17
	Managing Organization Virtual Datacenter Networks 18
	Managing Expired Items 30
2	Working in an Organization 21
3	Working in an Organization 31
	Understanding Leases 31
	Set Up an Organization 32
	Review Your Organization Profile 34 Modify Your Email Settings 35
	Modify Your Organization's Policies 35
	Set Detault Domain for Organization Virtual Machines 36 Enable Your Organization to Use an SAML Identity Provider 36
	Install Java Cryptography Extension Unlimited Strength Jurisdiction Policy Files 37
	Manage Users and Groups in Your Organization 38
	Manage Resources in Your Organization 38
	Manage Virtual Machines in Your Organization 38
	Viewing Organization Log Tasks and Events 39
4	Working with Catalogs 41
	Add a New Catalog 42
	Access a Catalog 43
	Share A Catalog 43
	Publish a Catalog to an External Organization 44
	Change the Owner of a Catalog 45
	Delete a Catalog 45
	Change the Properties of Your Catalog 45
	Subscribe to an External Catalog Feed 46

Understanding Catalogs and Their Contents 46 Working in Published Catalogs 47

5 Working with Media Files 49

Upload Media Files 49

Resume the Upload of a Media File 50

Copy Media Files to a Catalog 50

Move Media Files to Another Catalog 50

Delete Media Files 51

Modify Media File Properties 51

6 Working with vApp Templates 53

Open a vApp Template 53

Add a vApp Template to My Cloud 54

Download a vApp Template 54

Upload an OVF Package as a vApp Template 55

Resume the Upload of a vApp Template 56

Copy a vApp Template from a Public Catalog to an Organization Catalog 56

Copy a vApp Template Between an Organization's Catalogs 57

Move a vApp Template Between an Organization's Catalogs 57

Delete a vApp Template 57

Save a vApp as a vApp Template 58

Modify vApp Properties 58

Change the Guest OS Properties of a vApp Template 59

7 Working with vApps 61

Create a vApp From a vApp Template 62

Create a New vApp 62

Import a Virtual Machine as a vApp 64

Create a vApp From an OVF Package 64

About the vApp Placement Engine 65

Download a vApp as an OVF Package 66

Start a vApp 67

Start a vApp with an Older Version of VMware Tools 67

Stop a vApp 67

Suspend a vApp 68

Discard the Suspended State of a vApp 68

Reset a vApp or Virtual Machine 68

View vApp Virtual Machines 68

Add a Virtual Machine to a vApp 69

Import a Virtual Machine to a vApp from vSphere 69

Remove Virtual Machines from a vApp 70

Set vApp Start and Stop Options 70

Working with Networks in a vApp 71

Editing vApp Properties 83

Display a vApp Diagram 85

Change the Owner of a vApp 85

Upgrade the Virtual Hardware Version for a vApp 85

Save vApp as a vApp Template to Your Catalog 86
Save a Powered-On vApp to your Catalog 86
Create a Snapshot of a vApp 87
Revert a vApp to a Snapshot 87
Remove a Snapshot of a vApp 87
Copy a vApp to Another Virtual Datacenter 88
Copy a Powered-On vApp 88
Move a vApp to Another Virtual Datacenter 89
Delete a vApp 89

8 Working with Virtual Machines 91

Open a Virtual Machine Console 92

Power On a Virtual Machine 92

Power Off a Virtual Machine 92

Reset a vApp or Virtual Machine 93

Suspend a Virtual Machine 93

Resume a Suspended Virtual Machine 93

Discard the Suspended State of a Virtual Machine 93

Insert a CD/DVD 94

Eject a CD/DVD 94

Insert a Floppy 94

Eject a Floppy 95

Upgrade the Virtual Hardware Version for a Virtual Machine 95

Connect Remotely to a Virtual Machine 95

Create a Snapshot of a Virtual Machine 96

Revert a Virtual Machine to a Snapshot 96

Remove a Snapshot of a Virtual Machine 96

Copy or Move a Virtual Machine to a vApp 96

Delete a Virtual Machine 97

Editing Virtual Machine Properties 97

Installing VMware Tools 104

Guest Operating Systems 114

Index 121

The *VMware vCloud Director User's Guide* provides information about managing organizations, catalogs, vApps, and virtual machines.

Intended Audience

This book is intended for anyone who wants to set up and configure organizations in VMware vCloud Director. The information in this book is written for non-system administrators, including organization administrators who will create and set up vApps, catalogs, and virtual machines.

Updated Information

This $vCloud\ Director\ User's\ Guide$ is updated with each release of the product or when necessary.

This table provides the update history of the *vCloud Director User's Guide*.

Revision	Description	
001257-01	 Removed outdated table information in "Guest Operating System Support," on page 119. Corrected the procedure in "Share A Catalog," on page 43. 	
001257-00	Initial release.	

Getting Started with vCloud Director

1

When you log in to the vCloud Director Web console, the **Home** tab provides access to your resources and links to common tasks.

You can also set your user preferences and view the product help.

This chapter includes the following topics:

- "Understanding VMware vCloud Director," on page 11
- "Log In to the Web Console," on page 12
- "Using vCloud Director," on page 12
- "Set Mozilla Firefox Options," on page 13
- "Set Microsoft Internet Explorer Options," on page 14
- "Set User Preferences," on page 15
- "Change Your Password," on page 16

Understanding VMware vCloud Director

VMware[®] vCloud Director provides role-based access to a Web console that allows the members of an organization to interact with the organization's resources to create and work with vApps and virtual machines.

Before you can access your organization, a vCloud Director system administrator must create the organization, assign it resources, and provide the URL to access the Web console. Each organization includes one or more organization administrators, who finishes setting up the organization by adding members and setting policies and preferences. After the organization is set up, non-administrator users can log in to create, use, and manage virtual machines and vApps.

Organizations

An organization is a unit of administration for a collection of users, groups, and computing resources. Users authenticate at the organization level, supplying credentials established by an organization administrator when the user was created or imported. System administrators create and provision organizations, while organization administrators manage organization users, groups, and catalogs.

Users and Groups

An organization can contain an arbitrary number of users and groups. Users can be created locally by the organization administrator or imported from a directory service such as LDAP. Groups must be imported from the directory service. Permissions within an organization are controlled through the assignment of rights and roles to users and groups.

Virtual Datacenters

An organization virtual datacenter provides resources to an organization. Virtual datacenters provide an environment where virtual systems can be stored, deployed, and operated. They also provide storage for virtual media, such as floppy disks and CD ROMs. An organization can have multiple virtual datacenters.

Organization Virtual Datacenter Networks

An organization virtual datacenter network is contained within a vCloud Director organization virtual datacenter and is available to all the vApps in the organization. An organization virtual datacenter network allows vApps within an organization to communicate with each other. An organization virtual datacenter network can be connected to an external network or isolated and internal to the organization. Only system administrators can create organization virtual datacenter networks, but organization administrators can manage organization virtual datacenter networks, including the network services they provide.

vApp Networks

A vApp network is contained within a vApp and allows virtual machines in the vApp to communicate with each other. You can connect a vApp network to an organization virtual datacenter network to allow the vApp to communicate with other vApps in the organization and outside of the organization, if the organization virtual datacenter network is connected to an external network.

Catalogs

Organizations use catalogs to store vApp templates and media files. The members of an organization that have access to a catalog can use the catalog's vApp templates and media files to create their own vApps. Organizations administrators can copy items from public catalogs to their organization catalog.

Log In to the Web Console

Use the organization URL to log in to your organization and access the Web console.

Contact your organization administrator if you do not know the organization URL.

Procedure

- In a browser, type the URL of your organization and press Enter.
 For example, type https://cloud.example.com/cloud/org/myOrg.
- 2 Type your user name and password and click **Login**. .

What to do next

The Web console displays a list of the common tasks and resources available to you based on your role. An organization administrator can click the **Set up this organization** link on the **Home** tab to finish setting up a newly created organization. See "Set Up an Organization," on page 32 for more information.

Using vCloud Director

When you log into vCloud Director, the first page you see is the Home page. The information that appears on this page are the most common tasks for your role.

Organization administrators see the **Set up this organization** link as their first task. They also see tasks under these headings.

- Organizations and resources
- Content

■ Users & Groups

The vApps in your organization are displayed for easy access.

Catalog authors see links to these tasks.

- Add Cloud Computer System
- Build new vApp
- Manage Catalogs
- New Catalog

vApp authors see links to these tasks.

- Add Cloud Computer System
- Build new vApp

vApp users see links to these tasks.

■ Add Cloud Computer System

The vApps in your organization are displayed for easy access.

Console Access Only users have a read-only access to vCloud Director.

Set Mozilla Firefox Options

These options and settings help you display and use the vCloud Director Web console in Mozilla Firefox.

Prerequisites

You have the following.

- At least Firefox 3.x
- SSL 3.0 Encryption
- TLS 1.0 Encryption

Procedure

- 1 In Firefox, select **Tools > Options**.
- 2 Click **Content** and select the **JavaScript** check box.
- 3 Click Privacy.
- 4 In the Firefox will: drop-down menu, select Use custom settings for history.
- 5 Select the Accept cookies from sites.

This selection also selects the **Accept third-party cookies** check box.

6 Click **OK**.

Bypass the Proxy in Mozilla Firefox

You can configure the Firefox proxy server to bypass certain Web addresses.

If all of these conditions exist, you can configure Firefox to bypass specific Web addresses.

- The internal network is configured with a proxy server to access the external network.
- The browser's proxy server connection has no local exceptions.
- The proxy is not configured to look in the internal network after not finding or connecting to the target on the external network.

The user looks for a target on the internal network using Firefox.

Procedure

1 Select an option.

Operating System	Action
Windows	Tools > Options
Linux	Edit > Preferences

- 2 Click the **Advanced** button.
- 3 On the **Network** tab, click the **Settings** button.
- Enter the IP of the cell or load balancer in the **No Proxy for:** field.

The specified Web addresses are bypassed by the Firefox proxy server.

Set Microsoft Internet Explorer Options

These options help you display and use the vCloud Director Web console in Microsoft Internet Explorer.

You have the following.

- At least Internet Explorer 7.
- SSL 3.0 Encryption
- TLS 1.0 Encryption

Procedure

- 1 In Internet Explorer, select **Tools > Internet Options**.
- 2 Click the Security tab.
- 3 Select the **Internet content** zone for the vCloud Director server.
- 4 Click **Custom Level** and select **Enable** or **Prompt** for these options.
 - Download signed ActiveX controls
 - Run ActiveX controls and plug-ins
 - Allow META REFRESH
 - Active scripting of Microsoft web browser control
- 5 Click **OK**.
- 6 Click the **Advanced** tab.
- 7 If you are using Internet Explorer on Windows 2003, complete these tasks.
 - a Select Start > Settings > Control Panel.
 - b Select Add or Remove Programs.
 - c Click Add/Remove Windows Components.
 - d Disable Internet Explorer Enhanced Security Configuration.

Bypass the Proxy in Internet Explorer

You can configure the Internet Explorer proxy server to bypass certain Web addresses.

If all of these conditions exist, you can configure Internet Explorer to bypass specific Web addresses.

- The internal network is configured with a proxy server to access the external network.
- The browser's proxy server connection has no local exceptions.
- The proxy is not configured to look in the internal network after not finding or connecting to the target on the external network.
- The user looks for a target on the internal network using Internet Explorer.

Procedure

- Type the IP address of the cell or load balancer so that VMware Remote Console (VMRC) can bypass the proxy setting.
- 2 Select **Tools** > **Internet Options**.
- 3 On the **Connections** tab, click **LAN Settings** in the bottom panel.
- 4 In the Proxy Server panel, click **Advanced**.
- 5 In the Exception panel, in the **Do not use proxy server for addresses beginning with:** text box, type the IP address of the cell or load balancer.
 - If the configuration management vehicle supports the use of regular expressions, you must type the DNS name of the cell or load balancer.
- 6 Click **OK**.

The specified Web addresses are bypassed by the Internet Explorer proxy server.

Set User Preferences

You can set certain display and system alert preferences that take effect every time you log in to the system. You can also change the password for your system administrator account.

Procedure

- 1 In the title bar of the Web console, click **Preferences**.
- 2 Click the **Defaults** tab.
- 3 Select the page to display when you log in.
- 4 Select the number of days or hours before a runtime lease expires that you want to receive an email notification.
- 5 Select the number of days or hours before a storage lease expires that you want to receive an email notification.
- 6 Click the **Change Password** tab.
- 7 (Optional) Type your current password and type your new password twice.
- 8 Click OK.

Change Your Password

If you have a local user account, you can change your password.

Procedure

- 1 Log in to your organization.
- 2 In the title bar of the Web console, click **Preferences**.
- On the **Change Password** tab, type your current password, type your new password, and retype your new password.
- 4 Click **OK**.

vCloud Director logs you out.

What to do next

Log in using your new password.

Managing Cloud Resources

A vCloud Director system administrator creates and assigns virtual datacenters and networks to an organization. An organization administrator can view information about these resources and perform a limited set of management tasks. Contact your system administrator if you need more organization virtual datacenters or organization virtual datacenter networks..

This chapter includes the following topics:

- "Managing Virtual Datacenters," on page 17
- "Managing Organization Virtual Datacenter Networks," on page 18
- "Managing Expired Items," on page 30

Managing Virtual Datacenters

Virtual datacenters provide processor, memory, and storage resources to your organization. They are assigned to your organization by your system administrator. An organization can have multiple virtual datacenters.

Display Virtual Datacenters

When you display the virtual datacenters in your organization, you can monitor the resources, users, and policy settings that you manage.

You are an organization administrator.

Procedure

- 1 Click **Administration**.
- 2 In the left pane, select **Cloud Resources** > **Virtual Datacenters**.
 - A list of virtual datacenters in your organization appears in the right pane.
- 3 For details about a virtual datacenter, right-click, and select Open.

The vApps, vApp templates, media, and networks attached to this virtual datacenter are displayed. When you click through each tab, you can right click on an object to see the operations you can complete.

Review Virtual Datacenter Properties

You can review the properties of the virtual datacenters that are assigned to your organization.

Procedure

1 Click **Administration**.

- 2 Select Cloud Resources > Virtual Datacenters.
- 3 Select a virtual datacenter, right-click, and select **Properties**.
- 4 Review the properties and click **OK**.

What to do next

To modify your organizational virtual datacenters, contact your system administrator.

Monitor Your Virtual Datacenter

You can monitor the virtual datacenter assigned to your organization and determine when to request additional capacity.

You are an organization administrator.

Procedure

- 1 Click **Administration**.
- 2 Select Cloud Resources > Virtual Datacenters.
- 3 Click the **Monitor** button.

Details about the processor, memory, storage, and allocation model appear.

What to do next

Contact your system administrator for more capacity.

Manage Your Virtual Datacenters

You can review information such as the status, allocation model, and the number of vApps in a virtual datacenter in your organization.

You are an organization administrator

Procedure

- 1 Click **Administration**.
- 2 In the left pane, select Cloud Resources > Virtual Datacenters.
- 3 Click the Manage button.
- 4 Review the information.

What to do next

You can open the virtual datacenter to see the objects in it, notify users about issues or changes, or review the virtual datacenter's properties. Contact your system administrator to make changes to your virtual datacenter.

Managing Organization Virtual Datacenter Networks

Organization virtual datacenter networks are created and assigned to your organization virtual datacenter by a system administrator. An organization administrator can view information about networks, configure network services, and more.

You can use direct, routed, or internal organization virtual datacenter networks.

Table 2-1. Types of Organization Virtual Datacenter Networks

Organization Virtual Datacenter Network Type	Description			
Direct	Accessible by multiple organizations. Virtual machines belonging to different organizations can connect to and see traffic on this network.			
	This network provides direct layer 2 connectivity to virtual machines outside of the organization. Virtual machines outside of this organization can connect to virtual machines in the organization directly.			
Routed	Accessible only by this organization. Only virtual machines in this organization can connect to this network.			
	This network also provides controlled access to an external network. System administrators and organization administrators can configure network address translation (NAT), firewall, and VPN settings to make specific virtual machines accessible from the external network.			
Internal	Accessible only by this organization. Only virtual machines in this organization can connect to and see traffic on this network.			
	This network provides an organization with an isolated, private network that multiple vApps can connect to. This network provides no connectivity to machines outside this organization. Machines outside of this organization have no connectivity to machines in the organization.			

Configuring Oganization Virtual Datacenter Network Services

An organization administrator can configure services, such as DHCP, firewalls, network address translation (NAT), VPN, and static routing for certain organization virtual datacenter networks.

The network services available depend on the type of organization virtual datacenter network.

Table 2-2. Network Services Available by Network Type

Organization Virtual Datacenter Network Type	DHCP	Firewall	NAT	VPN	Static Routing
Direct					
Routed	X	X	X	Х	X
Internal	X				

Configure DHCP for an Organization Virtual Datacenter Network

Organization administrators can configure certain organization virtual datacenter networks to provide DHCP services to virtual machines in the organization.

When you power on a virtual machine with the following configuration, vCloud Director assigns a DHCP IP address to that virtual machine.

- A NIC connected to an organization virtual datacenter network that has DHCP enabled.
- The IP mode for the connected NIC set to **DHCP**.

Prerequisites

Verify that you have a routed organization virtual datacenter network or an internal organization virtual datacenter network.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the **Org VDC Networks** tab, right-click the organization virtual datacenter network name and select **Configure Services**.

- 3 Select Enable DHCP.
- 4 Type a range of IP addresses or use the default range.
 vCloud Director uses these addresses to satisfy DHCP requests. The range of DHCP IP addresses cannot overlap with the static IP pool for the organization virtual datacenter network.
- 5 Set the default lease time and maximum lease time or use the default values.
- 6 Click OK.

vCloud Director updates the network to provide DHCP services.

Configure the Firewall for an Organization Virtual Datacenter Network

An organization administrator can configure certain organization virtual datacenter networks to provide firewall services. Enable the firewall on an organization virtual datacenter network to enforce firewall rules on incoming traffic, outgoing traffic, or both.

When you enable the firewall, you can specify a default firewall action to deny all incoming and outgoing traffic or to allow all incoming and outgoing traffic. You can also add specific firewall rules to allow or deny traffic that matches the rules to pass through the firewall. These rules take precedence over the default firewall action. See "Add a Firewall Rule to an Organization Virtual Datacenter Network," on page 20.

If a system administrator specified syslog server settings and those settings were applied to the organization virtual datacenter network, then you can log events related to the default firewall action. For information about applying syslog server settings, see "Apply Syslog Server Settings to an Organization Virtual Datacenter Network," on page 29. To view the current syslog server settings see "View Syslog Server Settings for an Organization Virtual Datacenter Network," on page 29.

Prerequisites

Verify that a routed organization virtual datacenter network is in place.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the **Org VDC Networks** tab, right-click the organization virtual datacenter network name, and select **Configure Services**.
- 3 Click the Firewall tab and select Enable firewall to enable firewall services, or deselect it to disable firewall services.
- 4 Select the default firewall action.

Option	Description		
Deny	Blocks all traffic except when overridden by a firewall rule.		
Allow	Allows all traffic except when overridden by a firewall rule.		

- 5 (Optional) Select the **Log** check box to log events related to the default firewall action.
- 6 Click **OK**.

Add a Firewall Rule to an Organization Virtual Datacenter Network

An organization administrator can add firewall rules to an organization virtual datacenter network that supports a firewall. You can create rules to allow or deny traffic that matches the rules to pass through the firewall.

When you add a new firewall rule to an organization virtual datacenter network, it appears at the bottom of the firewall rule list. For information about how to set the order in which firewall rules are enforced, see "Reorder Firewall Rules for an Organization Virtual Datacenter Network," on page 22.

If a system administrator specified syslog server settings and those settings have been applied to the organization virtual datacenter network, then you can log firewall rule events. For information about applying syslog server settings, see "Apply Syslog Server Settings to an Organization Virtual Datacenter Network," on page 29. To view the current syslog server settings see "View Syslog Server Settings for an Organization Virtual Datacenter Network," on page 29.

Prerequisites

Verify that you have a routed organization virtual datacenter network and enable the firewall for the organization virtual datacenter network. See "Configure the Firewall for an Organization Virtual Datacenter Network," on page 20

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 On the **Org VDC Networks** tab, right-click the organization virtual datacenter network name and select **Configure Services**.
- 3 Click the **Firewall** tab and click **Add**.
- 4 Type a name for the rule.
- 5 (Optional) Select **Match rule on translated IP** to have the rule check against translated IP addresses rather than original IP addresses and choose a traffic direction to apply this rule on.
- 6 Type the traffic **Source**.

Option	Description	
IP address Type a source IP address to apply this rule on.		
Range of IP addresses	Type a range of source IP addresses to apply this rule on.	
CIDR Type the CIDR notation of traffic to apply this rule on.		
internal	Apply this rule to all internal traffic.	
external	Apply this rule to all external traffic.	
any	Apply this rule to traffic from any source.	

- 7 Select a **Source port** to apply this rule on from the drop-down menu.
- 8 Type the traffic **Destination**.

Option	Description	
IP address Type a destination IP address to apply this rule on.		
Range of IP addresses Type a range of destination IP addresses to apply this rule on.		
CIDR Type the CIDR notation of traffic to apply this rule on.		
internal Apply this rule to all internal traffic.		
external	Apply this rule to all external traffic.	
any	Apply this rule to traffic with any destination.	

- 9 Select the **Destination port** to apply this rule on from the drop-down menu.
- 10 Select the **Protocol** to apply this rule on from the drop-down menu.
- 11 Select the action.
 - A firewall rule can allow or deny traffic that matches the rule.
- 12 Select the **Enabled** check box.

13 (Optional) Select the **Log network traffic for firewall rule** check box.

If you enable this option, vCloud Director sends log events to the syslog server for connections affected by this rule. Each syslog message includes logical network and organization UUIDs.

14 Click OK and click OK again.

Reorder Firewall Rules for an Organization Virtual Datacenter Network

Firewall rules are enforced in the order in which they appear in the firewall list. An organization administrator can change the order of the rules in the list.

When you add a firewall rule to an organization virtual datacenter network, the new rule appears at the bottom of the firewall rule list. To enforce the new rule before an existing rule, reorder the rules.

Prerequisites

Verify that a routed organization virtual datacenter network with two or more firewall rules is in place.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the **Org VDC Networks** tab, right-click the organization virtual datacenter network name, and select **Configure Services**.
- 3 Click the Firewall tab.
- 4 Drag the firewall rules to establish the order in which the rules are applied.
- 5 Click OK.

Enable VPN for an Organization Virtual Datacenter Network

An organization administrator can enable VPN for an organization virtual datacenter network, then create a secure tunnel to another network.

vCloud Director supports VPN between organization virtual datacenter networks in the same organization and remote networks.

Prerequisites

Verify that you have a routed organization virtual datacenter network.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the **Org VDC Networks** tab, right-click the organization virtual datacenter network name, and select **Configure Services**.
- 3 Click the **VPN** tab and select **Enable VPN**.
- 4 (Optional) Type a public IP address.
- 5 Click OK.

What to do next

Create a VPN tunnel to another network.

Create a VPN Tunnel In an Organization

An organization administrator can create a VPN tunnel between two organization virtual datacenter networks in the same organization.

If the tunnel endpoints have a firewall between them, configure the firewall to allow the following IP protocols and UDP ports:

- IP Protocol ID 50 (ESP)
- IP Protocol ID 51 (AH)
- UDP Port 500 (IKE)
- UDP Port 4500

Prerequisites

Verify that you have at least two routed organization virtual datacenter networks with nonoverlapping IP subnets and VPN enabled on both networks.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the **Org VDC Networks** tab, right-click the organization virtual datacenter network name, and select **Configure Services**.
- 3 Click the **VPN** tab and click **Add**.
- 4 Type a name and optional description.
- 5 Select a network in this organization from the drop-down menu and select a peer network.
- 6 Review the tunnel settings and click OK.

vCloud Director configures both peer network endpoints.

Create a VPN Tunnel Between Organizations

An organization administrator can create a VPN tunnel between two organization virtual datacenter networks in different organizations. The organizations can be part of the same vCloud Director installation or a different installation.

Prerequisites

Verify that you have a routed organization virtual datacenter network in each of the organizations. The organization virtual datacenter networks must have IP subnets that do not overlap and a site-to-site VPN enabled.

If the tunnel endpoints have a firewall between them, you must configure it to allow the following IP protocols and UDP ports:

- IP Protocol ID 50 (ESP)
- IP Protocol ID 51 (AH)
- UDP Port 500 (IKE)
- UDP Port 4500

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the **Org VDC Networks** tab, right-click the organization virtual datacenter network name, and select **Configure Services**.

- 3 Click the **VPN** tab and click **Add**.
- 4 Type a name and optional description.
- 5 Select **A network in another organization** from the drop-down menu.
- 6 Click Connect to another organization, type the login information for the peer organization, and click Continue.

Option	Description
vCloud URL	Base URL of the vCloud instance that contains the peer organization. For example, https://www.example.com. Do not include /cloud or /cloud/org/orgname in the URL.
Organization	Organization name that is used as the unique identifier in the organization URL. For example, if the organization URL is https://www.example.com/cloud/org/myOrg, type myOrg .
User name of an organization administrator or system a	
Password Password associated with the user name.	

- 7 Select a peer network.
- 8 Review the tunnel settings and click Connect.

vCloud Director configures both peer network endpoints.

Create a VPN Tunnel to a Remote Network

An organization administrator can create a VPN tunnel between an organization virtual datacenter network and a remote network.

If the tunnel endpoints have a firewall between them, configure it to allow the following IP protocols and UDP ports:

- IP Protocol ID 50 (ESP)
- IP Protocol ID 51 (AH)
- UDP Port 500 (IKE)
- UDP Port 4500

Prerequisites

Verify that you have a routed organization virtual datacenter network and a routed remote network that uses IPSec.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Select Cloud Resources > Networks.
- 3 Click the **Organization VDC Network** tab, right-click the organization virtual datacenter network name, and select **Configure Services**.
- 4 Click the **VPN** tab and click **Add**.
- 5 Type a name and optional description.
- 6 Select a remote network from the drop-down menu.
- 7 Type the peer settings.
- 8 Review the tunnel settings and click OK.

vCloud Director configures the organization peer network endpoint.

What to do next

Manually configure the remote peer network endpoint.

Enable Static Routing for an Organization Virtual Datacenter Network

An organization administrator can configure certain organization virtual datacenter networks to provide static routing services. After you enable static routing on an organization virtual datacenter network, you can add static routes to allow traffic between different vApp networks routed to the organization virtual datacenter network.

Prerequisites

Verify that a routed organization virtual datacenter network is in place.

Procedure

- Click Administration.
- 2 Select Cloud Resources > Networks.
- 3 Right-click the organization virtual datacenter network name and select Configure Services.
- 4 On the **Static Routing** tab, select **Enable static routing** and click **OK**.

What to do next

Create static routes.

Add Static Routes Between vApp Networks Routed to the Same Organization Virtual Datacenter Network

An organization administrator can add static routes between two vApp networks that are routed to the same organization virtual datacenter network. Static routes allow traffic between the networks.

You cannot add static routes between overlapping networks or fenced vApps. After you add a static route to an organization virtual datacenter network, configure the network firewall rules to allow traffic on the static route. For vApps with static routes, select the **Always use assigned IP addresses until this vApp or associated networks are deleted** check box.

Static routes only function when the vApps included in the routes are running. If you change the parent network of a vApp, delete a vApp, or delete a vApp network, and the vApp includes static routes, those routes cannot function and you must remove them manually.

Prerequisites

Verify that the following conditions are met.

- A routed organization virtual datacenter network is in place.
- Static routing is enabled on the organization virtual datacenter network.
- Two vApp networks are routed to the organization virtual datacenter network.
- The vApp networks are in vApps that were started at least once.

Procedure

- 1 Click **Administration**.
- 2 Select Cloud Resources > Networks.
- 3 Right-click the organization virtual datacenter network name and select **Configure Services**.

- 4 Click the **Static Routing** tab and click **Add**.
- 5 Type a name, network address, and next hop IP address.

The network address is for the first vApp network to which you want to add a static route. The next hop IP address is the external IP address of that vApp network's router.

- 6 Select Within this network, and click OK.
- 7 Click **OK**.
- Repeat Step 4 through Step 7 to add a route to the second vApp network.

Example: Static Routing Example

vApp Network 1 and vApp Network 2 are both routed to Org Network Shared. You can create static routes on the organization virtual datacenter network to allow traffic between the vApp networks. You can use information about the vApp networks to create the static routes.

Table 2-3. Network Information

Network Name	Network Specification	Router External IP Address
vApp Network 1	192.168.1.0/24	192.168.0.100
vApp Network 2	192.168.2.0/24	192.168.0.101
Org Network Shared	192.168.0.0/24	NA

On Org Network Shared, create a static route to vApp Network 1 and another static route to vApp Network 2.

Table 2-4. Static Routing Settings

Static Route to Network	Route Name	Network	Next Hop IP Address	Route
vApp Network 1	tovapp1	192.168.1.0/24	192.168.0.100	In this network
vApp Network 2	tovapp2	192.168.2.0/24	192.168.0.101	In this network

What to do next

Create firewall rules to allow traffic on the static routes.

Add Static Routes Between vApp Networks Routed to Different Organization Virtual Datacenter Networks

An organization administrator can add static routes between two vApp networks that are routed to different organization virtual datacenter networks. Static routes allow traffic between the networks.

You cannot add static routes between overlapping networks or fenced vApps. After you add a static route to an organization virtual datacenter network, configure the network firewall rules to allow traffic on the static route. For vApps with static routes, select the **Always use assigned IP addresses until this vApp or associated networks are deleted** check box.

Static routes only function when the vApps included in the routes are running. If you change the parent network of a vApp, delete a vApp, or delete a vApp network, and the vApp includes static routes, those routes cannot function and you must remove them manually.

Prerequisites

Verify that you have the following items.

- Two organization virtual datacenter networks routed to the same external network.
- Static routing is enabled on both organization virtual datacenter networks.

- A vApp network is routed to each organization virtual datacenter network.
- The vApp networks are in vApps that were started at least once.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the Org virtual datacenter Networks tab, right-click the organization virtual datacenter network name, and select **Configure Services**.
- 3 Click the **Static Routing** tab and click **Add**.
- 4 Type a name, network address, and next hop IP address.

The network address is for the vApp network to which you want to add a static route. The next hop IP address is the external IP address of the router for the organization virtual datacenter network to which that vApp network is routed.

- 5 Select To external network and click OK.
- 6 Click Add.
- 7 Type a name, network address, and next hop IP address.

The network address is for the vApp network that is routed to this organization virtual datacenter network. The next hop IP address is the external IP address of the router for that vApp network.

- 8 Select Within this network and click OK.
- 9 Repeat Step 2 through Step 8 to add static routes to the second organization virtual datacenter network.

Example: Static Routing Example

vApp Network 1 is routed to Org virtual datacenter Network 1. vApp Network 2 is routed to Org virtual datacenter Network 2. You can create static routes on the organization virtual datacenter networks to allow traffic between the vApp networks. You can use information about the vApp networks and organization virtual datacenter networks to create the static routes.

Table 2-5. Network Information

Network Name	Network Specification	Router External IP Address
vApp Network 1	192.168.1.0/24	192.168.0.100
vApp Network 2	192.168.11.0/24	192.168.10.100
Org VDC Network 1	192.168.0.0/24	10.112.205.101
Org VDC Network 2	192.168.10.0/24	10.112.205.100

On Org VDC Network 1, create a static route to vApp Network 2 and another static route to vApp Network 1. On Org VDC Network 2, create a static route to vApp Network 1 and another static route to vApp Network 2.

Table 2-6. Static Routing Settings for Org VDC Network 1

Static Route to Network	Route Name	Network	Next Hop IP Address	Route
vApp Network 2	tovapp2	192.168.11.0/24	10.112.205.100	To external network
vApp Network 1	tovapp1	192.168.1.0/24	192.168.0.100	Within this network

Table 2-7. Static Routing Settings for Org VDC Network 2

Static Route to			Next Hop IP	
Network	Route Name	Network	Address	Route
vApp Network 1	tovapp1	192.168.1.0/24	10.112.205.101	To external network
vApp Network 2	tovapp2	192.168.11.0/24	192.168.10.100	Within this network

What to do next

Create firewall rules to allow traffic on the static routes.

Reset an Organization Virtual Datacenter Network

If the network services, such as DHCP settings, firewall settings, and so on, that are associated with an organization virtual datacenter network are not working as expected, reset the network.

No network services are available while an organization virtual datacenter network resets.

Prerequisites

- Verify that you have an external NAT-routed organization virtual datacenter network or an internal organization network.
- Verify that you have organization administrator privileges.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Right-click an organization virtual datacenter network, and select **Reset Network**.
- 3 Click Yes.

View IP Use for an Organization Virtual Datacenter Network

You can view a list of the IP addresses from an organization virtual datacenter network IP pool that are currently in use.

Prerequisites

Verify that you are an organization administrator.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Right-clicki an organization virtual datacenter network, and select **IP Allocations**.

Add IP Addresses to an Organization Virtual Datacenter Network IP Pool

If an organization virtual datacenter network is running out of IP addresses, you can add more addresses to its IP pool.

You are an organization administrator.

You cannot add IP addresses to external organization virtual datacenter networks that have a direct connection.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Right-click an organization virtual datacenter network and select Properties.

- 3 On the Network Specification tab, type an IP address or a range of IP addresses in the text box and click Add.
- 4 Click OK.

View vApps and vApp Templates That Use an Organization Virtual Datacenter Network

You can view a list of the all the vApps and vApp templates that include virtual machines with a NIC connected to an organization virtual datacenter network.

Prerequisites

Verify that you are an organization administrator.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Right-click an organization virtual datacenter network and select **Connected vApps**.
- 3 Click OK.

View Syslog Server Settings for an Organization Virtual Datacenter Network

You can view the syslog server settings for a routed organization virtual datacenter network.

vCloud Director supports logging events related to firewall rules to a syslog server specified by a system administrator.

If an organization virtual datacenter network does not have any syslog server settings and you think it should, or if the settings are not what you expected, then you can synchronize the network with the current syslog server settings. See "Apply Syslog Server Settings to an Organization Virtual Datacenter Network," on page 29. If a problem still exists after you synchronize, contact your system administrator.

Prerequisites

- Verify that an external NAT-routed organization virtual datacenter network exists.
- Verify that you are an organization administrator.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the **Org VDC Networks** tab, right-click the organization virtual datacenter network name, and select **Properties**.
- 3 Click the **Syslog Server Settings** tab.

Apply Syslog Server Settings to an Organization Virtual Datacenter Network

You apply syslog server settings to a routed organization virtual datacenter network to enable firewall rule logging.

Only a system administrator can specify syslog server settings. Apply those settings to any organization virtual datacenter network that was created before the system administrator specified them. Also, apply the syslog server settings to an organization virtual datacenter network whenever a system administrator changes the settings.

Prerequisites

Verify that an external NAT-routed organization virtual datacenter network is in place.

You are an organization administrator.

Procedure

- 1 Click **Administration** and select the organization virtual datacenter.
- 2 Click the Org VDC Networks tab, right-click the organization virtual datacenter network name, and select Synchronize syslog server settings.
- 3 Click Yes.

Managing Expired Items

When vApps or vApp templates expire, you can determine whether you want to renew or delete them.

Manage Expired vApps

You can display a list of expired vApps, delete them, or restore them to your organization.

You are an organization administrator.

The organization policy for what to do when a vApp storage lease expires is set to **Move to Expired Items**. See "Configure Organization Lease, Quota, and Limit Settings," on page 34.

Procedure

- 1 Select My Cloud > Expired Items.
- 2 On the **Expired vApps** tab, review the list of expired vApps.
- 3 Right-click a vApp and select **Delete** or **Renew** and click **Yes**.

If you selected **Delete**, the vApp is deleted from the list. If you selected **Renew**, the restored vApp appears on the **vApps** page.

Manage Expired vApp Templates

You can display a list of expired vApp templates and delete them or restore them to your organization.

You are an organization administrator.

The organization policy for what to do when a vApp template storage lease expires is set to **Move to Expired Items**. See "Configure Organization Lease, Quota, and Limit Settings," on page 34.

Procedure

- 1 Select My Cloud > Expired Items.
- 2 Click the Expired vApp Templates tab.
- 3 Right-click on a vApp template, select **Delete** or **Renew**, and click **Yes**.

If you selected **Delete**, the vApp template is deleted from the list. If you selected **Renew**, the vApp template is restored to its catalog.

Working in an Organization

3

Most operations in vCloud Director occur in an organization. The system administrator creates the organization and assigns an organization administrator to it.

The system administrator emails the URL of the organization to the organization administrator, who can log in to the organization and set it up. In the Home page the organization administrator clicks the **Set up the Organization** link to assign resources and manage a variety of operations on the organization.

This chapter includes the following topics:

- "Understanding Leases," on page 31
- "Set Up an Organization," on page 32
- "Review Your Organization Profile," on page 34
- "Modify Your Email Settings," on page 35
- "Modify Your Organization's Policies," on page 35
- "Set Default Domain for Organization Virtual Machines," on page 36
- "Enable Your Organization to Use an SAML Identity Provider," on page 36
- "Install Java Cryptography Extension Unlimited Strength Jurisdiction Policy Files," on page 37
- "Manage Users and Groups in Your Organization," on page 38
- "Manage Resources in Your Organization," on page 38
- "Manage Virtual Machines in Your Organization," on page 38
- "Viewing Organization Log Tasks and Events," on page 39

Understanding Leases

Creating an organization involves specifying leases. Leases provide a level of control over an organization's storage and compute resources by specifying the maximum amount of time that vApps can be running and that vApps and vApp templates can be stored.

The goal of a runtime lease is to prevent inactive vApps from consuming compute resources. For example, if a user starts a vApp and goes on vacation without stopping it, the vApp continues to consume resources.

A runtime lease begins when a user starts a vApp. When a runtime lease expires, vCloud Director stops the vApp.

The goal of a storage lease is to prevent unused vApps and vApp templates from consuming storage resources. A vApp storage lease begins when a user stops the vApp. Storage leases do not affect running vApps. A vApp template storage lease begins when a user adds the vApp template to a vApp, adds the vApp template to a workspace, downloads, copies, or moves the vApp template.

When a storage lease expires, vCloud Director marks the vApp or vApp template as expired, or deletes the vApp or vApp template, depending on the organization policy you set.

For more information about specifying lease settings, see "Configure Organization Lease, Quota, and Limit Settings," on page 34.

Users can configure email notification to receive a message before a runtime or storage lease expires. See "Set User Preferences," on page 15 for information about lease expiration preferences.

Set Up an Organization

After you receive the URL of your organization from the system administrator, you must set it up. On the vCloud Director **Home** page, click **Set up this organization**.

You are an organization administrator.

Procedure

1 Change the Organization Full Name on page 32

You can change the full name of an organization. This name appears in the Cloud Director application header when users log in.

2 Import Users and Groups on page 33

You can add users and groups from an LDAP or SAML server to the organization and assign them a role within the organization.

3 Add Local Users to the Organization on page 33

Every organization should have at least one local organization administrator account, so that users can log in even if the LDAP and SAML services are unavailable.

4 Configure Email Preferences on page 33

vCloud Director requires an SMTP server to send user notification and system alert emails. An organization can use the system email settings or use its own email settings.

5 Configure Organization Lease, Quota, and Limit Settings on page 34

Leases, quotas, and limits constrain the ability of organization users to consume storage and processing resources. Use these settings to prevent users from depleting or monopolizing an organization's resources.

Change the Organization Full Name

You can change the full name of an organization. This name appears in the Cloud Director application header when users log in.

You are an organization administrator.

Procedure

- 1 On Name this Organization page, in the Organization full name, type the new full name.
- 2 (Optional) Type a description of the organization.
- 3 Click Next.

Import Users and Groups

You can add users and groups from an LDAP or SAML server to the organization and assign them a role within the organization.

Prerequisites

Verify that your organization has a valid connection to an LDAP or SAML server.

Procedure

- 1 Click Import.
- 2 Select the type of server to import from.
- Type a full or partial name of a user or group and click **Search**.

 If you are importing from a SAML server, you must include the domain name (ex. user@domain.com).
- 4 Select the users or groups to import and click **Add**.
- 5 Select a role for the users and groups and click **OK**.
- 6 Click Next.

Add Local Users to the Organization

Every organization should have at least one local organization administrator account, so that users can log in even if the LDAP and SAML services are unavailable.

Procedure

- 1 Click Add.
- 2 Type a user name and password.
- 3 Assign a role to the user.
- 4 (Optional) Type the contact information for the user.
- 5 Select **Unlimited** or type a user quota for stored and running virtual machines and click **OK**.
 These quotas limit the user's ability to consume storage and compute resources in the organization.
- 6 Click Next.

Configure Email Preferences

vCloud Director requires an SMTP server to send user notification and system alert emails. An organization can use the system email settings or use its own email settings.

Procedure

1 Select an SMTP server option.

Option	Description	
Use system default SMTP server	The organization uses the system SMTP server.	
Set organization SMTP server	The organization uses its own SMTP server. Type the DNS host name or II address and port number of the SMTP server. (Optional) Select the Requires authentication check box and type a user name and password.	

2 Select a notification settings option.

Option	Description	
Use system default notification settings	The organization uses the system notification settings.	
Set organization notification settings	The organization uses its own notification settings. Type an email addres that appears as the sender for organization emails, type text to use as the subject prefix for organization emails, and select the recipients for organization emails.	

- 3 (Optional) Type a destination email address and click **Test Email Settings** to verify that all SMTP server settings are configured as expected.
- 4 Click Next.

Configure Organization Lease, Quota, and Limit Settings

Leases, quotas, and limits constrain the ability of organization users to consume storage and processing resources. Use these settings to prevent users from depleting or monopolizing an organization's resources.

For more information about leases, see "Understanding Leases," on page 31.

Procedure

- 1 Select the lease options for vApps and vApp templates.
 - Leases provide a level of control over an organization's storage and compute resources by specifying the maximum amount of time that vApps can run and that vApps and vApp templates can be stored. You can also specify what happens to vApps and vApp templates when their storage lease expires.
- 2 Select the quotas for running and stored virtual machines.
 - Quotas determine how many virtual machines each user in the organization can store and power on in the organization's virtual datacenters. The quotas that you specify act as the default for all new users added to the organization.
- 3 Select the limits for resource intensive operations.
 - Certain vCloud Director operations, for example copy and move, are more resource intensive than others. Limits prevent resource intensive operations from affecting all the users in an organization and also provide a defense against denial-of-service attacks.
- 4 Select the number of simultaneous VMware Remote Console connections for each virtual machine.
 - You might want to limit the number of simultaneous connections for performance or security reasons.
 - **N**ote This setting does not affect Virtual Network Computing (VNC) or Remote Desktop Protocol (RDP) connections.
- 5 (Optional) Select the **Account lockout enabled** check box, select the number of invalid logins to accept before locking a user account, and select the lockout interval.
- 6 Click Next.

Review Your Organization Profile

You can review and modify some of the information in your organization's profile

You are an organization administrator.

Procedure

1 Click **Administration**.

- 2 In the left pane, select Settings > General.
- 3 You can complete these operations.
 - Review your organization's default URL.
 - Modify your organization's full name.
 - Type a description.
- 4 Click Apply.

Modify Your Email Settings

You can review and modify the default email settings that were set when the system administrator created your organization.

You are an organization administrator.

Procedure

- 1 Click **Administration**.
- 2 In the left pane, select Settings > Email.
- 3 Select an SMTP server option.

Option	Description	
Use system default SMTP server	The organization uses the system SMTP server.	
Set organization SMTP server	The organization uses its own SMTP server. Type the DNS host name or II address and port number of the SMTP server. (Optional) Select the Requires authentication check box and type a user name and password.	

4 Select a notification settings option.

Option	Description	
Use system default notification settings	The organization uses the system notification settings.	
Set organization notification settings	The organization uses its own notification settings. Type an email address that appears as the sender for organization emails, type text to use as the subject prefix for organization emails, and select the recipients for organization emails.	

- Optional) Type a destination email address and click **Test Email Settings** to verify that all SMTP server settings are configured as expected.
- 6 Click Apply.

Modify Your Organization's Policies

You can review and modify the default policies that were set by the system administrator when your organization was created.

You are an organization administrator.

Procedure

- 1 Click **Administration**.
- 2 In the left pane, select Settings > Policies.

3 Select the lease options for vApps and vApp templates.

Leases provide a level of control over an organization's storage and compute resources by specifying the maximum amount of time that vApps can be running and that vApps and vApp templates can be stored. You can also specify what happens to vApps and vApp templates when their storage lease expires.

4 Select the quotas for running and stored virtual machines.

Quotas determine how many virtual machines each user in the organization can store and power on in the organization's virtual datacenters. The quotas you specify act as the default for all new users added to the organization.

5 Select the limits for resource intensive operations.

Certain vCloud Director operations, for example copy and move, are more resource intensive than others. Limits prevent resource intensive operations from affecting all the users in an organization and also provide a defense against denial-of-service attacks.

6 Select the number of simultaneous VMware Remote Console connections for each virtual machine.

You may want to limit the number of simultaneous connections for performance or security reasons.

NOTE This setting does not affect Virtual Network Computing (VNC) or Remote Desktop Protocol (RDP) connections.

- 7 (Optional) Select the **Account lockout enabled** check box, select the number of invalid logins to accept before locking a user account, and select the lockout interval.
- 8 Click **Apply**.

Set Default Domain for Organization Virtual Machines

You can set a default domain which virtual machines created in your organization can join. Virtual machines can always join a domain for which they have credentials, regardless of whether or not you specify a default domain.

You are an organization administrator.

Procedure

- 1 Click **Administration**.
- 2 In the left pane, select Settings > Guest Personalization.
- 3 Select the Enable domain join for virtual machines in this organization.
- 4 Type the domain name, domain user name, domain password.
 These credentials apply to a regular domain user, not a domain administrator.
- 5 Click Apply.

Enable Your Organization to Use an SAML Identity Provider

Enable your organization to use an SAML identity provider, also called single sign-on, to import users and groups from an SAML identity provider and allow imported users to sign on to the organization with the credentials established in the SAML identity provider.

Prerequisites

■ Verify that you are logged in as a system or organization administrator.

- Verify that you have access to an OpenAM or Active Directory Federation Services SAML identity provider.
- Create an XML file with the following metadata from your SAML identity provider.
 - The location of the single sign-on service
 - The location of the single logout service
 - The location of the service's X.509 certificate

For information on configuring and acquiring metadata from an OpenAM or Active Directory Federation Services SAML provider, consult the documentation for your SAML provider.

Procedure

- 1 Click **Administration**.
- 2 In the left pane, select **Settings** > **Federation**.
- 3 Select Use SAML Identity Provider.
- 4 Copy and paste the SAML provider metadata XML into the text box or click **Browse** to upload the metadata XML file.
- 5 Click Apply.

What to do next

- Configure your SAML provider with vCloud Director metadata. See your SAML provider's documentation and the vCloud Director Installation and Upgrade Guide.
- Configure your SAML provider to provide tokens with the following attribute mappings.
 - email address = "EmailAddress"
 - user name = "UserName"
 - full name = "FullName"
 - user's groups = "Groups"
- Import users and groups from your SAML provider.
- Install the JCE unlimited strength jurisdiction policy files. See

Install Java Cryptography Extension Unlimited Strength Jurisdiction Policy Files

Install Java Cryptography Extension unlimited strength jurisdiction files to remove restrictions on cryptographic strength in JCE. These restrictions can prevent users from successfully logging in to vCloud Director using vSphere Single Sign On.

Because of import control restrictions of some countries, the version of the JCE policy files that are bundled in the JRE bundled in vCloud Director, allow strong but limited cryptography to be used, which is insufficient to deal with the encryption strength used by the SAML identity provider.

Prerequisites

Verify that you are a system administrator.

Procedure

In the /opt/vmware/vcloud-director/jre/bin/java -version directory, identify the version of Java used by vCloud Director.

- 2 Download the policy files for the version of Java being used from the following links.
 - Java Runtime Environment 6
 - Java Runtime Environment 7
- 3 Use the cell management tool to quiesce the vCloud Director cell.

See the vCloud Director Installation and Upgrade Guide.

4 Stop vCloud Director services.

See the vCloud Director Installation and Upgrade Guide.

- 5 Locate the JRE policy files in the \$VCLOUD_HOME/jre directory and replace them with the downloaded policy files using the same permissions as the replaced files.
- 6 Enable the cell using the cell management tool.

What to do next

Repeat this procedure for all cells in vCloud Director.

Manage Users and Groups in Your Organization

You can manage the roles and rights that users and groups have in your organization.

You are an organization administrator.

Procedure

- 1 Click **Administration**.
- 2 In the left pane, select **Members > Users** or **Members > Groups**.

You can modify properties or roles.

- 3 Right-click the user or group and select Properties.
- 4 Make the necessary changes and click OK.

Your user or group settings are updated.

Manage Resources in Your Organization

You must monitor and manage the resources you add to your organization.

You are an organization administrator.

Procedure

- Click Administration.
- 2 In the left pane, under Cloud Resources, select Virtual Datacenters.

The virtual datacenters in your organization appear in the right pane. See also Chapter 2, "Managing Cloud Resources," on page 17

Manage Virtual Machines in Your Organization

You can manage virtual machines in your organization. Virtual machines provide access to vCloud Director operations at the virtual machine console level.

You are an organization administrator.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select **VMs**.
- 3 Select a virtual machine, right-click, and select Properties.
- 4 Modify the relevant properties in each of the tabs and click **OK**.

What to do next

For more information on managing virtual machines, see Chapter 8, "Working with Virtual Machines," on page 91.

Viewing Organization Log Tasks and Events

You can view tasks and events in your organization to monitor and audit vCloud Directory activities.

vCloud Director tasks are long-running operations and their status changes as the task progresses. For example, a task's status generally starts as Running. When the task finishes, its status changes to Successful or Error.

vCloud Director events are one-time occurrence that indicate an important part of an operation or a significant state change for a vCloud Director object. vCloud Director also logs an event every time a user logs in, and notes whether the attempt was successful or not.

View Organization Events

You can view the log for an organization to monitor organization-level events. Failed events and view events are listed by user.

You are an organization administrator.

Procedure

- 1 Click the **My Cloud**.
- 2 In the left pane, click **Logs**.
- 3 Click the Events tab.

vCloud Director displays information about each organization-level event.

4 Double-click an event for more information.

Only system administrators can view the details about most events.

View Organization Tasks

You can view the tasks in an organization, which helps you monitor and troubleshoot more effectively.

You are an organization administrator.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click Logs.
- 3 On the **Tasks** tab, you can examine the tasks in the organization.
- 4 Select a task, right-click, and select **Open**.
- 5 Review the information and click **OK**.

What to do next

To troubleshoot a failed task, contact your system administrator.

Working with Catalogs

4

A catalog is a container for vApp templates and media files in an organization. Organization administrators and catalog authors can create catalogs in an organization. Catalog contents can be shared with other users or organizations in the vCloud Director installation or published externally for access by organizations outside the vCloud Director installation.

vCloud Director contains private catalogs, shared catalogs, and externally accessible catalogs. Private catalogs include vApp templates and media files that you can share with other users in the organization. If a system administrator enables catalog sharing for your organization, you can share an organization catalog to create a catalog accessible to other organizations in the vCloud Director installation. If a system administrator enables external catalog publishing for your organization, you can publish an organization catalog for access by organizations outside the vCloud Director installation. An organization outside the vCloud Director installation must subscribe to an externally published catalog to access its contents.

You can upload an OVF package directly to a catalog, save a vApp as a vApp template, or import a vApp template from vSphere. See "Upload an OVF Package as a vApp Template," on page 55 and "Save a vApp as a vApp Template," on page 58. You can upload media files directly to a catalog. See "Upload Media Files," on page 49.

Members of an organization can access vApp templates and media files that they own or that are shared with them. Organization administrators and system administrators can share a catalog with everyone in an organization or with specific users and groups in an organization. See "Share A Catalog," on page 43.

This chapter includes the following topics:

- "Add a New Catalog," on page 42
- "Access a Catalog," on page 43
- "Share A Catalog," on page 43
- "Publish a Catalog to an External Organization," on page 44
- "Change the Owner of a Catalog," on page 45
- "Delete a Catalog," on page 45
- "Change the Properties of Your Catalog," on page 45
- "Subscribe to an External Catalog Feed," on page 46
- "Understanding Catalogs and Their Contents," on page 46
- "Working in Published Catalogs," on page 47

Add a New Catalog

You can create catalogs to group your vApp templates and media files.

Prerequisites

Verify that you are at least a catalog author.

Procedure

- 1 Click Catalogs and select My Organization's Catalogs in the left pane.
- 2 On the Catalogs tab, click Add Catalog.
- 3 Type a catalog name and optional description and click Next.
- 4 Select the type of storage to use for vApp templates and ISOs in this catalog and click Next.

Option	Description
Use any available storage in the organization	This catalog uses any available storage in the organization.
Pre-provision storage on specific storage policy	Select a virtual datacenter storage policy to use for this catalog's vApp templates and ISOs and click Add . The selected storage policy causes the vApp template size to count against your catalog storage quota.

5 Click Add Members.

Note This option might be unavailable, depending on your organizational settings.

- a Select which users and groups in the organization can access this catalog.
 - Select Everyone in this organization to grant catalog access to all users and groups in the organization.
 - Select Specific users and groups to grant catalog access to certain users or groups and click Add.
- b Select the access level for users with access to this catalog from the drop-down menu and click **OK**.
 - Select Read Only to grant read access to the catalog's vApp templates and ISOs.
 - Select Read/Write to grant read access to the catalog's vApp templates and ISOs, and to allow user to add vApp templates and ISOs to the catalog.
 - Select Full Control to grant full access to the catalog's contents and settings.

6 Click Add Organizations.

Note This option might be unavailable, depending on your organizational settings.

- a Select which organizations on this vCloud Director installation can access this catalog.
 - Select All organizations to grant catalog access to all organizations in the vCloud Director installation.
 - Select Specific organizations to grant catalog access to certain organizations and click Add.
- b Select the access level for users with access to this catalog from the drop-down menu and click **OK**.
 - Select **Read Only** to grant read access to the catalog's vApp templates and ISOs.
 - Select Read/Write to grant read access to the catalog's vApp templates and ISOs, and to allow organizations to add vApp templates and ISOs to the catalog.
 - Select Full Control to grant full access to the catalog's contents and settings.
- 7 Click Next.
- 8 (Optional) Select **Enabled** and click to allow the creation of a catalog feed for consumption by catalogs outside this vCloud Director installation and supply a password for the catalog feed.
- 9 (Optional) Select Enable early catalog export to optimize synchronization.
 - Before selecting this option, verify that you have available storage at the transfer server location for the exported catalog.
- 10 (Optional) Select **Preserve identity information** to include BIOS and UUID information in the downloaded OVF package.
 - Enabling this option limits portability of the OVF package.
- 11 Review the catalog settings and click **Finish**.

The new catalog appears in My Organization's Catalogs. A catalog's displayed status on this page does not reflect the status of the templates and vApps in the catalog.

Access a Catalog

If the system administrator granted you catalog access, you can access catalogs in your organization and public catalogs that other organizations published.

Procedure

- Click Catalogs.
- 2 In the left pane, click a catalog option.
- 3 In the right pane, select a catalog, right-click, and select **Open**.

Share A Catalog

You can share a catalog to make it visible to the administrators in all other organizations in a cloud. Users with the proper rights and access level can use vApp templates and media from the shared catalog to create their own vApps.

Prerequisites

Verify that you are an organization administrator and the system administrator has granted you write access to the catalog.

Procedure

- 1 Click **Catalog** and select **My Organization's Catalogs** in the left pane.
- 2 On the **Catalogs** tab, right-click the catalog name and select **Publish Settings**.
- 3 On the **Sharing** tab, click **Add Members**.
- 4 Select which users and groups in the organization can access this catalog.

Option	Description
Everyone in this organization	All users and groups in the organization have access to this catalog.
Specific users and groups	Select users or groups to grant catalog access to and click Add .

5 Select the access level for users with access to this catalog from the drop-down menu.

Option	Description
Read Only	Users with access to this catalog have read access to the catalog's vApp templates and ISOs.
Read/Write	Users with access to this catalog have read access to the catalog's vApp templates and ISOs and can add vApp templates and ISOs to the catalog.
Full Control	Users with access to this catalog have full control of the catalog's contents and settings.

- 6 Click OK.
- 7 Click Add Organizations.
- 8 Select which organizations on this vCloud Director installation can access this catalog.

Option	Description
All organizations	All organizations in the vCloud Director installation have access to this catalog.

9 Click **OK** and click **OK** again.

The catalog and all of its contents appear under Public Catalogs for selected users and groups in the vCloud Director installation.

Publish a Catalog to an External Organization

If the system administrator has granted you catalog access, you can publish a catalog externally to make its vApp templates and media files available for subscription by organizations outside the vCloud Director installation.

Prerequisites

Verify that the system administrator enabled external catalog publishing for the organization and granted you catalog access.

Procedure

- 1 Click **Catalog** and select **My Organization's Catalogs** in the left pane.
- 2 On the Catalogs tab, right-click the catalog name and select Publish Settings.
- 3 On the External Publishing tab, select Enabled and supply a password for the catalog feed.
- 4 Click **OK**.

What to do next

Provide the subscription URL listed on the **External Publishing** tab and the password to grant access to the catalog. An organization must subscribe to the catalog to gain access to its contents.

Change the Owner of a Catalog

You can change the owner of a catalog. Before you can delete a user who owns a catalog, you must change the owner or delete the catalog.

Prerequisites

Verify that the system administrator gave you access to the catalog.

Procedure

- 1 Select Catalog > My Organization's Catalogs.
- 2 Click the **Catalogs** tab, right-click a catalog, and select **Change Owner**.
- 3 Select a user from the list or search for one.
 - You can search for a user by full name or by their user name.
- 4 Click OK.

Delete a Catalog

You can delete a catalog from your organization.

Prerequisites

Verify that the system administrator gave you access to the catalog.

The catalog must not contain any vApp templates or media files. You can move these items to a different catalog or delete them.

Procedure

- 1 Click Catalog.
- 2 In the left pane, click My Organization's Catalogs.
- 3 Select a catalog, right-click, and select **Delete**.
- 4 Click Yes.

The empty catalog is deleted from your organization.

Change the Properties of Your Catalog

You can review and change your catalog properties.

Prerequisites

Verify that you are at least a catalog author.

Procedure

- 1 Click Catalog.
- 2 In the left pane, click My Organization's Catalogs.
- 3 Select a catalog, right-click, and select **Properties**.
- 4 Review the properties in the General, Sharing, and External Publishing tabs.

5 Change the relevant properties and click **OK**.

Your catalog properties are updated.

Subscribe to an External Catalog Feed

You subscribe an organization to an external catalog feed to access a catalog from outside of the installation of vCloud Director.

Procedure

- 1 Click Catalogs and select My Organization's Catalogs in the left pane.
- 2 Click **Add Catalog** and type a name and optional description for the catalog feed.
- 3 Select Subscribe to an external catalog and click Next.
- 4 Select the type of storage to use for this catalog feed and click **Next**.

Option	Description
Use any available storage in the organization	This catalog feed uses any available storage in the organization.
Pre-provision storage on specific storage policy	Select a virtual datacenter storage policy to use for this catalog feed and click Add .

- 5 Click Add Members.
- 6 Select which users and groups in the organization can access this catalog feed and click OK.

Option	Description
Everyone in this organization	All users and groups in the organization have access to this catalog feed.
Specific users and groups	Select users or groups to which to grant catalog feed access and click Add .

- 7 Click **Add Organizations**.
- 8 Select which organizations on this vCloud Director installation can access this catalog feed and click OK.

Option	Description
All organizations	All organizations in the vCloud Director installation have access to this catalog feed.
Specific organizations	Select the organizations to which to grant catalog feed access and click Add .

- 9 Click Next.
- 10 Review the catalog feed settings and click **Finish**.

Understanding Catalogs and Their Contents

An organization's catalog consists of a list of catalogs, vApp templates, and media files in your organization.

When you click **Catalog** in the menu bar, these tabs appear.

- Catalogs
- vApp Templates
- Media

If you are an organization administrator, you can access catalogs in the left pane.

Access vApp Templates in a Catalog

You can access vApp templates in a catalog in your organization or, if you are an organization administrator, from a published catalog.

Procedure

- 1 Click Catalog.
- 2 In the left pane, click My Organization's Catalogs and click the vApp Templates tab.
- 3 Right-click a vApp template to see the operations you can complete.

Access Media Files in a Catalog

You can access media files in a catalog in your organization or, if you are a organization administrator, a published catalog.

Procedure

- 1 Click Catalog.
- 2 In the left pane, click **My Organization's Catalogs** and click the **Media** tab.
- 3 Right-click a media file to see the operations you can complete.

Working in Published Catalogs

Organization administrators can access a published catalog and copy its vApp templates and media files to a catalog in their organization. They can then share the organization catalog with other members of their organization so that they can use the vApp templates and media files.

Accessing vApp Templates from a Public Catalog

You can access vApp templates from published catalogs and copy them to your catalog.

Prerequisites

Verify that you are an organization administrator.

Procedure

- Click Catalog.
- 2 In the left pane, click **Public Catalogs**.
- 3 On the **vApp Templates** tab, select a vApp template, right-click and select an operation.
 - You cannot change properties until you copy the vApp template to your catalog. If you select **Add to My Cloud**, the vApp template is saved and added as a vApp.
- 4 Click **OK**.

The vApp template you selected is added to the catalog that you selected in your organization.

Accessing a Media File from a Public Catalog

You can access a media file from a published catalog and add it to your organization.

Prerequisites

Verify that you are an organization administrator.

Procedure

- 1 Click Catalogs.
- 2 In the left pane, click Public Catalogs.
 Media files are available for use if they reside in the same virtual datacenter as your Cloud vApp.
- 3 On the Media tab, select a media file, right-click and select Copy to Catalog.
- 4 Click **OK**.

The media file is copied to your catalog.

What to do next

You can select the media file and move it to another catalog in your organization, delete it, or change its properties.

Working with Media Files

5

The catalog allows you to upload, copy, move, and edit the properties of media files.

This chapter includes the following topics:

- "Upload Media Files," on page 49
- "Resume the Upload of a Media File," on page 50
- "Copy Media Files to a Catalog," on page 50
- "Move Media Files to Another Catalog," on page 50
- "Delete Media Files," on page 51
- "Modify Media File Properties," on page 51

Upload Media Files

You can upload media files to a catalog. Users with access to the catalog can use the media files to install applications on their virtual machines.

Prerequisites

Verify that the computer from which you are uploading has Java Plug-in 1.6.0_10 or later installed.

You are at least a catalog author.

Procedure

- 1 Select Catalogs > My Organization's Catalogs.
- 2 On the **Media** tab, click **Upload**.
- 3 Type the path to the media file path or click **Browse**, locate the file, and click **Upload**.
- 4 Type a name and optional description for the media file.
 - This is the name that appears in vCloud Director.
- 5 Select the destination virtual datacenter, storage policy, and catalog.
- 6 Click Upload.

The media file is uploaded to the specified location. You can click **Launch Uploads and Downloads Progress Window** to track the progress.

Resume the Upload of a Media File

If you paused, cancelled, or interrupted the upload of a media file, you can resume it.

- You are at least a catalog author.
- If you log out of vCloud Director and log in, transfer history is lost. You cannot resume the upload.
- The default timeout for pending transfer sessions is one hour. You can configure this value.
- During pending or stopped transfers, the session keep alive heartbeat kicks in every 15 minutes. To ensure that the session does not time out while tasks are paused, make sure the session timeout value is more than 15 minutes.

Prerequisites

You have initiated the upload or download of a media file.

Procedure

- In the Launch the Uploads and Downloads Progress Window, click Pause or Cancel.
 The status changes to Stopped in the progress window and Waiting in the Media Files page.
- 2 In the Launch the Uploads and Downloads Progress Window, click Resume.
 - The upload or download process resumes.
- 3 Monitor the progress in the Launch the Uploads and Downloads Progress window.

Copy Media Files to a Catalog

You can copy media files to another catalog.

Prerequisites

- Verify that you have access to multiple virtual datacenters.
- Verify that you are at least a catalog author.

Procedure

- Click Catalogs.
- 2 On the Media tab, select a media file, right-click, and select Copy To Catalog.
- 3 Type a name and description.
- 4 Select the destination catalog.
- 5 Click OK.

The media file is copied to and stored in the selected catalog.

Move Media Files to Another Catalog

You can move media files to another catalog in your organization.

Prerequisites

- Verify that you have access to multiple catalogs and virtual datacenters.
- Verify that you are at least a catalog author.

Procedure

- 1 Click Catalogs.
- 2 Click the Media tab, select a media file, right-click, and select Move To Catalog.
- 3 Select a catalog.

The catalog you select must be in your organization.

4 Click **OK**.

The media file is moved to the selected catalog.

Delete Media Files

You can delete media files from your catalog.

You are at least a catalog author.

Procedure

- 1 Click Catalogs > My Organization's Catalogs.
- 2 On the **Media** tab, select a media file, right-click, select **Delete**.
- 3 Click Yes.

The media file is deleted.

Modify Media File Properties

You can review and modify some properties of a media file.

You are at least a catalog author.

Procedure

- 1 Click Catalogs > My Organization's Catalogs.
- 2 On the Media tab, select a media file, right-click, and select Properties.
- 3 Modify the name or description.
- 4 Click **OK**.

vCloud Director User's Guide

Working with vApp Templates

A vApp template is a virtual machine image that is loaded with an operating system, applications, and data. These templates ensure that virtual machines are consistently configured across an entire organization.

This chapter includes the following topics:

- "Open a vApp Template," on page 53
- "Add a vApp Template to My Cloud," on page 54
- "Download a vApp Template," on page 54
- "Upload an OVF Package as a vApp Template," on page 55
- "Resume the Upload of a vApp Template," on page 56
- "Copy a vApp Template from a Public Catalog to an Organization Catalog," on page 56
- "Copy a vApp Template Between an Organization's Catalogs," on page 57
- "Move a vApp Template Between an Organization's Catalogs," on page 57
- "Delete a vApp Template," on page 57
- "Save a vApp as a vApp Template," on page 58
- "Modify vApp Properties," on page 58
- "Change the Guest OS Properties of a vApp Template," on page 59

Open a vApp Template

You can open a vApp template to learn more about the virtual machines that it contains.

You are at least a vApp user.

Procedure

- 1 Click Catalogs.
- 2 In the left pane, click on a catalog option.
 - My Organization's Catalogs
 - Public Catalogs

You can open vApp templates in your organization's catalogs or, if you are an organization administrator, from a public catalog.

3 On the **vApp Templates** tab, select a vApp template, right-click, and select **Open**.

Add a vApp Template to My Cloud

You can add a vApp template as a vApp from your catalog to My Cloud.

You are at least a vApp author.

If the vApp template is based on an OVF file that includes OVF properties for customizing its virtual machines, those properties are passed to the vApp. If any of those properties are user-configurable, you can specify the values.

Prerequisites

A vApp template is available in a published or a locally shared catalog.

Procedure

- 1 Click Catalogs.
- In the left pane, click a catalog option.

You can access vApp templates in your organization's shared catalogs or, if you are an organization administrator, from a public catalog.

- 3 On the vApp Templates tab, select a vApp template, right-click, and select Add to My Cloud.
- 4 Type a name and optional description for the vApp.
- 5 Select a virtual datacenter to add the vApp to.
- 6 Select the storage policies for the vApp's virtual machines to use when deployed from each virtual machine's drop-down menu.
- 7 Select runtime and storage lease duration from the drop-down menus.
- 8 Configure the networking options for the vApp.
- 9 (Optional) Configure vApp hardware settings.

Option	Description
VCPUs	Type the number of virtual CPUs and cores per socket for the vApp's virtual machines or leave this section unchanged to use the template's default virtual CPU configuration.
Memory	Type the amount of memory for the vApp's virtual machines or leave this section unchanged to use the template's default memory configuration.
Hard disk space	Type the hard disk space for the vApp's virtual machines or leave this section unchanged to use the template's default hard disk configuration.

- 10 Click Next.
- 11 (Optional) Select **Power on vApp after this wizard is finished** to power on the vApp after vApp creation is complete.
- 12 Review the vApp summary information and click Finish.

vCloud Director creates a vApp on the vApps page.

Download a vApp Template

You can download a vApp template from a catalog locally as an OVF file.

You are at least a catalog author.

Prerequisites

The computer from which you are downloading must have Java Plug-in 1.6.0_10 or later installed.

Procedure

- 1 Click Catalogs.
- 2 In the left pane, click on a catalog option.
 - My Organization's Catalogs
 - Public Catalogs

You can download vApp templates from your organization's catalogs or, if you are an organization administrator, from a public catalog.

- 3 On the **vApp Templates** tab, select a vApp template, right-click, and select **Download**.
- 4 Navigate to the local folder where you want to save the OVF file and click Save.

You can click the **Launch Uploads and Downloads Progress Window** button from **My Organization's Catalogs** to track the progress.

Upload an OVF Package as a vApp Template

You can upload an OVF package from remote shares and your local directory to vCloud Director as a vApp template.

You are at least a catalog creator.

vCloud Director supports OVFs based on the Open Virtualization Format (OVF) Specification. If you upload an OVF file that includes OVF properties for customizing its virtual machines, those properties are preserved in the vApp template.

Prerequisites

- The computer from which you are uploading must have Java Plug-in 1.6.0_10 or later installed.
- For information about creating OVFs, see the *OVF Tool User Guide* and *VMware vCenter Converter 4.0.1 User's Guide*.
- vCloud Director does not support uploading compressed OVF files.

Procedure

- 1 Click Catalogs > My Organization's Catalogs.
- 2 On the **vApp Templates** tab, click the **Upload** button.
- 3 Type the name and path of the OVF file to upload, or click **Browse**, select the OVF file, and click **Upload**.
- 4 Type a name and optional description for the vApp template.
- 5 Select a destination virtual datacenter and catalog.
- 6 Click Upload.

You can click the Launch Uploads and Downloads Progress Window button to track the progress.

What to do next

Verify that VMware Tools is installed in each virtual machine in the vApp. See "Installing VMware Tools in a vApp," on page 105.

Resume the Upload of a vApp Template

If the upload process is interrupted, paused, or cancelled you can resume it.

- You are at least a catalog creator.
- If you log out of vCloud Director and log in, transfer history is lost. You cannot resume the upload.
- The default timeout for pending transfer sessions is one hour. You can configure this value up to one hour.
- During pending or stopped transfers, the session keep alive heartbeat kicks in every 15 minutes. To ensure that the session does not time out while tasks are paused, make sure the session timeout value is more than 15 minutes.

Prerequisites

You have initiated the upload or download of a vApp template.

Procedure

- In the Launch Uploads and Downloads Progress Window, click Pause or Cancel.

 The status changes to Stopped in the progress window and Waiting in the vApp Template page.
- 2 In the Launch Uploads and Downloads Progress Window, click Resume.
 - The upload or download process resumes.
- 3 Monitor the progress in the Launch Uploads and Downloads Progress Window.

Copy a vApp Template from a Public Catalog to an Organization Catalog

You can copy a vApp template from a public catalog to your organization catalog to make it available to users in your organization.

You are a vApp author or organization administrator.

Prerequisites

You have a catalog and virtual datacenter.

Procedure

- Click Catalogs.
- 2 In the left pane, click **Public Catalogs**.
- 3 On the **vApp Templates** tab, select a vApp template, right-click, and select **Copy To Catalog**.
- 4 Type a name and optional description for the vApp.
- 5 Select a destination catalog and virtual datacenter.
 - Select a shared catalog to give organization users access to the template.
- 6 Click OK.

vCloud Director copies the vApp template to the organization catalog. The vApp appears on the **vApp Templates** tab in **My Organization's Catalogs**.

Copy a vApp Template Between an Organization's Catalogs

You can copy a vApp template from one catalog in your organization to another catalog in the same organization. This is useful if the catalogs are shared with different users and you want both groups of users to have access to the vApp template.

You are an organization administrator, catalog author, or vApp author.

Prerequisites

You must have access to at least two catalogs and a virtual datacenter with available space.

Procedure

- 1 Click Catalogs > My Organization's Catalogs.
- 2 On the vApp Templates tab, right-click a vApp template and select Copy to Catalog.
- 3 Type a name and optional description for the vApp template.
- 4 Select the destination catalog and virtual datacenter.
 - If you select a published catalog, the vApp template will be available to all organizations in the vCloud Director installation.
- 5 Click OK.

Move a vApp Template Between an Organization's Catalogs

You can move a vApp template from one catalog in your organization to another catalog in the same organization. This is useful if you want to move a template from a published catalog to an unpublished catalog or the reverse.

You are an organization administrator or catalog author.

Prerequisites

You must have access to at least two catalogs and a virtual datacenter with available space.

Procedure

- 1 Click Catalogs > My Organization's Catalogs.
- 2 On the vApp Templates tab, right-click a vApp template and select Move To Catalog.
- 3 Select a destination catalog and virtual datacenter.
 - If you select a published catalog, the vApp template will be available to all organizations in the vCloud Director installation.
- 4 Click OK.

vCloud Director copies the source vApp template to the destination catalog and then deletes the source vApp template.

Delete a vApp Template

You can delete a vApp template from an organization catalog. If the catalog is published, the vApp template is also deleted from **Public Catalogs**.

You are at least a vApp author.

Procedure

- 1 Click Catalogs > My Organization's Catalogs.
- On the **vApp Templates** tab, select a vApp template, right-click, and select **Delete**.
- 3 Click Yes.

The selected vApp is deleted.

Save a vApp as a vApp Template

You can save a vApp to a catalog as a vApp template.

Prerequisites

Verify that the following conditions are met.

- Your organization has a catalog and a virtual datacenter with available space.
- You are at least a vApp author.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Right-click a vApp and select Add to Catalog.

Beginning with vCloud Director 5.5, you can add a running vApp to a catalog. If you select a running vApp, it will be added to the catalog as a vApp template with all of its virtual machines in a suspended state.

- 4 Type a name and optional description for the vApp template.
- 5 Select a virtual datacenter, a catalog, and a storage lease.
- 6 Select a vApp creation option.

This option applies when creating a vApp based on this template. It is ignored when building a vApp using individual virtual machines from this template.

Option	Description
Make identical copy	vApps that are created from this vApp template must follow the guest operating system settings of the vApp template. If you select this option, and guest customization is enabled, the guest operating system is personalized.
Customize VM settings	Guest operating system is personalized regardless of the vApp template settings, and the guest operating system is personalized when the vApp is deployed. This option requires that a supported version of VMware Tools be installed on all virtual machines in the vApp.

7 Click OK.

The vApp is saved as a vApp template and appears in the destination catalog.

Modify vApp Properties

You are an organization administrator.

Procedure

1 Click Catalogs > My Organization's Catalogs.

- On the vApp Templates tab, right-click a vApp template and select Properties.
- 3 On the **General** tab, modify the vApp template name and description.
- 4 Select a vApp creation option.

This option applies when creating a vApp based on this template. It is ignored when building a vApp using individual virtual machines from this template.

Option	Description
Make identical copy	vApps that are created from this vApp template must follow the guest operating system settings of the vApp template. If you select this option, and guest customization is enabled, the guest operating system is personalized.
Customize VM settings	Guest operating system is personalized regardless of the vApp template settings, and the guest operating system is personalized when the vApp is deployed. This option requires that a supported version of VMware Tools be installed on all virtual machines in the vApp.

- 5 Choose whether or not to mark the vApp template as a Gold Master in the catalog.
- If you mark a vApp template as a Gold Master, this information appears in the list of vApp templates.
- 6 To reset the vApp template storage lease, select the **Reset lease** check box and select a new storage lease.
- 7 Click **OK**.

Change the Guest OS Properties of a vApp Template

You can change the guest operating system properties of an existing vApp template, such as password and domain properties.

Prerequisites

Verify that you are at least a vApp author.

Procedure

- 1 Click Catalogs.
- 2 In the left pane, click My Organization's Catalogs.
- 3 Click the **vApp Templates** tab, right-click the vApp template to change and select **Open**.
- 4 Click the **VMs** tab, right-click the virtual machine to change and select **Properties**.
- 5 Click the **Guest OS Customization** tab.
- 6 (Optional) Change guest OS properties.

Option	Description
Guest customization.	Enables or disables guest customization.
Change SID	Runs Sysprep to change Windows SID. This option is available only for virtual machines running a Windows guest operating system.
Allow local administrator password	Allows setting an administrator password on the guest operating system.
Require administrator to change password on first login	Requires the administrator to change this password the first time they log in to the guest operating system.
Enable this VM to join a domain	Type domain properties to have the virtual machine join a domain
Browse	Navigate to a customization script, and click OK to add the customization script to the vApp template.

7 Click **OK**.

Working with vApps

7

A vApp consists of one or more virtual machines that communicate over a network and use resources and services in a deployed environment. A vApp can contain multiple virtual machines.

This chapter includes the following topics:

- "Create a vApp From a vApp Template," on page 62
- "Create a New vApp," on page 62
- "Import a Virtual Machine as a vApp," on page 64
- "Create a vApp From an OVF Package," on page 64
- "About the vApp Placement Engine," on page 65
- "Download a vApp as an OVF Package," on page 66
- "Start a vApp," on page 67
- "Start a vApp with an Older Version of VMware Tools," on page 67
- "Stop a vApp," on page 67
- "Suspend a vApp," on page 68
- "Discard the Suspended State of a vApp," on page 68
- "Reset a vApp or Virtual Machine," on page 68
- "View vApp Virtual Machines," on page 68
- "Add a Virtual Machine to a vApp," on page 69
- "Import a Virtual Machine to a vApp from vSphere," on page 69
- "Remove Virtual Machines from a vApp," on page 70
- "Set vApp Start and Stop Options," on page 70
- "Working with Networks in a vApp," on page 71
- "Editing vApp Properties," on page 83
- "Display a vApp Diagram," on page 85
- "Change the Owner of a vApp," on page 85
- "Upgrade the Virtual Hardware Version for a vApp," on page 85
- "Save vApp as a vApp Template to Your Catalog," on page 86
- "Save a Powered-On vApp to your Catalog," on page 86

- "Create a Snapshot of a vApp," on page 87
- "Revert a vApp to a Snapshot," on page 87
- "Remove a Snapshot of a vApp," on page 87
- "Copy a vApp to Another Virtual Datacenter," on page 88
- "Copy a Powered-On vApp," on page 88
- "Move a vApp to Another Virtual Datacenter," on page 89
- "Delete a vApp," on page 89

Create a vApp From a vApp Template

You can create a new vApp based on a vApp template stored in a catalog to which you have access.

- Only organization administrators and vApp authors can access vApp templates in public catalogs.
- vApp users and above can access vApp templates in organization catalogs shared to them.

If the vApp template is based on an OVF file that includes OVF properties for customizing its virtual machines, those properties are passed to the vApp. If any of those properties are user-configurable, you can specify the values.

Procedure

- 1 Click My Cloud > vApps.
- 2 Click the **Add vApp from Catalog** button.
- 3 Select My organization's catalogs or Public catalogs from the drop-down menu.
- 4 Select a vApp template and click **Next**.
- 5 Type a name and optional description for the vApp.
- 6 Select a runtime and storage lease and click Next.
- 7 Select a virtual datacenter, configure the virtual machines in the vApp, and click Next.
- 8 Configure the custom properties, if any, and click Next.
- 9 Configure the networking options for the vApp and click **Next**.
- 10 Review the vApp summary information and click Finish.

vCloud Director creates a vApp in My Cloud.

Create a New vApp

If you don't want to create a vApp based on a vApp template, you can create a new vApp using virtual machines from vApp templates, new virtual machines, or a combination of both.

You are at least a vApp author.

Procedure

- Complete the vApp Profile on page 63
 When you create a new vApp, you must provide some basic information.
- 2 Add Virtual Machines to the vApp on page 63

You can search your catalogs for virtual machines to add to the vApp or add new, blank virtual machines.

3 Configure the Virtual Machines on page 63

Select the virtual datacenter in which this vApp is stored and runs when it's started. Name each virtual machine and select the network to which you want it to connect. You can configure additional properties for virtual machines after you complete the wizard.

4 Configure Networks on page 64

You can determine how the vApp, its virtual machines, and its networks connect to the organization's networks.

Complete the vApp Profile

When you create a new vApp, you must provide some basic information.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps** and click the **Build New vApp** button.
- 3 Type a name and optional description.
- 4 Select a runtime and storage lease and click Next.

Add Virtual Machines to the vApp

You can search your catalogs for virtual machines to add to the vApp or add new, blank virtual machines.

You must be an organization administrator or vApp author to access public catalogs.

Procedure

- To add virtual machines from vApp templates, select **My organization's catalogs** or **Public catalogs** from the drop-down menu, select one or more virtual machines, and click **Add**.
- 2 To add a new virtual machine, click New Virtual Machine, provide the required information about the virtual machine, and click OK.
 - After you finish creating the new vApp, you can power on the new virtual machine and install an operating system.
- 3 Click Next.

Configure the Virtual Machines

Select the virtual datacenter in which this vApp is stored and runs when it's started. Name each virtual machine and select the network to which you want it to connect. You can configure additional properties for virtual machines after you complete the wizard.

Procedure

- 1 Select a virtual datacenter.
- 2 (Optional) Modify the full name and computer name of each virtual machine.
- 3 Select a primary NIC and network for each virtual machine.
- 4 Select an IP assignment method for each NIC.
 - If you select **Static Manual**, type the IP address.
- 5 Click Next.

Configure Networks

You can determine how the vApp, its virtual machines, and its networks connect to the organization's networks.

Procedure

- 1 Select Show networking details.
- 2 Review the network information.
- 3 Click Next.
- 4 Review the summary for the vApp.
- 5 Click Finish.

Import a Virtual Machine as a vApp

You can import a vSphere virtual machine to your organization as a vApp.

Prerequisites

Verify that you are at least a vApp author.

Procedure

- 1 Select **My Cloud > vApps**.
- 2 Click Import from vSphere.
- 3 Select a vCenter server from the drop-down menu and select a virtual machine to import.
- 4 Type a name and optional description for the vApp.
- 5 Select a virtual datacenter to which to import the vApp from the drop-down menu.
- 6 (Optional) Select a storage policy for the vApp from the drop-down menu.
- 7 Choose whether to move or copy the imported virtual machine, and click **OK**.

vCloud Director imports the vApp into My Cloud.

Create a vApp From an OVF Package

You can create and deploy a vApp directly from an OVF package without creating a vApp template and corresponding catalog item.

Prerequisites

Verify that you have an OVF package to upload and that you have permission to upload OVF packages and create vApps.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps** and click **Add vApp from OVF**.

Select the source from which to upload the OVF package and click **Next**.

Option	Action
URL	Type the URL of the OVF package to use.
Local file	Click Browse and navigate to the OVF package to use.

- 4 Review the details of the uploaded OVF and click **Next**.
- 5 Type a name and optional description for the vApp.
- 6 Select a virtual datacenter on which to store and run the vApp from the drop-down menu and click Next.
- 7 Select a storage policy for the vApp's virtual machines from the drop-down menu and click Next.
- 8 Select the network for the virtual machines to connect to from each virtual machine's drop-down menu and click Next.
- Review the hardware settings for the virtual machines in the vApp and optionally change those configurations.
 - If you change the hard disk size, you might need to configure the guest operating system after you power on the virtual machine. You can only increase hard disk size, but not decrease it.
- 10 Click Next.
- 11 Review the vApp's configuration and click **Finish**.

About the vApp Placement Engine

The vCloud Director placement engine determines what resources, including resource pools, datastores, and networks or network pools, on which to place the virtual machines in a vApp. The placement decision is made independently for each virtual machine in a vApp based on the requirements of that virtual machine.

The placement engine runs in the following scenarios.

- When you create a vApp, the placement engine determines what resource pool, datastore, and network pool on which to place the vApp's virtual machines.
- When you start a vApp, the placement engine might selectively move the vApp's virtual machines to another resource pool, datastore, or network pool if the current resource pool, datastore, or network pool lacks sufficient resources for the vApp to power on.
- When you change the storage policy of a virtual machine, the placement engine moves the virtual machine to a datastore and resource pool that support the new storage policy.
- When virtual machines are migrated to different resource pools.

The placement engine uses the following criteria to select candidate resource pools for a virtual machine.

- CPU capacity
- Memory capacity
- Number of virtual CPUs
- Hardware version supported by the host

The placement engine filters out disabled resource pools from the candidate list so that no virtual machine is created on a disabled resource pool. When possible, the placement engine places virtual machines on the same hub as other virtual machines in the organization virtual datacenter.

The placement engine uses the following criteria to select candidate datastores for a vApp and its virtual machines.

- Storage capacity
- Storage policy

The placement engine filters out disabled datastores from the candidate list so that no virtual machine is created on a disabled datastore.

The placement engine uses the network name to select candidate network pools for a vApp and its virtual machines.

After the placement engine selects a set of candidate resources, it ranks the resources and picks the best location for each virtual machine based on the CPU, virtual RAM, and storage configuration of each virtual machine.

While ranking resources, the placement engine examines the current and estimated future resource use. Estimated future use is calculated based on powered-off virtual machines currently placed on a given resource pool and their expected use after they are powered on. For CPU and memory, the placement engine looks at the current unreserved capacity, the maximum use, and the estimated future unreserved capacity. For storage, it looks at the aggregated provisioned capacity provided by the cluster that each resource pool belongs to. The placement engine then considers the weighted metrics of the current and future suitability of each resource pool.

The placement engine favors resource pools that provide the minimum of unreserved capacity for CPU and memory and free capacity for storage. It also gives lower preference to yellow clusters so that yellow clusters are only selected if no healthy cluster is available that satisfies the placement criteria.

When a virtual machine is powered on, either as part of starting a vApp or on its own, the placement engine runs to validate that the resource pool the virtual machine is assigned to has sufficient resources to support the requirements of the virtual machine. This step is necessary because the resource availability on the resource pool might have changed since the virtual machine was created on the resource pool. If the resource pool lacks sufficient capacity to power on the virtual machine, the placement engine finds another compatible resource pool on the provider virtual datacenter that satisfies the requirements of the virtual machine and places the virtual machine there. This substitution might result in the migration of the virtual machine's VMDKs to a different datastore if no suitable resource pools are connected to the datastore the VMDKs are located on.

During concurrent deployment situations when a resource pool is close to capacity, the validation of that resource pool might succeed even though the resource pool lacks the resources to support the virtual machine. In these cases, the virtual machine cannot power on. If a virtual machine fails to power on in this situation, start the power on operation again to prompt the placement engine to migrate the virtual machine to a different resource pool.

When the cluster that a resource pool belongs to is close to capacity, a virtual machine on that resource pool might still be able to power on even when no individual host has the capacity to power on the virtual machine. This happens as a result of capacity fragmentation at the cluster level. In such cases, a system administrator should migrate a few virtual machines out of the cluster so that the cluster maintains sufficient capacity.

Download a vApp as an OVF Package

You can download a vApp as an OVF package.

Prerequisites

Verify that the vApp is powered off and undeployed.

Procedure

1 Click My Cloud.

- 2 In the left pane, click **vApps**.
- 3 Right-click a vApp and select **Download**.
- 4 Type a name for the downloaded OVF package and click Browse to select a download destination.
- 5 (Optional) Select **Preserve Identity** to include the UUIDs and MAC addresses of the vApp's virtual machines in the downloaded OVF package.
- 6 Click OK.

Start a vApp

Starting a vApp powers on all the virtual machines in the vApp that are not already powered on.

You are at least a vApp author.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right click, and select **Start**.

Start a vApp with an Older Version of VMware Tools

If a virtual machine in a vApp has an older version of VMware Tools installed and is enabled for guest customization, you might not be able to start it.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select **vApps**.
- 3 Select a vApp, right-click, and select **Open**.
- 4 Select a virtual machine, right-click, and select **Properties**.
- 5 On the **Guest OS Customization** tab, deselect the **Enable Guest Customization** check box and click **OK**.
- 6 (Optional) Repeat this step for all your virtual machines.
- 7 Select the vApp, right-click, and select **Start**.

Stop a vApp

Stopping a vApp powers off or shuts down all the virtual machines in the vApp. You must stop a vApp before you can perform certain actions. For example, adding it to a catalog, copying it, moving it, and so on.

You can specify whether stopping a vApp powers off or shuts down its virtual machines in the vApp properties page.

Prerequisites

The vApp must be started.

Procedure

- Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Stop**.

4 Click **OK**.

Suspend a vApp

You can suspend a vApp to save its current state.

Prerequisites

The vApp is running.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select Suspend.

The vApp is stopped and is labeled as **Stopped**.

Discard the Suspended State of a vApp

You can discard the suspended state of a vApp.

Prerequisites

The vApp must be stopped and in a suspended state.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select **Discard Suspended State**.
- 4 Click Yes.

Reset a vApp or Virtual Machine

Resetting a virtual machine clears state (memory, cache, and so on), but the vApps and virtual machines continue to run.

Prerequisites

Your vApp is started and virtual machine is powered on.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select **vApps** or **VMs**.
- 3 Select a vApp or virtual machine, right-click, and select **Reset**.

View vApp Virtual Machines

You can access and display the virtual machines in a vApp.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.

- 3 Select a vApp, right-click, and select **Open**.
- 4 Click on the Virtual Machines tab.

Add a Virtual Machine to a vApp

You can add a virtual machine to a vApp.

If the virtual machine is based on an OVF file that includes OVF properties for customization, those properties are retained in the vApp. If any of those properties are user-configurable, you can specify the values in the virtual machine's properties pane after you add it to the vApp.

For information about supported network adapter types, see http://kb.vmware.com/kb/1001805.

Prerequisites

You must be an organization administrator or vApp author to access virtual machines in public catalogs.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click the vApp and select **Open**.
- 3 On the **Virtual Machines** tab, click the **Add VM** button.
- 4 To add virtual machines from vApp templates, select **My organization's catalogs** or **Public catalogs** from the drop-down menu, select one or more virtual machines, and click **Add**.
- To add a new virtual machine, click **New Virtual Machine**, provide the required information about the virtual machine, and click **OK**.
 - After you finish creating the new vApp, you can power on the new virtual machine and install an operating system.
- 6 Click Next.
- 7 (Optional) Modify the full name and computer name of each virtual machine.
- 8 Select a primary NIC and network for each virtual machine.
- 9 (Optional) Select **Show network adapter type** and select a type for each NIC.
- 10 Select an IP assignment method for each NIC.
 - If you select **Static Manual**, type the IP address.
- 11 Click Next.
- 12 Select Show networking details, review the network information, and click Next.
- 13 Review the summary for the vApp and click Finish.

Import a Virtual Machine to a vApp from vSphere

You can import an existing virtual machine to a vApp from vSphere

Prerequisites

Verify that you are a system administrator.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click the vApp and select **Open**.
- 3 On the **Virtual Machines** tab, click **Import from vSphere**.

- 4 Select the source vCenter server from the drop-down menu and select the virtual machine to import.
- 5 Enter a name for the imported virtual machine.
- 6 (Optional) Enter a description for the imported virtual machine.
- 7 (Optional) Select a storage policy for the imported virtual machine.
- 8 Choose whether to copy the virtual machine or to move it from the source vCenter server, and click **OK**

Remove Virtual Machines from a vApp

You can remove virtual machines from a vApp.

You are at least a vApp author.

Prerequisites

The virtual machine is powered off.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the Virtual Machines tab, select a virtual machine, right-click and select Delete.
- 5 Click Yes.

Set vApp Start and Stop Options

You can specify certain options that affect what happens to the virtual machines when a vApp is started and stopped.

Prerequisites

You are at least a vApp user.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Properties**.
- 4 On the **Starting and Stopping VMs** tab, specify the options.

Option	Description		
Order	For vApps with multiple virtual machines, you can specify the order in which the machines start and stop by typing numbers in the text box. Virtual machines with lower numbers start first and stop last. You cannot enter negative numbers. Virtual machines with the same order are started and stopped at the same time.		
Start Action	Determines what happens to virtual machines when you start the vApp that contains them. By default, this option is set to Power On .		
Boot Delay	How many seconds vCloud Director waits after starting the virtual machine before starting the next virtual machine.		

Option	Description		
Stop Action	Determines what happens to virtual machines when you stop the vApp that contains them. By default, this option is set to Power Off , but you can also set it to Shutdown .		
Stop Delay	How many seconds vCloud Director waits after stopping the virtual machine before stopping the next virtual machine.		

5 Click OK.

Example: Starting and Stopping Virtual Machines

This example shows a the order, boot delay, and stop delay options for the virtual machines in a vApp and how those options affect when each virtual machine starts and stops.

Table 7-1. Virtual Machine Start and Stop Options on vApp1

Virtual Machine	Order	Boot Delay	Stop Delay
VM1	1	0	10
VM2	1	10	10
VM3	1	20	30
VM4	2	0	20
VM5	2	30	60
VM6	3	40	10

When vApp1 is started, the virtual machines start as follows.

- 1 VM1, VM2, and VM3 start at the same time.
- 2 After 20 seconds (the longest boot delay from the order 1 virtual machines), VM4 and VM5 start.
- 3 After 30 seconds (the longest boot delay from the order 2 virtual machines) VM6 starts.

When vApp1 is stopped, the virtual machines stop as follows.

- 1 VM6 stops.
- 2 After 10 seconds, VM5 and VM4 stop.
- 3 After 60 seconds, VM3, VM2, and VM1 stop.

Working with Networks in a vApp

The virtual machines in a vApp can connect to vApp networks (isolated or routed) and organization virtual datacenter networks (direct or fenced). You can add networks of different types to a vApp to address multiple networking scenarios.

Select the **Networking** tab in a vApp and select the **Show networking details** check box to view a list of the networks that are available to the vApp. Virtual machines in the vApp can connect to these networks. If you want to connect a virtual machine to a different network, you must first add it to the vApp.

A vApp can include vApp networks and organization virtual datacenter networks. A vApp network can be isolated by selecting **None** in the **Connection** drop-down menu. An isolated vApp network is totally contained within the vApp. You can also route a vApp network to an organization virtual datacenter network to provide connectivity to virtual machines outside of the vApp. For routed vApp networks, you can configure network services, such as a firewall and static routing.

You can connect a vApp directly to an organization virtual datacenter network. If you have multiple vApps that contain identical virtual machines connected to the same organization virtual datacenter network and you want to start the vApps at the same time, you can fence the vApp. This allows you to power on the virtual machines without conflict, by isolating their MAC and IP addresses.

View vApp Networks

You can access and display the networks in a vApp.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select **Open**.
- 4 Click on the **Networking** tab.
- 5 Select the **Show networking details** to display details about each network.

Adding Networks to a vApp

You can add vApp networks and organization virtual datacenter networks to a vApp.

- Add a vApp Network to a vApp on page 72
 Add a vApp network to a vApp to make the network available to virtual machines in the vApp.
- Add an Organization Virtual Datacenter Network to a vApp on page 73
 You can add an organization virtual datacenter network to a vApp to make the network available to virtual machines in the vApp.

Add a vApp Network to a vApp

Add a vApp network to a vApp to make the network available to virtual machines in the vApp.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**, right-click, and select **Open**.
- 3 On the **Networking** tab, select the **Show networking details** check box.
- 4 Click the **Add Network** button.
- 5 Select vApp Network and click Next.
- 6 Type the network specifications and click **Next**.
- 7 Type a network name and optional description and click **Next**.
- 8 Review your vApp network settings and click Finish.
 - vCloud Director creates an isolated vApp network and displays it in the network list.
- 9 (Optional) Select an organization virtual datacenter network in the **Connection** drop-down menu.
 - This routes the vApp network to the organization virtual datacenter network.
- 10 Click Apply.

What to do next

Connect a virtual machine in the vApp to the network.

Add an Organization Virtual Datacenter Network to a vApp

You can add an organization virtual datacenter network to a vApp to make the network available to virtual machines in the vApp.

Connections can be direct or fenced. Fencing allows identical virtual machines in different vApps to be powered on without conflict by isolating the MAC and IP addresses of the virtual machines.

When fencing is enabled and the vApp is powered on, an isolated network is created from the organization virtual datacenter's network pool. An edge gateway is created and attached to the isolated network and the organization virtual datacenter network. Traffic going to and from the virtual machines pass through the edge gateway, which translates the IP address using NAT and proxy-AR, which allows a router to pass traffic between two networks using the same IP space.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**, right-click, and select **Open**.
- 3 Click the **Networking** tab and select the **Show networking details** check box.
- 4 Click Add Network.
- 5 Select Organization VDC Network and click Next.
- Select an organization virtual datacenter network and click Finish.
 vCloud Director adds the organization virtual datacenter network and displays it in the network list.
- 7 (Optional) Select the **Fence vApp** check box.
 - The connection changes from direct to fenced for all organization virtual datacenter networks in the vApp.
- 8 Click Apply.

What to do next

Connect a virtual machine in the vApp to the network.

Configuring Network Services for a vApp Network

You can configure network services, such as DHCP, firewalls, network address translation (NAT), and static routing for certain vApp networks.

The network services available depend on the type of vApp network.

Table 7-2. Network Services Available by Network Type

vApp Network Type	DHCP	Firewall	NAT	Static Routing
Direct				
Routed	X	X	X	X
Isolated	X			

Configure DHCP for an vApp Network

You can configure certain vApp networks to provide DHCP services to virtual machines in the vApp.

When you enable DHCP for a vApp network, connect a NIC on virtual machine in the vApp to that network, and select **DHCP** as the IP mode for that NIC, vCloud Director assigns a DHCP IP address to the virtual machine when you power it on.

Prerequisites

A routed vApp network or an isolated vApp network.

Procedure

- 1 Click the My Cloud tab and click vApps in the left pane.
- 2 Right-click a vApp and select **Open**.
- 3 On the **Networking** tab, select **Show networking details**.
- 4 Right-click the vApp network and select Configure Services.
- 5 Click the **DHCP** tab and select **Enable DHCP**.
- Type a range of IP addresses or use the default range.

 vCloud Director uses these addresses to satisfy DHCP requests. The range of DHCP IP addresses cannot overlap with the static IP pool for the vApp network.
- 7 Set the default lease time and maximum lease time or use the default values and click OK.
- 8 Click Apply.

vCloud Director updates the network to provide DHCP services.

NOTE If the DNS settings on a DHCP-enabled vApp network are changed, the vApp network no longer provides DHCP services. To correct this issue, disable and reenable DHCP on the vApp network.

Configure the Firewall for a vApp Network

You can configure certain vApp networks to provide firewall services. Enable the firewall on a vApp network to enforce firewall rules on incoming traffic, outgoing traffic, or both.

When you enable the firewall, you can specify a default firewall action to deny all incoming and outgoing traffic or to allow all incoming and outgoing traffic. You can also add specific firewall rules to allow or deny traffic that matches the rules to pass through the firewall. These rules take precedence over the default firewall action. See "Add a Firewall Rule to a vApp Network," on page 75.

If a system administrator specified syslog server settings and those settings have been applied to the vApp network, then you can log events related to the default firewall action. For information about applying syslog server settings, see "Apply Syslog Server Settings to a vApp Network," on page 82. To view the current syslog server settings see "View Syslog Server Settings for a vApp Network," on page 82.

Prerequisites

A routed vApp network.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click a vApp and select Open.
- 3 On the Networking tab, select Show networking details.
- 4 Right-click the vApp network and select Configure Services.
- 5 Click the Firewall tab and select Enable firewall to enable firewall services or deselect it to disable firewall services.

6 Select the default firewall action.

Option Description		
Deny	Blocks all traffic except when overridden by a firewall rule.	
Allow	Allows all traffic except when overridden by a firewall rule.	

- 7 (Optional) Select the **Log** check box to log events related to the default firewall action.
- 8 Click OK.
- 9 Click Apply.

Add a Firewall Rule to a vApp Network

You can add firewall rules to a vApp network that supports a firewall. You can create rules to allow or deny traffic that matches the rules to pass through the firewall.

For a firewall rule to be enforced, you must enable the firewall for the vApp network. See "Configure the Firewall for a vApp Network," on page 74.

When you add a new firewall rule to a vApp network, it appears at the end of the firewall rule list. For information about setting the order in which firewall rules are enforced, see "Reorder Firewall Rules for a vApp Network," on page 76.

If a system administrator specified syslog server settings and those settings were applied to the vApp network, then you can log firewall rule events. For information about applying syslog server settings, see "Apply Syslog Server Settings to a vApp Network," on page 82. To view the current syslog server settings, see "View Syslog Server Settings for a vApp Network," on page 82.

Prerequisites

A routed vApp network.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click a vApp and select **Open**.
- 3 On the **Networking** tab, select **Show networking details**.
- 4 Right-click the vApp network and select Configure Services.
- 5 Click the **Firewall** tab and click **Add**.
- 6 Type a name for the rule.
- 7 (Optional) Select **Match rule on translated IP** to have the rule check against translated IP addresses rather than original IP addresses and choose a traffic direction to apply this rule on.
- 8 Type the traffic **Source**.

Option	Description	
IP address	Type a source IP address to apply this rule on.	
Range of IP addresses	Type a range of source IP addresses to apply this rule on.	
CIDR	Type the CIDR notation of traffic to apply this rule on.	
internal	Apply this rule to all internal traffic.	
external	Apply this rule to all external traffic.	
any	Apply this rule to traffic from any source.	

9 Select a **Source port** to apply this rule on from the drop-down menu.

10 Type the traffic **Destination**.

Option	Description Type a destination IP address to apply this rule on.	
IP address		
Range of IP addresses	Type a range of destination IP addresses to apply this rule on.	
CIDR	Type the CIDR notation of traffic to apply this rule on.	
internal	Apply this rule to all internal traffic.	
external	Apply this rule to all external traffic.	
any	Apply this rule to traffic with any destination.	

- 11 Select the **Destination port** to apply this rule on from the drop-down menu.
- 12 Select the **Protocol** to apply this rule on from the drop-down menu.
- 13 Select the action.

A firewall rule can allow or deny traffic that matches the rule.

- 14 Select the **Enabled** check box.
- 15 (Optional) Select the **Log network traffic for firewall rule** check box.

If you enable this option, vCloud Director sends log events to the syslog server for connections affected by this rule. Each syslog message includes logical network and organization UUIDs.

- 16 Click OK and click OK again.
- 17 Click Apply.

Reorder Firewall Rules for a vApp Network

Firewall rules are enforced in the order in which they appear in the firewall list. You can change the order of the rules in the list.

When you add a new firewall rule to a vApp network, it appears at the bottom of the firewall rule list. If you want to enforce the new rule before an existing rule, reorder the rules.

Prerequisites

A routed vApp network with two or more firewall rules.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click a vApp and select **Open**.
- 3 On the **Networking** tab, select **Show networking details**.
- 4 Right-click the vApp network and select **Configure Services**.
- 5 Click the **Firewall** tab.
- 6 Drag and drop the firewall rules to establish the order in which the rules are applied.
- 7 Click OK.
- 8 Click Apply.

Enable IP Masquerading for a vApp Network

You can configure certain vApp networks to provide IP masquerade services. Enable IP masquerading on a vApp network to hide the internal IP addresses of virtual machines from the organization virtual datacenter network.

When you enable IP masquerade, vCloud Director translates a virtual machine's private, internal IP address to a public IP address for outbound traffic.

Prerequisites

Verify that a routed vApp network exists.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click a vApp and select **Open**.
- 3 On the **Networking** tab, select **Show networking details**.
- 4 Right-click the vApp network and select **Configure Services**.
- 5 Click the **NAT** tab and select **Port Forwarding**.
- 6 Select **Enable IP Masquerade** and click **OK**.
- 7 Click Apply.

Add a Port Forwarding Rule to a vApp Network

You can configure certain vApp networks to provide port forwarding by adding a NAT mapping rule. Port forwarding provides external access to services running on virtual machines on the vApp network.

When you configure port forwarding, vCloud Director maps an external port to a service running on a port on a virtual machine for inbound traffic.

When you add a new port forwarding rule to a vApp network, it appears at the bottom of the NAT mapping rule list. For information about how to set the order in which port forwarding rules are enforced, see "Reorder Port Forwarding Rules for a vApp Network," on page 78.

Prerequisites

A routed vApp network.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click a vApp and select Open.
- 3 On the **Networking** tab, select **Show networking details**.
- 4 Right-click the vApp network and select **Configure Services**.
- 5 Click the **NAT** tab, select **Port Forwarding**, and click **Add**.
- 6 Configure the port forwarding rule.
 - a Select an external port.
 - b Select an internal port.
 - c Select a protocol for the type of traffic to forward.

- d Select a VM interface.
- e Click OK.
- 7 Click OK.
- 8 Click Apply.

Add an IP Translation Rule to a vApp Network

You can configure certain vApp networks to provide IP translation by adding a NAT mapping rule.

When you create an IP translation rule for a network, vCloud Director adds a DNAT and SNAT rule to the edge gateway associated with the network's port group. The DNAT rule translates an external IP address to an internal IP address for inbound traffic. The SNAT rule translates an internal IP address to an external IP address for outbound traffic. If the network is also using IP masquerade, the SNAT rule takes precedence.

Prerequisites

Verify that you have a routed vApp network.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click a vApp and select **Open**.
- 3 Click the **Networking** tab and select **Show networking details**.
- 4 Right-click the vApp network and select **Configure Services**.
- 5 Click the **NAT** tab, select **IP Translation**, and click **Add**.
- 6 Select a virtual machine interface and mapping mode and click **OK**.
 - For Manual mapping mode, type an external IP address.
- 7 If you select manual mapping mode, type an external IP address.
- 8 Click OK.
- 9 Click **Apply**.

Reorder Port Forwarding Rules for a vApp Network

Port forwarding rules are enforced in the order in which they appear in the NAT mapping list. You can change the order of the rules in the list.

When you add a new port forwarding rule to a vApp network, it appears at the bottom of the NAT mapping rule list. To enforce the new rule before an existing rule, reorder the rules.

Prerequisites

A routed vApp network with two or more port forwarding rules.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click a vApp and select **Open**.
- 3 On the **Networking** tab, select **Show networking details** and click **Details**.
- 4 On the **NAT** tab, click and drag the rules to establish the order in which the rules are applied and click **OK**.
- 5 Click **Apply**.

Enable Static Routing for a vApp Network

You can configure certain vApp networks to provide static routing services. After you enable static routing on two or more vApp networks, you can add static routes to allow virtual machines on different vApp networks to communicate.

To route traffic between two vApp networks, you must enable static routing on both networks.

Prerequisites

A routed vApp network.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click a vApp and select **Open**.
- 3 On the **Networking** tab, select **Show networking details**.
- 4 Right-click the vApp network and select **Configure Services**.
- 5 On the **Static Routing** tab, select **Enable static routing** and click **OK**.
- 6 Click Apply.

What to do next

Enable static routing on another vApp network and create static routes between the two vApp networks.

Add Static Routes to vApp Networks

You can add static routes between two vApp networks that are routed to the same organization virtual datacenter network. Static routes allow traffic between the networks.

You cannot add static routes to a fenced vApp or between overlapping networks. After you add a static route to a vApp network, configure the network firewall rules to allow traffic on the static route. For vApps with static routes, select the **Always use assigned IP addresses until this vApp or associated networks are deleted** check box.

Static routes function only when the vApps containing the routes are running. If you change the parent network of a vApp, delete a vApp, or delete a vApp network, and the vApp includes static routes, those routes cannot function and you must remove them manually.

Prerequisites

Verify that the following conditions are met.

- Two vApp networks are routed to the same organization virtual datacenter network.
- The vApp networks are in vApps that were started at least once.
- Static routing is enabled on both vApp networks.

Procedure

- 1 Click the **My Cloud** tab and click **vApps** in the left pane.
- 2 Right-click the first vApp and select Open.
- 3 Click the **Networking** tab and select **Show networking details**.
- 4 Right-click the vApp network and select Configure Services.
- 5 Click the **Static Routing** tab and click **Add**.

6 Type a name, network address, and next hop IP and click **OK**.

The network address is for the vApp network to which to add a static route. The next hop IP is the external IP address of that vApp network's router.

- 7 Click **OK**.
- 8 Click Apply.
- 9 Repeat Step 2 through Step 8 for the second vApp network.

Example: Static Routing Example

vApp Network 1 and vApp Network 2 are both routed to Org Network Shared. You can create a static route on each vApp network to allow traffic between the networks. You can use information about the vApp networks to create the static routes.

Table 7-3. Network Information

Network Name Network Specification		Router External IP Address	
vApp Network 1	192.168.1.0/24	192.168.0.100	
App Network 2 192.168.2.0/24		192.168.0.101	
Org Network Shared 192.168.0.0/24		NA	

On vApp Network 1, create a static route to vApp Network 2. On vApp Network 2, create a static route to vApp Network 1.

Table 7-4. Static Routing Settings

vApp Network	Route Name	Network	Next Hop IP Address
vApp Network 1	tovapp2	192.168.2.0/24	192.168.0.101
vApp Network 2	tovapp1	192.168.1.0/24	192.168.0.100

What to do next

Create firewall rules for the vApp networks to allow traffic on the static routes.

Reset Your vApp Network

If the network services, such as DHCP settings, firewall settings, and so on, that are associated with a vApp network are not working as expected, an organization administrator can reset the network. Network services are not available during the reset.

Prerequisites

The vApp is running.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the **Networking** tab, select the **Show networking details** check box.
- 5 Select a vApp network, right-click, and select **Reset Network**.
- 6 Click Yes.

Delete a vApp Network

If you no longer need a network in your vApp, you can delete the network.

Prerequisites

The vApp is stopped and no virtual machines in the vApp are connected to the network.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select **vApps**.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the **Networking** tab, select the **Show networking details** check box.
- 5 Right-click a network in the list and select **Delete**.
- 6 Click Apply.

Modify Network Properties

You can modify the properties of the networks in a vApp.

Procedure

- 1 Select Administration.
- 2 Select Cloud Resources > Networks.
- 3 Select a network, right-click, and select **Properties**.

You can modify the name, description, and portions of the network specification.

- 4 Modify the relevant properties and click **OK**.
- 5 Click Apply.

Display the IP Allocations for Your vApp Network

You can review the IP allocations for the networks in your vApp.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select vApps.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the **Networking** tab, select the **Show networking details** check box.
- 5 Select a network, right-click, and select **IP Allocations**.
- 6 Review your allocations and click **OK**.

Configure IP Address Persistence

By default, when you stop a running vApp or power off a virtual machine, vCloud Director releases any IP and MAC addresses the virtual machines were using. You can configure a vApp to retain the network addresses of its virtual machines until the vApp, VM, or network is deleted.

Static routing relies on the IP addresses of the virtual machines and virtual routers in a vApp. For vApps that use static routing, enable IP persistence to make sure that static routes to and from the vApp remain valid.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select **vApps**.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the **Networking** tab, select the **Always use assigned IP addresses...** check box and click **Apply**.

The virtual machines in the vApp keep their assigned IP and MAC addresses, even when they are powered off.

View Syslog Server Settings for a vApp Network

You can view the syslog server settings for a routed vApp network.

vCloud Director supports logging events related to firewall rules to a syslog server specified by a system administrator.

If a vApp network does not have any syslog server settings and you think it should, or if the settings are not what you expected, then you can synchronize the network with the most current syslog server settings. See "Apply Syslog Server Settings to a vApp Network," on page 82. If there is still a problem after you synchronize, contact your system administrator.

Prerequisites

A routed vApp network.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the **Networking** tab, select a vApp network, right-click, and select **Properties**.
- 5 Click the **Syslog Server Settings** tab.

Apply Syslog Server Settings to a vApp Network

You apply syslog server settings to a routed vApp network to enable firewall rule logging.

Syslog server settings can only be specified by a system administrator. You should apply those settings to any vApp network that was created before the system administrator specified them. You should also apply the syslog server settings to a vApp network any time a system administrator changes the settings.

Prerequisites

A routed vApp network.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the **Networking** tab, select a vApp network, right-click, and select **Synchronize syslog server settings**.
- 5 Click Yes.

Editing vApp Properties

You can edit the properties of an existing vApp, including the vApp name and description, OVF environment properties, leases, and sharing settings.

- Modify a vApp Name and Description on page 83
 - You can change the name and description associated with a vApp to make it more meaningful.
- Modify vApp OVF Environment Properties on page 83
 - If a vApp includes user-configurable OVF environment properties, you can review and modify those properties.
- Reset vApp Leases on page 84
 - You can reset the runtime and storage leases for a vApp.
- Share a vApp on page 84
 - You can share your vApps with other groups or users in your organization. The access controls you set determine the operations that can be completed on the shared vApps.

Modify a vApp Name and Description

You can change the name and description associated with a vApp to make it more meaningful.

You are at least a vApp user.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select **Properties**.
- 4 On the **General** tab, modify the vApp name and description and click **OK**.

Modify vApp OVF Environment Properties

If a vApp includes user-configurable OVF environment properties, you can review and modify those properties.

If a virtual machine in the vApp includes a value for a user-configurable property of the same name, the virtual machine value takes precedence.

Prerequisites

The vApp is stopped and its OVF environment includes user-configurable properties.

Procedure

1 Click My Cloud.

- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Properties**.
- 4 On the **Custom Properties** tab, modify the properties and click **OK**.

Reset vApp Leases

You can reset the runtime and storage leases for a vApp.

You are at least a vApp user.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Properties**.
- 4 On the General tab, select the Reset leases check box, select a runtime and storage lease, and click OK.

Share a vApp

You can share your vApps with other groups or users in your organization. The access controls you set determine the operations that can be completed on the shared vApps.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Share**.
- 4 Click **Add Members**.
- 5 Select the users with whom you want to share the vApp.

Option	Action	
Everyone in the organization	Select this option.	
Specific users and group	Select this option, select the users and groups, and click Add .	

6 Select an access level for the users and groups.

Option	Description
Full control	Users can open, start, save a vApp as a vApp template (Add to Catalog), change the owner, copy to a catalog, and modify properties.
Read/write	Users can open, start, save a vApp as a vApp template (Add to Catalog), copy to catalog, and modify properties.
Read only	Users only have read access to a vApp.

7 Click **OK**.

Your vApp is shared with the specified users or groups.

Display a vApp Diagram

A vApp diagram provides a graphical view of the virtual machines and networks in a vApp.

Procedure

- 1 Click My Cloud.
- 2 On the **vApps** page, select a vApp, right-click, and select **Open**.
- 3 Click the **vApp Diagram** tab.

The vApp diagram is displayed.

What to do next

You can perform most of the same operations from this tab that you can from the **Virtual Machines** and **Networking** tabs.

Change the Owner of a vApp

You can change the owner of the vApp, for example, if a vApp owner leaves the company or changes roles within the company.

You are an organization administrator.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select Change Owner.
- 4 Search for a user or select one from the list.
 - You can search by user name or full name.
- 5 Click OK.

The new owner's name appears in the **Owner** column on the **vApp** page.

Upgrade the Virtual Hardware Version for a vApp

You can upgrade the virtual hardware version for all the virtual machines in a vApp. Higher virtual hardware versions support more features.

vCloud Director supports hardware version 4, hardware version 7, hardware version 8, hardware version 9, and hardware version 10 virtual machines depending on the resources backing the organization's virtual datacenters.

You cannot downgrade the hardware version of the virtual machines in a vApp.

Prerequisites

The vApp must be stopped and its virtual machines must have the latest version of VMware Tools installed.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select Upgrade Virtual Hardware Version.

4 Click Yes.

Save vApp as a vApp Template to Your Catalog

You can save a vApp as a vApp template and add it to the catalog.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Add to Catalog**.
- 4 (Optional) Modify the name and description.
- 5 Select the destination virtual datacenter and catalog.
- 6 In the **Storage lease:** drop-down menu, select when you would like the vApp template to expire.
- 7 Select an option.

Option	Description	
Make Identical Copy	vApps that are created from this vApp template must follow the guest operating system settings of the vApp template. If you select this option, and guest customization is enabled, the guest operating system is personalized.	
Customize VM Settings	Guest operating system is personalized regardless of the vApp template settings, and the guest operating system is personalized when the vApp is deployed.	

8 Click OK.

The vApp is saved as a vApp template in the selected catalog.

Save a Powered-On vApp to your Catalog

You can save a powered-on vApp as a vApp template and add it to the catalog.

You do not need to power off virtual machines in the vApp before you save the vApp to a catalog. The memory state of running virtual machines is preserved in the saved vApp.

Prerequisites

Verify that the following conditions are met.

- You are at least a vApp user.
- The organization virtual datacenter is backed by vCenter Server 5.5.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Add to Catalog**.
- 4 (Optional) Modify the name and description.
- 5 Select the destination catalog.
- 6 In the **Storage lease** drop-down menu, select when the vApp template should expire.

7 Select an option.

Option	Description	
Make Identical Copy	vApps that are created from this vApp template must follow the guest operating system settings of the vApp template. If you select this option, and guest customization is enabled, the guest operating system is personalized.	
Customize VM Settings	Guest operating system is personalized regardless of the vApp template settings, and the guest operating system is personalized when the vApp is deployed.	

8 Click OK.

The vApp is added to the catalog in a suspended mode. The added vApp is enabled for network fencing.

What to do next

Modify the network properties of the vApp or power on the vApp.

Create a Snapshot of a vApp

You can take a snapshot of all the virtual machines in a vApp. After you take the snapshots, you can revert all virtual machines in the vApp to the most recent snapshot, or remove all snapshots.

vApp snapshots have the following limitations.

- They do not capture NIC configurations.
- You cannot create them if any virtual machine in the vApp is connected to an independent disk.

Procedure

- 1 Select **My Cloud > vApps**.
- 2 Right-click the vApp and select **Create Snapshot**.
- 3 Click **OK**.

Revert a vApp to a Snapshot

You can revert all virtual machines in a vApp to the state they were in when the vApp snapshot was created.

Prerequisites

Verify that the vApp has a snapshot.

Procedure

- 1 Select My Cloud > vApps.
- 2 Right-click the vApp and select **Revert to Snapshot**.
- 3 Click Yes.

Remove a Snapshot of a vApp

You can remove a snapshot of a vApp.

Procedure

1 Select My Cloud > vApps.

- 2 Right-click the vApp and select Remove Snapshot.
- 3 Click Yes.

Copy a vApp to Another Virtual Datacenter

When you copy a vApp to another virtual datacenter, the original vApp remains in the source virtual datacenter.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select Copy to.
- 4 Type a name and description.
- 5 Select a virtual datacenter.
- 6 Click OK.

The new virtual datacenter for this vApp appears in the VDC column on the vApps page.

Copy a Powered-On vApp

To create a vApp based on an existing vApp, you can copy a vApp and change the copy to meet your needs.

You do not need to power off virtual machines in the vApp before you copy the vApp. The memory state of running virtual machines is preserved in the copied vApp.

Prerequisites

Verify that the following conditions are met.

- You are at least a vApp user.
- The organization virtual datacenter is backed by vCenter Server 5.5.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select **Copy to**.
- 4 Type a name and optional description.
- 5 Select a virtual datacenter.
- Select a storage policy from the drop-down menu.
- 7 Click **OK**.

A copy of the vApp is created in a suspended mode. The copied vApp is enabled for network fencing.

What to do next

Modify the network properties of the new vApp or power on the vApp.

Move a vApp to Another Virtual Datacenter

When you move a vApp to another virtual datacenter, the vApp is removed from the source virtual datacenter.

You are at least a vApp author.

Prerequisites

Your vApp is stopped.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Move to**.
- 4 Select a **VDC**.
- 5 Click OK.

Delete a vApp

You can delete a vApp, which removes it from your organization.

You must be at least a vApp author.

Prerequisites

Your vApp must be stopped.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.
- 3 Select a vApp, right-click, and select **Delete**.
- 4 Click Yes.

vCloud Director User's Guide

Working with Virtual Machines

8

Virtual machines have a guest operating system on which you can install and run any software supported by that operating system. In vCloud Director, you can install VMware Tools, insert DVDs and floppy disks, and remotely connect to virtual machines.

These are the most basic operations that you can do on a virtual machine.

- **Power On**, which is equal to powering on a physical machine.
- **Power Off**, which is equal to powering off a physical machine.
- **Suspend**, where the CPU of a deployed virtual machine is frozen. You can suspend a machine when you need to leave a virtual machine but do not want to lose its current state.
- **Reset**, which power cycles the virtual machine.

This chapter includes the following topics:

- "Open a Virtual Machine Console," on page 92
- "Power On a Virtual Machine," on page 92
- "Power Off a Virtual Machine," on page 92
- "Reset a vApp or Virtual Machine," on page 93
- "Suspend a Virtual Machine," on page 93
- "Resume a Suspended Virtual Machine," on page 93
- "Discard the Suspended State of a Virtual Machine," on page 93
- "Insert a CD/DVD," on page 94
- "Eject a CD/DVD," on page 94
- "Insert a Floppy," on page 94
- "Eject a Floppy," on page 95
- "Upgrade the Virtual Hardware Version for a Virtual Machine," on page 95
- "Connect Remotely to a Virtual Machine," on page 95
- "Create a Snapshot of a Virtual Machine," on page 96
- "Revert a Virtual Machine to a Snapshot," on page 96
- "Remove a Snapshot of a Virtual Machine," on page 96
- "Copy or Move a Virtual Machine to a vApp," on page 96
- "Delete a Virtual Machine," on page 97

- "Editing Virtual Machine Properties," on page 97
- "Installing VMware Tools," on page 104
- "Guest Operating Systems," on page 114

Open a Virtual Machine Console

Accessing your virtual machine console allows you to view information about a virtual machine, work with the guest operating system, and perform operations that affect the guest operating system.

You might be required to download and install VMware Remote Console Plug-In. Click **OK** in the dialog box that appears.

Prerequisites

The virtual machine is powered on.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select **Popout Console**.

If you close or refresh a virtual machine console while you have one or more client devices connected, those devices are disconnected.

Power On a Virtual Machine

Powering on a virtual machine is the equivalent of powering on a physical machine.

You cannot power on a virtual machine that has guest customization enabled unless the virtual machine has a current version of VMware Tools installed.

Prerequisites

A virtual machine that is powered off.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select **Power On**.

Power Off a Virtual Machine

Powering off a virtual machine is the equivalent of powering off a physical machine.

Prerequisites

A virtual machine that is powered on.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select **Power Off**.

Reset a vApp or Virtual Machine

Resetting a virtual machine clears state (memory, cache, and so on), but the vApps and virtual machines continue to run.

Prerequisites

Your vApp is started and virtual machine is powered on.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select **vApps** or **VMs**.
- 3 Select a vApp or virtual machine, right-click, and select Reset.

Suspend a Virtual Machine

Suspending a virtual machine preserves its current state.

Prerequisites

A virtual machine that is powered on.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select Suspend.
- 4 Click Yes.

Resume a Suspended Virtual Machine

You can resume a suspended virtual machine to power it on and return it to the state it was in when you suspended it.

Prerequisites

A suspended virtual machine.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select **Resume**.

Discard the Suspended State of a Virtual Machine

If a virtual machine is in a suspended state, you can discard this state, for example, to free storage space.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Discard Suspended State**.

4 Click Yes.

Insert a CD/DVD

You can access CD/DVD images from catalogs to use in a virtual machine guest operating system. You can install operating systems, applications, drivers, and so on.

Prerequisites

You have access to a catalog with media files.

Procedure

- Click My Cloud.
- 2 In the left pane, click VMs.
- 3 In the right pane, select a virtual machine, right-click, and select Insert CD/DVD from Catalog.
- 4 Select a media file and click Insert.

The selected CD or DVD is inserted.

Eject a CD/DVD

After you have finished using a CD or DVD in your virtual machine you can eject it.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select VMs.
- 3 Select a virtual machine, right-click, and select Eject CD/DVD.

The media file is removed from the virtual machine.

Insert a Floppy

You can access floppy disk images from catalogs to use in a guest operating system. When you insert a floppy disk, you can install operating systems, applications, drivers, and so on.

Prerequisites

You have media files in your catalog.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select Insert Floppy from Catalog.
- 4 Using the drop-down menu, select a floppy disk image or select one from the list and click Insert.

The selected floppy disk is inserted.

Eject a Floppy

After you have finished using a floppy disk in your virtual machine you can eject it.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select **VMs**.
- 3 Select a virtual machine, right-click, and select **Eject Floppy**.

The floppy disk is removed from the virtual machine.

Upgrade the Virtual Hardware Version for a Virtual Machine

You can upgrade the virtual hardware version for a virtual machine. Higher virtual hardware versions support more features.

vCloud Director supports hardware version 4, hardware version 7, hardware version 8, hardware version 9, and hardware version 10 virtual machines depending on the resources backing the organization's virtual datacenters.

You cannot downgrade the hardware version of a virtual machine.

Prerequisites

Verify that the virtual machine is powered off and and that it has the latest version of VMware Tools installed.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select Upgrade Virtual Hardware Version.
- 4 Click Yes.

Connect Remotely to a Virtual Machine

You can use the Remote Desktop Connection file to connect to a deployed virtual machine from your desktop.

Prerequisites

- The virtual machine must be powered on, running a Windows guest OS, and have **Remote Desktop** enabled in the guest OS.
- The virtual machine must have an IP assigned on its network that is accessible by the client.
- The RDP port 3389 must be open on the guest OS.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select Download Windows Remote Desktop Shortcut File.
- 4 In the **Download RDP Shortcut File** dialog box, click **Yes**.

- 5 Navigate to the location where you want to save the file and click **Save**.
- 6 Double-click the file and select **Connect**.

Create a Snapshot of a Virtual Machine

You can take a snapshot of a virtual machine. After you take the snapshot, you can revert all the virtual machines to the most recent snapshot, or remove the snapshot.

Snapshots do not capture NIC configurations.

Prerequisites

Verify that the virtual machine is not connected to an independent disk.

Procedure

- 1 Select My Cloud > VMs.
- Right-click the vApp and select Create Snapshot.
- 3 Click OK.

A snapshot of the virtual machine's state is saved. This doubles the virtual machine's storage consumption on the organization virtual datacenter.

Revert a Virtual Machine to a Snapshot

You can revert a virtual machine to the state it was in when the snapshot was created.

Prerequisites

Verify that the virtual machine has a snapshot.

Procedure

- 1 Select My Cloud > VMs.
- 2 Right-click the vApp and select **Revert to Snapshot**.
- 3 Click Yes.

Remove a Snapshot of a Virtual Machine

You can remove a snapshot of a virtual machine.

Procedure

- 1 Select My Cloud > VMs.
- 2 Right-click the vApp and select Remove Snapshot.
- 3 Click Yes.

Copy or Move a Virtual Machine to a vApp

You can copy or move a virtual machine to another vApp. When you copy a virtual machine, the original virtual machine remains in the source vApp. If you move a virtual machine, it is removed from the source vApp.

Prerequisites

The virtual machine must be powered off.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select Copy to or Move to.
- 4 Follow the prompts to complete the wizard.
- 5 Click Finish.

Delete a Virtual Machine

You can delete a virtual machine from your organization.

Prerequisites

Your virtual machine must be powered off.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select **Delete**.
- 4 Click Yes.

Editing Virtual Machine Properties

You can edit the properties of a virtual machine, including the virtual machine name and description, CPU and memory settings, and OVF environment settings.

- Change Virtual Machine General Properties on page 98
 - You can review and change the name, description, and other general properties of a virtual machine.
- Change Virtual Machine CPU and Memory on page 98
 - You can change virtual machine hardware, such as CPU, memory, hard disks, and NICs.
- Change Virtual Machine Guest OS Properties on page 99
 - You can change a virtual machine's guest operating system properties, such as password and domain properties.
- Configuring Virtual Machine Resource Allocation Settings on page 100
 - Reservation pool virtual datacenters support the ability to control resource allocation at the virtual machine level. Users with the necessary rights can customize the amount of resources that are allocated to their virtual machines.
- Modifying Virtual Machine Hard Disks on page 101
 - You can add hard disks, edit hard disks, and delete hard disk from a virtual machine.
- Modifying Virtual Machine Network Interfaces on page 102
 - You can modify virtual machine network settings, reset a MAC address, add a network interface, and delete a network interface.

Change Virtual Machine General Properties

You can review and change the name, description, and other general properties of a virtual machine.

Prerequisites

Verify that the virtual machine is powered off.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the **General** tab, change the properties, and click **OK**.

Option	Action		
Computer name	Type the computer and host name set in the guest operating system that identifies the virtual machine on a network. This field is restricted to 15 characters because of a Windows OS limitation on computer names.		
Description	Type an optional description of the virtual machines.		
Operating System Family	Select an operating system family from the drop-down menu.		
Operating System	Select an operating system from the drop-down menu.		
Virtual hardware version	Virtual hardware version of the virtual machine. Select the Upgrade to as select a hardware version to upgrade the virtual machine hardware.		
Virtual CPU hot add	Select the check box to enable virtual CPU hot add. This option allows y to add virtual CPUs to a powered on virtual machine. This feature is on supported on certain guest operating systems and virtual machine hardware versions.		
Memory hot add	Select the check box to enable memory hot add. This option allows you to add memory to a powered on virtual machine. This feature is only supported on certain guest operating systems and virtual machine hardware versions.		
Synchronize time	Select the check box to enable time synchronization between the virtual machine guest operating system and the virtual datacenter in which it is running.		
Storage Policy	Select a storage policy for the virtual machine to use from the drop-down menu.		

Change Virtual Machine CPU and Memory

You can change virtual machine hardware, such as CPU, memory, hard disks, and NICs.

The number of virtual CPUs and memory that a virtual machine supports depends on its virtual hardware version.

 Table 8-1. Virtual Hardware Versions and CPU and Memory Support

Maximum CPUs	Maximum Memory
4	64GB
8	255GB
32	1011GB
64	1011GB
64	1011GB
	4 8 32 64

Prerequisites

If CPU hot add or memory hot add is not enabled for the virtual machine, power off the virtual machine before you change the CPU or memory.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the Hardware tab and select the number of CPUs and cores per socket for the virtual machine.
- 5 (Optional) Select **Expose hardware-assisted CPU virtualization to guest OS** to support virtualization servers or 64-bit virtual machines running on the virtual machine.
- 6 Select the total memory for the virtual machine from the **Total memory** drop-down menu.
- 7 Click OK.

Change Virtual Machine Guest OS Properties

You can change a virtual machine's guest operating system properties, such as password and domain properties.

Procedure

- Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the **Guest OS Customization** tab and select **Enable guest customization**.
- 5 (Optional) Select Change SID to run Sysprep to change Windows SID.
 This option is available only for virtual machines running a Windows guest operating system.
- 6 (Optional) Select **Allow local administrator password** to allow setting an administrator password on the guest operating system.

Option	Description
Auto generate password	vCloud Director generates an administrator password for the guest operating system.
Specify password	Type an administrator password for the guest operating system.

- 7 (Optional) Select **Require administrator to change password on first login** to require the administrator to change this password the first time they log in to the guest operating system.
- 8 (Optional) Click **Enable this VM to join a domain** and type domain properties to have the virtual machine join a domain.
- 9 (Optional) Click **Browse**, navigate to a customization script, and click **OK** to add the customization script to the virtual machine.
- 10 Click OK.

Configuring Virtual Machine Resource Allocation Settings

Reservation pool virtual datacenters support the ability to control resource allocation at the virtual machine level. Users with the necessary rights can customize the amount of resources that are allocated to their virtual machines.

Use the resource allocation settings (shares, reservation, and limit) to determine the amount of CPU, memory, and storage resources provided for a virtual machine. Users have several options for allocating resources.

- Ensure that a certain amount of memory for a virtual machine is provided by the virtual datacenter.
- Guarantee that a particular virtual machine is always allocated a higher percentage of the virtual datacenter resources than other virtual machines.
- Set an upper bound on the resources that can be allocated to a virtual machine.

Resource Allocation Shares

Shares specify the relative importance of a virtual machine within a virtual datacenter. If a virtual machine has twice as many shares of a resource as another virtual machine, it is entitled to consume twice as much of that resource when these two virtual machines are competing for resources.

Shares are typically specified as **High**, **Normal**, or **Low** and these values specify share values with a 4:2:1 ratio, respectively. You can also select **Custom** to assign a specific number of shares (which expresses a proportional weight) to each virtual machine.

When you assign shares to a virtual machine, you always specify the priority for that virtual machine relative to other powered-on virtual machines.

The following table shows the default CPU and memory share values for a virtual machine.

Table 8-2. Share Values

Setting	CPU share values	Memory share values
High	2000 shares per virtual CPU	20 shares per megabyte of configured virtual machine memory.
Normal	1000 shares per virtual CPU	10 shares per megabyte of configured virtual machine memory.
Low	500 shares per virtual CPU	5 shares per megabyte of configured virtual machine memory.

For example, a virtual machine with two virtual CPUs and 1GB RAM with CPU and memory shares set to **Normal** has 2x1000=2000 shares of CPU and 10x1024=10240 shares of memory.

The relative priority represented by each share changes when a new virtual machine is powered on. This affects all virtual machines in the same virtual datacenter.

Resource Allocation Reservation

A reservation specifies the guaranteed minimum allocation for a virtual machine.

vCloud Director allows you to power on a virtual machine only if there are enough unreserved resources to satisfy the reservation of the virtual machine. The virtual datacenter guarantees that amount even when its resources are heavily loaded. The reservation is expressed in concrete units (megahertz or megabytes).

For example, assume you have 2GHz available and specify a reservation of 1GHz for VM1 and 1GHz for VM2. Now each virtual machine is guaranteed to get 1GHz if it needs it. However, if VM1 is using only 500MHz, VM2 can use 1.5GHz.

Reservation defaults to 0. You can specify a reservation if you need to guarantee that the minimum required amounts of CPU or memory are always available for the virtual machine.

Resource Allocation Limit

Limit specifies an upper bound for CPU and memory resources that can be allocated to a virtual machine.

A virtual datacenter can allocate more than the reservation to a virtual machine, but never allocates more than the limit, even if there are unused resources on the system. The limit is expressed in concrete units (megahertz or megabytes).

CPU and memory resource limits default to unlimited. When the memory limit is unlimited, the amount of memory configured for the virtual machine when it was created becomes its effective limit in most cases.

In most cases, it is not necessary to specify a limit. You might waste idle resources if you specify a limit. The system does not allow a virtual machine to use more resources than the limit, even when the system is underutilized and idle resources are available. Specify a limit only if you have good reasons for doing so.

Configure Virtual Machine Resource Allocation Settings

You can configure the resource allocation settings (shares, reservation, and limit) to determine the amount of CPU, memory, and storage resources provided for a virtual machine.

For more information about shares, reservations, and limits, see "Resource Allocation Shares," on page 100, "Resource Allocation Reservation," on page 100, and "Resource Allocation Limit," on page 101.

Prerequisites

A reservation pool virtual datacenter.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the **Resource Allocation** tab and set the priority, reservation, and limit for CPU and memory.
- 5 Click OK.

Modifying Virtual Machine Hard Disks

You can add hard disks, edit hard disks, and delete hard disk from a virtual machine.

You do not have to power off virtual machines that are not fast provisioned to add or edit a virtual machine hard disk.

Add a Virtual Machine Hard Disk

You can add a virtual hard disk to a virtual machine.

Prerequisites

If the virtual machine uses fast provisioning, power off the virtual machine. Non-fast-provisioned virtual machines support adding virtual machine hard disks while the virtual machine is running.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the **Hardware** tab and click **Add** in the Hard Disks section.
- 5 Select the disk size, bus type, bus number, and unit number and click **OK**.

What to do next

Use the guest operating system tools to partition and format the new disk.

Change a Virtual Machine Hard Disk

You can change the bus number and unit number of a virtual machine hard disk.

Prerequisites

If the virtual machine uses fast provisioning, power off the virtual machine. Non-fast-provisioned virtual machines support editing virtual machine hard disks while the virtual machine is running.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 On the **Hardware** tab, select a new size, bus number, and unit number in the Hard Disks section and click **OK**.

Delete a Virtual Machine Hard Disk

You can delete a virtual machine hard disk.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the **Hardware** tab, click **Delete** in the Hard Disks section, and click **Yes**.
- 5 Click **OK**.

Modifying Virtual Machine Network Interfaces

You can modify virtual machine network settings, reset a MAC address, add a network interface, and delete a network interface.

Virtual machine version 4 supports up to four NICs, and virtual machine versions 7, 8, 9, and 10 support up to ten NICs. vCloud Director supports modifying virtual machine NICs while the virtual machine is running.

Change Network Interface Settings

You can disconnect a virtual machine NIC, change the network to which a NIC connects, select a primary NIC, and change the IP addressing mode for a NIC.

You do not need to power off the virtual machine to edit network interface settings.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the Hardware tab, and in the NICs section, select the network settings for each NIC.

Option	Action	
Connected	Deselect the check box to disconnect a NIC.	
Network	Select a network from the drop-down menu.	
Primary NIC	Select a primary NIC. The primary NIC setting determines the default and only gateway for the virtual machine. The virtual machine can use any NIC to connect to virtual and physical machines that are directly connected to the same network as the NIC, but it can only use the primary NIC to connect to machines on networks that require a gateway connection.	
IP Mode	Select an IP mode.	
	■ Static - IP Pool pulls IP addresses from the network's IP pool.	
	Static - Manual allows you to specify an IP address.	
	 DHCP pulls IP addresses from a DHCP server. 	
IP Address	If you selected Static - Manual , type an IP address.	

5 Click OK.

Reset a Network Interface MAC Address

You can reset a network interface MAC address if, for example, you have a MAC address conflict or to discard a saved state quickly.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the Hardware tab and in the NICs section, select Reset from the MAC Address drop-down menu..
- 5 Click **OK**.

Add a Network Interface

You can add one or more virtual NICs to a virtual machine.

Virtual machine version 4 supports up to four NICs, and virtual machine versions 7, 8, 9, and 10 support up to ten NICs. You do not need to power off the virtual machine to add a network interface.

For information about supported network adapter types, see http://kb.vmware.com/kb/1001805.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the **Hardware** tab, and in the NICs section, click **Add**.
- 5 (Optional) Modify the NIC settings.
- 6 Click OK.

Remove a Network Interface

You can remove NICs from a virtual machine.

You do not need to power off the virtual machine to remove a network interface.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 Click the **Hardware** tab, and click **Delete** in the NICs section.
- 5 Click **OK**.

Installing VMware Tools

VMware Tools supports shared folders and cut and paste operations between the guest operating system and the machine from which you launch the vCloud Director Web console.

vCloud Director depends on VMware Tools to customize the guest OS. Using VMware Tools, you can move the pointer in and out of the virtual machine console window.

A virtual machine must be powered on to install VMware Tools.

Install VMware Tools in a New Virtual Machine with No Guest Operating System

If your newly created virtual machine has no guest operating system, you must install it before you can install VMware Tools.

You must be at least a vApp User.

Prerequisites

You have created a vApp in which you have a blank virtual machine.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, selectvApps > Open.
- 3 On the **Virtual Machines** tab, select a virtual machine, right-click, and select **Power On**.
- 4 Log into the virtual machine console and install the guest operating system.
- 5 Install **VMware Tools**.
- 6 Power off the virtual machine.
- 7 Select the virtual machine, right-click and select **Properties**.

- 8 On the **Guest OS Customization** tab, select the **Enable guest customization** check box.
- 9 Power the virtual machine on.

The guest OS in your newly created virtual machine has been customized.

Installing VMware Tools in a vApp

When you install VMware Tools in a virtual machine in a vApp, you need to understand the process.

You can trigger VMware Tools installation on a powered on guest virtual machine in a vApp by selecting the virtual machine, right-click, and selecting **Install VMware Tools**. Popout the virtual machine console to continue with the installation. For information on installing in a variety of guest OSs, see Table 8-3.

Table 8-3. Installing VMware Tools

Action	Reference
To install on a Windows Guest	"Install VMware Tools on a Windows Guest," on page 111
To install on a Linux Guest	 "Install VMware Tools on a Linux Guest in X with the RPM Installer," on page 112
	■ "Install VMware Tools on a Linux Guest with the Tar Installer or RPM Installer," on page 112
To install on a Solaris Guest	"Install VMware Tools on a Solaris Guest," on page 113

If the settings on a guest virtual machine are not in synch with vCloud Director or an attempt to perform guest customization has failed, you can select the virtual machine, right-click, and select **Power on and Force re-customization**.

When you select **Add to My Cloud** or **Add from Catalog** on a vApp template, these are the available options on the vApp template **Properties** page.

- Make identical copy
- Customize VM Settings

The vApp template is added and saved as a vApp in your organization. These options are not used when you use a virtual machine, when you create a new vApp, or add a new virtual machine.

Install VMware Tools in a Virtual Machine in a vApp

vApp deployment can fail if VMware Tools are not installed on the virtual machines in the vApp.

Prerequisites

You must stop the vApp.

Procedure

- 1 Disable Guest Customization on page 106
 - To install VMware Tools in a virtual machine in a vApp, you must disable guest customization.
- 2 Start the vApp on page 106
 - After you install VMware Tools, you must start the vApp.
- 3 Install VMware Tools on page 106
 - You must install VMware Tools in your virtual machines to customize the guest operation system.
- 4 Stop the vApp on page 107
 - To enable guest customization on a virtual machine, you must stop the vApp.

5 Enable Guest Customization on page 107

After you install or upgrade VMware Tools in your virtual machines, you must enable guest customization.

6 Start the vApp on page 107

After you install VMware Tools, you must start the vApp.

Disable Guest Customization

To install VMware Tools in a virtual machine in a vApp, you must disable guest customization.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select VMs.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 On the Guest OS Customization tab, deselect the Enable guest customization check box.

Start the vApp

After you install VMware Tools, you must start the vApp.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.

The virtual machines in the vApp will customize when you power on. The guest OS will be rebooted during customization if necessary.

3 Select the vApp, right click, and select **Start**.

Install VMware Tools

You must install VMware Tools in your virtual machines to customize the guest operation system.

You are at least a vApp User.

Prerequisites

Guest customization is disabled on the relevant virtual machines.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the Virtual Machines tab, select a virtual machine, right-click, and select Power On.
- 5 Select the virtual machine, right-click, and select **Install VMware Tools**.

VMware tools installation is triggered or Tools CD is mounted. You need to open the virtual machine console to complete the installation.

VMware Tools is installed.

Stop the vApp

To enable guest customization on a virtual machine, you must stop the vApp.

You are at least a vApp User.

Prerequisites

Your vApp is started.

Procedure

- 1 Click My Cloud.
- 2 Power off your virtual machines.
- 3 Select a vApp, right-click, and select **Stop**.

The vApp is stopped.

Enable Guest Customization

After you install or upgrade VMware Tools in your virtual machines, you must enable guest customization.

Procedure

- 1 On the **Guest OS Customization** tab, select the **Enable guest customization** check box.
- 2 Select the other check boxes in the dialog box as relevant.

Start the vApp

After you install VMware Tools, you must start the vApp.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApps**.

The virtual machines in the vApp will customize when you power on. The guest OS will be rebooted during customization if necessary.

3 Select the vApp, right click, and select **Start**.

Install VMware Tools in a vApp Template

You can install VMware Tools on a virtual machine for which guest customization is enabled.

Prerequisites

Guest customization is enabled on the virtual machine's **Properties** page.

Procedure

- 1 Save the vApp Template as a vApp on page 108
 - To install VMware Tools in a vApp, you must save it as a vApp.
- 2 Disable Guest Customization on page 108
 - Before you can install VMware Tools on a virtual machine, you must disable guest customization.
- 3 Install VMware Tools on page 108

You must install VMware Tools in your virtual machines to customize the guest operation system.

4 Enable Guest Customization on page 109

After you install or upgrade VMware Tools in your virtual machines, you must enable guest customization.

5 Add a vApp to a Catalog on page 109

After you install or upgrade VMware Tools, you can add the updated vApp to your catalog.

Save the vApp Template as a vApp

To install VMware Tools in a vApp, you must save it as a vApp.

Procedure

- 1 Click Catalogs.
- 2 On the vApp Templates tab, select a vApp template, right-click, and select Properties.
- 3 Select Make Identical Copy.
- 4 Select the vApp template, right-click, and select Add to My Cloud.

The vApp template has been saved as a vApp.

What to do next

You need to install VMware Tools.

Disable Guest Customization

Before you can install VMware Tools on a virtual machine, you must disable guest customization.

Procedure

- 1 On the **vApps** page, select a vApp, right-click, and select **Open**.
- 2 Select My Cloud > vApps.
- 3 In a vApp, select a virtual machine, right-click, and select **Open**.
- 4 On the **Guest OS Customization** tab, deselect the **Enable guest customization** and other check boxes as desired.
- 5 Select a virtual machine, right-click, and select **Properties**
- 6 On the Guest OS Customization tab, deselect the Enable guest customization check box.
- 7 Select the vApp, right-click, and select **Start**.

Install VMware Tools

You must install VMware Tools in your virtual machines to customize the guest operation system.

You are at least a vApp User.

Prerequisites

Guest customization is disabled on the relevant virtual machines.

Procedure

- Click My Cloud.
- 2 In the left pane, click vApps.
- 3 Select a vApp, right-click, and select **Open**.
- 4 On the **Virtual Machines** tab, select a virtual machine, right-click, and select **Power On**.

5 Select the virtual machine, right-click, and select Install VMware Tools.

VMware tools installation is triggered or Tools CD is mounted. You need to open the virtual machine console to complete the installation.

VMware Tools is installed.

Enable Guest Customization

After you install or upgrade VMware Tools in your virtual machines, you must enable guest customization.

Procedure

- 1 On the **Guest OS Customization** tab, select the **Enable guest customization** check box.
- 2 Select the other check boxes in the dialog box as relevant.

Add a vApp to a Catalog

After you install or upgrade VMware Tools, you can add the updated vApp to your catalog.

You do not need to stop the vApp before you add it to a catalog. If you add a running vApp to a catalog, the memory state of running virtual machines is preserved and the added vApp is enabled for network fencing.

Procedure

- 1 Select the vApp, right-click, and select **Add vApp to Catalog**.
- 2 Select the vApp template, right-click, and select **Properties**.
- 3 Select Customize VM Settings or Make Identical Copy.
- 4 (Optional) Delete any previous versions of the vApp template.

Install VMware Tools With Guest Customization Disabled

You can install VMware Tools in a vApp template when guest customization is disabled.

Prerequisites

Guest customization is disabled on the virtual machine Properties page.

Procedure

- Save the vApp Template as a vApp on page 109To install VMware Tools in a vApp, you must save it as a vApp.
- 2 Install or Upgrade VMware Tools on page 110

You can either install VMware Tools or upgrade the current version in your virtual machine.

- 3 Enable Guest Customization on page 110
 - After you install or upgrade VMware Tools in your virtual machines, you must enable guest customization.
- 4 Add a vApp to a Catalog on page 110

After you install or upgrade VMware Tools, you can add the updated vApp to your catalog.

Save the vApp Template as a vApp

To install VMware Tools in a vApp, you must save it as a vApp.

Procedure

Click Catalogs.

- 2 On the **vApp Templates** tab, select a vApp template, right-click, and select **Properties**.
- 3 Select Make Identical Copy.
- 4 Select the vApp template, right-click, and select **Add to My Cloud**.

The vApp template has been saved as a vApp.

What to do next

You need to install VMware Tools.

Install or Upgrade VMware Tools

You can either install VMware Tools or upgrade the current version in your virtual machine.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, select **vApps**.
- 3 On the **vApps** page, select a vApp, right-click, and select **Open**.
- 4 Select a virtual machine, right-click, and select **Properties**.
- 5 In the Guest OS Customization tab, deselect the Enable guest customization and other check boxes as desired.
- 6 Right-click the virtual machine and select Install VMware Tools.

Enable Guest Customization

After you install or upgrade VMware Tools in your virtual machines, you must enable guest customization.

Procedure

- 1 On the **Guest OS Customization** tab, select the **Enable guest customization** check box.
- 2 Select the other check boxes in the dialog box as relevant.

Add a vApp to a Catalog

After you install or upgrade VMware Tools, you can add the updated vApp to your catalog.

You do not need to stop the vApp before you add it to a catalog. If you add a running vApp to a catalog, the memory state of running virtual machines is preserved and the added vApp is enabled for network fencing.

Procedure

- 1 Select the vApp, right-click, and select **Add vApp to Catalog**.
- 2 Select the vApp template, right-click, and select **Properties**.
- 3 Select Customize VM Settings or Make Identical Copy.
- 4 (Optional) Delete any previous versions of the vApp template.

Upgrade VMware Tools

If the version of VMware Tools is earlier than 7299 in a virtual machine in your vApp, you must upgrade it.

Upgrading VMware Tools might involve uninstalling your existing VMware Tools versions and installing a new one from a CD mounted in the operating system. This process can also be done automatically.

Prerequisites

You must stop the vApp.

Procedure

1 Install a New Version of VMware Tools on page 111

After you disable guest customization, you can upgrade VMware Tools.

2 Enable Guest Customization on page 111

After you install or upgrade VMware Tools in your virtual machines, you must enable guest customization.

3 Start the vApp on page 111

After you install VMware Tools, you must start the vApp.

Install a New Version of VMware Tools

After you disable guest customization, you can upgrade VMware Tools.

Procedure

- 1 Select the vApp, right-click, and select **Start**.
- 2 Select the virtual machine, right-click, and select **Install VMware Tools**.

The process is different based on the operating system.

Enable Guest Customization

After you install or upgrade VMware Tools in your virtual machines, you must enable guest customization.

Procedure

- 1 On the **Guest OS Customization** tab, select the **Enable guest customization** check box.
- 2 Select the other check boxes in the dialog box as relevant.

Start the vApp

After you install VMware Tools, you must start the vApp.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click vApps.

The virtual machines in the vApp will customize when you power on. The guest OS will be rebooted during customization if necessary.

3 Select the vApp, right click, and select **Start**.

Install VMware Tools on a Windows Guest

vCloud Director uses VMware Tools to customize the Windows guest operating system.

Prerequisites

- The VMware Remote Console plug-in is installed.
- Your virtual machine is powered off.
- You have disabled the option to install VMware Tools on a powered off virtual machine.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Install VMware Tools**.
- 4 Follow the prompts to complete the installation wizard.
- 5 Click Finish.
- 6 Restart your virtual machine.

Install VMware Tools on a Linux Guest in X with the RPM Installer

You can use an RPM installer to install VMware Tools on a Linux guest operating system.

Prerequisites

The VMware Remote Console plug-in is installed.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a Linux virtual machine, right-click, and select **Popout Console**.
- 4 In the guest operating system, start the RPM installer.
 - Double-click the VMware Tools CD icon on your desktop and double-click the RPM installer in the root of the CD-ROM.
 - Double-click the RPM installer in the file manager window.
- 5 Type the root password and click **OK**.
- 6 Click **Continue** when the package is ready.
 - When VMware Tools is installed, no confirmation or Finish button appears.
- 7 In an X terminal, as root, run the vmware-config-tools.pl script to configure VMware Tools.
- 8 Press Enter to accept the default value.
- 9 After the upgrade is complete, enter /etc/init.d/network to restart the network.
- 10 Type exit.
- 11 To start the VMware Tools control panel, enter vmware-toolbox &.

Install VMware Tools on a Linux Guest with the Tar Installer or RPM Installer

You can use a Tar command or RPM installer to install VMware tools on a Linux guest OS with a Tar or RPM.

Prerequisites

- The VMware Remote Console plug-in is installed.
- The virtual machine is powered on.
- With an existing installation, delete the vmware-tools-distrib directory before you install. The location of this directory depends on where you placed it during the previous installation (such as, tmp/vmware-tools-distrib).

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a Linux virtual machine, right-click, and select **Install VMware Tools**.
- 4 Right-click the virtual machine again and click **Popout Console**.
- In the guest operating system, log in as root (su-), mount the VMware Tools virtual CD-ROM image, and change to a working directory (for example, /tmp.

Some Linux distributions automatically mount CD-ROMs. If your distribution uses automounting, do not use the mount and unmount commands. You still must untar the VMware Tools installer to /tmp. Some Linux distributions use different device names or organize the /dev directory differently. If your CD-ROM drive is not /dev/cdrom, or if the mount point for a CD-ROM is not /mnt/cdrom, modify these commands to reflect the conventions used by your distribution.

mount /dev/cdrom /mnt/cdrom
cd /tmp

6 Uncompress the installer and unmount the CD-ROM image.

If you install an RPM installation over a tar installation, or the reverse, the installer detects the previous installation and must convert the installer database format before continuing.

Option	Action	
In the tar installer	At the command prompt, type tar zxpf /mnt/cdrom/VMwareTools-8.5.1- <xxxxxx>.tar.gz unmount /dev/cdrom where <xxxxxx> is the build or revision number of the release.</xxxxxx></xxxxxx>	
In the RPM installer	At the command prompt, type tar zxpf /mnt/cdrom/VMwareTools-8.5.1- <xxxxxx>.i386.gz unmount /dev/cdrom where <xxxxxx> is the build/revision number of the release.</xxxxxx></xxxxxx>	

7 Run the installer.

Option	Action
In the tar installer	Type cd vmware-tools-distrib./vmware-install.pl . Press Enter to accept the default values.
In the RPM installer	Configure VMware Tools, type vmware-config-tools.pl Press Enter to accept the default values.

- 8 After the upgrade is complete, restart the network by running /etc/init.d/network restart.
- 9 Type exit.
- 10 Start your graphical environment.
- 11 In an X terminal, run vmware-toolbox &.

Install VMware Tools on a Solaris Guest

You can install VMware Tools on a Solaris guest OS.

Prerequisites

The VMware Remote Console plug-in is installed.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a Solaris virtual machine, right click, and select Install VMware Tools.
- 4 Click **Popout Console**.
- 5 In the virtual machine, log in as root and, if necessary, mount the VMware Tools virtual CD-ROM image.

The Solaris volume manager vold mounts the CD-ROM under /cdrom/vmwaretools.

- 6 If the CD-ROM is not mounted, restart the volume manager by running these commands.
 - /etc/init.d/volmgt stop
 - /etc/init.d/volmgt start
- 7 After the CD-ROM is mounted, change to a working directory, for example, /tmp and extract VMware Tools
 - cd /tmp
 - gunzip -c /cdrom/vmwaretools/vmware-solaris-tools.tar.gz | tar xf-
- 8 Run the VMware Tools tar installer.
 - cd vmware-tools-distrib
 - ./vmware-install.pl
- 9 Press Enter to accept the default value.
- 10 Type exit.
- 11 Start your graphical environment.
- 12 In an X terminal, enter vmware-toolbox &.

Guest Operating Systems

A guest operating system is an operating system that runs inside a virtual machine. You can install a guest operating system in a virtual machine and control guest operating system customization for virtual machines created from vApp templates.

Install a Guest Operating System

With a guest OS you can manage virtual machines that are based on the available operating systems.

Prerequisites

The appropriate media file must be in your catalog.

Procedure

- Click My Cloud.
- 2 In the left pane, click VMs.
- 3 Select a virtual machine, right-click, and select **Insert CD/DVD**.
- 4 Select an available media file in the top panel or select one and add it to your virtual datacenter in the bottom panel.
- 5 Click **OK**.

- Point to the virtual machine name and press Ctrl+Alt+Del to boot from the ISO image and start the operating system installer.
- 7 In the virtual machine console, type the required information to complete the installation.
- 8 Click Finish.

Customizing Your Guest Operating System

When you customize your guest OS you can set up a virtual machine with the operating system that you want.

vCloud Director can customize the network settings of the guest operating system of a virtual machine created from a vApp template. When you customize your guest operating system, you can create and deploy multiple unique virtual machines based on the same vApp template without machine name or network conflicts.

When you configure a vApp template with the prerequisites for guest customization and add a virtual machine to a vApp based on that template, vCloud Director creates a package with guest customization tools. When you deploy and power on the virtual machine for the first time, vCloud Director copies the package, runs the tools, and deletes the package from the virtual machine.

Understanding Guest Customization

When you customize your guest operating system, there are some settings and options you should know about.

Enable Guest Customization Check Box

This check box is found on the **Guest OS customization** tab on the virtual machine **Properties** page. The goal of guest customization is to configure based on the options selected in the **Properties** page. If this check box is selected, guest customization and re-customization is performed when required.

This process is required for all guest customization features, such as the computer name, network settings, setting and expiring the administrator/root password, SID change for Windows Operating systems, and so on, to work. This option should be selected for **Power on and Force re-customization** to work.

If the check box is selected, and the virtual machine's configuration parameters in vCloud Director are out of synch with the settings in the guest OS, the **Profile** tab on the virtual machines **Properties** page displays that the settings out of synch with the guest OS and the virtual machine needs guest customization.

Guest customization Behavior for vApps and Virtual Machines

The check boxes are deselected.

- **■** Enable guest customization
- In Windows guest OSs, Change SID
- Password reset

If you want to perform customization (or you made changes to network settings that need to be reflected in the guest OS), you can select the **Enable guest customization** check box and set the options on the **Guest OS Customization** tab of the virtual machine **Properties** page. When virtual machines from vApp templates are used to create a new vApp and then add a virtual machine, the vApp templates act as building blocks. When you add virtual machines from the catalog to a new vApp, the virtual machines are enabled for guest customization by default. When you save a vApp template from a catalog as a vApp, virtual machines are enabled for guest customization only if the **Enable guest customization** check box is selected.

These are the default values of guest customization settings:

■ The Enable guest customization check box is the same as the source virtual machine in your Catalog.

- For Windows guest virtual machines, **Change SID** is the same as the source virtual machine in your catalog.
- The password reset setting is same as the source virtual machine in your catalog.

You can deselect the **Enable guest customization** check box if required before you start the VApp.

If blank virtual machines, which are pending guest OS installation, are added to a vApp, the **Enable guest customization** check box is deselected by default because these virtual machines are not yet ready for customization.

After you install the guest OS and VMware Tools, you can power off the virtual machines, stop vApp, and select the **Enable guest customization** check box and start the vApp and virtual machines to perform guest customization.

If the virtual machine name and network settings are updated on a virtual machine that has been customized, the next time you power on the virtual machine, it is re-customized, which resynchronizes the guest virtual machine with vCloud Director

Customizing a Guest OS When Saving a vApp Template as a vApp

Before you customize a guest OS in a vApp template, you need to understand the settings you need to make.

On the **vApp Templates Properties** page, if you select **Customize VM Settings** for the **When creating a vApp from this template** option, and you select **Add to My Cloud** or **Add from Catalog**, the **Enable guest customization** check box is selected by default and guest customization is performed.

These are the default values of guest customization settings.

- The **Enable guest customization** check box is selected.
- For Windows guest VMs, the Change SID option is the same as the source virtual machine in your catalog.
- Password reset setting is the same as the source virtual machine in your catalog.

If you select **Make Identical Copy** on the vApp template **Properties** page, and select **Add to My Cloud**, the settings in the vApp Template are applied to the new vApp, regardless of whether customization is enabled.

These are the default values of guest customization settings.

- The **Enable guest customization** check box is deselected.
- In Windows guest virtual machines, the **Change SID** check box is deselected.
- The password reset setting is deselected.

After you import or upload to a catalog, these are the default values.

- The **Customize VM Settings** check box is selected in the vApp
- The **Enable guest customization** check box is selected for the virtual machines.
- For Windows guest VMs, the **Change SID** check box is selected for the virtual machines.
- The Password reset setting is selected by default for the virtual machines.

If you are a vApp template owner and you import or upload to a catalog, you must check the VMware Tools version installed on the virtual machines in the vApp. To do this, select the vApp template, right-click, and select **Open**. Tools version is shown in the **VMware Tools** column. If you select **Customize VM Settings**, VMware Tools should be installed on all virtual machines. See "Installing VMware Tools," on page 104 for more information.

Enable or Disable Guest Customization

You can disable guest customization for a virtual machine or a vApp template.

Prerequisites

VMware Tools is installed.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **vApp** or **VMs**.
- 3 Select a vApp or virtual machine, right-click, and select **Properties**.
- 4 On the Guest OS Customization tab, select or deselect the Enable guest customization check box.
- 5 Click **OK**.

Guest customization in the selected virtual machine is enabled or disabled.

Change Guest Customization Settings for Virtual Machines in a vApp Template

You can change the guest customize settings on virtual machines in a vApp template when the virtual machines are used as building blocks to create a new vApp.

Procedure

- 1 Click Catalogs.
- 2 On the **vApp Templates** tab, select a vApp template, right-click, and select **Add to My Cloud**. The vApp template is saved as a vApp.
- 3 Select the vApp, right-click, and select **Open**.
- 4 On the Virtual Machines tab, select the virtual machine, right-click, and select Properties.
- 5 On the **Guest Customization OS** tab, select or deselect the **Enable guest customization** check box and click **OK**.
- 6 Select the vApp, right-click, and select **Add to Catalog**.

The vApp is saved as a vApp template in the selected catalog.

Power on and Force Recustomization of a Virtual Machine

If the settings on a guest virtual machine are not in synch with vCloud Director or an attempt to perform guest customization has failed, you can power on and force the recustomization of the virtual machine.

You are at least a vApp user.

Note If you select the Change SID check box, a SID change will occur on the guest virtual machine.

Procedure

- 1 Click My Cloud.
- 2 In **vApps**, select a vApp, right-click, and select **Open**.
- 3 On the Virtual Machines tab, select a virtual machine, right-click, and select Power On and Force Recustomization.

The virtual machine is now recustomized.

Upload a Customization Script

You can upload a customization script to a virtual machine. The script runs before and after guest customization when you deploy a virtual machine based on a vApp template.

When you add a customization script to a virtual machine, the script is called:

- Only on initial customization and force recustomization.
- With the "precustomization" command line parameter before guest customization begins.
- With the "postcustomization" command line parameter after guest customization finishes.

The customization script cannot exceed 1500 characters.

Procedure

- Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 In the right pane, select a virtual machine, right-click, and select **Properties**.
- 4 On the **Guest OS Customization** tab, in the **Customization Script** panel, click **Browse**.
- 5 Navigate to your script file and click **Open**.

The file must be a batch file for Windows virtual machines and a shell script for Unix virtual machines.

6 Click **OK**.

Example: Customization Script Examples

A sample Windows batch file:

```
@echo off
if "%1%" == "precustomization" (
echo Do precustomization tasks
) else if "%1%" == "postcustomization" (
echo Do postcustomization tasks
)
A sample Unix shell script:

#!/bin/sh
if [ x$1 == x"precustomization" ]; then
echo Do Precustomization tasks
elif [ x$1 == x"postcustomization" ]; then
echo Do Postcustomization tasks
fi
```

Reset Your Virtual Machine's Password

You can reset your virtual machine's password.

Prerequisites

The virtual machine's guest OS is personalized, and your virtual machine is powered off.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Right-click a virtual machine and select **Properties**.

- 4 On the **Guest OS Customization** tab, select the **Enable guest customization** check box.
- 5 Select Allow local administrator password.
- 6 Select **Require administrator to change password on first login** to require all administrators to change the password upon initial log in.
 - Administrators must know the old password.
- 7 Choose how to generate the virtual machine password.

Option	Description	
Auto generate password	vCloud Director generates a password for the virtual machine.	
Specify password	Type a password for the virtual machine.	

- 8 (Optional) Select Automatically log on as Administrator for vCloud Director to log on as Administrator when the virtual machine powers on and select the number of times to log on automatically from the drop-down list.
- 9 Click OK.

The password for your virtual machine is reset.

Join a Windows Guest Domain During Guest Operating System Personalization

A virtual machine can join a Windows guest domain when you personalize your guest OS.

Prerequisites

On a virtual machine's **Properties** page, verify that the **Enable guest customization** check box is selected.

Procedure

- 1 Click My Cloud.
- 2 In the left pane, click **VMs**.
- 3 Select a virtual machine, right-click, and select **Properties**.
- 4 On the **Guest OS Customization** tab, select the **Enable this VM to join a domain** check box.
 - Override organization settings is selected by default.
- 5 Type a domain name, user name, password, and account organizational unit.
- 6 Under Customization Script, click Browse, to upload a locally saved file.
- 7 Click OK.

The selected virtual machine joins the Windows guest domain.

Guest Operating System Support

vCloud Director supports a wide variety of 32-bit and 64-bit operating systems in its virtual machine templates and virtual machines. VMware recommends that you use version 10, but you can import version 4, 7, 8, and 9 virtual machines.

Microsoft Windows Guest Operating System Support

The following Microsoft Windows guest operating systems are supported. Unless stated otherwise, all OS variants and 32-bit/64-bit editions are supported. Unless specified, all SP, minor or maintenance versions are supported.

■ Microsoft Windows Server 2012 64-bit

- Microsoft Windows Server 2012 R2 64-bit
- Microsoft Windows 8
- Microsoft Windows 8.1
- Microsoft Windows 7
- Microsoft Windows Server 2008
- Microsoft Windows Server 2008 R2 64-bit
- Microsoft Windows Server 2003
- Microsoft Windows Small Business Sever 32-bit
- Microsoft Windows Vista
- Microsoft Windows XP Professional

UNIX/Linux Guest Operating System Support

The following UNIX and Linux guest operating systems are supported. Unless stated otherwise, all OS variants and 32-bit/64-bit editions are supported. Unless specified, all SP, minor or maintenance versions are supported.

- Red Hat Enterprise Linux 6
- Red Hat Enterprise Linux 5
- Red Hat Enterprise Linux 4
- SUSE Enterprise Linux 11
- SUSE Enterprise Linux 10
- Oracle Linux 6
- Oracle Linux 5
- Oracle Linux 4
- CentOS
- Ubuntu Linux
- Other 3.x Linux
- Other 2.6.x Linux
- Other 2.4.x Linux
- Other Linux

Index

C	L
catalog, delete 45	leases, runtime and storage 31
catalogs	limit 101
access contents 43	
add new 42	M
change owner 45	media files
media file from public catalog 47	access in a catalog 47
properties, modify 45	copy 50
public catalogs 47	delete 51
publish 44	modify properties 51
sharing 43	move 50
subscribe 46	resume upload 50
understanding 46	upload 49
vApp template from public catalog 47	working with 49
working with 41	, and the second
changing your password 15	N
changing your password 19	network services 19, 73
D	
DHCP network services 19, 73	0
Differ network services 15, 75	organization virtual datacenter networks
E	adding a firewall rule 20
enabling VPN 22	adding a static route 25, 26
expired items, working with 30	adding IP addresses 28
expired items, working with 30	apply syslog server settings 29
F	configuring DHCP 19
firewall rules, setting the order 22, 76	configuring firewalls 20
	configuring services 19
G	connected vApp templates 29
getting started 11	connected vApps 29
getting started, Home page 12	create VPN tunnel 23, 24
guest customization	enabling static routing 25
change settings in a virtual machine 117	managing 18
customization script 118	ordering firewall rules 22
enable or disable guest customization 117	resetting 28
guest OS support 119	•
guest OS customization 115	view syslog server settings 29
join Windows guest domain 119	viewing IP usage 28 organizations
reset password 118	adding LDAP users and groups 33
guest OS	adding local users 33
customizing guest OS when saving vApp	adding SAML users and groups 33
template as a vApp 116	change full name 32
understanding guest customization 115	
3 3	cloud resources 17
I	email preferences 33
importing virtual machines 69	enable domain join 36
IP address persistance 82	lease settings 34

limit settings 34	retaining IP addresses 82
manage resources 38	to download as OVF package 66
manage users and groups 38	vApp networks
manage virtual machines 38	adding a firewall rule 75
modify email settings 35	adding a static route 79
modify policies 35	apply syslog server settings 82
monitoring events 39	configuring DHCP 73
monitoring tasks 39	configuring firewalls 74
monitoring the log 39	configuring IP translation 78
quota settings 34	configuring NAT 77, 78
review the profile 34	configuring port forwarding 77
•	configuring services 73
set up 32	enabling static routing 79
SMTP server 33	IP masquerade 77
working in 31	ordering firewall rules 76
P	ordering port forwarding rules 78
port forwarding rules, setting the order 78	view syslog server settings 82
port forwarding rules, setting the order 70	vApp templates
R	add from another catalog 56
reservation 100	add to My Cloud 54
resource allocation settings	change guest OS password 59
limit 101	copy to published catalog 57
reservation 100	delete 57
shares 100	download 54
runtime leases 31	edit guest OS domain 59
	edit guest OS properties 59
S	managed expired 30
SAML 36	modify properties 58
shares 100	move to published catalog 57
sharing catalogs 43	· · · · · · · · · · · · · · · · · · ·
single sign-on 36	open 53
snapshots	resume upload 56
remove 87, 96	save vApp as vApp template 58
revert 87, 96	upload 55
vApp 87	using in a catalog 47
virtual machine 96	working with 53
SSO 36	vApps add a vApp network 72
storage leases 31	add a vapp network 72 add an organization virtual datacenter
_	network 73
T	add existing virtual machine 63
Technical Support, to obtain 7	add new 62
	adding virtual machines 69
U	boot delay 70
updated information 9	change the owner 85
user preferences 15	changing name 83
N.	configure networks 64
V vAnn	configure VM 63
vApp create from OVF 64	copy to another virtual datacenter 88
import 64	copying 88
	creating from a vApp template 62
placement 65	delete 89
resource pools 65	delete a network 81
	w

deploy 67	copy or move to a vApp 96
discard suspended state 68	CPUs 98
display diagram 85	delete 97
display IP allocations for your vApp	deleting hard disks 102
network 81	discard suspended state 93
force recustomization of a virtual machine 117	edit guest OS domain 99
managing expired 30	edit guest OS properties 99
modify network properties 81	eject a floppy 95
move to another virtual datacenter 89	eject CD/DVD 94
networks 71, 72	guest OS 114
profile 63	hard disks 101
properties 83	import 69
remove VMs 70	insert a floppy 94
reset 68, 93	insert CD/DVD 94
reset a vApp network 80	install guest OS 114
resetting leases 84	memory 98
save as vApp template 86	modifying properties 98
share 84	modifying hard disks 102
snapshots 87	• •
start action 70	modifying OVF environment properties 83
start with an older version of VMware	network interface settings 103
Tools 67	NICs 102
starting and stopping VMs 70	open console 92
stop 67	powering off 92
stop action 70	powering on 92
stop delay 70	properties 97
stopping 107	removing NICs 104
suspend 68	reset 68, 93
upgrading virtual hardware version 85	resetting MAC address 103
view networks 72	resource allocation limit 101
view virtual machines 68	resource allocation reservations 100
working with 61	resource allocation settings 100
vCloud Director	resource allocation shares 100
accessing Web console 12	resuming 93
bypass the proxy in Internet Explorer 15	snapshots 96
change your password 16	suspending 93
Firefox options 13	upgrading virtual hardware version 95
Internet Explorer options 14	working with 91
understanding 11	VMware Tools
vCloud Director, bypass the proxy in Firefox 13	add vApp to catalog 109, 110
virtual datacenter	disable guest customization 106, 108
determine when to add capacity 18	enable guest customization 107, 109–111
display 17	install in a vApp 105
manage in an organization 18	install with guest customization disabled 109
modify properties 17	install with guest customization enabled 107
working with 17	installing 106, 108
virtual machines	installing in a new virtual machine 104
adding hard disks 101	installing or upgrading 110
adding NICs 103	Linux
change guest OS password 99	Tar or RPM installer 112
configuring resource allocation 101	X with RPM installer 112
connecting remotely 95	save vApp template to My Cloud 108, 109

Solaris 113
start the vApp after installation 106, 107, 111
understanding 104
upgrade 111
upgrading 110
Windows 111
VMware Tools, in a vApp 105
VPN 22