5 Steps to Setup User and Group Disk Quota on UNIX / Linux

On Linux, you can setup disk quota using one of the following methods:

- File system base disk quota allocation
- User or group based disk quota allocation

On the user or group based quota, following are three important factors to consider:

- Hard limit For example, if you specify 2GB as hard limit, user will not be able to create new files after 2GB
- Soft limit For example, if you specify 1GB as soft limit, user will get a warning message "disk quota exceeded", once they reach 1GB limit. But, they'll still be able to create new files until they reach the hard limit
- Grace Period For example, if you specify 10 days as a grace period, after user reach their hard limit, they would be allowed additional 10 days to create new files. In that time period, they should try to get back to the quota limit.

1. Enable quota check on filesystem

First, you should specify which filesystem are allowed for quota check.

Modify the /etc/fstab, and add the keyword usrquota and grpquota to the corresponding filesystem that you would like to monitor.

The following example indicates that both user and group quota check is enabled on /home filesystem

```
# cat /etc/fstab
LABEL=/home /home ext2 defaults,usrquota,grpquota 1 2
```

Reboot the server after the above change.

2. Initial quota check on Linux filesystem using quotacheck

Once you've enabled disk quota check on the filesystem, collect all quota information initially as shown below.

```
# quotacheck -avug
quotacheck: Scanning /dev/sda3 [/home] done
quotacheck: Checked 5182 directories and 31566 files
quotacheck: Old file not found.
quotacheck: Old file not found.
```

In the above command:

- a: Check all quota-enabled filesystem
- v: Verbose mode
- u: Check for user disk quota

• g: Check for group disk quota

The above command will create a aquota file for user and group under the filesystem directory as shown below.

```
# 1s -1 /home/
```

```
-rw----- 1 root root 11264 Jun 21 14:49 aquota.user
-rw----- 1 root root 11264 Jun 21 14:49 aquota.group
```

3. Assign disk quota to a user using edquota command

Use the edquota command as shown below, to edit the quota information for a specific user.

For example, to change the disk quota for user 'ramesh', use edquota command, which will open the soft, hard limit values in an editor as shown below.

```
# edquota ramesh
```

```
Disk quotas for user ramesh (uid 500):
Filesystem blocks soft hard inodes soft hard
/dev/sda3 1419352 0 0 1686 0 0
```

Once the edquota command opens the quota settings for the specific user in a editor, you can set the following limits:

- soft and hard limit for disk quota size for the particular user.
- soft and hard limit for the total number of inodes that are allowed for the particular user.

4. Report the disk quota usage for users and group using repquota

Use the repquota command as shown below to report the disk quota usage for the users and groups.

```
# repquota /home
*** Report for user quotas on device /dev/sda3
Block grace time: 7days; Inode grace time: 7days
```

	Block limits					File limits			
User		used	soft	hard	grace	used	soft	hard	grace
root		566488	0	0		5401	0	0	
nobody		1448	Θ	0		30	0	0	
ramesh		1419352	Θ	0		1686	0	0	
john		26604	Θ	0		172	0	0	

5. Add quotacheck to daily cron job

Add the quotacheck to the daily cron job. Create a quotacheck file as shown below under the /etc/cron.daily directory, that will run the quotacheck command everyday. This will send the output of the quotacheck command to root email address.

```
# cat /etc/cron.daily/quotacheck
quotacheck -avug
```