PROP TRADERS COMMUNITY (PTC)

Enterprise Discord Security & Mass DM Bot

Official Administrator & Founder Operations Manual | Version 2.0

RESTRICTED ACCESS: All bot commands are strictly enforced for **Server Founder** and **Administrators** only. Built-in Anti-Spam protection prevents Discord token suspension through humanized jitter, HTTP 429 exponential backoff, and DM closed (50007) error isolation.

1. Verification Onboarding & Scheduled Reminder System

Automatically sends a welcoming DM to newly joined members with the verification instructions and attached image banner. Members holding the **@unverified** role receive automated scheduled reminders (e.g. 24 hours after joining, then repeated every 24 hours).

Command	Parameters	Description & Action
`/verify preview`	None	Sends a test preview of the verification message and banner directly to your DMs.
`/verify status`	None	Displays active verification configuration, target channel, unverified count, and reminder cadence.
`/verify trigger_reminders`	None	Instantly runs a reminder pass across all unverified members under safe rate-limiting.

2. Mass DM Broadcast & Message Link Mirroring (With Yes/No Confirmation & Preview)

Dispatch text announcements with multiple image attachments or clone an existing Discord message with all attachments into members' private DMs. **Safety Feature:** Manual broadcasts automatically display an interactive preview and require clicking **[Confirm & Send DMs]** (Yes) or **[Cancel Broadcast]** (No) before any DMs are sent.

Command	Parameters	Description & Action
`/dm send`	**target_type:** all | role | user **message:** text *image_1..3:* file attachments	Shows full preview & asks for Yes/No confirmation. Dispatches custom DM with up to 3 attachments to Everyone, a Role, or a specific User.
`/dm from_link`	**message_link:** URL **target_type:** all | role | user *role:* optional *user:* optional	Shows full preview & asks for Yes/No confirmation. Clones any server announcement by URL (text, embeds, downloaded attachments) into DMs.

3. Campaign Management & Queue Control (CRUD)

Monitor live deliveries in real-time, pause active campaigns if needed, resume them, or cancel pending messages.

Command	Parameters	Description & Action
`/campaign list`	None	**[READ]** Lists recent broadcast campaigns with real-time status and delivery percentages.

`/campaign status`	**campaign_id:** int	**[READ]** Shows detailed breakdown of delivered, blocked DMs (50007), failed, and remaining queue items.
`/campaign pause`	**campaign_id:** int	**[UPDATE]** Halts an ongoing DM broadcast instantly.
`/campaign resume`	**campaign_id:** int	**[UPDATE]** Resumes a paused campaign safely.
`/campaign cancel`	**campaign_id:** int	**[DELETE]** Cancels campaign and purges pending queue entries.

4. Server Configuration, Blacklist & Reusable Templates (CRUD)

Manage roles, verification channels, custom reusable templates, and user opt-outs.

Command	Parameters	Description & Action
`/config view`	None	**[READ]** View current verification channel, roles, delays, and message template.
`/config set`	verification_channel, unverified_role, verified_role, initial_delay_hours, repeat_interval_hours, reminder_enabled	**[UPDATE]** Configure role IDs, target channels, and schedule cadence (e.g. 24h delay, 24h repeat).
`/config set_message`	**message:** text	**[UPDATE]** Set custom verification reminder template text with {channel_id} token.
`/blacklist add`	**user:** Member, *reason:* text	**[CREATE]** Exclude a member from receiving all automated and broadcast DMs.
`/blacklist remove`	**user:** Member	**[DELETE]** Remove user from the opt-out blacklist.
`/blacklist list`	None	**[READ]** View all blacklisted members and reasons.
`/template create`	**name:** str, **content:** str	**[CREATE]** Save reusable announcement/marketing templates in SQLite.
`/template get`	**name:** str	**[READ]** Retrieve a saved template body.
`/template list`	None	**[READ]** List all saved templates.
`/template delete`	**name:** str	**[DELETE]** Remove a saved template.

5. Discord Anti-Spam & Rate-Limit Protection Mechanics

Humanized Jitter Delay	Applies a randomized 3.0 to 6.0 second wait between each individual DM. Prevents sudden traffic bursts that trigger Discord's spam bot filters.
Batch Cool-Down Breaks	After every 20 DMs dispatched, the bot pauses for a 25-second cool-down breather before continuing the queue.
HTTP 429 Exponential Backoff	If Discord returns a 429 rate limit code, the worker extracts the exact `retry_after` parameter, pauses safely for that duration + 2s buffer, then resumes without dropping messages.
Error 50007 Isolation (Closed DMs)	When users have closed DMs or blocked the bot, it logs 'Blocked DM' without retrying or causing gateway abuse flags.
Circuit Breaker Fail-Safe	If 5 consecutive hard network or permission errors occur, the bot auto-pauses the campaign to prevent spamming failed sockets.

6. 24/7 Free Hosting Setup (Render + UptimeRobot)

Step 1: Discord Developer Portal Setup

• Go to discord.com/developers/applications, select your Bot.
• Under **Bot -> Privileged Gateway Intents**, ENABLE: **SERVER MEMBERS INTENT** and **MESSAGE CONTENT INTENT**.
• Under **Installation**, ensure bot has **Send Messages, Attach Files, Read Messages, Administrator** permissions.

Step 2: Deploy to Render
• Push code to a private GitHub repository.
• In render.com, create a **New Web Service** pointing to your repo.
• Environment: **Python 3** | Build Command: **pip install -r requirements.txt** | Start Command: **python bot.py**.
• Add Environment Variables: **DISCORD_TOKEN**, **FOUNDER_ID**, **ADMIN_ROLE_ID**, **PORT=8080**.

Step 3: Keep-Alive 24/7 with UptimeRobot (Upbot)
• Copy your Render Web Service URL: *https://your-bot-name.onrender.com/health*.
• Go to uptimerobot.com, create a New Monitor -> Type: **HTTP(s)**.
• Monitoring Interval: **Every 5 minutes**. This pings the bot's embedded server and prevents Render free tier from sleeping!