# Zugriff per PGAdmin auf ein lokales AKTIN DWH

Anleitung für Zugriff auf ein I2B2 DWH mit Postgresql Datenbank via PGAdmin

## Voraussetzungen

Anmeldung auf Datenbank erfolgt mit User postgres. Standartmäßig ohne Passwort. Das Passwort kann mit diesen Befehlen gesetzt werden (oder ersetzen):

In der shell eingeben:

```
sudo -u postgres psql postgres
```

Dann folgenden Befehl in die postgres Shell eingeben und das Passwort setzen:

```
postgres=# \password postgres
```

# Schritt-für-Schritt-Anleitung

1. in /etc/postgresql/VERSIONSNUMMER/main die config Dateien ändern. Zugriff von Extern in postgresql.conf ändern:

```
nano /etc/postgresql/12/main/postgresql.conf
```

2. Zugriff von Extern in postgresql.conf ändern durch ändern der Zeile wie folgt (Auskommentieren und '\*' hinzufügen). Es können auch explizite IP Adressen konfiguriert werden.

```
postgresql.conf

#-----
# CONNECTIONS AND AUTHENTICATION
#------
# - Connection Settings -
listen_addresses = '*' # what IP address(es) to listen on;
```

3. Zugriff per MD5/scram-sha-256 Authentifizierung aktivieren in pg\_hba.conf

```
nano /etc/postgresql/12/main/pg_hba.conf
```

4. Zugriff per MD5 Authentifizierung in postgresql.conf ändern durch ändern der Zeile wie folgt (IP des Zugreifenden Systems muss hinzugefügt werden):

#### pg\_hba.conf

```
# DO NOT DISABLE!
# If you change this first entry you will need to make sure that the
# database superuser can access the database using some other method.
# Noninteractive access to all databases is required during automatic
# maintenance (custom daily cronjobs, replication, and similar tasks).
# Database administrative login by Unix domain socket
local all
                      postgres
                                                              peer
# TYPE DATABASE
                                      ADDRESS
                      USER
                                                              METHOD
# "local" is for Unix domain socket connections only
local all
                      all
                                                              peer
# IPv4 local connections:
                                  127.0.0.1/32
host.
     all
                    all
                                                              md5
# IPv6 local connections:
host all
                      all
                                      ::1/128
                                                              md5
# Allow replication connections from localhost, by a user with the
# replication privilege.
local replication all host replication all
                                                              peer
                                     127.0.0.1/32
                                                              md5
host replication all
                                      ::1/128
                                                              md5
host
      all
                      all
                                      0.0.0.0/0
                                                              md5
host
       all
                       all
                                       ::/0
                                                              md5
```


### oder in neueren Postgres Versionen:

```
# DO NOT DISABLE!
# If you change this first entry you will need to make sure that the
# database superuser can access the database using some other method.
# Noninteractive access to all databases is required during automatic
# maintenance (custom daily cronjobs, replication, and similar tasks).
# Database administrative login by Unix domain socket
local all
                     postgres
                                                           peer
# TYPE DATABASE
                    USER
                                    ADDRESS
                                                           METHOD
# "local" is for Unix domain socket connections only
local all
                     all
                                                           peer
# IPv4 local connections:
      all
                                    127.0.0.1/32
                                                          scram-sha-256
                    all
# IPv6 local connections:
host.
     all
                     all
                                    ::1/128
                                                           scram-sha-256
# Allow replication connections from localhost, by a user with the
# replication privilege.
local replication all
                                                           peer
host replication all
                                   127.0.0.1/32
                                                           scram-sha-256
host replication all
                                    ::1/128
                                                           scram-sha-256
host all all host all all
                                    0.0.0.0/0
                                                           scram-sha-256
                                     ::/0
                                                           scram-sha-256
```

## 5. Postgresql und Wildfly neustarten

```
service postgresql restart
service wildfly restart
```

6. Zugriff per PGAdmin(v4 oder höher) mit folgender Konfiguration:



## Verwandte Artikel

- DWH 1.6 Update depends on postgresql <=229</li>
   DWH Update 1.6 verbindet sich nicht mehr mit dem Broker
- Zugriff per PGAdmin auf ein lokales AKTIN DWH
   HTTPS-Zugriff aktivieren
- DWH Logdateien erstellen