autodie::exception(3pm)

autodie::exception(3pm) User Contributed Perl Documentation autodie::exception(3pm)

NAME

autodie::exception - Exceptions from autodying functions.

SYNOPSIS

```
eval {
    use autodie;
    open(my $fh, '<', 'some_file.txt');
    ...
};
if (my $E = $@) {
    say "Ooops! ",$E->caller," had problems: $@";
}
```

DESCRIPTION

When an autodie enabled function fails, it generates an "autodie::exception" object. This can be interrogated to determine further information about the error that occurred.

This document is broken into two sections; those methods that are most useful to the end-developer, and those methods for anyone wishing to subclass or get very familiar with "autodie::exception".

Common Methods

These methods are intended to be used in the everyday dealing of exceptions.

The following assume that the error has been copied into a separate scalar:

```
if ($E = $@) {
     ...
}
```

This is not required, but is recommended in case any code is called which may reset or alter \$@.

 args

```
my $array_ref = $E->args;
```

Provides a reference to the arguments passed to the subroutine that died. function

```
my $sub = $E->function;
```

The subroutine (including package) that threw the exception.

file

```
my $file = $E->file;
```

The file in which the error occurred (eg, "myscript.pl" or "MyTest.pm"). package

```
my $package = $E->package;
```

The package from which the exceptional subroutine was called.

 $\underline{\text{caller}}$

```
my $caller = $E->caller;
```

The subroutine that $\underline{\text{called}}$ the exceptional code.

 $\underline{\mathrm{line}}$

```
my $line = $E->line;
```

The line in "\$E->file" where the exceptional code was called.

 $\underline{\operatorname{context}}$

```
my $context = $E->context;
```

The context in which the subroutine was called by autodie; usually the same as the context in which you called the autodying subroutine. This can be 'list', 'scalar', or undefined (unknown). It will never be 'void', as "autodie" always captures the return value in one way or another.

For some core functions that always return a scalar value regardless of their context (eg, "chown"), this may be 'scalar', even if you used a list context.

return

```
my $return_value = $E->return;
```

The value(s) returned by the failed subroutine. When the subroutine was called in a list context, this will always be a reference to an array containing the results. When the subroutine was called in a scalar context, this will be the actual scalar returned.

errno

```
my $errno = $E->errno;
```

The value of \$! at the time when the exception occurred.

NOTE: This method will leave the main "autodie::exception" class and become part of a role in the future. You should only call "errno" for exceptions where \$! would reasonably have been set on failure.

eval_error

```
my $old_eval_error = $E->eval_error;
```

The contents of \$@ immediately after autodic triggered an exception. This may be useful when dealing with modules such as Text::Balanced that set (but do not throw) \$@ on error.

 $\underline{\text{matches}}$

```
if ( $e->matches('open') ) { ... }
if ( $e ~~ 'open' ) { ... }
```

"matches" is used to determine whether a given exception matches a particular role. On Perl 5.10, using smart-match ("~~") with an "autodie::exception" object will use "matches" underneath.

An exception is considered to match a string if:

- For a string not starting with a colon, the string exactly matches the package and subroutine that threw the exception. For example, "MyModule::log". If the string does not contain a package name, "CORE::" is assumed.
- For a string that does start with a colon, if the subroutine throwing the exception <u>does</u> that behaviour. For example, the "CORE::open" subroutine does ":file", ":io" and ":all".

See "CATEGORIES" in autodie for further information.

Advanced methods

The following methods, while usable from anywhere, are primarily intended for developers wishing to subclass "autodie::exception", write code that registers custom error messages, or otherwise work closely with the "autodie::exception" model.

register

```
autodie::exception->register( 'CORE::open' => \&mysub );
```

The "register" method allows for the registration of a message handler for a given subroutine. The full subroutine name including the package should be used.

Registered message handlers will receive the "autodie::exception" object as the first parameter.

```
add file and line
```

```
say "Problem occurred",$@->add_file_and_line;
```

Returns the string " at %s line %d", where %s is replaced with the filename, and %d is replaced with the line number.

Primarily intended for use by format handlers.

stringify

```
say "The error was: ",$0->stringify;
```

Formats the error as a human readable string. Usually there's no reason to call this directly, as it is used automatically if an "autodie::exception" object is ever used as a string.

Child classes can override this method to change how they're stringified.

 $format_default$

```
my $error_string = $E->format_default;
```

This produces the default error string for the given exception, without using any registered message handlers. It is primarily intended to be called from a message handler when they have been passed an exception they don't want to format.

Child classes can override this method to change how default messages are formatted.

 $\underline{\text{new}}$

```
my $error = autodie::exception->new(
    args => \@_,
    function => "CORE::open",
    errno => $!,
    context => 'scalar',
    return => undef,
);
```

Creates a new "autodie::exception" object. Normally called directly from an autodying function. The "function" argument is required, its the function we were trying to call that generated the exception. The "args" parameter is optional.

The "errno" value is optional. In versions of "autodie::exception" 1.99 and earlier the code would try to automatically use the current value of \$!, but this was unreliable and is no longer supported.

Attributes such as package, file, and caller are determined automatically, and cannot be specified.

SEE ALSO

autodie, autodie::exception::system

LICENSE

Copyright (C)2008 Paul Fenwick

This is free software. You may modify and/or redistribute this code under the same terms as Perl 5.10 itself, or, at your option, any later version of Perl 5.

AUTHOR

Paul Fenwick <pjf@perltraining.com.au>

2014-01-27 perl v5.18.2