# Ganeshell: browsing/debugging tool for $GANESHA\ NFS\ server$

# thomas.leibovici@cea.fr

# 13th May 2008

# Contents

1	Getting started 1.1 Compiling, installing and running						
	1.2		an interactive session	$\frac{2}{2}$			
2	Using the shell						
	2.1	Layers		3			
		2.1.1	Layers overview	3			
		2.1.2	Setting current layer	3			
		2.1.3	Layer's debug level	4			
	2.2	Variab		4			
		2.2.1	Getting, setting, deleting a variable	4			
		2.2.2	Special variables	5			
	2.3	Expres	sions	6			
		2.3.1	Expression types	6			
		2.3.2	Handling expressions	7			
	2.4	Condit	ional execution	8			
	2.5		outines	8			
	2.6		$\operatorname{execution}$	9			
	2.7			10			
		2.7.1	Command line	10			
		2.7.2		10			
		2.7.3	v	10			
3	Accessing layers 10						
	3.1	$\widetilde{\mathrm{FSAL}}$		10			
		3.1.1		10			
		3.1.2		11			
		3.1.3	8	11			
		3.1.4		11			
	3.2			11			
	J			19			

	3.2.2	Getting started	12
	3.2.3	Paths and handles	12
3.3	NFS		12
	3.3.1	Initialization	12
	3.3.2	Getting started	13
	3.3.3	Paths and handles	14
3.4	$NFS_{-}$	remote	15
	3.4.1	Initialization	15
	3.4.2	How to use it	15

# 1 Getting started

## 1.1 Compiling, installing and running

Build the NFS-GANESHA distribution with the filesystem that you want. E.g:

```
./configure --with-fsal=<filesystem_type>
```

In the "shell" directory, a program called <fsname>.ganeshell is built. You can install it on your system by running "make install".

Then, you can simply run the shell without arguments (interactive mode), or specify one or several script files to be executed (batch mode).

## Synopsis:

```
<fsname>.ganeshell [-h][-v][-n <nb>][Script_File1 [Script_File2]...]
```

```
-h: display short help
```

- -v: verbose mode
- -n <nb>: number of script instances (threads) to run

## 1.2 Start an interactive session

Run the shell with no arguments, then type "help" for displaying available commands:

```
bash$ ./posix.ganeshell
```

### ganeshell>help

Shell built-in commands:

```
barrier: synchronization in a multi-thread shell
```

echo: print one or more arguments

exit: exit this shell

help: print this help

if: conditionnal execution

interactive: close script file and start interactive mode

print: print one or more arguments

quit: exit this shell

set: set the value of a shell variable

time: measures the time for executing a command

unset: free a shell variable

varlist: print the list of shell variables

#### Shell tools commands:

chomp: removes final newline character

cmp: compares two expressions

```
diff: lists differences between two expressions
```

eq: test if two expressions are equal
meminfo: prints information about memory use
ne: test if two expressions are different

shell: executes a real shell command

sleep: suspends script execution for some time

timer: timer management command

wc: counts the number of char/words/lines in a string

#### Layers list:

FSAL: File system abstraction layer

Cache\_inode: Cache inode layer

NFS: NFSv2, NFSv3, MNTv1, MNTv3 protocols (direct calls, not through RPCs)

NFS\_remote: NFSv2, NFSv3, MNTv1, MNTv3 protocols (calls through RPCs)

## 2 Using the shell

## 2.1 Layers

## 2.1.1 Layers overview

The shell deals with GANESHA's layers independently. You must initialize each layer that you want to use in the correct order (first the lowest layer, then the upper ones), and you can issue some commands on each of these layers.

The list of available layers is displayed in the return of the "help" command. Here is the list of server-side layers, from the lowest level to the highest:

- FSAL: the File System Abstraction Layer
- Cache inode: the metadata cache layer (FSAL layer must be initialized)
- NFS: the NFS protocol layer (FSAL and Cache\_inode layers must be initialized)

You can also use ganeshell only as a NFS client, with the "NFS\_remote" layer. This layer doesn't need any other layer to be initialized.

#### 2.1.2 Setting current layer

You can set the current layer by setting the LAYER shell variable. E.g:

ganeshell> set LAYER FSAL

Then, "help" will display the list of commands available for this layer. To obtains some help for a command, launch it with the "-h" option. E.g:

Each layer need to be initialized. Most of them provide an "init" call, that takes a GANESHA configuration file as argument. E.g.

## 2.1.3 Layer's debug level

The special shell variable DEBUG\_LEVEL is specific to each layer. Setting it will impact the next calls to this layer (even if the layer is called by an upper layer).

In the following example, FSAL will be in FULL\_DEBUG mode, and Cache\_inode will be in EVENT level:

```
# FSAL initialization
set LAYER FSAL
set DEBUG_LEVEL NIV_FULL_DEBUG
init_fs /etc/posix.ganesha.nfsd.conf

# Metadata cache initialization
set LAYER Cache_inode
set DEBUG_LEVEL NIV_EVENT
init_cache /etc/ganesha/posix.ganesha.nfsd.conf
```

## 2.2 Variables

Ganeshell provides variables management, so you can create custom variables, affect values to them and use their value afterward as argument of a command, a condition, ... Variable values are stored as strings.

You can list all defined variables with the shell built-in command varlist.

## 2.2.1 Getting, setting, deleting a variable

• To get the value of a variable, place a \$ sign before its name:

```
ganeshell> echo $LINE
42
```

• To set the value of a variable, execute:

```
set <var_name> <expression1> [expression2] ...
Example:
ganeshell> set A 5
```

This will create the variable if it does not exist, else it will override its previous value.

Expressions can be strings, other variables, command returns...

Note that set accepts several expressions that will be concatenated in the target variable:

```
ganeshell> set MYVAR "A:" 1345 " L:" $LINE
ganeshell> echo $MYVAR
A:1345 L:28
```

• Finally, you can destroy a variable definition using unset:

```
ganeshell> unset MYVAR
ganeshell> echo $MYVAR
****** ERROR in <stdin> line 49: Undefined variable "MYVAR"
```

## 2.2.2 Special variables

Some special variables are defined and interpreted by shell:

• \$? and \$STATUS: contain the status returned by the last operation

```
E.g:
ganeshell>toto
******* ERROR in <stdin> line 3: toto: command not found
ganeshell>echo $?
-2
```

- \$SHELLID: in a multi-instance (multi-thread) shell, this gives the index for the current thread (first is 0);
- \$PROMPT: you can modify the prompt string with this variable. This may me useful when several threads are writing to shell standard output

```
E.g:
ganeshell> set PROMPT "thread#" $SHELLID ">"
thread#0>
```

• \$INTERACTIVE: indicates whether the shell is in interactive or batch mode;

• \$INPUT: indicates the current input file for the shell (<stdin> is returned in interactive mode). Setting the value of this variable will result in executing the given file as a ganeshell script

```
E.g:
ganeshell> set INPUT /tmp/my_script.gsh
```

- \$LINE: returns the current line number in script or standard output;
- \$DEBUG LEVEL or \$DBG LVL: debug level of the current layer;
- \$VERBOSE: setting this variable will enable/disable shell verbose. This mode is similar to "set -o xtrace" in common UNIX shells: each executed command and its returned status are displayed on standard error output. This does not affect layer's trace level.

## 2.3 Expressions

## 2.3.1 Expression types

Several expression types can be used for affecting a value to a variable, or as a command argument:

• any unquoted sequence of characters, with no blank (space or tab)

```
Example:
ganeshell> set A 1
ganeshell> echo $A
1
ganeshell> set X 2.345
ganeshell> echo $X
2.345
```

• single or double quoted strings

```
Examples:
ganeshell> set D "This is a double-quoted string"
ganeshell> echo $D
This is a double-quoted string

ganeshell> set S 'This is a single-quoted string'
ganeshell> echo $S
This is a single-quoted string
```

• variable value: a \$ sign followed by a variable name

```
Example:
ganeshell> set B $A
ganeshell> echo $B
```

• command return: a backquoted string

```
Example:
ganeshell> set DATE "current time is: " 'shell date'
ganeshell> echo $DATE
current time is: Wed May 7 14:55:49 CEST 2008
```

Note that you can escape a character in an expression, using a backslash:

```
ganeshell> set E "There are some \"escaped\" caracters here !" ganeshell> echo \$E There are some "escaped" caracters here !
```

Variable references (\$<varname>) are not interpreted when they are used in a single or double-quoted string.

```
ganeshell> set STR "The value of A is A" ganeshell> echo STR The value of A is A
```

If you want to display the value of A, reference it outside the string:

```
ganeshell> set STR "The value of A is " A ganeshell> echo TR The value of A is 1
```

In a back-quoted string, they are however interpreted at command execution time.

## 2.3.2 Handling expressions

Several built-in commands can be used for handling expressions:

• chomp: remove newline chars at the end of an expression. It is useful for cleaning expressions returned by an external command:

```
ganeshell> set RET 'shell date'
ganeshell>echo "returned:[" $RET "]"
returned:[Wed May 7 14:55:49 CEST 2008
]
ganeshell> set RET 'chomp $RET'
ganeshell>echo "returned:[" $RET "]"
returned:[Wed May 7 14:55:49 CEST 2008]
```

- wc: count the number of characters and lines of an expression
- diff: compare two expressions
- eq: test if two expressions are the same (status is 0 if different, 1 if equal, -1 on error)

```
ganeshell> eq "ABCD" "ABCD"
ganeshell> echo $?
1
ganeshell> eq "ABCD" "abcd"
ganeshell> echo $?
0

# case insensitive string compare
ganeshell> eq -i "ABCD" "abcd"
ganeshell> echo $?
1

# numerical compare
ganeshell> eq -n 000001 1
ganeshell> echo $?
1
```

• ne: test if two expressions are different (status is 1 if different, 0 if equal, -1 on error)

## 2.4 Conditional execution

ganeshell provides a very basic structure for conditional execution. It's syntax is:

```
if command0 ? command1 [: command2]
```

command0 is first executed. If its return code is not null, then command1 is executed, else command2 (optional) is launched.

Basically, command can be a test command like eq or ne.

```
Example:
```

```
ganeshell> cd ..
```

```
ganeshell> if ne -n $STATUS 0 ? print "cd command ERROR" : print "cd command OK"
```

## 2.5 Time routines

Its often useful to benchmark filesystem performances. So the shell provides calls for measuring command execution time:

• time <command>: measures and display the time for executing a command.

## Example:

```
ganeshell> time init_fs /root/posix.ganesha.nfsd.conf
Execution time for command "init_fs": 0.027679 s
```

• timer start|stop|print: this timer makes it possible to measure the time since it was started.

```
Example:
ganeshell> timer start
ganeshell> cd /tmp
ganeshell> ls
ganeshell> timer print
0.804578 s
ganeshell> cd ..
ganeshell> ls
ganeshell> timer stop
ganeshell> timer print
1.423081 s
```

• sleep <seconds>: suspends shell execution for a given amount of seconds

## 2.6 Batch execution

For executing a ganeshell script file, simply give it as argument to the <fsname>.ganeshell command.

```
bash$ ./posix.ganeshell /tmp/myscript.gsh
```

You can also execute a script from the interactive mode, by setting the INPUT variable.

```
ganeshell> set INPUT /tmp/myscript.gsh
```

The script is then executed in batch mode. By default, the ganeshell processus terminates when the script is finished. You can however avoid this by using the 'interactive' command: writting this command at the end of your script will result in giving back control to interactive mode, so you can execute other commands after the script run.

This can also been used for writing initialization scripts with repetitive "boot straps" operations. Here is an exemple of such a script:

```
set CONFIG_FILE /etc/ganesha/posix.ganesha.nfsd.conf
set LAYER FSAL
init_fs $CONFIG_FILE
set LAYER Cache_inode
init_cache $CONFIG_FILE
set LAYER NFS
nfs_init $CONFIG_FILE
mount /export
interactive
```

## 2.7 Multi-threaded batch execution

### 2.7.1 Command line

For starting ganeshell with multiple threads, you can launch it with as many scripts as threads wanted:

bash\$ ./posix.ganeshell script-thr1.gsh script-other.gsh script-other.gsh

You can also launch multiple instances of the same script, using the -n option:

bash\$ ./posix.ganeshell -n 4 script.gsh

## 2.7.2 Synchronization

The shell provides a unique synchronization call: barrier. When calling barrier, the thread is suspended until all other threads joined the barrier.

Note that shell variables are NOT shared between threads. They are local to each thread.

## 2.7.3 About layers initialization

Each layer must only be initialized once for all threads. Thus, it recommanded that the first script does all layers initialization and calls barrier afterward, so the other threads will start working only when everything is initialized properly.

# 3 Accessing layers

Ganeshell provides an access to main GANESHA layers, from Filesystem to NFS. Each shell interface implements native filesystem calls (like access, setattr, open, read, write,...) but also higher level features like current directory management (cd, pwd), user management (su) and some classical unix shell commands (cat).

This section gives you a short help for using each of these layers.

## 3.1 FSAL

This layer provides an access to the File System Abstraction Layer of GANESHA (FSAL), so you can make operations directly on the filesystem, without any cache effect due to the Cache\_inode layer.

## 3.1.1 Initialization

For using the FSAL layer, first set the LAYER variable of the shell:

ganeshell> set LAYER FSAL

Then initialize the layer using a Ganesha configuration file:

ganeshell> init\_fs /etc/posix.ganesha.nfsd.conf

## 3.1.2 Getting started

Once initialized, you can use most common shell commands like cd, ls, pwd, stat, mkdir,...

Type help to get FSAL command list.

To get help about a command, type <command> -h.

#### 3.1.3 Paths and handles

FSAL layer of ganeshell makes it possible to address entries using their full or relative path. However, you can also address them using their FSAL handle (hexadecimal representation preceded with a '@' sign):

```
ganeshell> cd /
```

```
# is equivalent to:
```

The 'ls' command has a special option '-S' for displaying objects handle.

## 3.1.4 Users management

If Ganeshell is launched with sufficient permissions for accessing the filesystem or the required credentials, you can take the identity of any user with the 'su' command. This can be very useful for testing access rights of your filesystem.

You can give to 'su' a uid or a user name:

```
ganeshell>su root
Changing user to : root ( uid = 0, gid = 0 )
altgroups = 1, 2, 3, 4, 6, 10
Done.

# is equivalent to:
ganeshell>su 0
Changing user to : root ( uid = 0, gid = 0 )
altgroups = 1, 2, 3, 4, 6, 10
Done.
```

## 3.2 Cache\_inode

This layer provides an access to the Cache\_inode layer of GANESHA, so you can interact directly with it, without going through network or NFS Protocol service routines.

#### 3.2.1 Initialization

You must have initialized the FSAL layer before using the Cache\_inode layer. To do this, report to the previous section (FSAL).

Then, set the LAYER variable of the shell:

```
ganeshell> set LAYER Cache_inode
```

After that, initialize the layer using a Ganesha configuration file:

ganeshell> init\_cache /etc/ganesha/posix.ganesha.nfsd.conf

## 3.2.2 Getting started

Once initialized, you can use most common shell commands like cd, ls, pwd, stat, mkdir,... You can also make actions on data and metadata caches, like data\_cache, flush\_cache, garbagge collection, ...

Type help to get Cache inode command list.

To get help about a command, type <command> -h.

#### 3.2.3 Paths and handles

Like in the FSAL layer, filesystem entries can be addressed using their path or their FSAL handle beginning with '@'.

For displaying FSAL handles with 1s, use the '-H' option. You can also display their addresses in metadata cache with the '-L' option.

#### 3.3 NFS

This layer provides an access to the NFS layer of GANESHA, so you can execute NFS queries directly on the server, as if they were sent by a client.

## 3.3.1 Initialization

You must have initialized the FSAL and the Cache\_inode layers before using the NFS layer. To do this, report to the previous sections (FSAL and Cache\_inode). Then, set the LAYER variable of the shell:

```
ganeshell> set LAYER NFS
```

After that, initialize the layer using a Ganesha configuration file:

ganeshell> nfs\_init /etc/posix.ganesha.nfsd.conf

## 3.3.2 Getting started

This layer provides two ways of accessing the filesystem with NFS:

• You can use native NFS v2 and v3 calls (and mount protocol v1 and v3). In this mode, you need to be aware of manipulating NFS handles and structures;-)

```
ganeshell>mnt3_export
 {
 ex_dir = /tmp
 ex_groups =
   gr_name = 127.0.0.1
ganeshell>mnt3_mount /tmp
 mountres3 =
 {
 fhs_status = 0
 mountinfo =
   auth_flavor = 1
 }
ganeshell>nfs3_getattr @A10000000000000000000000000004F00A752000000000000CD03A747000
 GETATTR3res =
 status = 0 (NFS3_OK)
 fattr3 =
 {
   type = 2 (NF3DIR)
   mode = 01777
   nlink = 9
   uid = 0
   gid = 0
   size = 4096
   used = 8192
   rdev = 0.0
   fsid = 0xc1
   fileid = 0x2
   atime = 1210322525.0000000000 (2008-05-09 10:42:05)
   mtime = 1210326484.0000000000 (2008-05-09 11:48:04)
   ctime = 1210326484.0000000000 (2008-05-09 11:48:04)
 }
```

• You can also use simple shell commands (cd, ls, ...) wrapping MNT3/NFS3

protocol calls. All you have to do before is to make an inital "mount <path>", for beeing able to access an export. The export is then mounted as "/".

Note: you can get the list of exports using "mnt3\_export".

```
ganeshell>mnt3_export
 {
  ex_dir = /tmp
  ex_groups =
    gr_name = 127.0.0.1
ganeshell>mount /tmp
Current directory is "/"
Current File handle is "@A100000000000000000000000000004F00A752000000000000D03A74700
ganeshell>ls -1
                                  0
                                           0
         2 drwxrwxrwx
                                                         4096
                                                                 May 9 12:04 .
                                                                 May 9 12:04 ..
         2 drwxrwxrwx
                        9
                                  0
                                           0
                                                         4096
                        1
                                                                 May 9 11:12 krb5cc_3733
        17 -rw-----
                               3733
                                        5683
                                                          523
                                                                 Apr 9 11:15 gitapply.a2
        23 prw-----
                        1
                               3051
                                        5683
                                                            0
                                                                 Oct 31 2007 RPMS
    56ab41 dr-xr-xr-x
                         2
                                  0
                                           0
                                                         4096
        14 -rw-r--r--
                         1
                                  0
                                           0
                                                        15176
                                                                 May 6 13:07 ganesha.sta
        13 srwxrwxrwx
                         1
                               2931
                                        2931
                                                            0
                                                                 May 9 12:01 .s.PGSQL.54
         d -rw-----
                               3733
                                        5683
                                                          523
                                                                 May 9 10:58 krb5cc_3733
                         1
         f \quad -rwxr-x---
                         1
                               3733
                                        5683
                                                     10165193
                                                                 May 6 11:57 posix.ganes
                                                                 Apr 23 11:16 casimir.cmc
        11 -rw-r--r--
                        1
                                  0
                                           0
                                                            0
    6170a1 drwxr-x---
                        3
                                  0
                                           0
                                                         4096
                                                                 May 9 10:38 ganesha.dat
         c -rw-----
                        1
                               3733
                                                                 May 9 09:52 krb5cc_3733
                                        5683
                                                          523
        10 -rw-r--r--
                         1
                                                                 May 9 12:05 invocateur.
                                  0
                                           0
                                                           10
        15 -rw-r--r--
                        1
                                  0
                                           0
                                                        33531
                                                                 May 1 15:09 casimir.cmc
        12 -rw-----
                        1
                               2931
                                        2931
                                                           26
                                                                 May 9 12:01 .s.PGSQL.54
         b drwx----
                                                                 Oct 31 2007 lost+found
                        2
                                  0
                                                        16384
                                           0
                                        5683
        16 -rwxr-x---
                        1
                               3733
                                                      6967242
                                                                 May 7 13:27 posix.ganes
                                                                 Apr 29 13:59 casimir.cmc
        18 -rw-r--r--
                        1
                                  0
                                           0
                                                          148
    2b95c1 drwxrwxrwx
                         2
                                  0
                                           0
                                                         4096
                                                                 Apr 23 11:15 .font-unix
     28141 drwxrwxrwx
                         2
                                  0
                                           0
                                                         4096
                                                                 Apr 23 11:14 .ICE-unix
```

#### 3.3.3 Paths and handles

Of course, if you are using native NFSv2/v3 calls, you will need to address entries using their NFS handle. You also need to solve the path by yourself using LOOKUP call.

If your are using shell wrappers, you can address entries with their full path or with a path relative to the current directory (managed by shell). You can also address entries using their NFSv3 handle, beginning with '@'.

For displaying NFS handles with 1s, use the '-H' option.

## 3.4 NFS remote

This layer makes it possible to use ganeshell as a NFS client.

#### 3.4.1 Initialization

You don't need to initialize any other layer for using the NFS\_remote layer. First, set the LAYER variable of the shell:

```
ganeshell> set LAYER NFS_remote
```

After that, initialize the RPC connections to the remote NFS server for every protocol you need, by providing host name, protocol version and a port number (optional):

```
# initialize client for mount3 protocol
ganeshell> rpc_init localhost mount3 udp 2049
# initialize client for nfs3 protocol
ganeshell> rpc_init localhost nfs3 udp 2049
```

## 3.4.2 How to use it

You can now use the same functions as the NFS layer described in the previous section (both NFS native calls and high-level wrappers).