

Introduction to Microeconomics

Lecture 14—Production

Prof. Alejandro Melo-Ponce



NAZARBAYEV
UNIVERSITY

ECON101
Fall 2023

The production decisions of a firm

The production decisions of firms can be understood in three steps:

Production Technology: How inputs (such as labor, capital, and raw materials) can be transformed into outputs.

Cost Constraints: How inputs (such as labor, capital, and raw materials) can be transformed into outputs.

Input Choices: Just as a consumer is constrained by a limited budget, the firm is concerned about the cost of production and the prices of labor, capital, and other inputs.

The **Theory of the Firm** is an explanation of how a firm makes cost-minimizing production decisions and how its cost varies with its output.

Factors of Production

Inputs into the production process (e.g., labor, capital, and materials). We can divide inputs into the broad categories of labor, materials and capital, each of which might include more narrow subdivisions. Labor inputs include skilled workers (carpenters, engineers) and unskilled workers (agricultural workers), as well as the entrepreneurial efforts of the firm's managers. Materials include steel, plastics, electricity, water, and any other goods that the firm buys and transforms into final products. Capital includes land, buildings, machinery and other equipment, as well as inventories.

The Technology of Production

Production function

The firm's **production function** for a particular good q

$$q = F(K, L),$$

shows the maximum amount of the good that can be produced using alternative combinations of K and L .

Production functions describe what is **technically feasible** when the firm operates **efficiently**.

Short Run vs Long Run

Short Run Period of time in which quantities of one or more production factors cannot be changed.

- A **fixed input** is a production factor that cannot be varied.

Long Run Period of time in which all inputs are variable.

Marginal Physical Product

The **marginal physical product** of an input is the additional output that can be produced by using one more unit of that input while holding all other inputs constant.

For example, for a two input technology involving capital and labor $q = F(K, L)$:

$$MP_K = \frac{\Delta F(K, L)}{\Delta K}, \quad MP_L = \frac{\Delta F(K, L)}{\Delta L}$$



Diminishing Marginal Productivity?

- We might expect the marginal physical product of an input to depend on how much of that input is used.
- Example: labor cannot be added indefinitely to a given field.
- Formally, we expect that the rate of change of the MP with respect to changes in input to be decreasing.
- But changes on the marginal product do not only depend on how the input is used but also to **how other inputs are used**, i.e., they depend on the **input mix**, as well as on **technological growth**.
- Why has labor productivity, i.e., the MP_L risen over time?

- In common usage, **productivity** often means **average productivity**.
- In layman parlance, increases in productivity are taken to be increases in **average productivity**.
- From the very first part of the course we know that in economic discussions and analysis the relevant concept is marginal, not average productivity.
- However, average productivity is easily measured.
- We define the average products to be:

$$AP_K = \frac{F(K, L)}{K} \quad AP_L = \frac{F(K, L)}{L}$$

Relationship between average and marginal products



$$f(L) = 10L^2 - \frac{L^3}{3}$$

$$MP_L = 20L - L^2$$


$$AP_L = \frac{10L^2 - L^3/3}{L} = 10L - L^2/3$$

Isoquant

An **isoquant** shows those combinations of K and L that can produce a given level of output, say q_0 . Mathematically, is the set of input combinations that satisfy the equation:

$$q_0 = F(K, L)$$

$$\text{Isoquant}(q_0) = \{ (K, L) : q_0 = F(K, L) \}$$



$$q = F(K, L) = A K^{\alpha} L^{\beta}$$

Cobb - Douglas Production Function.

$$q_0 = A K^{\alpha} L^{\beta} : \text{implicit eq. for the isoquant}$$

$$\left(\frac{q_0}{A L^{\beta}} \right)^{1/\alpha} = K \quad \text{Cartesian eq. of the isoquant at } q_0$$

$$\alpha = 1/2 \quad \beta = 1/2 \quad \Rightarrow \quad K = \frac{q_0^2}{A^2 L}$$


The marginal rate of technical substitution (MRTS)

Marginal rate of technical substitution

The **marginal rate of technical substitution (MRTS)** of L for K shows the rate at which, having added an extra unit of labor, capital can be decreased while holding output constant along an isoquant. Mathematically

$$MRTS = \frac{MP_L}{MP_K} = -\text{slope of the isoquant when } q = q_0$$

→ depends on q_0 and the input mix (K, L)



$$q = F(K, L)$$

$$\Delta q = MP_K \cdot \Delta K + MP_L \cdot \Delta L$$

$$\hookrightarrow \text{at isoquant}(q_0): \Delta q = 0$$

$$\frac{\Delta K}{\Delta L} = - \frac{MP_L}{MP_K} / \text{slope of the isoquant}$$

$$\hookrightarrow MRTS = \frac{MP_L}{MP_K}$$

Returns to scale

If the production function given by $q = F(K, L)$ and if all inputs are multiplied by the same positive constant t , (where $t > 1$), then we classify **returns to scale** of the production function by

- **Constant returns to scale** $F(tK, tL) = tF(K, L) = tq$
- **Decreasing returns to scale** $F(tK, tL) < tF(K, L) = tq$
- **Increasing returns to scale** $F(tK, tL) > tF(K, L) = tq$

$$q = A K^{\alpha} L^{\beta} = F(K, L)$$

$$F(tK, tL) = A (tK)^{\alpha} (tL)^{\beta}$$

$$= t^{\alpha} t^{\beta} A K^{\alpha} L^{\beta}$$


$$= t^{\alpha+\beta} A K^{\alpha} L^{\beta} = t^{\alpha+\beta} F(K, L)$$

$$\bullet \text{ If } \alpha + \beta = 1 \quad \text{CRS}$$


$$\bullet \text{ If } \alpha + \beta < 1 \quad \text{DRS}$$


$$\bullet \text{ If } \alpha + \beta > 1 \quad \text{IRS}$$

$$f(L) = \sqrt{L}, \quad f(tL) = \sqrt{tL} = \sqrt{t} f(L) < t f(L)$$



$$f(L) = L^2 \rightarrow f(tL) = t^2 f(L) > t f(L) \quad \text{IRS}$$





Elasticity of Substitution

For the production function $q = F(K, L)$, the **elasticity of substitution** σ measures the proportionate change in K/L relative to the proportionate change in the MRTS along an isoquant. That is

$$\sigma = \frac{\Delta\%(K/L)}{\Delta\%MRTS} = \frac{\frac{\Delta(K/L)}{K/L}}{\frac{\Delta MRTS}{MRTS}}$$

$$\sigma = \frac{\Delta \ln(K/L)}{\Delta \ln(MRTS)}$$

Consider the arithmetic return: y_a, y_b

$$h := \frac{y_b - y_a}{y_a} \quad (\text{multiply by } 100\% \text{ is the percentage return})$$

$$y_b = y_a + h \cdot y_a = (1+h) y_a$$

$$\ln(y_b) = \ln(1+h) + \ln(y_a)$$

$$\Rightarrow \ln y_b - \ln(y_a) = \ln(1+h)$$

$$\Delta \ln = \ln(1+h) \approx h$$

h is
small close
to zero


$$\frac{\Delta \% Y}{\Delta \% X} = \frac{\frac{y_b - y_a}{y_a}}{\frac{x_b - x_a}{x_a}} = \frac{\Delta \ln(Y)}{\Delta \ln(X)}$$

Case 1: $\sigma = \infty$


$$q = F(K, L) = AK + BL \quad \text{where } A, B > 0 \text{ are parameters}$$

Say $q_0 = AK + BL \Rightarrow K = \frac{q_0}{A} - \frac{BL}{A}$

$$MP_L = B \quad MP_K = A \quad MRTS = \frac{B}{A}$$



Case 2: $\sigma = 0$, $q_0 = \min \{ AK, BL \}$, $A, B > 0$ are parameters.



The kink of the isoquant is found in the set of input combinations satisfying

$$AK = BL \Rightarrow K = \frac{B}{A}L$$

Case 3: $q = K^\alpha L^\beta$ (Cobb-Douglas) $\sigma = 1$

$$MP_K = \alpha K^{\alpha-1} L^\beta$$

$$MP_L = \beta K^\alpha L^{\beta-1}$$

$$MRTS = \frac{MP_L}{MP_K} = \frac{\beta}{\alpha} \frac{K^\alpha L^{\beta-1}}{K^{\alpha-1} L^\beta} = \frac{\beta}{\alpha} \frac{K}{L}$$

Take $\ln$ on both sides $\ln(MRTS) = \ln\left(\frac{\beta}{\alpha}\right) + \ln\left(\frac{K}{L}\right)$


$$\ln\left(\frac{K}{L}\right) = \ln(MRTS) - \ln\left(\frac{\beta}{\alpha}\right);$$

$\parallel$ $\parallel$
 y x

$$\frac{\Delta \ln\left(\frac{K}{L}\right)}{\Delta \ln(MRTS)} = 1 = \sigma$$

$y = x - \text{constant}$

$$\frac{\Delta y}{\Delta x} = 1$$



exponents α, β

Case 4: CES $q = (K^\sigma + L^\sigma)^{\frac{\gamma}{\sigma}}$

σ, γ are parameters.

$$MP_L = \frac{\gamma}{\sigma} (K^\sigma + L^\sigma)^{\frac{\gamma}{\sigma} - 1} \sigma L^{\sigma-1}$$

$$MP_K = \frac{\gamma}{\sigma} (K^\sigma + L^\sigma)^{\frac{\gamma}{\sigma} - 1} \sigma K^{\sigma-1}$$

$$MRTS = \frac{MP_L}{MP_K} = \frac{L^{\sigma-1}}{K^{\sigma-1}} = \left(\frac{K}{L}\right)^{1-\sigma}$$

$$\ln(MRTS) = (1-\sigma) \ln\left(\frac{K}{L}\right) \Rightarrow \ln\left(\frac{K}{L}\right) = \frac{1}{1-\sigma} \ln(MRTS)$$

$$\Rightarrow \text{elasticity of substitution } \sigma = \frac{1}{1-\sigma}$$

γ has to do with
returns to scale

σ has to do with the
elasticity of substitution.

