Navier-Stokes Equations

@X1alejandrox3

April 4, 2018

Contents

1	Diff	ferential Form	1
	1.1	Reynolds Transport Theorem	1
		Conservation of Mass	
	1.3	Conservation of Momentum	
		1.3.1 Inviscid flow:	4
2		vier-Stokes Equations	5
	2.1	Normal Stresses	ŀ
		1101Hall Delebbeb	-
	2.2	Shearing Stresses	

1 Differential Form

1.1 Reynolds Transport Theorem

Consider an integration of $\mathbf{f} = \mathbf{f}(\mathbf{x}, t)$ over the time-dependent region $\Omega(t)$ with boundary $\partial \Omega(t)$. Taking a derivative with respect to time,

$$\frac{d}{dt} \int_{\Omega(t)} d\mathbf{V} \, \mathbf{f}$$

To move the integral inside the integration, we need to account for the time dependence of ${\bf f}$ along with the introduction and removal of space from Ω due to its dynamic boundary.

Reynold's transport theorem allows us to do so!

$$\frac{d}{dt} \int_{\Omega(t)} d\mathbf{V} \, \mathbf{f} = \int_{\Omega(t)} d\mathbf{V} \, \frac{\partial \mathbf{f}}{\partial t} + \int_{\partial \Omega(t)} d\mathbf{A} \, \left(\mathbf{v}^b \cdot \mathbf{n} \right) \mathbf{f}$$

Here, $\mathbf{n}(\mathbf{x},t)$ is the outward-pointing unit normal vector and $\mathbf{v}^b(\mathbf{x},t)$ is the velocity of the area element.

1.2 Conservation of Mass

$$\frac{DM_{sys}}{Dt} = 0$$

Using Reynold's theorem we can then write a system of equations for a control volume (cv). We will have a couple terms:

- 1. Rate at which mass in the control volume changes.
- 2. Flux accross control surface (net rate at which mass is flowing).

both of this terms have to negate each other in order for mass to be conserved:

$$\frac{DM}{Dt} = \frac{\partial}{\partial} \int_{cv} \rho \, dV + \int_{cs} \rho \mathbf{V} \cdot \hat{\mathbf{n}} \, dA = 0$$

Where \mathbf{v} is the velocity of the fluid.

Differential Form:

Consider a small fluid element of size $\delta x \delta y \delta z$.

Assuming that the density is uniform accross the differential of volume (very small volume), we can see that the rate at which the mass inside the control volume changes is given by,

$$\frac{\partial \rho}{\partial t} \delta x \delta y \delta z$$

The x component of the mass flow rate, across a face of an infinitesimal cube:

$$\left[\rho u + \frac{\partial}{\partial x} \left(\rho u\right) \frac{\delta x}{2}\right] \delta y \delta z$$

the flux of mass across the opposite face:

$$\left[\rho u - \frac{\partial}{\partial x} \left(\rho u\right) \frac{\delta x}{2}\right] \delta y \delta z$$

So the net rate of mass outflow in the x direction:

$$\frac{\partial}{\partial x} (\rho u) \delta x \delta y \delta z$$

Nothing speacial about the x direction, hence one can see the net rate of mass outflow can be expressed as,

$$\left[\frac{\partial}{\partial x}\left(\rho u\right)+\frac{\partial}{\partial y}\left(\rho v\right)+\frac{\partial}{\partial z}\left(\rho w\right)\right]\delta x\delta y\delta z$$

From which we finally get the differential form:

$$\frac{\partial \rho}{\partial t} + \frac{\partial}{\partial x} (\rho u) + \frac{\partial}{\partial y} (\rho v) + \frac{\partial}{\partial z} (\rho w) = 0$$

In a nicer form,

$$\frac{\partial \rho}{\partial t} + \nabla \cdot \rho \mathbf{v} = 0$$

Notice that for a steady flow (constant fluid velocity) the first term will be zero.

1.3 Conservation of Momentum

$$\mathbf{F} = \frac{D}{Dt} \int \mathbf{V} dm$$

Following the same approach as before can obtain the differential form, which has an unsteady and a flux term,

$$\Sigma f = \frac{\partial}{\partial t} \int_{CV} \mathbf{v} \rho \, dV + \int_{CS} \mathbf{v} \rho \mathbf{v} \cdot \hat{\mathbf{n}} \, dA$$

Here again, we need to step back, look at our control volume and gather some inpiration so see what terms we need to take into account.

For an infitesimal volume of fluid, we will have,

$$\delta \mathbf{f} = \frac{D}{Dt} \left(\mathbf{v} \delta m \right) = \delta m \cdot \mathbf{a}$$

The system will experience two types of forces, body and surface forces. For our case, the only body force we may take into consideration may be that of gravity, in which case $\delta f_b = \delta m \cdot \mathbf{g}$.

Surface forces will consist of, think if a cube, one normal to the surface, and two tangential perpendicular to the normal force and to each other. From this point of view we will go on and define stresses:

• Normal stress:

$$\sigma_n = \lim_{\delta A \to 0} \frac{\delta f_b}{\delta A}$$

• Shearing stress:

$$\tau_i = \lim_{\delta A \to 0} \frac{\delta f_i}{\delta A}$$

Now, stresses make sense when you taken into account with respect to a coordinate system. Using plain and simple cartetian we will define the following notation: For the stresses on a plane in direction of coordinate i and parallel to the other two, we will talk about the normal stress σ_{ii} and τ_{ij} and τ_{ik} (assuming that the directions j and k are orthogonal to direction of the normal vector, i, for that plane). So first subscript is the direction of the normal vector, second subscript is the direction of the stress vector.

Sign convention? The positive direction for the stress is the positive coordinate direction on the surface for which the outward normal is in the positive coordinate direction.

Looking at the surface forces in terms of stresses, starting with planes orthogonal to the y-z directions, we then have, for the net normal stress,

$$\left[\left(\sigma_{xx} + \frac{\partial \sigma_{xx}}{\partial x} \frac{\delta x}{2} \right) - \left(\sigma_{xx} - \frac{\partial \sigma_{xx}}{\partial x} \frac{\delta x}{2} \right) \right] \delta y \delta z = \frac{\partial \sigma_{xx}}{\partial x} \delta x \delta y \delta z$$

The net shear stresses, same configuration,

$$\left[\left(\tau_{zx} + \frac{\partial \tau_{zx}}{\partial z} \frac{\partial z}{2} \right) - \left(\tau_{zx} - \frac{\partial \tau_{zx}}{\partial z} \frac{\partial z}{2} \right) \right] \delta x \delta y = \frac{\partial \tau_{zx}}{\partial z} \delta x \delta y \delta z$$

and

$$\left[\left(\tau_{yx} + \frac{\partial \tau_{yx}}{\partial y} \frac{\partial y}{2} \right) - \left(\tau_{yx} - \frac{\partial \tau_{yx}}{\partial y} \frac{\partial y}{2} \right) \right] \delta x \delta z = \frac{\partial \tau_{yx}}{\partial y} \delta x \delta y \delta z$$

Here, once again, we are fishing for patterns. Let's look at the total forces in the x direction due to surface forces:

$$\delta f_{sx} = \left(\frac{\partial \sigma_{xx}}{\partial x} + \frac{\partial \tau_{yx}}{\partial y} + \frac{\partial \tau_{zx}}{\partial z}\right) \delta x \delta y \delta z$$

Smilarly,

$$\delta f_{sy} = \left(\frac{\partial \tau_{xy}}{\partial x} + \frac{\partial \sigma_{yy}}{\partial y} + \frac{\partial \tau_{zy}}{\partial y}\right) \delta x \delta y \delta z$$

and,

$$\delta f_{sz} = \left(\frac{\partial \tau_{xz}}{\partial x} + \frac{\partial \tau_{yz}}{\partial y} + \frac{\partial \sigma_{zz}}{\partial z}\right) \delta x \delta y \delta z$$

Equations of Motion: Given that $\delta f = \delta m \cdot \mathbf{a}$ and $\delta m = \rho \delta x \delta y \delta z$. We can obtain equations of motion by noting that the sum of body and surface forces should equal the sum unsteady and convective acceleration terms.

$$\rho g_x + \left(\frac{\partial \sigma_{xx}}{\partial x} + \frac{\partial \tau_{yx}}{\partial y} + \frac{\partial \tau_{zx}}{\partial z}\right) = \rho \left(\frac{\partial u}{\partial t} + u \frac{\partial u}{\partial x} + v \frac{\partial u}{\partial y} + w \frac{\partial u}{\partial z}\right)$$

$$\rho g_x + \left(\frac{\partial \tau_{xy}}{\partial x} + \frac{\partial \sigma_{yy}}{\partial y} + \frac{\partial \tau_{zy}}{\partial y}\right) = \rho \left(\frac{\partial v}{\partial t} + u \frac{\partial v}{\partial x} + v \frac{\partial v}{\partial y} + w \frac{\partial v}{\partial z}\right)$$

$$\rho g_x + \left(\frac{\partial \tau_{xz}}{\partial x} + \frac{\partial \tau_{yz}}{\partial y} + \frac{\partial \sigma_{zz}}{\partial z}\right) = \rho \left(\frac{\partial w}{\partial t} + u \frac{\partial w}{\partial x} + v \frac{\partial w}{\partial y} + w \frac{\partial w}{\partial z}\right)$$

Thus far, we end up with 3 equations plus the continuity one from the previous section. However, we have no idea what the velocities or the stresses are (12 unkowns).

1.3.1 Inviscid flow:

shearing stresses are zero (no viscocity) and all normal stresses will equal each other and the negative of the pressure, which gives us Euler's equation.

$$\rho g_x - \frac{\partial P}{\partial x} = \rho \left(\frac{\partial u}{\partial t} + u \frac{\partial u}{\partial x} + v \frac{\partial u}{\partial y} + w \frac{\partial u}{\partial z} \right)$$

and so on and so forth. More illuminating:

$$\rho \mathbf{g} - \nabla P = \rho + \left(\frac{\partial \mathbf{v}}{\partial \mathbf{t}} + (\mathbf{v} \cdot \nabla) \mathbf{v} \right)$$

2 Navier-Stokes Equations

The magic behind this lies in finding constitutive relations; somehow find some relations between stress and velocity (stress deformation equations). So from here on, we will assume:

- Newtonian fluid Stresses are linearly related to the strain/deformation rates (derivatives of velocity).
- Incompressible flow constant density.
- Isothermal flow no need to consider an energy equation.
- Constant velocity.

Viscuous stresses are linear with respect to the strains.

2.1 Normal Stresses

For the case of the normal stresses,

$$\sigma_{xx} = -p + 2\mu \frac{\partial u}{\partial x}$$
$$\sigma_{yy} = -p + 2\mu \frac{\partial v}{\partial y}$$
$$\sigma_{zz} = -p + 2\mu \frac{\partial w}{\partial z}$$

Where p is thermodynamic pressure and μ is the coefficient of viscocity of a newtonian fluid.

Puting it all together:

$$(\sigma_{xx} + \sigma_{yy} + \sigma_{zz}) = 3(-p + 2\mu\nabla \cdot \mathbf{v}) = -3p$$

The last step is due to the fact that for incompressible fluids, the divergence of the velocity is zero $(\nabla \cdot \mathbf{v})$.

2.2 Shearing Stresses

Abusing symmetry, we are able to write expressions such as

$$\tau_{xy} = \tau_{zx} = \mu \left(\frac{\partial u}{\partial y} + \frac{\partial v}{\partial x} \right)$$
$$\tau_{yz} = \tau_{zy} = \mu \left(\frac{\partial v}{\partial z} + \frac{\partial w}{\partial y} \right)$$
$$\tau_{zx} = \tau_{xz} = \mu \left(\frac{\partial w}{\partial x} + \frac{\partial u}{\partial z} \right)$$

Now that we have all stresses in terms on derivatives of velocity, we can put them all back into the momentum conservation equation and we will get more fun stuff, we will get some terms which will be first order derivatives of the pressuer and we will also get second order drivatives of the velocity. For example, if we look at the stress terms - ignoring the body force and acceleration terms,

$$\begin{split} &\frac{\partial \sigma_{xx}}{\partial x} + \frac{\partial \tau_{yx}}{\partial y} + \frac{\partial \tau_{zx}}{\partial z} \\ &= -\frac{\partial p}{\partial x} + 2\mu \frac{\partial^2 u}{\partial x^2} + \mu \left(\frac{\partial^2 u}{\partial y^2} + \frac{\partial^2 v}{\partial y \partial x} \right) + \mu \left(\frac{\partial^2 w}{\partial z \partial x} + \frac{\partial^2 u}{\partial z^2} \right) \\ &= -\frac{\partial p}{\partial x} + \mu \left(\frac{\partial^2 u}{\partial x^2} + \frac{\partial^2 u}{\partial y^2} + \frac{\partial^2 u}{\partial z^2} \right) + \mu \left(\frac{\partial^2 u}{\partial x^2} + \frac{\partial^2 v}{\partial y \partial x} + \frac{\partial^2 w}{\partial z \partial x} \right) \\ &= -\frac{\partial p}{\partial x} + \mu \left(\frac{\partial^2 u}{\partial x^2} + \frac{\partial^2 u}{\partial y^2} + \frac{\partial^2 u}{\partial z^2} \right) + \mu \frac{\partial}{\partial x} \nabla \cdot \mathbf{v} \end{split}$$

So the x direction term for the momentum equation becomes,

$$\rho \left(\frac{\partial u}{\partial t} + u \frac{\partial u}{\partial x} + v \frac{\partial u}{\partial y} + w \frac{\partial u}{\partial z} \right) = \rho g_x - \frac{\partial p}{\partial x} + \mu \left(\frac{\partial^2 u}{\partial x^2} + \frac{\partial^2 u}{\partial y^2} + \frac{\partial^2 u}{\partial z^2} \right)$$
(1)

Now, don't even think about writing the entire thing by hand, we gots better things to do! So low and behold,

$$\rho \left(\frac{\partial \mathbf{v}}{\partial t} + (\mathbf{v} \cdot \nabla) \mathbf{v} \right) = \rho \mathbf{g} - \nabla p + \mu \nabla^2 \mathbf{v}$$
 (2)

Now, we have 3 momentum equations, 1 continuity equation and 5 unkowns - the velocity, the pressure, and the density.

If we can get an equation of state relating the pressure and density we would have a complete system, a nonlinear, second-order PDE, but a system nontheless.

2.3 Conclusions

$$\frac{\partial \mathbf{v}}{\partial t} + (\mathbf{v} \cdot \nabla) \mathbf{v} = -\frac{1}{\rho} \nabla p + \nu \nabla^2 \mathbf{v}$$
(3)

On the left we have two acceleration terms, the unsteady term (from forces) and the convective acceleration (from moving around the velocity field). The effect of moving within the velocity vector field is related to the gradient of the pressure. The last term represents the viscuous diffusion in the fluid.

Looking for a solution to these types of systems we are hoping to find the velocity and the pressure fields.

3 Finite Difference Method

- Discretize the numerical domain by defining a grid.
- Approximate derivatives by Taylor expansions.