
Digital Signal Processing for Music Part 3: Signals

alexander lerch





introduction sound



- sound is a vibration propagating through a medium
- vibrating source excites medium and vibration is received by microphone/ear
- microphone converts sound pressure (velocity) into electrical voltage
- the vibration/oscillation at each of these steps is a signal
- here, we are mostly interested in the electrical signal
- audio signa
 - representation of sound (speech, music, etc.)
 - main frequency content is below 12[kHz]

introduction sound



- sound is a vibration propagating through a medium
- vibrating source excites medium and vibration is received by microphone/ear
- microphone converts sound pressure (velocity) into electrical voltage
- the vibration/oscillation at each of these steps is a signal
- here, we are mostly interested in the electrical signal
- audio signa
 - representation of sound (speech, music, etc.)
 - main frequency content is below 12[kHz]

introduction sound



- sound is a vibration propagating through a medium
- vibrating source excites medium and vibration is received by microphone/ear
- microphone converts sound pressure (velocity) into electrical voltage
- the vibration/oscillation at each of these steps is a signal
- here, we are mostly interested in the electrical signal
- audio signal
 - representation of sound (speech, music, etc.)
 - main frequency content is below 12[kHz]

audio signals categorization



- deterministic signals:
 predictable: future shape of the signal can be known (example: sinusoidal)
- random signals: unpredictable: no knowledge can help to predict what is coming next (example: white noise)

Every "real-world" audio signal can be modeled as a time-varying combination of

- (quasi-)periodic parts
- (quasi-)random parts

audio signals categorization



- deterministic signals:
 predictable: future shape of the signal can be known (example: sinusoidal)
- random signals: unpredictable: no knowledge can help to predict what is coming next (example: white noise)

Every "real-world" audio signal can be modeled as a time-varying combination of

- (quasi-)periodic parts
- (quasi-)random parts

signals

properties of real-world signals

Georgia Center for Music Tech Techology

- real-valued:
 - real-world signals are usually real-valued.
- finite
 - amplitude: $max|x(t)| < \infty$
 - energy or power:

$$E = \int_{-\infty}^{\infty} x^{2}(t)dt$$

$$P = \lim_{T \to \infty} \frac{1}{2T} \int_{-T}^{T} x^{2}(t)dt$$

- smooth:
 - no "abrupt" changes → finite bandwidth

signals

properties of real-world signals

Georgia Center for Music Tech Technology

- real-valued:
 - real-world signals are usually real-valued.
- finite:
 - amplitude: $max|x(t)| < \infty$
 - energy or power

$$E = \int_{-\infty} x^{2}(t)dt$$

$$P = \lim_{T \to \infty} \frac{1}{2T} \int_{-T}^{T} x^{2}(t)dt$$

- smooth:
 - no "abrupt" changes → finite bandwidth

signals properties of real-world signals

Georgia Center for Music Technology

- real-valued:
 - real-world signals are usually real-valued.
- finite:
 - amplitude: $max|x(t)| < \infty$
 - energy or power:

$$E = \int_{-\infty}^{\infty} x^{2}(t)dt$$

$$P = \lim_{T \to \infty} \frac{1}{2T} \int_{-T}^{T} x^{2}(t)dt$$

- smooth:
 - no "abrupt" changes → finite bandwidth

signals

properties of real-world signals

Georgia Center for Music Tech College of Design

- real-valued:
 - real-world signals are usually real-valued.
- finite:
 - amplitude: $max|x(t)| < \infty$
 - energy or power:

$$E = \int_{-\infty}^{\infty} x^2(t)dt$$

$$P = \lim_{T \to \infty} \frac{1}{2T} \int_{-T}^{T} x^2(t) dt$$

- smooth:
 - no "abrupt" changes → finite bandwidth

Georgia Center for Music Tech College of Design

periodic signals most prominent examples of deterministic signals:

$$x(t) = x(t + T_0)$$

$$f_0 = \frac{1}{T_0}$$


$$\omega_0 = \frac{2\pi}{T_0}$$

periodic signals most prominent examples of deterministic signals:

$$x(t) = x(t + T_0)$$

$$f_0 = \frac{1}{T_0}$$

$$\omega_0 = \frac{2\pi}{T_0}$$




periodic signals most prominent examples of deterministic signals:

$$x(t) = x(t + T_0)$$

$$f_0 = \frac{1}{T_0}$$

$$\omega_0 = \frac{2\pi}{T_0}$$






reconstruction



reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t)$$





reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t) + a_2 \cdot \sin(2 \cdot \omega_0 t) + \ldots + a_3 \cdot \sin(3 \cdot \omega_0 t)$$





reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t) + a_2 \cdot \sin(2 \cdot \omega_0 t) + \ldots + a_{10} \cdot \sin(10 \cdot \omega_0 t)$$





reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t) + a_2 \cdot \sin(2 \cdot \omega_0 t) + \ldots + a_{25} \cdot \sin(25 \cdot \omega_0 t)$$





reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t) + a_2 \cdot \sin(2 \cdot \omega_0 t) + \ldots + a_{50} \cdot \sin(50 \cdot \omega_0 t)$$





reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t)$$





reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t) + a_3 \cdot \sin(3 \cdot \omega_0 t) + \ldots + a_5 \cdot \sin(5 \cdot \omega_0 t)$$





reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t) + a_3 \cdot \sin(3 \cdot \omega_0 t) + \ldots + a_{19} \cdot \sin(19 \cdot \omega_0 t)$$





reconstruction


$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t) + a_3 \cdot \sin(3 \cdot \omega_0 t) + \ldots + a_{49} \cdot \sin(49 \cdot \omega_0 t)$$





reconstruction

$$\hat{x}(t) = a_1 \cdot \sin(\omega_0 t) + a_3 \cdot \sin(3 \cdot \omega_0 t) + \ldots + a_{99} \cdot \sin(99 \cdot \omega_0 t)$$



Georgia Center for Music Tech College of Design

youtube — mechanical additive synthesis: http://youtu.be/8KmVDxkia_w

audio signals superposition of sinusoidals 1/2

Georgia Center for Music Tech College of Design


- partials: a set of frequencies comprising a (pitched) sound
- overtones: as partials but without the fundamental frequency
- harmonics: integer multiples of the fundamental frequency, including the fundamental frequency

audio signals

Georgia Center for Music Tech Technology

matlab source: matlab/dispBeating.m

superposition of sinusoidals 2/2



audio signals

Georgia Center for Music Tech College of Design

superposition of sinusoidals 2/2

$$y(t) = \underbrace{\sin\left(2\pi(f + \frac{\Delta f}{2})t\right)}_{\sin(2\pi f)\cos(2\pi t \frac{\Delta f}{2}) + \cos(2\pi f)\sin(2\pi t \frac{\Delta f}{2})} + \underbrace{\sin\left(2\pi(f - \frac{\Delta f}{2})t\right)}_{\sin(2\pi f)\cos(-2\pi t \frac{\Delta f}{2}) + \cos(2\pi f)\sin(-2\pi t \frac{\Delta f}{2})}$$


$$= 2\sin(2\pi f) \cdot \cos\left(2\pi \frac{\Delta f}{2}t\right)$$

audio examples: addition of sines

audio signals random process



random process: ensemble of random series




special cases:

- stationarity: all parameters (such as the mean) are time invariant
- ergodicity: process with equal time and ensemble mean (implies stationarity)

audio signals random process



random process: ensemble of random series



special cases:

- stationarity: all parameters (such as the mean) are time invariant
- ergodicity: process with equal time and ensemble mean (implies stationarity)

deterministic prototype signals periodic signals

Georgia Center for Music Tech College of Pesign

sinusoidal

$$x(t) = \sin(2\pi f t + \Phi)$$

sawtooth

$$x(t) = 2\left(\frac{t}{T_0} - \text{floor}\left(\frac{1}{2} + \frac{t}{T_0}\right)\right)$$

$$x(t) = \operatorname{sign}(\sin(\omega t))$$

deterministic prototype signals periodic signals

Georgia Center for Music Tech College of Pesign

sinusoidal

$$x(t) = \sin(2\pi f t + \Phi)$$

sawtooth

$$x(t) = 2\left(\frac{t}{T_0} - \text{floor}\left(\frac{1}{2} + \frac{t}{T_0}\right)\right)$$

$$x(t) = \operatorname{sign}(\sin(\omega t))$$

deterministic prototype signals periodic signals

Georgia Center for Music Tech College of Pesign

sinusoidal

$$x(t) = \sin(\underbrace{2\pi f}_{\omega} t + \Phi)$$

sawtooth

$$x(t) = 2\left(\frac{t}{T_0} - \text{floor}\left(\frac{1}{2} + \frac{t}{T_0}\right)\right)$$

$$x(t) = sign (sin(\omega t))$$

deterministic prototype signals periodic signals

Georgia Center for Music Tech College of Pesign

sinusoidal

$$x(t) = \sin(2\pi f t + \Phi)$$

sawtooth

$$x(t) = 2\left(\frac{t}{T_0} - \mathsf{floor}\left(\frac{1}{2} + \frac{t}{T_0}\right)\right)$$

$$x(t) = \operatorname{sign}(\sin(\omega t))$$

deterministic prototype signals non-periodic deterministic signals

Georgia Center for Music Tech College of Design

DC

$$x(t) = 1$$

impulse

$$\delta(t) = egin{cases} \infty & t = 0 \ 0 & t
eq 0 \end{cases}$$
 $\delta(t) = \int\limits_{-\infty}^{\infty} \delta(t) dt = \int\limits_{-\infty}^{$

exponential

$$x(t) = e^{-\alpha t}$$

deterministic prototype signals non-periodic deterministic signals

Georgia Center for Music Tech College of Design

DC

$$x(t) = 1$$

impulse

$$\delta(t) = egin{cases} \infty & t = 0 \ 0 & t
eq 0 \end{cases}$$
 $\delta(t) = \int\limits_{-\infty}^{\infty} \delta(t) dt = 1$

exponential

$$x(t) = e^{-\alpha t}$$

deterministic prototype signals non-periodic deterministic signals

Georgia Center for Music Tech College of Design

DC

$$x(t) = 1$$

impulse

$$\delta(t) = egin{cases} \infty & t = 0 \ 0 & t
eq 0 \end{cases}$$
 $\delta(t) = \int\limits_{-\infty}^{\infty} \delta(t) dt = 1$

exponential

$$x(t) = e^{-\alpha t}$$

audio signals



- two basic signal classes, deterministic and random
- deterministic signals can be described by a function and are predictable
 - special case: periodic signals sum of sinusoidals with freq. integer ratio
- random signals are not predictable
 - special case: ergodic signals can be described statistically