Unit 4 Advanced Wireless Networks

6GZ71004 ADVANCED COMPUTER NETWORKS & OPERATING SYSTEMS

DR MOHAMMAD HAMMOUDEH

Unit Outline

Introduction


Wireless

- 1. Wireless links, characteristics
 - i. CDMA
- 2. IEEE 802.11 wireless LANs ("wi-fi")
- 3. Cellular Internet Access
 - i. architecture
 - ii. standards (e.g., GSM)

Mobility


- Principles: addressing and routing to mobile users
- 2. Mobile IP
- 3. Handling mobility in cellular networks
- Mobility and higher-layer protocols

Summary




wireless hosts

- Laptop, smart phone
- run applications
- may be stationary (non-mobile) or mobile
 - wireless does not always mean mobility



base station


- typically connected to wired network
- relay responsible for sending packets between wired network and wireless host(s) in its "area"
 - e.g., cell towers, 802.11 access points




wireless link

- typically used to connect mobile(s) to base station
- also used as backbone link
- multiple access protocol coordinates link access
- various data rates, transmission distance


Characteristics of selected wireless link standards





infrastructure mode

- base station connects mobiles into wired network
- handoff: mobile changes base station providing connection into wired network



- ad hoc mode

- no base stations
- nodes can only transmit to other nodes within link coverage
- nodes organize themselves into a network: route among themselves

Wireless network taxonomy

	single hop	multiple hops		
infrastructure (e.g., APs)	host connects to base station (WiFi, WiMAX, cellular) which connects to larger Internet	host may have to relay through several wireless nodes to connect to larger Internet: <i>mesh net</i>		
no infrastructure	no base station, no connection to larger Internet (Bluetooth, ad hoc nets)	no base station, no connection to larger Internet. May have to relay to reach other a given wireless node MANET, VANET		

Wireless Link Characteristics

Differences from wired link

- decreased signal strength: radio signal attenuates as it propagates through matter (path loss)
- interference from other sources: standardized wireless network frequencies (e.g., 2.4 GHz) shared by other devices (e.g., phone); devices (motors) interfere as well
- multipath propagation: radio signal reflects off objects ground, arriving at destination at slightly different times

.... make communication across (even a point to point) wireless link much more "difficult"


Wireless Link Characteristics

SNR: signal-to-noise ratio

 larger SNR – easier to extract signal from noise (a "good thing")


SNR versus BER tradeoffs

- given physical layer: increase power increase SNR->decrease BER
- given SNR: choose physical layer that meets BER requirement, giving highest thruput
 - SNR may change with mobility: dynamically adapt physical layer (modulation technique, rate)




Wireless network characteristics

Multiple wireless senders and receivers create additional problems (beyond multiple access):



Hidden terminal problem

- B, A hear each other
- □ B, C hear each other
- A, C cannot hear each other means A, C unaware of their interference at B



Signal attenuation:

- □ B, A hear each other
- B, C hear each other
- A, C can not hear each other interfering at B

Code Division Multiple Access (CDMA)

- used in several wireless broadcast channels (cellular, satellite, etc) standards
- unique "code" assigned to each user; i.e., code set partitioning
- all users share same frequency, but each user has own "chipping" sequence (i.e., code) to encode data
- encoded signal = (original data) X (chipping sequence)
- decoding: inner-product of encoded signal and chipping sequence
- allows multiple users to "coexist" and transmit simultaneously with minimal interference (if codes are "orthogonal")

Unit Outline

Introduction

Wireless

- 1. Wireless links, characteristics
 - i. CDMA

IEEE 802.11 wireless LANs ("wifi")

- 1. Cellular Internet Access
 - i. architecture
 - ii. standards (e.g., GSM)

Mobility

- Principles: addressing and routing to mobile users
- Mobile IP
- 3. Handling mobility in cellular networks
- Mobility and higher-layer protocols

Summary

IEEE 802.11 Wireless LAN

802.11b

- 2.4-5 GHz unlicensed spectrum
- up to 11 Mbps

802.11ac

- 1.3Gbps
- to replace 802.11n by 2018

802.11a

- 5-6 GHz range
- up to 54 Mbps


802.11g

- 2.4-5 GHz range
- up to 54 Mbps

802.11n: multiple antennae

- 2.4-5 GHz range
- up to 200 Mbps
- all use CSMA/CA for multiple access
- all have base-station and ad-hoc network versions

802.11 LAN architecture



- wireless host communicates with base station
 - base station = accesspoint (AP)
- Basic Service Set (BSS) (aka "cell") in infrastructure mode contains:
 - wireless hosts
 - access point (AP): base station
 - o ad hoc mode: hosts only

802.11: Channels, association


802.11b: 2.4GHz-2.485GHz spectrum divided into 11 channels at different frequencies

- AP admin chooses frequency for AP
- interference possible: channel can be same as that chosen by neighboring AP!

host: must associate with an AP


- scans channels, listening for beacon frames containing AP's name (SSID) and MAC address
- selects AP to associate with
- may perform authentication
- will typically run DHCP to get IP address in AP's subnet

802.11: passive/active scanning



Passive Scanning:

- (1) beacon frames sent from APs
- (2) association Request frame sent:H1 to selected AP
- (3) association Response frame sent: H1 to selected AP





Active Scanning

- (1) Probe Request frame broadcast from H1
- (2) Probes response frame sent from APs
- (3) Association Request frame sent: H1 to selected AP
- (4) Association Response frame sent: H1 to selected AP

IEEE 802.11: multiple access

- avoid collisions: 2+ nodes transmitting at same time
- 802.11: CSMA sense before transmitting
 - don't collide with ongoing transmission by other node
- 802.11: no collision detection!
 - difficult to receive (sense collisions) when transmitting due to weak received signals (fading)
 - can't sense all collisions in any case: hidden terminal, fading
 - goal: avoid collisions: CSMA/C(ollision)A(voidance)





IEEE 802.11 MAC Protocol: CSMA/CA

802.11 sender

1 if sense channel idle for **DIFS** then transmit entire frame (no CD)


2 if sense channel busy then

start random backoff time timer counts down while channel idle transmit when timer expires if no ACK, increase random backoff interval, repeat

802.11 receiver

- if frame received OK

return ACK after **SIFS** (ACK needed due to hidden terminal problem)




Avoiding collisions (more)

idea: allow sender to "reserve" channel rather than random access of data frames: avoid collisions of long data frames


- sender first transmits small request-to-send (RTS) packets to BS using CSMA
 - RTSs may still collide with each other (but they're short)
- BS broadcasts clear-to-send CTS in response to RTS
- CTS heard by all nodes
 - sender transmits data frame
 - other stations defer transmissions

avoid data frame collisions completely using small reservation packets!

Collision Avoidance: RTS-CTS exchange



802.11 frame: addressing



Frame control field expanded (numbers indicate field length in bits):

2	2	4	1	1	1	1	1	1	1	1
Protocol version	Туре	Subtype	To AP	From AP	More frag	Retry	Power mgt	More data	WEP	Rsvd


Address 1: MAC address of wireless host or AP to receive this frame

Address 2: MAC address of wireless host or AP transmitting this frame


Address 3: MAC address of router interface to which AP is attached

Address 4: used only in ad hoc mode

802.11 frame: addressing




802.11 frame: more



802.11: mobility within same subnet


- H1 remains in same IP subnet: IP address can remain same
- switch: which AP is associated with H1?
 - self-learning: switch will see frame from H1 and "remember" which switch port can be used to reach H1




802.11: advanced capabilities

Rate Adaptation

dynamically change transmission rate (physical layer modulation technique) as mobile moves, SNR varies





- 1. SNR decreases, BER increase as node moves away from base station
- 2. When BER becomes too high, switch to lower transmission rate but with lower BER


802.11: advanced capabilities

Power Management

- node-to-AP: "I am going to sleep until next beacon frame"
 - AP knows not to transmit frames to this node
 - o node wakes up before next beacon frame
- beacon frame: contains list of mobiles with AP-tomobile frames waiting to be sent
 - node will stay awake if AP-to-mobile frames to be sent; otherwise sleep again until next beacon frame

802.15: personal area network

- less than 10 m diameter
- replacement for cables (mouse, keyboard, headphones)
- ad hoc: no infrastructure
- master/slaves:
 - slaves request permission to send (to master)
 - master grants requests
- 802.15: evolved from Bluetooth specification
 - 2.4-2.5 GHz radio band
 - up to 721 kbps




Bluetooth

- An IEEE 802.15.1 network operates over a short range, at low power, and at low cost
- operate in the 2.4 GHz unlicensed radio band in a TDM manner,
 with time slots of 625 microseconds
- transmits on one of 79 channels,
- frequency-hopping spread spectrum (FHSS), spreads transmissions in time over the frequency spectrum. 802.15.1 can provide data rates up to 4 Mbp
- ad hoc networks
- devices are first organized into a piconet

Zigbee

- standardized by the IEEE is the 802.14.5
- Technological Standard Created for Control and Sensor Networks
- Based on the IEEE 802.15.4 Standard
- Created by the ZigBee Alliance
- Zigbee is targeted at lower powered, lower-data-rate, lower-duty-cycle applications than Bluetooth

IEEE 802.15.4 & ZigBee In Context



Stack

App

Silicon



ZigBee Alliance

- "the software"
- Network, Security & Application layers
- Brand management

IEEE 802.15.4

- "the hardware"
- Physical & Media Access
 Control layers


Source:
http://www.zigbee.org/resources/documents/IWAS_presentation_M
ar04_Designing_with_802154_and_zigbee.ppt


Reading

Dedicated Short-Range Communication

802.16: WIMAX


- like 802.11 & cellular: base station model
 - transmissions to/from base station by hosts with omni-directional antenna
 - base station-to-base station backhaul with point-to-point antenna
- unlike 802.11:
 - range ~ 6 miles ("city rather than coffee shop")
 - ~14 Mbps





802.16: WiMAX: downlink, uplink scheduling

- transmission frame
 - down-link subframe: base station to node
 - uplink subframe: node to base station



 WiMAX standard provide mechanism for scheduling, but not scheduling algorithm