# 6.004 Spring 2020 Tutorial Problems **L01 – Binary Encoding and Arithmetic**

### **Problem 1. Encoding positive integers**

1. What is the 5-bit binary representation of the decimal number 21?

Multiple ways to solve this: a) repeated division by 2 with remainder (build bits from right to left), b) repeated subtraction of powers of 2 (build bits from left to right)

```
a. 21/2 = 10 remainder 1 (least significant bit)
    10/2 = 5 remainder 0
   5/2 = 2 remainder 1
    2/2 = 1 remainder 0
    1/2 = 0 remainder 1 (most significant bit)
    →10101
```

b. Find largest power of 2 that is less than or equal to remaining value and subtract it until you get to zero

```
21 - 16 = 5
5 - 4 = 1
1 - 1 = 0
```

Fill in bit positions for the powers you used with 1's, other positions with 0's:

```
16 = 2^4 \rightarrow 0b\underline{1}0000

4 = 2^2 \rightarrow 0b10\underline{1}00
1 = 2^0 \rightarrow 0b10\overline{101}
```

- 2. What is the hexadecimal representation for decimal 219 encoded as an 8-bit binary number?
  - 1. Convert decimal 219 to binary as in part 1 (repeated subtraction used here):  $219 = 128 + 64 + 16 + 8 + 2 + 1 \rightarrow 0b11011011$
  - 2. Group bits into sets of four starting on the right:  $0b11011011 \rightarrow 0b1101 \ 1011$
  - 3. Lookup hex value for each set of bits in table (see lecture 1):  $0b1101 \rightarrow 0xD, 0b1011 \rightarrow 0xB : 0b1101 \ 1011 = 0xDB$
- 3. What is the hexadecimal representation for decimal 51 encoded as a 6-bit binary number?

Same as in part 2 but you add extra 0's on the left if the last group has fewer than 4 bits (i.e., total number of bits is not evenly divisible by 4):  $51 = 32 + 16 + 2 + 1 \rightarrow 0b110011 \rightarrow 0b11_0011 \rightarrow 0b0011_0011 \rightarrow 0x33$ 

- 4. The hexadecimal representation for an 8-bit unsigned binary number is 0x9E. What is its decimal representation?
  - 1. Convert hex to binary by looking up bit pattern for each hex digit in table:  $0x9E = 0b1001_1110$
  - 2. Convert binary to decimal by multiplying each bit by the decimal value for that position:  $0b1001 \ 1110 \rightarrow 1 \cdot 2^7 + 0 \cdot 2^6 + 0 \cdot 2^5 + 1 \cdot 2^4 + 1 \cdot 2^3 + 1 \cdot 2^2 + 1 \cdot 2^1 + 0 \cdot 2^0$ = 128+0+0+16+8+4+2+0 = 158

(Shortcut: ignore the zeros in the binary number and just sum the values for the ones.)

- 5. What is the range of integers that can be represented with a single unsigned 8-bit quantity?
  - **Unsigned** always goes from zero to  $2^N 1$ , where N is the number of bits.  $2^8 1 = 255$  so the range is from 0 to 255.
- 6. Since the start of official pitching statistics in 1988, the highest number of pitches in a single game has been 172. Assuming that remains the upper bound on pitch count, how many bits would we need to record the pitch count for each game as an unsigned binary number?

#### At least three options:

- **a.** Convert 172 to binary as above and count digits [172 = 0b10101100, 8 bits]. This is the obvious approach but also the most work.
- **b.** Find smallest power of two larger than 172 and take exponent  $[256 = 2^8]$ . This one is good if you have the powers of 2 memorized.
- c. Take the ceiling of the log base  $2 \left[ \text{ceil} \left( \log 2(172+1) \right) = 8 \right]$ . Note that we need to add one to 172 because the log<sub>2</sub>N is actually giving us the number of bits needed to represent N different values. If we need to be able to represent all the numbers from 0 to 172, that is actually 173 different values. We take the ceiling because we can't have a fractional number of bits and this would give us the extra value we need, except for the corner case where N is an exact power of 2.
- 7. Compute the sum of these two 4-bit unsigned binary numbers: 0b1101 + 0b0110. Express the result in hexadecimal.

Add bits in each position from right to left, just as you would with decimal numbers. However, express the individual sums in binary and carry if the sum is a two-bit number (0b10 or 0b11). Convert result to hex by grouping and adding zeros as above.

```
11
 1101
+0110
1\overline{0011} = 1\_0011 = 0001\_0011 = 0x13
```

# Problem 2. Two's complement representation

1. What is the 6-bit two's complement representation of the decimal number -21?

Easiest method is to find the representation of +21 and then use the fact that we can negate a two's complement binary number by inverting all the bits individually (bitwise NOT) and then adding 1 to the result:

21 = 16+4+1 = 0b010101, (we were asked for 6 bits so fill in the other 3 positions with 0's) Inverting each bit individually gives: 0b101010

```
-21 = 0b101010 + 1 = 0b101011
```

Note that if you are *only* given a sequence of bits, you don't actually know what number they represent. You also need be told how to interpret those bits: as an unsigned number or as a signed number stored in two's complement representation. For example, 0b101011 represents -21 if those bits are interpreted as two's complement but 43 (32+8+2+1) if they are interpreted as unsigned. The same sequence of bits can mean two different things. In fact, there are many other possible ways to interpret these bits. For example, we might have meant for each bit to represent a simple yes/no flag for six different things. We will see another possible interpretation in Problem 4. For the rest of this course, you may assume two's complement unless you are told otherwise.

2. What is the hexadecimal representation for decimal -51 encoded as an 8-bit two's complement number?

Hexadecimal is just a shorthand way of writing down a sequence of bits. Therefore, it doesn't matter what those bits represent. To solve this problem we find the two's complement binary representation of -51 and then translate groups of four bits just as we did in Problem 1 for unsigned numbers:

```
51 = 32 + 16 + 2 + 1 = 0b0011 _0011 (using 8-bit binary)
-51 = 0b1100_{-}1100 + 1 = 0b1100_{-}1101 = 0xCD
```

3. The hexadecimal representation for an 8-bit two's complement number is 0xD6. What is its decimal representation?

Again, hexadecimal is just a compressed form of binary so the first step is to decompress it:  $0xD6 = 0b1101_0110$ 

Now, we are told that we are supposed to interpret these bits as two's complement. The process is the same as for signed numbers except that we flip the sign for the value represented by the most significant bit:

```
0b1101 \ 0110 = 1*-128 + 1*64 + 0*32 + 1*16 + 0*8 + 1*4 + 1*2 + 0*1 = -42
```

Alternative (*may* be easier, especially if more than half the bits are 1):  $0xD6 = 0b1101 \ 0110$ 

By looking at the most significant bit (MSB), we can see that this number must be negative (for two's complement, MSB=1 implies negative and MSB=0 implies non-negative). So we can negate this binary number (by flipping all bits and adding 1), find the decimal equivalent (exactly as for unsigned numbers since we now know the MSB=0), and then negate that (which is just adding a minus sign in front for decimal numbers):

```
-0xD6 = 0b0010 \ 1001 + 1 = 0b0010 \ 1010 = 32 + 8 + 2 = 42, which gives +0xD6 = -42
```

4. Using a 5-bit two's complement representation, what is the range of integers that can be represented with a single 5-bit quantity?

```
-2^{N-1} to 2^{N-1}-1 \rightarrow -2^{4} to (2^{4})-1 \rightarrow -16 to 15
Note that the negative range is one larger than the positive range.
```

5. Can the value of the sum of two 2's complement numbers 0xB3 + 0x47 be represented using an 8-bit 2's complement representation? If so, what is the sum in hex? If not, write NO.

Yes: from the MSBs ("sign" bits) 0xB3 is negative and 0x47 is positive. The sum of a negative number and a positive number must always have an absolute value less than or equal to either addend (i.e., the sum will be in between the addends on a number line). Since the addends were in range, the sum must be too.

```
0xB3 + 0x47 =
0b1011 0011 +
0b0100 0111 =
0b1111_1010 = 0xFA (in decimal: -6, can you see why it's a very small negative?)
```

6. Can the value of the sum of two 2's complement numbers 0xB3 + 0xB1 be represented using an 8-bit 2's complement representation? If so, what is the sum in hex? If not, write NO.

This one is trickier. 0xB3 and 0xB1 are both negative so their sum will be more negative than either addend and *might* be outside the range we can represent with 8 bits (-128 to 127). For example, if they were both -1, we would be fine but if they were both -128, we would be in trouble. To check, we have to actually perform the addition and check the result:

```
0xB3 + 0xB1 =
0b1011\_0011 +
0b1011 \ 0001 =
0b0110 0100
```

There was a carry from the 8<sup>th</sup> bit to the 9<sup>th</sup> bit, but when performing two's complement arithmetic, we drop any carries beyond the MSB so that the result stays the same size. Remember that we are actually computing the result modulo 2<sup>N</sup>. (The reason for this is that hardware is built with a fixed number of bits for each piece of data.) The fact that we dropped the carry is not necessarily bad. To see if our result is valid, we can compare the signs of the addends and the sum. In this case, we summed two negative numbers but the result came out positive (MSB of 0b0110\_0100 is 0). Since this is impossible, we know that the result is outside the range and the answer is **NO**.

Here is the complete process for detecting overflow (results out of range) for two's complement addition: If the sign bits of the addends are the different, the result will be in range. If they are the same, perform the addition (mod N) and compare the sign bit of the result to the sign bit of one of the addends. If they match, the result is in range, otherwise no. 7. Please compute the value of the expression 0xBB – 8 using 8-bit two's complement arithmetic and give the result in decimal (base 10).

To perform subtraction, we simply negate the second operand and perform addition. (That way we only need to put an adder in our machine instead of an adder and a subtractor. We will see more about this is later lectures.)

```
0xBB - 8 = 0xBB + (-8) = 0b1011_1011 + 0b1111_1000
0b1011_1011 +
0b1111 1000 =
0b1011 \ 0011 = -128 + 32 + 16 + 2 + 1 = -77
```

Note that the sign bits of the addends are the same but the sign bit of the sum matches. So the result is valid, even though we had a carry to the 9<sup>th</sup> bit that we dropped.

8. Consider the following subtraction problem where the operands are 5-bit two's complement numbers. Compute the result and give the answer as a decimal (base 10) number.

```
0b10101
                0b10101
                                    0b10101
- 0b00011 \Rightarrow + 0b11100 + 1 \Rightarrow + 0b11101
                                  = 0b10010 = -(0b01101 + 1) = -14
```

This solution combines the technique for performing subtraction from part 7 with the alternative technique from converting from binary to decimal from part 3.

## **Problem 3. Multiples of 4**

1. Given an unsigned n-bit binary integer  $= b_{n-1} \dots b_1 b_0$ , prove that v is a multiple of 4 if and only if  $b_0 = 0$  and  $b_1 = 0$ .

To solve this problem, remember that  $v = \sum_{k=0}^{n-1} b_k 2^k$ 

- Powers of 2 greater than or equal to 4 are multiples of 4 (for all k>=2,  $2^k = 4*2^k=2$ ) and  $2^k=2$  is an integer)
- The sum of numbers evenly divisible by 4 is evenly divisible by 4: 4\*x + 4\*y = 4\*(x+y)). Therefore, any number of the form  $b_{n-1}$  ... 00 is a multiple of 4.

More intuitively, if a number ends in one of 01, 10, or 11 we are adding 1, 2, or 3 respectively to a multiple of 4 (the sum of factors from all the higher bits). Therefore, a number is a multiple 4 only if it ends in 00.

2. Does the same relation hold for two's complement encoding?

Yes, the above proof still works. In two's complement notation the highest-order bit represents  $-2^{(n-1)}$  instead of  $+2^{(n-1)}$ , and negating a number does not change its divisibility  $(-2^{(n-1)})$  is still evenly divisible by 4 for n>=3).

## **Problem 4. Encoding text**

There are multiple standards to encode characters and strings using binary values. ASCII is a classic standard to encode English alphabet characters (modern formats like UTF support other alphabets, but are typically based on ASCII). ASCII encodes each character using an 8-bit (1byte) value. The table below shows ASCII's mapping of characters to values.

ASCII (1977/1986), adapted from https://en.wikipedia.org/wiki/ASCII																
	_0	_1	_2	_3	_4	_5	_6	_7	_8	_9	_A	_B	_C	_D	_E	_F
0_	NUL	SOH	STX	ETX	EOT	ENQ	ACK	BEL	BS	HT	LF	VT	FF	CR	SO	SI
	0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0A	0x0B	0x0C	0x0D	0x0E	0x0F
1_	DLE	DC1	DC2	DC3	DC4	NAK	SYN	ETB	CAN	EM	SUB	ESC	FS	GS	RS	US
	0x10	0x11	0x12	0x13	0x14	0x15	0x16	0x17	0x18	0x19	0x1A	0x1B	0x1C	0x1D	0x1E	0x1F
2_	space 0x20	! 0x21	" 0x22	# 0x23	\$ 0x24	% 0x25	& 0x26	ox27	( 0x28	) 0x29	* 0x2A	+ 0x2B	, 0x2C	- 0x2D	0x2E	/ 0x2F
3_	0	1	2	3	4	5	6	7	8	9	:	;	<	=	>	?
	0x30	0x31	0x32	0x33	0x34	0x35	0x36	0x37	0x38	0x39	0x3A	0x3B	0x3C	0x3D	0x3E	0x3F
4_	@	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O
	0x40	0x41	0x42	0x43	0x44	0x45	0x46	0x47	0x48	0x49	0x4A	0x4B	0x4C	0x4D	0x4E	0x4F
5_	P	Q	R	s	T	U	V	W	X	Y	Z	[	)	]	^	_
	0x50	0x51	0x52	0x53	0x54	0x55	0x56	0x57	0x58	0x59	0x5A	0x5B	0x5C	0x5D	0x5E	0x5F
6_	0x60	a 0x61	b 0x62	c 0x63	d 0x64	e 0x65	f 0x66	g 0x67	h 0x68	i 0x69	j 0x6A	k 0x6B	1 0x6C	m 0x6D	n 0x6E	o 0x6F
7_	p	q	r	s	t	u	v	w	x	у	z	{		}	~	DEL
	0x70	0x71	0x72	0x73	0x74	0x75	0x76	0x77	0x78	0х79	0x7A	0x7B	0x7C	0x7D	0x7E	0x7F
	Let	ter	Nun	nber	Pu	nctuat	tion	Syı	nbol	O	ther/no	on-pri	ntable			

Computers often store variable-length text as a null-terminated string: a sequence of bytes, where each byte denotes a different character, terminated by the value 0x00 (null) to denote the end of the string. For example, the string "6.004" is encoded as the 6-byte sequence 0x36 0x2E 0x30 0x30 0x34 0x00. For brevity, we can also just stick these hex values together to form one large hex number: 0x362E30303400.

1. Encode your name as a null-terminated ASCII string (use the best approximation if your name contains non-English characters)

0x 59 6F 75 72 20 4E 61 6D 65 20 3A 29 00

2. Decode the following null-terminated ASCII string:

0x 52 49 53 43 2D 56 20 69 73 20 63 6F 6D 69 6E 67 21 00

RISC-V is coming!