

MikroTik.MTCNA.v2026-01-17.q90

Exam Code:	MTCNA
Exam Name:	MikroTik Certified Network Associate Exam
Certification Provider:	MikroTik
Free Question Number:	90
Version:	v2026-01-17
# of views:	103
# of Questions views:	900
https://www.freecram.net/torrent/MikroTik.MTCNA.v2026-01-17.q90.html	

NEW QUESTION: 1

The network address is:

- A. The first address of the subnet
- B. The first usable address of the subnet
- C. The last address of the subnet

Answer: (SHOW ANSWER)

The network address is the first IP address in a subnet. It identifies the entire network segment and cannot be assigned to any host.

For example, in 192.168.1.0/24:

- * 192.168.1.0 # Network Address (non-assignable)#
- * 192.168.1.1 - 192.168.1.254 # Usable host addresses
- * 192.168.1.255 # Broadcast address

Clarifying:

- * A. First address of the subnet ##Correct
- * B. First usable address ##That would be second address
- * C. Last address of the subnet ##That's the broadcast

MTCNA Course Manual - Subnet Addressing:

"The first address in a subnet is reserved as the network ID. It cannot be assigned to a host."

Rene Meneses Guide - Network and Broadcast Addresses:

"Network address = first IP in block, broadcast = last. Usable range lies in between." Terry Combs Notes - Host and Network Addressing:

"Always subtract 2 IPs: one for network and one for broadcast. Never assign .0 (network address) to a host."

NEW QUESTION: 2

Which is a default baud-rate of currently manufactured RouterBOARDS?

- A. 9600

B. 115200

C. 38400

D. 11520

Answer: (SHOW ANSWER)

The default serial console baud rate for most modern MikroTik RouterBOARD devices is 115200 bps. This is important when accessing the router via serial console (e.g., through RS-232 or USB-to-serial adapters).

Let's evaluate:

- * A. 9600 ##Too slow; used in legacy systems
- * B. #115200 # Correct default for MikroTik boards
- * C. 38400 ##Incorrect
- * D. 11520 ##Typo; not a standard rate

MTCNA Hardware Module - Serial Access:

"Default baud-rate is 115200. Use this setting when connecting via serial cable." Rene Meneses Study Guide - RouterBOARD Console Access:

"Use 115200 baud to access RouterBOARD via serial port."

Terry Combs Notes - Serial Console Tips:

"Almost all modern RouterBOARDS use 115200 as default serial speed."

NEW QUESTION: 3

Which port does PPTP use by default?

A. TCP 1721

B. UDP 1723

C. TCP 1723

D. UDP 1721

Answer: (SHOW ANSWER)

PPTP (Point-to-Point Tunneling Protocol) uses:

- * TCP port 1723 for control and session initiation
- * GRE (Generic Routing Encapsulation) protocol (protocol number 47) for tunneling No UDP port is used by PPTP.

Evaluation:

- * A. TCP 1721 ##Invalid port
- * B. UDP 1723 ##Incorrect protocol (TCP is used, not UDP)
- * C. #TCP 1723 # Correct
- * D. #Invalid (wrong protocol and port)

MTCNA Tunneling Section - PPTP Overview:

"PPTP uses TCP port 1723 for control and GRE protocol for tunneling traffic." Rene Meneses

MTCNA Guide - PPTP Characteristics:

"PPTP = TCP/1723 + GRE (not a port, but a protocol). Allow both on firewall." Terry Combs Notes - VPN Protocol Reference:

"PPTP: TCP 1723. GRE must be permitted for tunnel data."

NEW QUESTION: 4

What are the two main types of access control lists (ACLs)?

- * Standard
- * IEEE
- * Extended
- * Specialized

A. 1 and 3

B. 2 and 4

C. 3 and 4

D. 1 and 2

Answer: (SHOW ANSWER)

Cisco IOS supports two primary types of ACLs:

- * Standard ACLs: Filter traffic based only on source IP address
- * Extended ACLs: Filter traffic based on source, destination IP, protocol type, and port numbers

Cisco IOS Security Guide - ACL Fundamentals:

"Standard ACLs use only source IP for filtering. Extended ACLs can match based on source, destination, ports, and protocols." Rene Meneses MTCNA Study Guide - ACL Types:

"Two types of IP ACLs: standard and extended. IEEE or specialized ACLs do not exist in Cisco terminology." Other options:

- * IEEE: Refers to Ethernet or wireless standards, not ACLs
- * Specialized: Not a defined ACL type

NEW QUESTION: 5

A client uses a RouterBOARD1000. The clock is configured in '/system clock'. The clock resets to default after each reboot.

Select the best solution for the problem.

- A. Write a script in '/system script' to set the clock**
- B. Configure '/system ntp server' and set a valid and reachable NTP client address**
- C. Configure '/system ntp client' and set a valid and reachable NTP server address**
- D. Open the router and ensure the CMOS battery is fine**

Answer: (SHOW ANSWER)

RouterBOARD devices (such as RB1000) typically do not have a battery-backed hardware clock (RTC). This means the system time resets after each reboot. To keep time accurate, you must configure the router to synchronize with an external NTP (Network Time Protocol) server.

- * A.#Inefficient and non-scalable solution.
- * B.#The /system ntp server is used to act as an NTP server for others - not for receiving time.
- * C.#Correct - You must enable /system ntp client and point to a reachable NTP server to get the correct time on boot.
- * D.#Irrelevant - RouterBOARDS do not have CMOS batteries for timekeeping like traditional PCs.

Extract from MTCNA Course Material - Time Synchronization:

"To maintain correct system time, configure NTP client to sync with a public or internal time server after reboot." Extract from Rene Meneses Study Guide - Clock and Scheduler:

"RouterBOARD devices don't have battery-backed RTC. Use the NTP client to update time after reboot." Extract from MikroTik Wiki - NTP Setup:

"Use /system ntp client to sync time. /system clock alone will reset on reboot without NTP."

NEW QUESTION: 6

The DoD model (also called the TCP/IP stack) has four layers. Which layer of the DoD model is equivalent to the Network layer of the OSI model?

- A. Application
- B. Host-to-Host
- C. Internet
- D. Network Access

Answer: (SHOW ANSWER)

The TCP/IP or DoD model includes the following layers:

- * Application
- * Host-to-Host
- * Internet
- * Network Access

The Internet layer in the DoD model is responsible for logical addressing and routing - matching the function of the OSI model's Layer 3 (Network Layer), which handles IP addressing and packet forwarding.

MTCNA Course Material - TCP/IP vs OSI Model:

"The Internet layer of the TCP/IP model maps directly to the OSI's Network Layer and is responsible for logical addressing and routing." Rene Meneses MTCNA Study Guide - Layer Mapping Table:

"TCP/IP Internet Layer = OSI Network Layer. Handles IP routing, addressing." Other mappings:

- * Application = OSI Layers 5-7
- * Host-to-Host = OSI Layer 4 (Transport)
- * Network Access = OSI Layers 1-2

NEW QUESTION: 7

Which of the following are valid IP addresses?

- A. 10.10.14.0
- B. 192.168.256.1
- C. 192.168.13.255
- D. 1.27.14.254

Answer: (SHOW ANSWER)

An IPv4 address is a 32-bit number divided into 4 octets. Each octet must be between 0 and 255. Let's evaluate:

- * A. 10.10.14.0 ##Valid; .0 is legal, may represent a network or host depending on subnet

- * B. 192.168.256.1 ##Invalid; 256 exceeds the max octet value (0-255)
- * C. 192.168.13.255 ##Valid broadcast or host IP, depending on subnet
- * D. 1.27.14.254 ##All octets are within valid range

MTCNA Training Manual - IP Basics:

"Each octet must be between 0 and 255. Addresses like 192.168.256.1 are invalid." Rene

Meneses Guide - Valid IP Criteria:

"Watch for octets above 255 - they are illegal in IPv4."

Terry Combs Notes - Address Format Validation:

"Decimal format must be checked - 256, 999, or negative values break IPv4 standards."

NEW QUESTION: 8

It is possible to create an encrypted PPPoE tunnel in RouterOS:

A. true

B. false

Answer: (SHOW ANSWER)

PPPoE (Point-to-Point Protocol over Ethernet) does not include encryption by default. It can authenticate users using PAP or CHAP, but the data payload is transmitted in cleartext unless another secure tunneling protocol (e.g., IPsec) is layered on top.

MikroTik supports encryption in other tunneling protocols, such as:

- * SSTP (uses SSL)
- * L2TP with IPsec
- * OpenVPN (SSL-based)
- * IPsec itself (for IP layer encryption)

MTCNA Tunneling Chapter - PPP Protocol Features:

"PPPoE offers authentication, compression, but no native encryption. Use IPsec if encryption is needed." Rene Meneses Guide - Tunnel Comparison Table:

"PPPoE is not encrypted. SSTP and L2TP/IPsec are alternatives when encryption is a requirement." Terry Combs Notes - PPP Family Summary:

"PPPoE: Authentication = Yes, Encryption = No. Use with caution over untrusted networks."

NEW QUESTION: 9

Which command is used to determine if an IP access list is enabled on a particular interface?

A. show access-lists

B. show interface

C. show ip interface

D. show interface access-lists

Answer: (SHOW ANSWER)

The command show ip interface displays the status of IP-level interface parameters, including whether an access list (ACL) is applied inbound or outbound.

Cisco IOS Command Reference - Interface ACL Check:

"Use show ip interface to verify whether an access list is applied to the interface and in which direction (in or out)." Rene Meneses MTCNA Study Guide - Cisco Access List Monitoring:
"To verify ACL assignment to an interface, use show ip interface. It provides ACL status along with IP addressing info." Breakdown:

- * A: show access-lists # shows ACL contents, not interface bindings
- * B: show interface # shows interface stats, not ACL usage
- * D: Invalid syntax in Cisco IOS

NEW QUESTION: 10

Which of the following Route statuses are possible?

A. A = Active

B. C = Connected

C. S = Static

D. D = Drop

Answer: (SHOW ANSWER)

In the MikroTik routing table, route status flags describe the type and status of each route:

- * A = Active # The route is being used to forward packets#
- * C = Connected # The route is to a directly connected subnet#
- * S = Static # The route was added manually by the administrator#
- * D = Drop ##There is no such routing flag; "drop" may be an action in firewall or route rules but not a route status Correct route flags in MikroTik include:
 - * D = Dynamic
 - * A = Active
 - * C = Connected
 - * S = Static
 - * r = RIP
 - * o = OSPF
 - * b = BGP

MTCNA Routing Section - Route Flags Overview:

"Static routes show as S, connected routes as C, and routes in use are marked with A." Rene Meneses Guide - Routing Table Flags:

"Check route flags: A (Active), C (Connected), S (Static). Drop is not a valid route flag." Terry Combs Notes - Route Status Flags:

"Drop = firewall action, not route flag. Don't confuse it with routing status."

NEW QUESTION: 11

You have a router with configuration

- * Public IP: 202.168.125.45/24
- * Default gateway: 202.168.125.1
- * DNS server: 248.115.148.136, 248.115.148.137
- * Local IP: 192.168.2.1/24

Mark the correct configuration on client PC to access the Internet:

- A. IP: 192.168.0.1/24, gateway: 192.168.2.1
- B. IP: 192.168.2.253/24, gateway: 202.168.0.1
- C. IP: 192.168.2.115/24, gateway: 192.168.2.1
- D. IP: 192.168.2.2/24, gateway: 202.168.125.45
- E. IP: 192.168.1.223/24, gateway: 248.115.148.136

Answer: (SHOW ANSWER)

To correctly configure a host in a private network behind a router:

- * The IP must match the local subnet (192.168.2.0/24)
- * The gateway must be the router's local IP (192.168.2.1)
- * DNS settings can be default or custom, but IP and gateway must be valid Let's evaluate:
- * A. 192.168.0.1 # Wrong subnet (192.168.0.0/24 # 192.168.2.0/24)#
- * B. Gateway 202.168.0.1 # Invalid internal gateway#
- * C. IP 192.168.2.115 with gateway 192.168.2.1 ##Correct subnet and correct gateway
- * D. Gateway 202.168.125.45 # This is router's public IP, not the correct gateway for LAN#
- * E. IP 192.168.1.223 # Wrong subnet; also, gateway is DNS IP#

MTCNA NAT Section - Network Configuration:

"Clients should be in the same subnet as the router's local IP and must use that local IP as their gateway to reach outside networks." Rene Meneses Guide - Gateway and Addressing:

"The client's IP should belong to the same subnet as the local router interface. Always verify gateway IP points to the internal address." Terry Combs Notes - Default Gateway Setup:

"The default gateway for local clients must be the internal router IP - not the public or DNS IP."

NEW QUESTION: 12

Where can you monitor (see addresses and ports) real-time connections which are processed by the router?

- A. Firewall Connection Tracking
- B. Firewall Counters
- C. Tool Torch
- D. Queue Tree

Answer: A (LEAVE A REPLY)

Firewall Connection Tracking (also known as conntrack) is used to monitor real-time connections that pass through the router. It shows source and destination IPs, ports, protocols, connection states (established, new, related), and more.

Let's evaluate the options:

- * A.#Correct - Shows live connection table with IPs, ports, and statuses
- * B.#Shows rule match counters only - no detailed connection info
- * C.#Torch shows per-interface traffic; useful for bandwidth, but not a connection list
- * D.#Queue Tree is used for traffic shaping, not for viewing connections MTCNA Course Manual - Firewall Concepts:

"Connection tracking shows all active sessions through the router with IP and port details." Rene Meneses Guide - Firewall Tools:

"Use connection tracking to diagnose connection states and NAT behavior." Terry Combs Notes - Monitoring Tools:

"conntrack is your real-time connection monitor. Torch is per-interface, not per-flow."

NEW QUESTION: 13

Which type of encryption could be used to establish a connection with a simple passkey without using a 802.1 X authentication server?

A. WPA PSK/WPA2 PSK

B. WPA EAP/WPA2 EAP

Answer: (SHOW ANSWER)

Wireless encryption modes differ in how they authenticate clients:

* WPA/WPA2 PSK (Pre-Shared Key): Uses a passphrase shared by all clients. No external authentication server (like RADIUS or 802.1X) is required. Simple and suitable for home or small networks.

* WPA/WPA2 EAP: Uses 802.1X (Enterprise mode) and requires a centralized authentication server.

Option analysis:

* A.#Correct - Pre-Shared Key does not require 802.1X server

* B.#Incorrect - Requires EAP-based authentication with 802.1X infrastructure Extract from Official MTCNA Course Material - Wireless Security:

"WPA PSK/WPA2 PSK uses a pre-shared password. WPA/WPA2 EAP requires 802.1X authentication with a RADIUS server." Extract from Rene Meneses MTCNA Study Guide - Wireless Encryption:

"To use a simple password for connecting wireless clients, select WPA2-PSK. It does not require server-based authentication." Extract from Terry Combs Notes - Wireless Security Profiles:

"WPA2 PSK = password-based; WPA2 EAP = 802.1X based. Use PSK for fast, simple authentication."

NEW QUESTION: 14

Evaluate the following information:

Access Point configuration:

-- wlan1 is in 'AP-Bridge' mode

-- Bridge1 has wlan1 and ether1 as ports

CPE configuration:

-- wlan1 is in 'Station-Bridge' mode

-- Bridge1 has wlan1 and ether1 as ports

Select protocols that will pass from ether1 on the CPE to ether1 on the Access Point:

A. IPv4

B. ARP

C. USB

D. BGP

E. Firewire

F. IPv6

G. DHCP

H. PPPoE

Answer: (SHOW ANSWER)

In this configuration, the wireless interface (wlan1) on the AP is in ap-bridge mode, and on the CPE it's in station-bridge mode. This mode allows full Layer 2 bridging over wireless, supporting all Ethernet-based protocols and services, including:

* IPv4, IPv6, DHCP, ARP, PPPoE, and routing protocols like BGP (which use TCP/IP). Protocols like USB or Firewire are hardware-level or local bus protocols and cannot be transmitted over Ethernet frames or wireless.

Option Review:

- * A.#IPv4 - supported
- * B.#ARP - Layer 2 protocol, supported
- * C.#USB - not a network protocol, not transmitted over bridges
- * D.#BGP - Layer 3 protocol, supported over bridged links
- * E.#Firewire - not a Layer 2 or network protocol
- * F.#IPv6 - fully supported
- * G.#DHCP - Layer 3 broadcast protocol, works over bridges
- * H.#PPPoE - Ethernet-based protocol, passes over Layer 2 bridge

Extract from Official MTCNA Course Material - Wireless Bridging:

"station-bridge mode allows transparent Layer 2 bridging, supporting all Ethernet protocols including IPv4, IPv6, ARP, DHCP, PPPoE, and more." Extract from Rene Meneses MTCNA Study Guide - Wireless Modes:

"Use station-bridge with ap-bridge to pass full Layer 2 traffic. This allows DHCP, PPPoE, and other protocols to work transparently." Extract from MikroTik Wiki - Station Bridge:

"station-bridge mode is used with MikroTik-only links and allows full Layer 2 protocol support, including dynamic IP assignments and bridging."

NEW QUESTION: 15

From which of the following locations can you obtain Winbox?

A. Router's webpage

B. Files menu in your router

C. Via the console cable

D. mikrotik.com

Answer: (SHOW ANSWER)

Winbox is a small, native Windows utility provided by MikroTik for graphical administration of RouterOS devices. It is typically downloaded from MikroTik's official website.

- * A. Router's webpage # Incorrect. While the router's WebFig interface may allow configuration, it does not offer a Winbox download.
- * B. Files menu # Incorrect. The Files menu is for storing backups or firmware packages, not distributing Winbox.
- * C. Console cable # Incorrect. Console access is CLI only; no GUI utilities can be transferred through it.
- * D. mikrotik.com # Correct. The only official and secure location to download Winbox is the MikroTik website.

Extract from Official MTCNA Course Material - RouterOS Introduction:

"Winbox can be downloaded from the official MikroTik website. It provides a GUI frontend for managing RouterOS." Extract from Rene Meneses MTCNA Study Guide - RouterOS Access Methods:

"You can download Winbox from mikrotik.com under the Software Tools section." Extract from Terry Combs MTCNA Notes - Access Methods:

"Winbox is a Windows application that must be downloaded from MikroTik's website. It is not available directly from the router."

NEW QUESTION: 16

Select which of the following are 'Public IP addresses':

- A. 172.168.254.2
- B. 172.28.73.21
- C. 11.63.72.21
- D. 10.110.50.37
- E. 192.168.0.1

Answer: (SHOW ANSWER)

IP addresses are categorized as either public or private. According to the IANA (Internet Assigned Numbers Authority), the following are reserved for private use:

- * 10.0.0.0 to 10.255.255.255 (Class A Private)
- * 172.16.0.0 to 172.31.255.255 (Class B Private)
- * 192.168.0.0 to 192.168.255.255 (Class C Private)

Any IP outside of these ranges is considered public and routable on the global internet.

Evaluation of each option:

- * A. 172.168.254.2 # This is in the 172.16.0.0 - 172.31.255.255 range # Private
- * B. 172.28.73.21 # Also falls in the same private 172.16.0.0/12 range # Private
- * C. 11.63.72.21 # Outside all private ranges # Public#
- * D. 10.110.50.37 # In the 10.0.0.0/8 range # Private
- * E. 192.168.0.1 # In the 192.168.0.0/16 private range # Private

Extract from Rene Meneses MTCNA Study Guide:

"Private IP ranges include 10.0.0.0/8, 172.16.0.0/12, and 192.168.0.0/16. These are non-routable over the public internet." Extract from Terry Combs Notes:

"Only IPs outside of the above ranges are considered public and routable. Watch out for 172.X.X.X - not all are public; only 172.0.0.0-172.15.255.255 and 172.32.0.0+ are public."

MikroTik Wiki - IP Addressing Reference:

"Private addresses are not globally routable. They are used inside local networks and must be NATed for internet access."

Valid MTCNA Dumps shared by ExamDiscuss.com for Helping Passing MTCNA Exam!

ExamDiscuss.com now offer the **newest MTCNA exam dumps**, the ExamDiscuss.com

MTCNA exam **questions have been updated** and **answers have been corrected** get the **newest** ExamDiscuss.com MTCNA dumps with Test Engine here:

<https://www.examdiscuss.com/MikroTik/exam/MTCNA/premium/> (205 Q&As Dumps, **35%OFF**

Special Discount Code: freecram)

NEW QUESTION: 17

What is the correct action for a NAT rule on a router that should intercept SMTP traffic and send it over to a specified mail server?

A. tarpit

B. dst-nat

C. passthrough

D. redirect

Answer: (SHOW ANSWER)

To forward traffic from one destination to another (such as from the public IP to an internal mail server), the dst-nat action is used in MikroTik NAT rules.

* dst-nat: Modifies the destination IP address and/or port of the packet. Used to forward traffic to an internal resource.

* tarpit: Captures and holds TCP connections (used for spam traps or slowing down bots) ##

* passthrough: Used in mangle rules; allows the packet to be evaluated by the next rule ##

* redirect: Redirects traffic to the router itself (e.g., proxy or DNS services) ## So, for external SMTP traffic (e.g., TCP port 25), we use a dst-nat rule that forwards the traffic to the internal mail server.

MTCNA NAT Section - Destination NAT:

"To forward SMTP traffic from a public address to a private server, use dst-nat with appropriate port and IP." Rene Meneses Guide - Practical NAT Examples:

"Use dst-nat for port forwarding. Redirect is for internal services like DNS or web proxy." Terry Combs Notes - NAT Action Summary:

"dst-nat = most common for external-to-internal mapping (e.g., mail servers, web servers)."

NEW QUESTION: 18

What is possible with Netinstall?

A. MikroTik RouterOS reinstall

B. MikroTik RouterOS password reset with saving router's configuration

C. MikroTik RouterOS configuration reset

Answer: (SHOW ANSWER)

Netinstall is a powerful utility provided by MikroTik that allows reinstallation of RouterOS on RouterBOARD devices. It is primarily used for:

- * Reflashing or reinstalling RouterOS
- * Recovering devices that are not booting correctly
- * Clearing configurations during reinstall

It does not allow you to reset the password without losing the configuration, nor is it used just for configuration reset.

MTCNA Official Course Material - Tools & Netinstall:

"Netinstall is used to reinstall RouterOS onto a MikroTik device via the network. It can be used to install a specific RouterOS version or wipe the existing installation." Rene Meneses MTCNA Guide - Tools Chapter:

"Netinstall allows you to reinstall RouterOS and optionally reset the configuration. It does not allow recovery of the existing password or configuration unless backed up beforehand." MikroTik Wiki - Netinstall Utility:

"Netinstall is a tool used for reinstalling RouterOS. It formats the system partition and reinstalls RouterOS.

This is useful in case of misconfiguration or firmware corruption."

Option B is incorrect - password reset is only possible via full configuration wipe.

Option C is not accurate - Netinstall reinstalls the entire OS, not just resets configuration.

Only A is correct.

NEW QUESTION: 19

What is necessary for PPPoE client configuration?

A. Interface (on which PPPoE client is going to work)

B. Static IP address on PPPoE client interface

C. ip firewall nat masquerade rule

Answer: (SHOW ANSWER)

To configure a PPPoE client on MikroTik, you need to:

- * Set the client interface (usually ether1 or another WAN-facing port).
- * Optionally add NAT masquerading to enable LAN users to reach the internet.
- * IP address on the interface is assigned dynamically from the ISP after PPPoE negotiation, so a static IP is not required.

Option Analysis:

- * A.#Required - You must select the interface that initiates the PPPoE connection.
- * B.#Not Required - The IP is typically assigned by the PPPoE server (ISP).
- * C.#Required - NAT masquerade is commonly used to allow internet access for private IP clients behind the router.

Extract from MTCNA Course Material - PPPoE Client Setup:

"The PPPoE client must have an interface specified. A NAT masquerade rule is recommended for internet access sharing." Extract from Rene Meneses MTCNA Study Guide - PPPoE:

"You do not need to assign a static IP to the PPPoE client interface. IP is received after successful login." Extract from MikroTik Wiki - PPPoE Client:

"After setting up the interface and credentials, PPPoE client negotiates and receives dynamic IP. Add NAT if routing LAN traffic."

NEW QUESTION: 20

You want to use PCQ and allow 256k maximum download and upload for each client. Choose correct argument values for the required queue.

A. kind=pcq pcq-rate=256000 pcq-classifier=src-address

B. kind=pcq pcq-rate=1256000 pcq-classifier=dst-address

C. kind=pcq pcq-rate=256000 pcq-classifier=dst-address

D. kind=pcq pcq-rate=5000000 pcq-classifier=src-address

E. kind=pcq pcq-rate=5000000 pcq-classifier=dst-address

Answer: (SHOW ANSWER)

PCQ (Per Connection Queue) is used in MikroTik to enforce bandwidth fairness across multiple users. To limit each client to 256k:

* pcq-rate=256000 # sets maximum bandwidth per client to 256,000 bps (256 kbps)

* pcq-classifier=src-address # used in upload queues

* pcq-classifier=dst-address # used in download queues

So:

* A.#Used for upload: src-address

* C.#Used for download: dst-address

The other options have incorrect rates or classifiers:

* B.#Incorrect rate (1256000 # 256k)

* D & E.#Incorrect rate (5000000 = 5 Mbps)

MTCNA Course Manual - PCQ Explanation:

"Use pcq-classifier=src-address for upload, and dst-address for download. pcq-rate sets per-client limit." Rene Meneses Study Guide - Queue Management:

"To cap clients to 256k, configure pcq-rate=256000. Adjust classifiers based on traffic direction."

Terry Combs Notes - PCQ Parameters:

"Classifier is the key. src-address = upload, dst-address = download. Don't mix."

NEW QUESTION: 21

If you wanted to delete the configuration stored in NVRAM, what would you type?

A. erase startup

B. erase nvram

C. delete nvram

D. erase running

Answer: A ([LEAVE A REPLY](#))

In Cisco IOS (used as a common reference in networking), the startup configuration is stored in NVRAM. To delete it and reset the device to factory defaults upon reboot, you use:

Command: erase startup-config or write erase

Networking Fundamentals - Cisco CLI:

"To remove the startup-config file from NVRAM, use erase startup-config. This will delete saved settings and reboot will load default settings." Rene Meneses MTCNA Study Guide - Cisco Integration:

"erase startup-config is used to clear saved configuration. Running-config is stored in RAM, and 'erase running' is invalid." Other options:

* B and C: Not valid Cisco commands

* D: erase running is invalid - running-config must be cleared manually or overwritten

NEW QUESTION: 22

Which computers would be able to communicate directly (without any routers involved)?

A. 192.168.17.15/29 and 192.168.17.20/28

B. 10.5.5.1/24 and 10.5.5.100/25

C. 10.10.0.17/22 and 10.10.1.30/23

D. 192.168.0.5/26 and 192.168.0.100

Answer: ([SHOW ANSWER](#))

To determine if two hosts can communicate directly, their IP addresses must:

* Belong to the same subnet

* Have matching subnet boundaries (based on their masks)

Let's evaluate each:

A: 192.168.17.15/29 # Subnet: 192.168.17.8 - 192.168.17.15

192.168.17.20/28 # Subnet: 192.168.17.16 - 192.168.17.31

Different subnets

B: 10.5.5.1/24 # Subnet: 10.5.5.0 - 10.5.5.255

10.5.5.100/25 # Subnet: 10.5.5.0 - 10.5.5.127

Different masks # Host with /25 may treat others outside /25 as unreachable ## C:

10.10.0.17/22 # Range: 10.10.0.0 - 10.10.3.255

10.10.1.30/23 # Range: 10.10.0.0 - 10.10.1.255

Both addresses fall within same larger /22 range

D: 192.168.0.5/26 # Subnet: 192.168.0.0 - 192.168.0.63

192.168.0.100 # Not enough info; assume default /24

/26 and /24 will not overlap fully # likely unreachable

MTCNA Course Manual - IP Subnetting:

"Hosts can communicate directly if they are in the same IP range and have the same subnet mask. Different subnet boundaries require routing." Rene Meneses Guide - Mask Comparison:

"Be cautious of overlapping address ranges. Matching IPs in same range with differing subnet masks may fail to communicate." Terry Combs Notes - Direct Connectivity Rules:

"Same subnet mask and same address block = direct communication. If masks differ, communication needs a router."

NEW QUESTION: 23

How many different priorities can be selected for queues in MikroTik RouterOS?

- A. 16
- B. 1
- C. 8
- D. 0

Answer: (SHOW ANSWER)

MikroTik RouterOS allows you to assign one of 8 different priority levels to each queue. These range from 1 (highest) to 8 (lowest). This allows for traffic shaping and prioritization in simple queues and queue trees.

These priority levels are used when multiple queues are competing for bandwidth or processing time. They influence which traffic gets handled first when congestion occurs.

- * A. 16 ##Invalid. Only 8 supported.
- * B. 1 ##Not correct. Only says one value; MikroTik supports multiple.
- * C. 8 ##Correct. There are 8 valid priority values.
- * D. 0 ##Priority 0 is not valid in MikroTik queues.

MTCNA Course Manual - Queues and Priorities:

"MikroTik queues support 8 priority levels (1-8). These affect which traffic is processed first."

Rene Meneses Study Guide - QoS Mechanics:

"You can select between 8 priorities. These are configured per queue to define traffic importance." Terry Combs Notes - Simple Queues:

"Only 8 priority values exist. They follow a numerical scale from 1 to 8, not 0 or beyond."

NEW QUESTION: 24

Router has wireless and ethernet client interfaces, all client interfaces are bridged. To create a DHCP service for all clients, DHCP server must be configured on:

- A. Ethernet and wireless interfaces
- B. DHCP service is not possible in this setup
- C. Every bridge port
- D. Only on the bridge interface

Answer: (SHOW ANSWER)

When you place multiple interfaces (ethernet, wlan) into a bridge, the bridge interface becomes the logical Layer 3 interface. Any IP-related services (e.g., DHCP server, firewall rules) must be applied to the bridge interface, not the individual ports.

- * A.#Incorrect - IP services are not bound to physical ports in a bridged setup.
- * B.#Incorrect - DHCP works perfectly in this setup.
- * C.#Incorrect - The bridge ports are Layer 2; DHCP must bind to the Layer 3 bridge interface.
- * D.#Correct - Configure the DHCP server on the bridge interface.

Extract from Official MTCNA Course Material - Bridging and DHCP:

"When using a bridge interface with multiple ports, IP services (like DHCP) must be bound to the bridge itself." Extract from Rene Meneses MTCNA Study Guide - Bridging Concepts:

"DHCP server should be created on the bridge interface if it includes both wireless and ethernet clients." Extract from MikroTik Wiki - DHCP Server:

"Always assign the DHCP server to the bridge interface when clients are behind bridged ports."

NEW QUESTION: 25

Which of the following keystrokes enables safe mode in console?

- A. Ctrl+x
- B. Ctrl+c
- C. Ctrl+d
- D. Ctrl+s

Answer: (SHOW ANSWER)

Safe Mode in MikroTik CLI is a protective mode that helps revert any unintended changes if you get disconnected. It is activated by pressing Ctrl+X in older versions, but the current standard keybinding for enabling safe mode is Ctrl+S.

MTCNA Course Material - Safe Mode:

"To enable safe mode in the terminal, press Ctrl+S. A confirmation [Safe Mode] will appear in the prompt. If the terminal is closed or disconnected, the changes are rolled back." Rene Meneses MTCNA Study Guide - Terminal Commands:

"Safe Mode can be activated using Ctrl+S. This is useful during remote configuration. It reverts changes if the terminal is closed." MikroTik Wiki - Safe Mode Section:

"To enter safe mode, press Ctrl+S in CLI. This ensures configuration rollback if disconnected."

Other options:

- * Ctrl+C terminates commands or CLI input
- * Ctrl+X may not activate safe mode in newer versions
- * Ctrl+D is used to log out in some Unix-like terminals

Correct answer: Ctrl+S

NEW QUESTION: 26

You want to transfer existing '/ip firewall filter' configuration from one router to a new system.

Choose the best possible way to do:

- A. Export only '/ip firewall filter'
- B. Create backup only of '/ip firewall filter' rules
- C. Create backup, edit backup file and restore on target router
- D. Export global configuration and remove everything apart from '/ip firewall filter'

Answer: (SHOW ANSWER)

The best way to transfer only the firewall filter rules is to use the export command for just that section:

Command:

/ip firewall filter export

This produces a readable script containing only the firewall filter rules. This method is safer than editing binary backups and more efficient than exporting the global configuration and deleting unrelated parts.

Evaluation:

- * A.#Correct - clean and script-based approach
- * B.#You cannot selectively back up just firewall rules using the backup function (it's system-wide)
- * C.#Editing a backup file is not recommended and often not possible (it's binary)
- * D.#Too cumbersome and error-prone

MTCNA Course Manual - Configuration Transfer:

"Use export to get script output of specific sections. Backups are for full system restore." Rene Meneses Guide - Migrating Configurations:

"Export is recommended for transferring specific configurations like firewall rules." Terry Combs Notes - Export vs Backup:

"Backups = full system. Use export for clean, readable configuration transfer."

NEW QUESTION: 27

Select minimal set of software packages in RouterOS required to configure a wireless AP:

- A. Wireless**
- B. advanced-tools
- C. dhcp
- D. routing
- E. system

Answer: (SHOW ANSWER)

To configure a wireless access point (AP) in RouterOS, the only required software package is wireless. All other functionalities like DHCP or routing are optional depending on the network setup. The system package is always present and not removable, so it's not listed as a required dependency in package selection.

MTCNA Course Material - Wireless Configuration Basics:

"Wireless functionality is provided by the wireless package. Without it, no wireless interfaces are present or configurable." Rene Meneses MTCNA Guide - Wireless Module:

"Only the wireless package is required to configure an AP. DHCP is used optionally for IP address assignment." MikroTik Wiki - Packages:

"The wireless package is responsible for enabling WLAN interfaces and features such as AP mode, client mode, and security." Other packages:

- * advanced-tools: includes tools like bandwidth-test and traffic generator
- * dhcp: only needed if the router is issuing IPs
- * routing: required for static/dynamic routing but not AP setup

Only Option A is required.

NEW QUESTION: 28

Please select valid scan-list values in interface wireless configuration:

A. 5560,5620-5700

B. 5640~5680

C. default,5560,5600,5660-5700

D. 5540,5560,5620+5700

Answer: C (LEAVE A REPLY)

The scan-list option defines the frequencies that a wireless interface should scan or operate on.

Valid formats include:

- * Single frequencies: e.g., 5560
- * Ranges: e.g., 5660-5700
- * Including "default" for system-determined values
- * Comma-separated lists are accepted

Characters like ~ or + are not allowed.

MTCNA Official Course Material - Wireless Configuration:

"scan-list can include frequency numbers and ranges separated by commas. Example:

5500,5520-5700. Use

'default' to use the standard channel list."

Rene Meneses MTCNA Guide - Wireless Interface Options:

"Valid scan-list includes entries like: 5180,5200-5320, or default. Invalid characters such as '~' or '+' are not supported." MikroTik Wiki - Wireless Manual:

"Values can be comma-separated frequencies and ranges. Symbols such as '+' or '~' are not allowed in scan-list values." Option A: valid format Option B: invalid ('~' is not allowed) Option C: valid - includes default and proper ranges Option D: invalid - '+' symbol is not allowed Thus, Option C is the only valid and complete answer.

NEW QUESTION: 29

To connect your MikroTik router to a wireless access point, you have to:

A. Use the same SSID as on accesspoint

B. Use the same Radio Name

C. Use the same Band (5 GHz, 2.4 GHz, ...)

Answer: (SHOW ANSWER)

To establish a wireless client connection to an access point:

- * The SSID must match exactly - including capitalization.
- * The Band must be compatible - i.e., both devices must support and use the same frequency band (2.4 GHz or 5GHz).
- * Radio Name is an identifier for display purposes only and does not affect connectivity.

Option Analysis:

- * A.#Required - Matching SSID is essential.
- * B.#Not Required - Radio Name is just a display label in tools like Winbox.
- * C.#Required - Band compatibility is critical to ensure the device can "see" and connect to the AP.

Extract from Official MTCNA Course Material - Wireless Client Configuration:

"To connect to an AP, the client must use the same SSID and operate on a compatible band and frequency." Extract from Rene Meneses MTCNA Study Guide - Wireless Modes:

"SSID and band must match to connect. Radio name is not used in the authentication or association process." Extract from Terry Combs Notes - Wireless Settings:

"SSID is like the network name, and it must be identical. Mismatched bands (e.g., 2.4 vs 5GHz) will prevent discovery."

NEW QUESTION: 30

During a scan, in order to see all the available wireless frequencies that are supported by the card, the following option must be selected in the wireless card's "Frequency Mode":

A. superchannel

B. regulatory domain

C. manual txpower

Answer: (SHOW ANSWER)

In MikroTik RouterOS, enabling the "superchannel" frequency mode allows access to all frequencies supported by the wireless chip, including those that may be outside of country-specific regulatory limits. This mode is typically used in lab testing or in regions where regulations permit.

* A. superchannel ##Correct. Enables full frequency range

* B. regulatory domain # Restricts visible frequencies to region's law

* C. manual txpower # Controls power output, not frequency scanning

MTCNA Course Material - Wireless Configuration Options:

"To unlock all available wireless frequencies for scanning or connection, enable the

'superchannel' frequency mode." Rene Meneses Study Guide - Wireless Advanced Config:

"Superchannel mode shows all channels supported by the hardware. Use with caution - may violate regulations." Terry Combs Notes - Wireless Modes:

"Want to see hidden or extended frequencies? Use superchannel mode. Not legal in every region."

NEW QUESTION: 31

Which of the following are layers in the TCP/IP model?

Application

Session

Transport

Internet

Data Link

Physical

A. 1 and 2

B. 1, 3 and 4

C. 2, 3 and 5

D. 3, 4 and 5

Answer: (SHOW ANSWER)

The TCP/IP model has four layers:

- * Application
- * Transport
- * Internet
- * Network Access (includes Data Link & Physical in OSI terms)

Session is part of the OSI model, not TCP/IP.

MTCNA Course Material - TCP/IP vs OSI Model:

"The TCP/IP model has Application, Transport, Internet, and Network Access layers. Application includes OSI's Session, Presentation, and Application layers." Rene Meneses MTCNA Guide - Model Comparison:

"The TCP/IP model consists of: Application, Transport, Internet, and Network Access (which covers Data Link and Physical). Session layer is part of OSI." So, correct TCP/IP layers from the given list:

- * Application (#)
- * Transport (#)
- * Internet (#)

Session is not part of TCP/IP model.

Valid MTCNA Dumps shared by ExamDiscuss.com for Helping Passing MTCNA Exam!

ExamDiscuss.com now offer the **newest MTCNA exam dumps**, the ExamDiscuss.com MTCNA exam **questions have been updated** and **answers have been corrected** get the **newest** ExamDiscuss.com MTCNA dumps with Test Engine here:

<https://www.examdiscuss.com/MikroTik/exam/MTCNA/premium/> (205 Q&As Dumps, **35%OFF**

Special Discount Code: freecram)

NEW QUESTION: 32

Which of the following is true for connection tracking?

- A. Connection tracking must be enabled for NAT'ed network
- B. Enabling connection tracking reduces CPU usage in RouterOS
- C. Disable connection tracking for mangle to work
- D. Connection tracking must be enabled to be able to use all firewall features**

Answer: (SHOW ANSWER)

Connection tracking (conntrack) is a feature that enables RouterOS to monitor and manage the state of all network connections passing through the router. It is essential for features like NAT, stateful firewalling, and proper use of mangle and filter rules.

MTCNA Course Material - Connection Tracking:

"Most firewall and NAT functionality depends on connection tracking being enabled. Without connection tracking, many features (like NAT) won't function properly." Rene Meneses MTCNA Study Guide - Firewall Section:

"Connection tracking is required for NAT and most firewall filters. When disabled, connection-state-based filtering or NAT is not possible." Terry Combs MTCNA Notes - Conntrack Section:

"Conntrack must be enabled to use full firewall capabilities, including NAT and filtering by connection states like established and related." Option A is partially true but not complete.

Option B is incorrect - conntrack may increase CPU load due to session tracking.

Option C is incorrect - mangle rules often depend on connection marks which require conntrack.

Only Option D accurately captures the critical requirement of connection tracking.

NEW QUESTION: 33

What is the term for the hardware coded address found on an interface?

A. FQDN Address

B. IP Address

C. Interface Address

D. MAC Address

Answer: ([SHOW ANSWER](#))

The hardware-coded address that uniquely identifies a device's network interface card (NIC) on the local network is called a MAC address. It is "burned in" by the hardware manufacturer and remains constant unless manually overridden.

MAC stands for Media Access Control, and it operates at Layer 2 of the OSI model. It is used to identify devices on a local area network.

* A. FQDN (Fully Qualified Domain Name) refers to a human-readable name used in DNS.

* B. IP Address is a logical address used for routing at Layer 3.

* C. Interface Address is a generic term and not a standard identifier.

* D. MAC Address is correct and refers to the physical, hardware-encoded address on an interface.

Extract from MTCNA Course Manual - RouterBOARD Overview:

"A MAC address is a globally unique hardware identifier assigned to each Ethernet or wireless interface. It is used by Layer 2 to ensure local delivery." Rene Meneses Study Guide - MAC & OSI Layering:

"The MAC address is a 48-bit physical identifier, hardcoded by the device vendor and located in the NIC chip." Terry Combs MTCNA Notes - Layer 2 Concepts:

"MAC = Physical Address = Layer 2 Identifier. It's what switches use to forward Ethernet frames."

NEW QUESTION: 34

Your company has been assigned a 172.16.25.0/25 network from your ISP. What are the possible options to divide the network into subnets?

A. one /23 and one /27

B. four times /27

C. two times /24

D. two times /26

Answer: (SHOW ANSWER)

The 172.16.25.0/25 subnet provides 128 IP addresses ($2^7 = 128$), including network and broadcast.

To subnet a /25 network (128 addresses), we can break it into:

* 2 x /26 # each with 64 addresses (62 usable) ##Valid

* 4 x /27 # each with 32 addresses # Also valid, but let's verify options Let's analyze the options:

A: one /23 and one /27 ##Invalid. /23 is larger than /25 - can't derive a larger subnet from a smaller one.

B: four times /27 ##Possible. $4 \times 32 = 128$. But not the best or only answer - and option D is more precise.

C: two times /24 ##Invalid. /24 = 256 addresses; you can't divide a 128-address block into 2 larger ones.

D: two times /26 ##Each /26 = 64 addresses. Two such subnets exactly fit into a /25 network.

MTCNA Course Manual - Subnetting and Address Planning:

"To divide a /25, you may use two /26s, four /27s, or other equal parts as long as they total no more than the parent subnet." Rene Meneses MTCNA Guide - Subnet Design:

"A /25 subnet can be split into 2 /26s (64 IPs each) or 4 /27s (32 IPs each), depending on host requirements." Terry Combs Notes - IP Subnetting Exercises:

"Always check if the proposed subnet sizes logically fit within the assigned block."

NEW QUESTION: 35

Bridging loops can be avoided by enabling:

A. RSTP protocol

B. STP protocol

C. Connection tracking

D. UDP filter

E. ICMP filter

Answer: (SHOW ANSWER)

Bridging loops occur when there are multiple active paths between switches or bridge interfaces, causing broadcast storms or MAC table instability. MikroTik RouterOS supports both STP (Spanning Tree Protocol) and RSTP (Rapid Spanning Tree Protocol) to detect and block redundant paths.

* A.#RSTP - Faster and preferred protocol to prevent loops.

* B.#STP - The original protocol, slower convergence but still effective.

* C.#Connection tracking - Not related to Layer 2 loop prevention.

* D.#UDP filter - Filters specific traffic types, doesn't handle loops.

* E.#ICMP filter - Not relevant to Layer 2 loop protection.

Extract from Official MTCNA Course Material - Bridging and STP:

"STP or RSTP must be enabled to prevent bridging loops. RSTP is the recommended version due to faster convergence." Extract from Rene Meneses MTCNA Study Guide - Bridging:
"Always enable STP or RSTP when using bridges with multiple paths to prevent Layer 2 loops."
Extract from MikroTik Wiki - STP / RSTP:
"STP and RSTP are loop prevention mechanisms for bridges. They dynamically block redundant links."

NEW QUESTION: 36

How long is level 1 (demo) license valid?

- A. 24 hours
- B. Infinite time**
- C. 1 month
- D. 1 year

Answer: (SHOW ANSWER)

RouterOS Level 1 license is the demo license that comes with all RouterOS installations (particularly on x86 or CHR before activation). It is unrestricted in time, meaning it never expires, but functionality is extremely limited.

- * A. 24 hours # Incorrect. There is no such time-limited restriction.
- * B. Infinite time # Correct. Level 1 license is perpetual but has limited features.
- * C. 1 month # Incorrect. MikroTik does not impose monthly timeouts on license levels.
- * D. 1 year # Incorrect. No temporary time-bound license is assigned by default.

Extract from Official MTCNA Course Material - Licensing Section:

"Level 1 (demo) license is unlimited in time but has very limited functionality. It is designed for testing purposes only." Extract from Rene Meneses MTCNA Study Guide - RouterOS Licensing:
"The Level 1 license is not time-limited, but it cannot be used in production due to its lack of key features." Extract from MikroTik Wiki - Licensing Model:
"License level 1 is a free demo license that does not expire."

NEW QUESTION: 37

/interface wireless access-list is used for:

- A. Handles a list of Client's MAC Address to permit/deny connection to AP**
- B. Shows a list of Client's MAC Address that are already registered at AP
- C. Contains the security profiles settings
- D. Authenticate Hot-Spot users

Answer: (SHOW ANSWER)

The /interface wireless access-list in MikroTik is used to define a set of rules that permit or deny wireless clients based on their MAC addresses and signal strength.

This list applies only to clients trying to connect to the router's wireless interface when it is configured as an Access Point.

Let's break down the options:

* A.#Correct - Used to allow or deny client MAC addresses and apply settings like rate limits, VLANs, etc.

* B.#That's the role of the registration table.

* C.#Security profiles are configured separately under /interface wireless security-profiles.

* D.#Hotspot authentication is handled via /ip hotspot, not wireless access lists.

MTCNA Wireless Module - MAC Access Control:

"Access-list matches incoming clients by MAC. You can allow, deny, and apply custom settings."

Rene Meneses Study Guide - Wireless Security:

"Access-list is used to explicitly permit or block clients based on their MAC address." Terry

Combs Notes - Wireless Filtering:

"Think of access-list like a whitelist/blacklist for Wi-Fi clients."

NEW QUESTION: 38

Which wireless mode allows you to connect to any standard AP (not only MikroTik) and to be able to bridge this wireless interface to an Ethernet?

A. station-pseudobridge

B. station

C. station-wds

D. bridge

Answer: (SHOW ANSWER)

The only wireless mode that allows bridging (Layer 2) over a connection to a non-MikroTik (standard 802.11) access point is station-pseudobridge. It fakes (spoofs) a bridge by using the wireless interface's MAC address for Ethernet clients behind it.

* A.#station-pseudobridge - Works with any AP and can bridge Ethernet # WiFi for one client.

* B.#station - Only works at Layer 3 (routing or NAT).

* C.#station-wds - Requires WDS support, which only MikroTik devices support.

* D.#bridge - Not a wireless mode; it's an interface type used in Layer 2.

Extract from Official MTCNA Course Material - Wireless Bridging:


"station-pseudobridge allows bridging to non-MikroTik APs. Suitable for simple Layer 2 extension with one client." Extract from Rene Meneses MTCNA Study Guide - Wireless Modes:

"For compatibility with standard APs, use station-pseudobridge mode. Other bridge modes require MikroTik AP." Extract from MikroTik Wiki - Wireless Bridging:

"station-pseudobridge is used when connecting to a standard access point while still wanting to bridge to local Ethernet."

NEW QUESTION: 39

What does this simple queue do (check the image)?



The screenshot shows a Simple Queue named "host_A" with:

- * Target Address: 192.168.1.10
- * Target Upload: Checked
- * Target Download: Checked
- * Max Limit: 1M (upload), unlimited (download)

A. Queue guarantees upload data rate of one megabit per second for host 192.168.1.10

B. Queue limits host 192.168.1.10 download data rate to one megabit per second.

C. Queue limits host 192.168.1.10 upload data rate to one megabit per second.

D. Queue guarantees download data rate of one megabit per second for host 192.168.1.10

Answer: (SHOW ANSWER)

The "Max Limit" value in Mikrotik Simple Queues defines the maximum allowed bandwidth. In this case:

- * Target Address: 192.168.1.10
- * Target Upload = 1M # The host can upload at a maximum of 1 Mbps
- * Target Download = unlimited # No restriction on download

This does not "guarantee" bandwidth - it enforces a ceiling. A guaranteed rate would require "Limit-at" to be set.

Evaluation:

- * A.#This queue limits, it does not guarantee a minimum bandwidth.
- * B.#Download is set to unlimited - no limitation.
- * C.#Upload is limited to 1 Mbps - correct.
- * D.#Download rate is unlimited - no guarantee or limit.

MTCNA Course Manual - Simple Queue Explanation:

"Max-limit sets the maximum throughput for upload/download. It's a ceiling, not a guarantee."

Rene Meneses Guide - Simple Queues Explained:

"In this case, upload is capped at 1M. No burst or download limit is applied." Terry Combs Notes - Queue Properties:

"Always distinguish between 'limit-at' (minimum guarantee) and 'max-limit' (maximum cap)."

NEW QUESTION: 40

A client that has successfully connected to a wireless network is considered to be which of the following?

Choose all that apply:

A. Authenticated

B. Associated

C. Unauthenticated

D. Unassociated

Answer: (SHOW ANSWER)

For a client to exchange data over a wireless network, it must complete two key steps:

* Association - Establishes the basic radio link between client and access point

* Authentication - Verifies credentials (e.g., WPA2 handshake)

When both are complete, the client is both authenticated and associated.

* A.#Authenticated - Encryption and access control is complete

* B.#Associated - Wireless radio link is established

* C.#Unauthenticated - Incorrect; client is verified

* D.#Unassociated - Incorrect; client is linked to AP

Extract from MTCNA Course Material - Wireless Client States:

"A connected client is associated (Layer 2) and authenticated (security/credentials verified)."

Extract from Terry Combs MTCNA Notes - Wireless States:

"Authenticated and associated are required for data transfer. Unassociated = disconnected."

NEW QUESTION: 41

PPP Secrets are used for:

A. PPPoE clients

B. L2TP clients

C. IPSec clients

D. PPP clients

E. PPTP clients

F. Router users

Answer: A,B,D,E (LEAVE A REPLY)

PPP Secrets is a user authentication mechanism used in MikroTik RouterOS for various PPP-based services.

These include:

- * PPP (Point-to-Point Protocol)
- * PPPoE (PPP over Ethernet)
- * PPTP (Point-to-Point Tunneling Protocol)
- * L2TP (Layer 2 Tunneling Protocol)

Each client authenticates with a username/password combination defined under PPP # Secrets.

PPP Secrets is not used for:

- * IPSec clients ##They use peer configurations and policies
- * Router users (Winbox/WebFig) ##Use system # users, not PPP secrets

MTCNA PPP Chapter - Secrets Authentication:

"PPP Secrets are used for all PPP services: PPP, PPPoE, L2TP, and PPTP. It defines usernames, passwords, profiles, and IP bindings." Rene Meneses Guide - Tunnels and PPP:

"Any PPP-based tunnel uses PPP secrets for login validation. This includes local dial-in and remote VPN tunnels." Terry Combs Notes - PPP Authentication Table:

"PPP Secrets = for PPP, PPPoE, PPTP, and L2TP. Not for IPSec or Winbox."

NEW QUESTION: 42

Which of the following protocols uses both TCP and UDP?

- A. FTP
- B. SMTP
- C. Telnet
- D. DNS**

Answer: (SHOW ANSWER)

DNS (Domain Name System) can use both UDP and TCP. Typically:

- * UDP port 53 is used for standard DNS queries due to its lower overhead.
- * TCP port 53 is used for DNS zone transfers and when DNS responses exceed the UDP packet size (e.g., DNSSEC).

MTCNA Course Material - Protocol Overview:

"DNS uses UDP port 53 for standard queries and TCP port 53 for zone transfers or large responses." Rene Meneses MTCNA Study Guide - Protocol Functions:

"DNS can operate over UDP and TCP. UDP is faster and used for most lookups. TCP is used when the payload is too large or for zone transfers." MikroTik Wiki - DNS Protocols:

"DNS primarily uses UDP 53. For zone transfers (AXFR), TCP 53 is used." Other options:

- * A. FTP uses TCP (ports 20/21)
- * B. SMTP uses TCP (port 25)
- * C. Telnet uses TCP (port 23)

Only DNS uses both TCP and UDP.

NEW QUESTION: 43

If you use either Telnet or FTP, which is the highest layer you are using to transmit data?

- A. Application**
- B. Presentation

C. Session

D. Transport

Answer: ([SHOW ANSWER](#))

Protocols like Telnet and FTP are considered Application Layer protocols in the OSI model. They operate at Layer 7, providing interfaces for user-level interaction and command control.

MTCNA Course Material - TCP/IP vs OSI Model:

"Telnet, FTP, HTTP are Application Layer protocols. They operate at the top of the OSI stack (Layer 7)." Rene Meneses MTCNA Study Guide - Protocol Layers:

"Telnet and FTP reside at the Application Layer. They initiate data exchange between hosts."

* Presentation and Session layers are not separately used in the TCP/IP model and are merged into the Application Layer.

* Transport (Layer 4) is used by these protocols (via TCP), but the protocol itself resides at the Application Layer.

NEW QUESTION: 44

You have a DHCP server on your MikroTik router. The IP addresses 10.1.2.2-10.2.2.20 are distributed in the DHCP network. Additionally, 3 static IP addresses are defined for your servers: 10.1.2.31-10.1.2.33.

After a while, 20 more IP addresses need to be distributed in the network. It is possible to distribute the extra IP addresses without adding another DHCP Server:

A. True

B. False

Answer: ([SHOW ANSWER](#))

MikroTik RouterOS allows DHCP administrators to modify the DHCP address pool without creating an additional DHCP server. You can simply edit or extend the address pool range, and the DHCP server will start offering those new IPs.

Therefore, it is completely possible to:

- * Extend the existing address pool
- * Exclude statically assigned IPs
- * Continue using the same DHCP Server instance

You do NOT need to create a second DHCP server on the same interface.

MTCNA Course Manual - DHCP Configuration:

"It is possible to expand the address-pool dynamically without adding additional DHCP servers. Just add more IPs to the pool." Rene Meneses Study Guide - DHCP Pools Section:

"You can edit the address pool associated with the DHCP server anytime to include more addresses. No need to create another server." Terry Combs Notes - DHCP Tips:

"Keep one DHCP server per subnet. Extend pools via IP > Pool if more IPs are needed."

NEW QUESTION: 45

PPPoE server only works within one Ethernet broadcast domain that it is connected to. If there is a router between server and end-user host, it will not be able to create PPPoE tunnel to that PPPoE server.

A. False

B. True

Answer: (SHOW ANSWER)

PPPoE (Point-to-Point Protocol over Ethernet) relies on Ethernet broadcast and discovery mechanisms. It uses a discovery stage (PPPoE Active Discovery Initiation - PADI) which is sent as a broadcast. Therefore, PPPoE only works within the same Layer 2 broadcast domain.

If a router (Layer 3 device) exists between the client and PPPoE server, it breaks the Layer 2 broadcast domain, making it impossible for the client to reach the server.

* A.#False - Routers break the broadcast domain; PPPoE will fail.

* B.#True - PPPoE requires L2 adjacency.

Extract from Official MTCNA Course Material - PPPoE Concepts:

"PPPoE operates only over Ethernet broadcast domains. If routed, PADI packets will not reach the PPPoE server." Extract from Rene Meneses MTCNA Study Guide - PPPoE:

"PPPoE discovery is broadcast-based and does not traverse routers."

Extract from MikroTik Wiki - PPPoE Limitations:

"PPPoE cannot function over routed networks. Server and client must be in the same broadcast domain."

NEW QUESTION: 46

What can be used as 'target-address' in the simple queue?

A. client's MAC address

B. server's address

C. address list name

D. client's address

Answer: D (LEAVE A REPLY)

In MikroTik's Simple Queues, the target-address field is used to define the IP address of the device (host) to which the queue will apply. This must be an IP address - not a MAC address or an address list name.

Let's evaluate:

* A.#MAC address is not supported as target-address in simple queues

* B.#"server's address" is vague; if it means an IP, then it could work, but the best answer is "client's address"

* C.#Address lists can be used in firewall and mangle rules, but not directly in simple queues

* D.#Correct - An individual IP address (like 192.168.1.100) can be assigned as the target-address MTCNA Course Manual - Simple Queue Structure:

"Use the target-address field to apply a queue to a specific host by IP." Rene Meneses Guide - Queue Setup:

"Only IP addresses can be used as targets in simple queues. Address lists are not accepted."

Terry Combs Notes - Bandwidth Limiting:

"Target-address = device IP. MACs and lists are not allowed here."

Valid MTCNA Dumps shared by ExamDiscuss.com for Helping Passing MTCNA Exam!

ExamDiscuss.com now offer the **newest MTCNA exam dumps**, the ExamDiscuss.com

MTCNA exam **questions have been updated** and **answers have been corrected** get the

newest ExamDiscuss.com MTCNA dumps with Test Engine here:

<https://www.examdiscuss.com/MikroTik/exam/MTCNA/premium/> (205 Q&As Dumps, **35%OFF**

Special Discount Code: freecram)

NEW QUESTION: 47

[RouterOS Introduction - Protocols and Transport Layers] Which of the following services use TCP?

- * DHCP
- * SMTP
- * HTTP
- * TFTP
- * FTP

A. 1 and 2

B. 2, 3 and 5

C. 1, 2 and 4

D. 1, 3 and 4

Answer: (SHOW ANSWER)

Services that use TCP:

- * SMTP (Simple Mail Transfer Protocol) - TCP port 25
- * HTTP (Hypertext Transfer Protocol) - TCP port 80
- * FTP (File Transfer Protocol) - TCP ports 20 and 21

Services that use UDP:

- * DHCP - UDP ports 67 (server), 68 (client)
- * TFTP (Trivial File Transfer Protocol) - UDP port 69

MTCNA Course Material - Protocol Port Assignments:

"TCP-based services include FTP, HTTP, and SMTP. UDP-based services include TFTP, DHCP." Rene Meneses MTCNA Study Guide - Port Numbers and Transport Protocols:

"SMTP = TCP 25, HTTP = TCP 80, FTP = TCP 20/21. DHCP = UDP, TFTP = UDP." So, the correct TCP services are: 2 (SMTP), 3 (HTTP), and 5 (FTP).

NEW QUESTION: 48

When sending out an ARP request, an IP host is expecting what kind of address for an answer?

- A. VLAN ID
- B. IP address
- C. MAC Address
- D. 802.11g

Answer: ([SHOW ANSWER](#))

The Address Resolution Protocol (ARP) is used to resolve an IP address into a MAC address. When a device sends an ARP request asking "Who has IP X.X.X.X?", it expects a MAC address in response.

- * A.#VLAN ID - Not involved in ARP
- * B.#IP address - The IP is already known; MAC is being queried
- * C.#MAC Address - The required Layer 2 address is returned
- * D.#802.11g - Wireless standard, irrelevant to ARP

Extract from MTCNA Course Material - ARP Basics:

"ARP maps IP addresses to MAC addresses. The reply to an ARP request contains the MAC address of the queried IP." Extract from Rene Meneses Study Guide - Layer 2/3 Functions:

"ARP is a Layer 2 protocol that returns a MAC address for a known IP."

NEW QUESTION: 49

How long is level 1 (free) license valid?

- A. 1 month
- B. 24 hours
- C. 1 year
- D. Infinite time

Answer: ([SHOW ANSWER](#))

Level 1 license in MikroTik RouterOS is a free license type. It is included with every installation but has very limited functionality. Despite the limitations, it is valid for an unlimited duration.

Features available in level 1:

- * Basic configuration
- * One active user session
- * Ideal for lab/testing with CHR

Incorrect options:

- * A. 1 month ##Not time-based
- * B. 24 hours ##No expiration limit
- * C. 1 year ##Invalid
- * D.#Correct # Valid forever, but feature-limited

MTCNA Course Material - Licensing Section:

"Level 1 license is free and does not expire. It provides minimal feature access." Rene Meneses Study Guide - License Levels:

"Level 1 is permanent but restrictive. Great for evaluation or learning." Terry Combs Notes - RouterOS Licensing Table:

"Level 1 license = lifetime access to basic RouterOS functionality."

NEW QUESTION: 50

You have 10 users plugged into a hub running 10 Mbps half-duplex. There is a server connected to the switch running 10 Mbps half-duplex as well. How much bandwidth does each host have to the server?

- A. 100 kbps
- B. 1 Mbps
- C. 2 Mbps
- D. 10 Mbps

Answer: (SHOW ANSWER)

When using a hub, all connected devices share the total bandwidth. Since it's a 10 Mbps half-duplex hub, all

10 users share the same collision domain and 10 Mbps. However, when calculating potential access to the server from any single host, each host can use the full 10 Mbps - as long as no other users are transmitting simultaneously.

More importantly, the connection to the server is also 10 Mbps half-duplex, so regardless of the internal collisions, each client could use the full 10 Mbps to the server - just not concurrently with others.

Cisco CCNA Curriculum - Hubs and Bandwidth Sharing:

"In a hub, all ports share bandwidth. However, each host is capable of utilizing the full bandwidth if no contention exists." Rene Meneses MTCNA Study Guide - Hub Limitations:

"A hub provides shared bandwidth, but each device can use the full rate momentarily, assuming no collisions." Hence, the correct answer is based on potential - not divided bandwidth.

NEW QUESTION: 51

The highest queue priority is:

- A. 1
- B. 256
- C. 16
- D. 8

Answer: (SHOW ANSWER)

MikroTik RouterOS supports prioritizing traffic in queues using a numerical priority system. The queue priority values range from 1 to 8, where:

- * 1 = Highest priority (most preferred)
- * 8 = Lowest priority (least preferred)

This means that traffic marked with priority 1 is processed before traffic with lower priorities.

Priorities are used within simple queues, queue trees, and in some packet marking strategies.

Evaluation:

- * A. 1 ##Correct. This is the highest priority.
- * B. 256 ##Invalid priority value in MikroTik queues.
- * C. 16 ##Priority range is only 1 to 8.
- * D. 8 ##Lowest priority.

MTCNA Course Slides - QoS and Queuing:

"Queue priority values range from 1 to 8. Lower values indicate higher priority." Rene Meneses

Study Guide - Traffic Management Section:

"MikroTik queues use priority values from 1 (highest) to 8 (lowest)."

Terry Combs Notes - QoS and Prioritization:

"Set queue priority to 1 for critical traffic like VoIP or routing protocols."

NEW QUESTION: 52

What does the passive command provide to dynamic routing protocols?

A. Stops an interface from sending or receiving periodic dynamic updates.

B. Stops an interface from sending periodic dynamic updates but not from receiving updates.

C. Stops the router from receiving any dynamic updates.

D. Stops the router from sending any dynamic updates.

Answer: ([SHOW ANSWER](#))

In dynamic routing (e.g., RIP, OSPF, EIGRP), the passive-interface command stops routing advertisements (outgoing updates) from being sent through the specified interface.

However, the router still listens for incoming routing updates.

Cisco IOS Configuration Guide - Passive Interface:

"The passive-interface command prevents routing updates from being sent on an interface, while still allowing updates to be received." Rene Meneses MTCNA Guide - Passive Mode:

"It suppresses sending routing advertisements but does not block receiving updates on that interface." Other options:

* A: Incorrect - it does not block receiving

* C: Incorrect - it applies to interfaces, not globally

* D: Also incorrect - it does not block all updates

Final answer: B

#####

NEW QUESTION: 53

Which router command allows you to view the entire contents of all access lists?

A. show all access-lists

B. show access-lists

C. show ip interface

D. show interface

Answer: ([SHOW ANSWER](#))

The show access-lists command in Cisco IOS is used to display all configured access control entries (ACEs) in every access list, both named and numbered. This command shows the complete content, including rules and hit counters.

Cisco IOS Command Reference - Access List Monitoring:

"Use show access-lists to view the complete list of all access control entries. This includes both standard and extended lists." Other options:

- * A: Invalid command syntax
- * C: show ip interface shows interface-level IP settings and ACL applications, but not full ACL content
- * D: show interface shows status and statistics, not ACL rules

NEW QUESTION: 54

In which order are the entries in Access List and Connect List processed?

- A. By Signal Strength Range
- B. By interface name
- C. In sequence order
- D. In a random order

Answer: (SHOW ANSWER)

MikroTik processes the entries in the Access List and Connect List in a top-down fashion - meaning that the first matching entry is the one applied. This is known as sequence order (from top to bottom).

Each rule is checked in the order it appears in the list, and once a match is found, the rest of the list is ignored for that client.

Incorrect options:

- * A. Signal strength is only a condition, not a sorting method
- * B. Interface names are part of rule conditions
- * D. Not random - rules are processed sequentially

MTCNA Official Training Manual - Wireless Access & Connect List:

"Rules in access-list and connect-list are checked in the order they are listed. Once a match is found, further rules are ignored." Rene Meneses Guide - Wireless Access Rules:

"Access-list is evaluated top-down. Sequence matters."

Terry Combs MTCNA Notes - Wireless Filtering:

"Be careful with order. The first matching rule is applied - no exceptions."

NEW QUESTION: 55

Mark the queue types that are available in RouterOS

- A. SFQ - Stochastic Fairness Queuing
- B. DRR - Deficit Round Robin
- C. FIFO - First In First Out (for Bytes or for Packets)
- D. LIFO - Last In First Out
- E. PCQ - Per Connection Queuing
- F. RED - Random Early Detect (or Drop)

Answer: (SHOW ANSWER)

MikroTik RouterOS offers several queuing types under /queue type. These queuing algorithms manage how packets are buffered and sent, affecting fairness, delay, and throughput.

Available queue types in RouterOS:

- * SFQ (Stochastic Fairness Queuing)#

- * FIFO (First In First Out - for bytes or packets)#
- * PCQ (Per Connection Queuing)#
- * RED (Random Early Detection/Drop)#

Unavailable queue types:

- * DRR#- Not supported by RouterOS
- * LIFO#- Not supported; not suitable for networking queues

Extract from Official MTCNA Course Material - Queue Types:

"RouterOS supports PCQ, SFQ, RED, FIFO, and more. DRR and LIFO are not implemented."

Extract from Rene Meneses MTCNA Study Guide - Traffic Management:

"Only PCQ, FIFO, SFQ, RED are listed under /queue type. DRR and LIFO do not appear in the supported list." Extract from MikroTik Wiki - Queue Types:

"Supported types include FIFO, PCQ, RED, and SFQ. Each has specific use cases for latency or fairness."

NEW QUESTION: 56

In RouterOS queue configurations the word "total" usually represents:

- A. download - upload
- B. upload
- C. upload + download
- D. download

Answer: (SHOW ANSWER)

In Simple Queues, MikroTik uses the term "total" to refer to the sum of the incoming and outgoing traffic for a particular target. This includes both upload (TX) and download (RX) traffic.

MTCNA Course Material - Queues Overview:

"Total limit represents the combined limit of upload and download traffic. If both target-upload and target-download are defined, total-limit should be equal or higher." Rene Meneses MTCNA Study Guide - Queues Chapter:

"In Simple Queues, 'max-limit' and 'limit-at' can be set individually for upload and download, or together as

'total' which combines both directions."

Terry Combs Notes - Queue Definitions:

"Total in RouterOS queues means sum of upload and download. Always consider total bandwidth used in both directions when using 'total-limit'." Therefore, the correct and verified answer is C: upload + download.

NEW QUESTION: 57

The correct order for PPPoE discovery stage is:

- A. Initialization, Session confirmation, Request and Offer
- B. Initialization, Offer, Request and Session confirmation
- C. Request, Initialization, Session confirmation and Offer
- D. Request, Offer, Initialization and Session confirmation

Answer: (SHOW ANSWER)

PPPoE (Point-to-Point Protocol over Ethernet) uses a discovery stage before establishing the actual PPP session. The correct sequence is:

- * Initialization # Client sends a PADI (PPPoE Active Discovery Initiation)
- * Offer # Server responds with PADO (PPPoE Active Discovery Offer)
- * Request # Client sends PADR (PPPoE Active Discovery Request)
- * Session Confirmation # Server sends PADS (PPPoE Active Discovery Session-confirmation)
- * A.#Wrong sequence
- * B.#Correct - Matches the technical flow: PADI # PADO # PADR # PADS
- * C.#Incorrect order
- * D.#Incorrect order

Extract from MTCNA Course Material - PPPoE Process:

"The PPPoE discovery stage includes PADI, PADO, PADR, and PADS messages. This translates to Initialization, Offer, Request, Session confirmation." Extract from MikroTik Wiki - PPPoE Protocol:

"The discovery stage is used to establish a PPPoE session and includes four steps: PADI, PADO, PADR, and PADS."

NEW QUESTION: 58

For static routing functionality, additionally to the RouterOS 'system' package, you will also need the following software package:

- A. no extra package required**
- B. advanced-tools
- C. routing
- D. dhcp

Answer: (SHOW ANSWER)

Static routing is a core feature of MikroTik RouterOS and is included in the default 'system' package. You do not need to install any additional packages (like the "routing" package) for simple static routing.

The routing package is only needed for advanced dynamic routing protocols like BGP, OSPF, and RIP. For manually configured static routes, the system package alone is sufficient.

Let's evaluate:

- * A.#Correct. Static routing is part of the default system.
- * B.#advanced-tools are for diagnostics and tools like traceroute, bandwidth-test, etc.
- * C.#routing package is for dynamic protocols (OSPF, BGP, etc.), not static routes
- * D.#dhcp is unrelated to routing - used for dynamic host IP assignment MTCNA Course Manual - Routing Fundamentals:

"Static routing requires no additional package - it is included in the base system." Rene Meneses Guide - Routing Overview:

"For static routes, you do not need the 'routing' package. That's only for protocols like BGP or OSPF." Terry Combs Notes - Routing Concepts:

"No extra packages needed for static routes. Just use /ip route."

NEW QUESTION: 59

Which of the following is the valid host range for the subnet on which the IP address

192.168.168.188

255.255.255.192 resides?

A. 192.168.168.129-190

B. 192.168.168.129-191

C. 192.168.168.128-190

D. 192.168.168.128-192

Answer: ([SHOW ANSWER](#))

IP address: 192.168.168.188

Subnet mask: 255.255.255.192 # /26 # Block size = 64

Subnets:

* 192.168.168.0/26 # 192.168.168.0 - 63

* 192.168.168.64/26 # 192.168.168.64 - 127

* 192.168.168.128/26 # 192.168.168.128 - 191 # Contains 192.168.168.188

* 192.168.168.192/26 # 192.168.168.192 - 255

Valid host range = 192.168.168.129 - 190

(Broadcast = 191, Network address = 128)

MTCNA Course Material - Subnetting Practice:

"To find valid hosts, exclude the subnet and broadcast address. In /26, each block is 64 addresses." Rene Meneses MTCNA Study Guide - IP Addressing:

"For /26 subnetting, calculate block size as $2^{(32-26)} = 64$. Subnet starts at multiples of 64."

NEW QUESTION: 60

What flavor of Network Address Translation can be used to have one IP address allow many users to connect to the global Internet?

A. NAT

B. Static

C. Dynamic

D. PAT

Answer: ([SHOW ANSWER](#))

PAT (Port Address Translation) is a subtype of NAT that maps multiple private IP addresses to a single public IP address using different port numbers. It is the most common form of NAT used in home and business networks to allow multiple internal hosts to access the internet using one public IP address.

MTCNA Course Material - NAT Concepts:

"PAT (also known as NAT overload) allows multiple devices to share a single public IP address. It uses different port numbers to distinguish sessions." Cisco IOS NAT Configuration Guide:

"PAT translates multiple local IP addresses to one public IP address by assigning different port numbers to each session." Other options:

- * A: Generic term - not specific enough
- * B: Static NAT maps one private IP to one public IP
- * C: Dynamic NAT maps private IPs to a pool of public IPs, not one-to-many Final answer: D

NEW QUESTION: 61

Action=redirect is applied in:

- A. chain=srcnat
- B. chain=forward
- C. chain=dstnat

Answer: ([SHOW ANSWER](#))

The redirect action is only valid in the dstnat chain. It is used to redirect traffic to a service running on the router itself (e.g., redirecting HTTP to a local proxy server).

- * A.#srcnat - Not compatible with redirect
- * B.#forward - Redirect doesn't apply in this chain
- * C.#dstnat - This is the correct and only supported chain for action=redirect Extract from Official MTCNA Course Material - NAT Actions:

"The redirect action is used within the dstnat chain to forward packets to the router's local services." Extract from MikroTik Wiki - NAT Rule Actions:

"Redirect is used in dstnat chain and changes destination address to a local router IP and port."

Valid MTCNA Dumps shared by ExamDiscuss.com for Helping Passing MTCNA Exam!

ExamDiscuss.com now offer the **newest MTCNA exam dumps**, the ExamDiscuss.com MTCNA exam **questions have been updated** and **answers have been corrected** get the **newest** ExamDiscuss.com MTCNA dumps with Test Engine here:

<https://www.examdiscuss.com/MikroTik/exam/MTCNA/premium/> (205 Q&As Dumps, **35%OFF**

Special Discount Code: **freecram**)

NEW QUESTION: 62

If you need to make sure that one computer in your Hot-Spot network can access the Internet without Hot-Spot authentication, which menu allows you to do this?

- A. Users
- B. IP bindings
- C. Walled-garden
- D. Walled-garden IP

Answer: ([SHOW ANSWER](#))

In a MikroTik Hotspot environment, you can bypass authentication for specific users using the IP Bindings feature. This feature lets you mark a host as bypassed (authorized without login), blocked, or regular.

- * A. Users # Incorrect. This contains login credentials for regular authenticated users.
- * B. IP bindings # Correct. This allows specific devices (by IP or MAC) to bypass login requirements.
- * C. Walled-garden # Incorrect. This allows unauthenticated access to specific domains or URLs, not devices.
- * D. Walled-garden IP # Incorrect. Similar to option C, it controls destination IP access, not client exemption.

Extract from Official MTCNA Course Material - Hotspot:

"To allow a specific host to bypass authentication, use IP Bindings with the 'bypassed' type."

Extract from Rene Meneses MTCNA Study Guide - Hotspot Section:

"The IP Bindings tab in the Hotspot menu is used to set specific IPs or MACs as bypassed. This exempts them from login." Extract from Terry Combs MTCNA Notes - Hotspot Bypass:

"Use IP Bindings for fixed clients (e.g., printers or servers) that should not be challenged by the Hotspot portal."

NEW QUESTION: 63

Which protocol does DHCP use at the Transport layer?

- A. IP
- B. TCP
- C. UDP**
- D. ARP

Answer: (SHOW ANSWER)

DHCP (Dynamic Host Configuration Protocol) operates over UDP:

- * Client uses UDP port 68
- * Server uses UDP port 67

It is a connectionless protocol, and because clients typically do not yet have IP addresses, UDP is used due to its simplicity.

MTCNA Course Material - DHCP Protocol Layering:

"DHCP uses UDP for communication between clients and servers. TCP is not used due to the stateless, broadcast nature of DHCP discovery." Rene Meneses MTCNA Study Guide - Port Assignments:

"UDP 67/68 are used by DHCP. TCP is not used because clients lack IPs initially." Other options:

- * A: IP is the network layer, not transport
- * B: TCP is used by reliable services (FTP, HTTP)
- * D: ARP resolves IP-to-MAC; unrelated to DHCP transport

NEW QUESTION: 64

What is a stub network?

- A. A network with more than one exit point.
- B. A network with more than one exit and entry point.
- C. A network with only one entry and no exit point.
- D. A network that has only one entry and exit point.

Answer: ([SHOW ANSWER](#))

A stub network is defined as a network segment that is accessible by only one path (single entry/exit point). It does not serve as a transit network for routing between other networks. Traffic entering or leaving the stub network must pass through a single interface.

MTCNA Course Material - Routing Concepts:

"A stub network is one that is connected to the rest of the network by a single router interface. It has only one entry and one exit point." Rene Meneses MTCNA Study Guide - Routing Terms: "Stub networks do not forward packets for other networks. They are endpoints with one route in and out." Other options:

- * A/B: Describe transit networks, not stub
- * C: Misleading-stub has both entry and exit, but only through one path
- * D: #Correct definition

NEW QUESTION: 65

What command will display the line, protocol, DLCI, and LMI information of an interface?

- A. sh pvc
- B. show interface
- C. show frame-relay pvc
- D. show run

Answer: ([SHOW ANSWER](#))

In Cisco IOS, to display detailed Frame Relay virtual circuit information, including the line status, protocol status, DLCI (Data Link Connection Identifier), and LMI (Local Management Interface) details, the correct command is:

show frame-relay pvc

Cisco IOS Command Reference - Frame Relay:

"The show frame-relay pvc command displays information about PVC status, including DLCI numbers and LMI statistics." Breakdown:

- * A: sh pvc - shorthand and ambiguous, may not be recognized
- * B: show interface - general interface stats but lacks detailed LMI/DLCI info
- * C: show frame-relay pvc - #correct, provides detailed DLCI/LMI info
- * D: show run - shows current configuration, not real-time PVC status

NEW QUESTION: 66

Action=redirect can be used in NAT chain src-nat

- A. true
- B. false

Answer: ([SHOW ANSWER](#))

The action=redirect is used only in the dstnat chain to redirect traffic to a local port (e.g., for transparent proxy or DNS capture). It is not valid in the srcnat chain.

* A.#Incorrect - RouterOS will not permit redirect in srcnat.

* B.#Correct - redirect is only supported in dstnat.

Extract from Official MTCNA Course Material - NAT Actions:

"Redirect is used in the dstnat chain to force traffic to a specific port on the local router." Extract from MikroTik Wiki - NAT Action Reference:

"Action=redirect is only meaningful in dstnat and is used to redirect traffic to router-local services."

Extract from Rene Meneses Study Guide - NAT Table:

"Redirect cannot be used in srcnat. Only valid in dstnat for local service interception."

NEW QUESTION: 67

DHCP server is configured on a router's ether1 interface. IP address 192.168.0.100/24 is assigned to the interface. Possible IP pools, that can be used by this DHCP server, are:

A. 192.168.0.1-192.168.0.255

B. 192.169.0.1-192.169.0.254

C. 192.168.0.1-192.168.0.99, 192.168.0.101-192.168.0.254

D. 192.168.0.1-192.168.0.14

Answer: ([SHOW ANSWER](#))

The router's interface IP is 192.168.0.100/24 # which belongs to the subnet 192.168.0.0-192.168.0.255.

However, 192.168.0.100 is already assigned to the router. So, this IP must be excluded from the DHCP pool to avoid conflicts.

* C offers two valid ranges excluding .100:# 192.168.0.1-192.168.0.99#

192.168.0.101-192.168.0.254 Let's evaluate other options:

* A. 192.168.0.1-192.168.0.255 ##Includes broadcast (.255) and router IP (.100) # Invalid

* B. 192.169.0.1-192.169.0.254 ##Completely wrong subnet

* D. 192.168.0.1-192.168.0.14 ##Valid but unnecessarily small

MTCNA DHCP Chapter - Address Pools:

"Make sure the pool does not include the router's IP or the network's broadcast address.

Common errors involve overlapping pools." Rene Meneses MTCNA Guide - DHCP Configuration:

"Exclude the router's own IP from the range. Use address pools below and above the assigned IP." Terry Combs Notes - DHCP Pool Tips:

"Split the pool to avoid assigning the interface IP to clients. Also avoid .0 and .255."

NEW QUESTION: 68

For a Simple Queue to apply bandwidth restrictions on a bridged interface, the following must be done:

A. Configure an IP address on the bridge interface

B. Use mangle to mark the connections

C. Associate the Simple Queue to the bridge interface

D. Enable 'Use IP Firewall' in bridge settings

Answer: (SHOW ANSWER)

By default, RouterOS does not pass traffic on a bridge interface through the firewall or queue system. If you want to apply queueing (Simple Queues or other policies) on a bridge interface, you must enable the bridge to use the IP Firewall.

MTCNA Official Course Material - Bridging & IP Firewall Integration:

"If you want to apply queues or firewall rules to traffic flowing through a bridge, you must enable 'use-ip- firewall' under the bridge settings." Rene Meneses MTCNA Guide - Bridge Queueing Section:

"Simple Queues do not affect bridged traffic unless you activate the 'Use IP Firewall' setting in bridge configuration. This pushes the packets through the normal firewall and queueing engine."

MikroTik Wiki - Bridge Settings:

"If use-ip-firewall is enabled, then all bridged traffic is also processed by firewall and queues."

Options A and C are incorrect because assigning an IP or linking the queue alone does not enforce restrictions at Layer 2.

Option B refers to advanced queueing with mangle + Queue Trees, not Simple Queues.

NEW QUESTION: 69

Which of the following describe the DHCP Discover message?

- * It uses FF:FF:FF:FF:FF:FF as a layer 2 broadcast.
- * It uses UDP as the Transport layer protocol.
- * It uses TCP as the Transport layer protocol.
- * It does not use a layer 2 destination address.

A. 1 only

B. 1 and 2

C. 3 and 4

D. 4 only

Answer: (SHOW ANSWER)

When a client sends a DHCP Discover message:

- * It does not yet have an IP address, so it sends a Layer 2 broadcast (FF:FF:FF:FF:FF:FF).
- * DHCP uses UDP, not TCP.
- * Specifically, it uses UDP port 67 (server) and 68 (client).
- * Layer 2 destination is broadcast - it certainly does use a Layer 2 address.

MTCNA Course Material - DHCP Process:

"The client broadcasts a DHCP Discover message to FF:FF:FF:FF:FF:FF using UDP ports 67 and 68." Rene Meneses MTCNA Study Guide - DHCP Message Types:

"DHCP uses UDP. Discovery messages are Layer 2 broadcasts to locate a DHCP server."

MikroTik Wiki - DHCP Protocol Behavior:

"The Discover message uses UDP and broadcast MAC addressing."

Statements:

- * 1: True (Layer 2 broadcast)

- * 2: True (Uses UDP)
- * 3: False (TCP not used)
- * 4: False (Layer 2 destination address is broadcast)

#####

NEW QUESTION: 70

How many IP addresses can one find in the header of an IP packet?

- A. 4
- B. 2**
- C. 3
- D. 1

Answer: ([SHOW ANSWER](#))

An IP packet contains two critical IP addresses in its header:

- * Source IP address - the IP of the sending host
- * Destination IP address - the IP of the receiving host

These addresses allow routers to forward the packet from source to destination over Layer 3 (Network Layer).

Other values in the IP header include TTL, protocol type, and checksum - but not additional IP addresses.

- * A. 4 ##Incorrect. Only 2 IPs are included
- * B. 2 ##Correct: Source and Destination
- * C. 3 ##Some protocols like NAT may temporarily associate more addresses, but not in header
- * D. 1 ##Incomplete

MTCNA Course Manual - IP Packet Structure:

"An IP packet always contains a source and destination IP address in the Layer 3 header. This allows routing to function across networks." Rene Meneses Guide - Packet Flow:

"IP headers are designed to carry the minimal information necessary for routing. That includes the source and destination IPs." Terry Combs Notes - Header Fields:

"Two IPs: one for sender, one for receiver. That's all you'll find in the IP header."

NEW QUESTION: 71

How many layers does the Open Systems Interconnection model have?

- A. 6
- B. 9
- C. 5
- D. 7**
- E. 12

Answer: ([SHOW ANSWER](#))

The OSI (Open Systems Interconnection) model is a conceptual framework that standardizes the functions of a communication system into seven distinct layers. It is used to understand and design computer networking systems.

The seven layers of the OSI model are:

- * Application
- * Presentation
- * Session
- * Transport
- * Network
- * Data Link
- * Physical

Each layer has its own specific purpose and interacts with adjacent layers to perform data transmission functions.

MTCNA Official Course Material - OSI Model Chapter:

"The OSI model consists of 7 layers. Understanding these layers is critical for troubleshooting and protocol analysis." Rene Meneses MTCNA Study Guide - OSI Model Section:

"There are exactly seven OSI layers. They range from the Physical Layer (Layer 1) to the Application Layer (Layer 7)." Terry Combs Notes - OSI Summary Page:

"OSI = 7 Layers. The most important ones for network engineers are Layer 1 through Layer 4."

NEW QUESTION: 72

What is the default TTL (time to live) on a router that an IP packet can experience before it will be discarded?

- A. 60
- B. 30
- C. 1
- D. 64**

Answer: (SHOW ANSWER)

TTL (Time to Live) is a field in the IP header that limits the number of hops a packet can travel. Each router that processes the packet decrements the TTL by 1. When TTL reaches 0, the packet is dropped.

Default TTL values vary by operating system, but in RouterOS and many Linux-based systems, the default TTL is 64.

- * A. 60 # Incorrect, used in some systems but not the MikroTik default
- * B. 30 # Incorrect
- * C. 1 # Incorrect; would allow only one hop
- * D. 64 ##Correct

Extract from Official MTCNA Course Material - TTL Field Explanation:

"The default TTL in RouterOS and most Unix-like systems is 64. Each router decrements this by 1 until the packet is discarded." Extract from Rene Meneses Study Guide - IP Protocol Details:

"TTL is initialized to 64 by default in MikroTik RouterOS."

Extract from MikroTik Wiki - IP Protocol Section:

"RouterOS sets default TTL of 64 unless manually configured otherwise."

NEW QUESTION: 73

Which Layer 4 protocol is used for a Telnet connection?

- A. IP
- B. TCP**
- C. TCP/IP
- D. UDP

Answer: ([SHOW ANSWER](#))

Telnet is a protocol used to access remote devices via command-line over the network. It operates over TCP at Layer 4, using port 23.

MTCNA Course Material - Layer 4 Protocols:

"Telnet uses TCP port 23 for remote shell access. TCP ensures ordered and reliable delivery of commands and responses." Rene Meneses MTCNA Study Guide - TCP/IP Protocols:

"Telnet is an Application Layer protocol using TCP as its transport protocol." MikroTik Wiki - Telnet Access:

"Telnet communicates over TCP. It does not use UDP."

Other options:

- * A. IP is a Layer 3 protocol
- * C. TCP/IP is a model, not a single protocol
- * D. Telnet does not use UDP

NEW QUESTION: 74

Which firewall chain should you use to filter clients' HTTP traffic going through the router?

- A. prerouting
- B. forward**
- C. output
- D. input

Answer: ([SHOW ANSWER](#))

When a router forwards traffic between two interfaces (such as from LAN to WAN), it uses the forward chain. HTTP traffic initiated by users destined to external servers passes through this chain.

- * A.#prerouting - Used mainly for routing decisions and NAT, not filtering.
- * B.#forward - Used to filter transit traffic.
- * C.#output - For traffic originating from the router itself.
- * D.#input - For traffic destined to the router itself.

Extract from MTCNA Course Material - Firewall Chains:

"Client-to-server traffic, like browsing the web, passes through the forward chain when routed through the router." Extract from Rene Meneses Study Guide - Firewall Structure:

"To block or allow traffic passing through the router (LAN to Internet), use the forward chain."

Extract from MikroTik Wiki - Firewall Filtering Overview:

"forward: filters all transit traffic routed through the router."

NEW QUESTION: 75

Can you manually add drivers to RouterOS in case your PCI Ethernet card is not recognized, and you suspect it is a driver issue?

A. Yes

B. No

Answer: (SHOW ANSWER)

RouterOS is a closed, embedded Linux-based system. It does not support adding custom drivers or compiling modules manually. You must use supported hardware that is natively compatible with RouterOS.

MTCNA Course Material - RouterBOARD Compatibility:

"RouterOS supports a fixed set of drivers. You cannot install third-party drivers or modules." Rene Meneses MTCNA Guide - Hardware Limitations:

"Custom drivers cannot be added to RouterOS. Use only supported network interface cards as listed by MikroTik." MikroTik Wiki - Hardware Support:

"RouterOS does not allow manual driver installation. All drivers are precompiled and built into the system image." Therefore, if your PCI Ethernet card is not recognized, you must replace it with a compatible model - you cannot add a driver manually.

NEW QUESTION: 76

What layer in the TCP/IP stack is equivalent to the Transport layer of the OSI model?

A. Application

B. Host-to-Host

C. Internet

D. Network Access

Answer: (SHOW ANSWER)

In the TCP/IP model (also known as the DoD model), the Host-to-Host layer is responsible for reliable end-to-end communication, which aligns directly with the Transport Layer (Layer 4) of the OSI model. This layer is where TCP and UDP protocols reside.

MTCNA Course Material - Protocol Layers Mapping:

"The Host-to-Host layer in TCP/IP model corresponds to the Transport layer in OSI. It handles reliable delivery through TCP and connectionless communication via UDP." Rene Meneses MTCNA Study Guide - TCP/IP vs OSI:

"Host-to-Host layer = OSI Layer 4. Protocols: TCP, UDP."

Other layers:

* Application # OSI Layers 5-7

* Internet # OSI Layer 3

* Network Access # OSI Layers 1-2

Valid MTCNA Dumps shared by ExamDiscuss.com for Helping Passing MTCNA Exam! ExamDiscuss.com now offer the **newest MTCNA exam dumps**, the ExamDiscuss.com MTCNA exam **questions have been updated** and **answers have been corrected** get the **newest** ExamDiscuss.com MTCNA dumps with Test Engine here:
<https://www.examdiscuss.com/MikroTik/exam/MTCNA/premium/> (205 Q&As Dumps, **35%OFF**
Special Discount Code: freecram)

NEW QUESTION: 77

Which features are removed when the advanced-tools package is uninstalled?

- A. neighbors
- B. LCD support
- C. ip-scan
- D. ping
- E. netwatch
- F. bandwidth-test

Answer: (SHOW ANSWER)

The advanced-tools package in MikroTik RouterOS contains a set of diagnostic and monitoring tools. If this package is removed, the following features are lost:

- * ip-scan ##Used for scanning IP ranges to discover hosts
- * netwatch ##Monitors host availability and runs scripts on status changes
- * bandwidth-test ##Used to measure throughput between MikroTik devices

Incorrect options:

- * A. neighbors # Part of the main system package (MAC discovery)
- * B. LCD support # Tied to specific hardware; not affected by advanced-tools
- * D. ping # Part of the base system package

MTCNA System Tools Section - Package Breakdown:

"The advanced-tools package includes netwatch, bandwidth-test, and ip-scan. These are not part of the base system." Rene Meneses Guide - Package Management:

"Removing advanced-tools disables several diagnostic commands like ip-scan and bandwidth-test." Terry Combs Notes - Tools Overview:

"Ping and neighbors are in core OS. Advanced-tools affects monitoring scripts and traffic tools."

NEW QUESTION: 78

[Networking Fundamentals - VLAN Trunking] What protocols are used to configure trunking on a switch?

- * VLAN Trunking Protocol
- * VLAN
- * 802.1Q
- * ISL

A. 1 and 2

B. 3 and 4

C. 1 only

D. 2 only

Answer: (SHOW ANSWER)

The two actual trunking protocols used to carry VLAN-tagged frames across switch links are:

- * IEEE 802.1Q - Industry-standard trunking protocol

- * ISL (Inter-Switch Link) - Cisco proprietary trunking protocol

VLANs themselves define broadcast domains but are not a trunking protocol. VLAN Trunking Protocol (VTP) is used to distribute VLAN configuration but not to trunk data.

MTCNA Course Material - VLAN and Trunking Overview:

"802.1Q is the standard VLAN trunking protocol. ISL is a Cisco-specific protocol. VTP is used for VLAN propagation, not actual trunking." Rene Meneses MTCNA Study Guide - VLAN

Technologies:

"802.1Q and ISL are trunking methods. VTP helps with VLAN configuration but is not a trunking protocol." Correct trunking protocols: 802.1Q and ISL Final

NEW QUESTION: 79

Which of the following is the decimal and hexadecimal equivalents of the binary number 10011101?

A. 155, 0x9B

B. 157, 0x9D

C. 159, 0x9F

D. 185, 0xB9

Answer: (SHOW ANSWER)

Binary to Decimal:

10011101

$$= 1 \times 2^7 + 0 \times 2^6 + 0 \times 2^5 + 1 \times 2^4 + 1 \times 2^3 + 1 \times 2^2 + 0 \times 2^1 + 1 \times 2^0$$

$$= 128 + 0 + 0 + 16 + 8 + 4 + 0 + 1$$

$$= 157$$

Decimal to Hexadecimal:

$$157 \div 16 = 9 \text{ remainder } 13 \# 13 = D$$

$$\text{So, } 157 = 0x9D$$

MTCNA Course Material - Binary and Hex Conversion:

"Convert binary to decimal by summing powers of 2. Then convert decimal to hexadecimal by dividing by 16."

Rene Meneses MTCNA Study Guide - Number Systems:

"For binary 10011101, the decimal is 157, and hex is 9D."

Only Option B is correct: 157, 0x9D.

NEW QUESTION: 80

What is the main reason the OSI model was created?

- A. To create a layered model larger than the DoD model.
- B. So application developers can change only one layer's protocols at a time.
- C. So different networks could communicate.
- D. So Cisco could use the model.

Answer: C ([LEAVE A REPLY](#))

The OSI (Open Systems Interconnection) model was developed by the ISO (International Standards Organization) to provide a universal standard for network communications. Its primary goal is to enable interoperability between different systems and vendors by establishing a common networking framework.

MTCNA Course Material - OSI Model Purpose:

"The OSI model helps standardize networking so that different systems and networks can communicate." Rene Meneses MTCNA Study Guide - OSI Principles:

"The model was designed to guide product developers and facilitate communication between heterogeneous network systems." Other options:

- * A: The OSI was not intended to be "larger" than DoD model
- * B: Helpful benefit, but not the main reason for creation
- * D: Incorrect and vendor-specific (not factual)

NEW QUESTION: 81

What protocol does PPP use to identify the Network layer protocol?

- A. NCP
- B. ISDN
- C. HDLC
- D. LCP

Answer: ([SHOW ANSWER](#)**)**

PPP (Point-to-Point Protocol) uses a modular architecture consisting of two main components:

- * LCP (Link Control Protocol): Establishes, configures, and tests the data-link connection
- * NCP (Network Control Protocol): Identifies and configures protocols at the Network Layer (e.g., IP, IPX) NCP allows multiple protocols to be used over the same PPP link by negotiating and identifying the type of Layer 3 protocol.

MTCNA Course Material - PPP Components:

"NCP handles Layer 3 protocol negotiation and support. For example, IPCP (IP Control Protocol) is a type of NCP used for IP." Rene Meneses MTCNA Study Guide - PPP Protocol Stack:

"PPP uses NCP to identify and configure multiple Layer 3 protocols such as IP, IPX, AppleTalk."

Other options:

- * B: ISDN is a WAN access technology, not part of PPP stack
- * C: HDLC is a data-link layer protocol, not used for identifying Layer 3
- * D: LCP configures link parameters, not network layer protocols

NEW QUESTION: 82

MikroTik RouterOS is sending logs to an external syslog server. Which protocol and port is used by RouterOS for sending logs (by default)?

A. UDP 514

B. UDP 21

C. UDP 113

D. TCP 110

Answer: (SHOW ANSWER)

RouterOS uses the industry-standard syslog protocol for remote logging. By default, syslog uses UDP port

514.

MTCNA Course Material - Logging Section:

"For sending logs to a remote syslog server, RouterOS uses the syslog protocol on UDP port 514 by default." Rene Meneses MTCNA Guide - Monitoring & Logging:

"External logging is done using UDP port 514, which is the standard syslog protocol port."

MikroTik Wiki - Logging Configuration:

"To send logs to a remote server, configure an action of type remote with a remote address and use UDP port

514 unless otherwise changed."

Other ports:

* UDP 21 = FTP (not logging)

* UDP 113 = Ident protocol

* TCP 110 = POP3

Only UDP 514 is correct.

NEW QUESTION: 83

To use masquerade, you need to specify:

A. action=accept, out-interface, chain=src-nat

B. action=masquerade, out-interface, chain=src-nat

C. action=masquerade, in-interface, chain=src-nat

D. action=masquerade, out-interface, chain=dst-nat

Answer: (SHOW ANSWER)

Masquerading is a form of source NAT (src-nat) where the router dynamically replaces the source address of outgoing packets with the IP address of the router's outgoing interface. This is commonly used when internal LAN clients access the internet through a single public IP.

Key points for masquerade configuration:

* Use chain=src-nat (because it modifies the source address)

* Use action=masquerade

* Specify the out-interface (i.e., the WAN interface)

MTCNA Course Material - NAT Section:

"To configure masquerading, use chain=src-nat and action=masquerade. Specify out-interface to define the traffic direction." Rene Meneses MTCNA Study Guide - NAT Examples:

"Masquerade automatically uses the IP address of the specified out-interface. Required parameters: chain=src-nat, action=masquerade, out-interface." MikroTik Wiki - Source NAT / Masquerade:

"Masquerade is a special form of src-nat. You must use it in chain=src-nat and define the out-interface for which NAT will be applied." Option A: Incorrect action=accept (used in filter rules, not NAT) Option C: in-interface is not applicable here Option D: chain=dst-nat is used for destination NAT, not source NAT Only Option B is fully correct.

NEW QUESTION: 84

It is possible to create a configuration where VLAN and PPTP interfaces are bridged together.

A. TRUE

B. FALSE

Answer: (SHOW ANSWER)

RouterOS allows different types of interfaces, including VLANs and PPP-based interfaces (like PPTP), to be added to a bridge. This creates a Layer 2 network between them, enabling transparent communication.

* A.#TRUE - Supported and commonly used in tunneling + VLAN transport.

* B.#FALSE - Incorrect.

Extract from MTCNA Course Material - Bridging Concepts:

"Bridging can include Ethernet, VLAN, wireless, and virtual interfaces such as PPTP and EOIP."

Extract from MikroTik Wiki - Bridge Interface:

"Any Layer 2-capable interface (including VLANs, PPP tunnels, and Ethernet) can be included in a bridge." Extract from Rene Meneses Study Guide - Bridging and VLANs:

"It is possible to bridge VLAN interfaces with VPN interfaces for advanced Layer 2 tunneling scenarios."

NEW QUESTION: 85

Is it possible to limit how many clients are able to connect to an access point?

A. No it's not possible at all

B. Yes, but only with access-lists

C. Yes

Answer: C (LEAVE A REPLY)

Yes, MikroTik RouterOS allows administrators to limit the maximum number of clients that can connect to a wireless access point. This can be done through the wireless interface settings using the max-station-count parameter.

The max-station-count option defines the maximum number of client devices (stations) that may be connected simultaneously. You are not restricted to access-lists; this setting works globally per interface.

* A.#Incorrect. It is definitely possible.

* B.#Limiting via access-list is one method (e.g., per MAC), but the more general and scalable method is via max-station-count.

* C.#Correct. MikroTik provides both general limits and fine control (like access-lists or registration- table rules).

MTCNA Official Wireless Module - Access Point Configuration:

"Set the maximum number of stations using max-station-count. This is a hardware-level control on the interface." Rene Meneses Study Guide - Wireless Configuration:

"Limiting clients can be done through access-lists or via interface properties such as max-station-count." Terry Combs Notes - Wireless Station Limits:

"Use max-station-count under wireless settings. This applies a hard limit on how many clients can connect."

NEW QUESTION: 86

You cannot use OSPF and RIP routing protocols simultaneously on RouterOS.

A. FALSE

B. TRUE

Answer: (SHOW ANSWER)

MikroTik RouterOS supports running multiple dynamic routing protocols simultaneously, including RIP, OSPF, and BGP. They are independent processes and can be configured in parallel. This is commonly used in complex network environments or during routing migrations.

* A.#FALSE - You can run OSPF and RIP at the same time.

* B.#TRUE - Incorrect; both protocols are fully supported to coexist.

Extract from MTCNA Course Material - Dynamic Routing:

"RouterOS supports multiple dynamic routing protocols, including simultaneous use of RIP and OSPF." Extract from Rene Meneses Study Guide - Routing Protocols:

"You can configure both RIP and OSPF to run at the same time on a single router." Extract from MikroTik Wiki - Routing Overview:

"RouterOS allows multiple routing protocols to operate concurrently."

NEW QUESTION: 87

Which protocol does Ping use?

A. TCP

B. ARP

C. ICMP

D. BootP

Answer: (SHOW ANSWER)

Ping is a diagnostic utility used to test reachability between devices. It sends ICMP Echo Request packets and waits for ICMP Echo Replies. ICMP (Internet Control Message Protocol) is used for these types of control messages and is encapsulated within IP.

MTCNA Course Material - Diagnostic Tools:

"Ping uses ICMP Echo Requests to verify if a destination is reachable. It does not use TCP or UDP." Rene Meneses MTCNA Study Guide - Ping and ICMP:

"Ping uses ICMP, not TCP or ARP. ICMP packets are used to check basic connectivity." MikroTik Wiki - Ping Tool Description:

"Ping works by sending ICMP packets. It cannot use TCP."

Other options:

- * TCP: Used by protocols like HTTP, FTP
- * ARP: Resolves IP to MAC, not used for ping
- * BootP: DHCP-related protocol, not diagnostic

NEW QUESTION: 88

Simple Queue number 0 defines 2M for upload and download for target IP 10.10.0.33.

Simple Queue number 1 defines 4M for upload and download for the same target IP 10.10.0.33.

Client 10.10.0.33 will be able to obtain:

- A. 6M upload/download
- B. 0M upload/download
- C. 4M upload/download
- D. 2M upload/download

Answer: ([SHOW ANSWER](#))

In MikroTik RouterOS, when multiple simple queues are configured for the same target (IP address), only the first matching queue in sequence is processed. This means that:

- * If queue 0 (2M) comes before queue 1 (4M), the 2M limit will be enforced.
- * The second queue is ignored, even if it provides a higher rate.

MikroTik does not sum the bandwidth of multiple queues. The first applicable queue (based on order) wins.

MTCNA Course Manual - Simple Queues:

"Simple Queues are matched top-down. Only the first matching queue is applied per packet."

Rene Meneses MTCNA Guide - QoS Queue Behavior:

"Queue order matters. The first rule that matches is the one used. Lower queues override lower ones if placed first." Terry Combs Notes - Queue Troubleshooting:

"If two queues match the same IP, only the first is active. Don't stack queues unless using a queue tree."

NEW QUESTION: 89

Which command is used to upgrade an IOS on a Cisco router?

- A. copy tftp run
- B. copy tftp start
- C. config net
- D. copy tftp flash

Answer: ([SHOW ANSWER](#))

To upgrade or install a new Cisco IOS image on a router, you typically copy the IOS image file from a TFTP server into the router's flash memory. The correct syntax is:

copy tftp flash

This command tells the router to copy the IOS image from a TFTP server into flash storage, where it can be booted.

Cisco IOS Documentation - Image Upgrade Process:

"Use the command copy tftp flash to transfer an IOS image from a TFTP server to the router's flash memory." Other options:

- * A: copy tftp run - invalid; you cannot copy into the running-config that way
 - * B: copy tftp start - used to copy configuration, not IOS image
 - * C: config net - an older and deprecated command, not for IOS upgrades
- Final answer:

NEW QUESTION: 90

What kind of users are listed in the "/user" menu?

A. router users

B. wireless users

C. Hot-Spot users

D. PPTP users

Answer: (SHOW ANSWER)

The /user menu in MikroTik RouterOS lists users who are allowed to log in to the router itself - via Winbox, SSH, WebFig, console, or API. These are administrative users of the RouterOS system.

Let's evaluate:

- * A.#Correct - These are RouterOS users (admin, techs, operators)
- * B.#Wireless users are authenticated via security-profiles and access-lists
- * C.#Hotspot users are managed under /ip hotspot user
- * D.#PPTP users are managed under /ppp secrets

MTCNA User Management Section:

"/user is used to configure login accounts for RouterOS access."

Rene Meneses Guide - User Types:

"Only RouterOS admin users are listed under /user. VPN and hotspot users are managed elsewhere." Terry Combs Notes - User Menu Summary:

"/user = login to router (Winbox/SSH). Not for PPP or hotspot authentication."

Valid MTCNA Dumps shared by ExamDiscuss.com for Helping Passing MTCNA Exam!

ExamDiscuss.com now offer the **newest MTCNA exam dumps**, the ExamDiscuss.com

MTCNA exam **questions have been updated** and **answers have been corrected** get the **newest** ExamDiscuss.com MTCNA dumps with Test Engine here:

<https://www.examdiscuss.com/MikroTik/exam/MTCNA/premium/> (205 Q&As Dumps, **35%OFF**)

Special Discount Code: freeexam)