

Learning PowerCLI

A practical guide to get you started with automating VMware vSphere via PowerCLI



Learning PowerCLI

A practical guide to get you started with automating VMware vSphere via PowerCLI

Robert van den Nieuwendijk

BIRMINGHAM - MUMBAI



Learning PowerCLI

Copyright © 2014 Packt Publishing

All rights reserved. No part of this book may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, without the prior written permission of the publisher, except in the case of brief quotations embedded in critical articles or reviews.

Every effort has been made in the preparation of this book to ensure the accuracy of the information presented. However, the information contained in this book is sold without warranty, either express or implied. Neither the author, nor Packt Publishing, and its dealers and distributors will be held liable for any damages caused or alleged to be caused directly or indirectly by this book.

Packt Publishing has endeavored to provide trademark information about all of the companies and products mentioned in this book by the appropriate use of capitals. However, Packt Publishing cannot guarantee the accuracy of this information.

First published: February 2014

Production Reference: 1050214

Published by Packt Publishing Ltd. Livery Place 35 Livery Street Birmingham B3 2PB, UK.

ISBN 978-1-78217-016-7

www.packtpub.com

Cover Image by John M. Quick (john.m.quick@gmail.com)

Credits

Author

Robert van den Nieuwendijk

Reviewers

Chris Halverson

Timothy J. Patterson

Victoria Peterson

Philip Sellers

Brian Wuchner

Acquisition Editors

Sam Birch

Gregory Wild

Content Development Editor

Madhuja Chaudhari

Technical Editors

Tanvi Bhatt

Akashdeep Kundu

Shiny Poojary

Copy Editors

Roshni Banerjee

Brandt D'Mello

Adithi Shetty

Project Coordinator

Joel Goveya

Proofreader

Stephen Copestake

Indexers

Monica Ajmera Mehta

Rekha Nair

Tejal Soni

Graphics

Yuvraj Mannari

Abhinash Sahu

Production Coordinator

Manu Joseph

Cover Work

Manu Joseph

About the Author

Robert van den Nieuwendijk is an IT veteran from the Netherlands with over 25 years of experience in the IT industry. He holds a bachelor's degree in Software Engineering. After working for a few years as a programmer of air traffic control and vessel traffic management systems for a company that is now called HITT, he started his own company Van den Nieuwendijk Informatica in 1988. Since then he has worked as a freelance systems administrator for OpenVMS, Windows Server, Linux, and VMware vSphere systems, mainly for Dutch governmental organizations. Currently, he is a VMware vSphere administrator at Wageningen UR (University and Research centre). During winter, he is also a ski and snowboard instructor at an indoor ski school.

With his background as a programmer, he always tries to make his job easier by writing programs or scripts to perform repetitive tasks. In the past, he used the C programming language, OpenVMS DCL, Visual Basic Script, and KiXtart to do this. Since Windows PowerShell 1.0, he uses Windows PowerShell and VMware vSphere PowerCLI for all of his scripting work.

Robert is a member of the Dutch VMware User group (VMUG) Customer Council and a frequent contributor and moderator at the VMware VMTN Communities. In 2012 and 2013, VMware awarded him the vExpert title for his "significant contributions to the community and a willingness to share his expertise with others".

He has his own blog at http://rvdnieuwendijk.com where he has shared his knowledge since 2011. He writes mainly about VMware vSphere PowerCLI, Windows PowerShell, and VMware vSphere.

If you want to get in touch with Robert, you can find him on Twitter. His username is @rvdnieuwendijk.

I would like to thank my wife, Ali, for supporting me in writing this book and all the hours she had to spend alone while I was writing.

About the Reviewers

Chris Halverson is the co-leader of his local VMUG and the principal consultant at Darus Consulting (www.darus.ca). He has been working in the IT industry for over 14 years and specifically 7 years in virtualization. He has worked hard to increase his skill in the automation and cloud realm over that point of time, thanks to his enjoyment in the PowerShell scripting arena. He excels in architecture and design space helping others conceptualize and design the ideal layout and performance for the company's infrastructure. In his spare time, he enjoys spending time with his wife and four children and participating in his local Tae Kwon Do Dojang.

Timothy J. Patterson is a Cloud and Virtualization Systems Engineer, currently working at ProQuest based in Ann Arbor, Michigan. Focused primarily on Amazon Web Services and VMware technologies, he is currently in possession of the VCAP5-DCA, VCAP5-DCD, VCP5-DCV technical certifications from VMware, as well as the AWS Certified Solutions Architect certification from Amazon. Additionally, he is a Bachelor of Science from Saginaw Valley State University in Computer Information Systems and is a Novell Certified Linux Engineer.

Throughout his career, Tim has gained over 10 years of direct hands-on experience working with VMware products and AWS with a passion towards cloud architecture, design, and automation technologies. He is currently a VCDX hopeful and is always looking ahead for the next challenge.

I would like to thank my wife, Danielle, for her never-ending support and love. I also want to mention my two little girls, Molly and Amelia, because without them I would not be complete. My family serves as a constant source of inspiration, driving me to succeed in both my personal and professional goals.

Additionally, I would like to take this opportunity to thank the individuals I have had the pleasure of working with throughout my professional career. I have learned a lot from each and every one of you. I look forward to what the future has in store for us as the technology we work with every day continues to evolve.

Victoria Peterson is originally from Scotland and is now based in the Netherlands. She has more than 15 years of experience in the IT industry.

Her expertise is mainly focused on systems monitoring, automation, and integration. She has extensive knowledge and experience of design and implementation of monitoring solutions and development of custom monitoring based on System Center Operations Manager. She is currently a System Center Monitoring Specialist at Wageningen UR.

Her product skill set includes technologies such as SCOM, SCCM, SCSM, Windows Server, Active Directory, SQL, Citrix XenApp, VMware vSphere, Unicenter NSM, and automation of various tasks using PowerShell scripting.

Victoria has MCSE (legacy) and MCDBA certifications and she additionally holds other non-Microsoft certifications such as Citrix Certified Administrator (XenApp 6.5) and Certified Unicenter Specialist Engineer for Unicenter NSM.

Philip Sellers is a Senior Systems Administrator based in Myrtle Beach, South Carolina, with 15 years of experience. Primarily focused in Microsoft and VMware technologies, he is the virtualization lead for Horry Telephone Cooperative (HTC) and works extensively with core technology platforms such as vSphere, Active Directory, and Exchange. Prior to his current role, he served as a trusted IT consultant for medical, legal, and hospitality companies administering their infrastructure and systems.

Philip is an active blogger, covering vSphere, Microsoft software, and HP hardware platforms. He is a VMware vExpert for 2013, and he has recognizing contributions to the VMware community and advocacy of the vSphere platform. He also participates with the VMware User Groups in his area.

To find out more about Philip, you may follow his blog at http://tech.philipsellers.com and on Twitter, @pbsellers.

Brian Wuchner is a Senior Systems Administrator for a government agency. He has over 10 years of industry experience with specialties in infrastructure automation, directory services, and data center virtualization. Brian holds the VCA-Cloud, VCA-WM, and VCP5-DCV certifications and was awarded the vExpert title from VMware for 2011-2013. He can be contacted on LinkedIn (http://www.linkedin.com/in/bwuch), Twitter (@bwuch), or through his blog at http://enterpriseadmins.org.

www.PacktPub.com

Support files, eBooks, discount offers and more

You might want to visit www. PacktPub. com for support files and downloads related to your book.

Did you know that Packt offers eBook versions of every book published, with PDF and ePub files available? You can upgrade to the eBook version at www.PacktPub.com and as a print book customer, you are entitled to a discount on the eBook copy. Get in touch with us at service@packtpub.com for more details.

At www.PacktPub.com, you can also read a collection of free technical articles, sign up for a range of free newsletters and receive exclusive discounts and offers on Packt books and eBooks.



http://PacktLib.PacktPub.com

Do you need instant solutions to your IT questions? PacktLib is Packt's online digital book library. Here, you can access, read and search across Packt's entire library of books.

Why Subscribe?

- Fully searchable across every book published by Packt
- Copy and paste, print and bookmark content
- On demand and accessible via web browser

Free Access for Packt account holders

If you have an account with Packt at www.PacktPub.com, you can use this to access PacktLib today and view nine entirely free books. Simply use your login credentials for immediate access.

Instant Updates on New Packt Books

Get notified! Find out when new books are published by following @PacktEnterprise on Twitter, or the *Packt Enterprise* Facebook page.

Table of Contents

Preface	1
Chapter 1: Introduction to PowerCLI	7
Downloading and installing PowerCLI	8
Downloading PowerCLI	8
Installing PowerCLI	9
Modifying the PowerShell execution policy	15
Connecting and disconnecting servers	17
Connecting to a server	17
Connecting to multiple servers	19
Suppressing certificate warnings	21
Disconnecting from a server	22
Retrieving the PowerCLI configuration	23
Using the credential store	24
Retrieving a list of all of your virtual machines	25
Suppressing displaying deprecated warnings	28
Using wildcard characters	28
Filtering objects	29
Using comparison operators	30
Using aliases	30
Retrieving a list of all of your hosts	31
Displaying the output in a grid view	33
Summary	34
Chapter 2: Learning Basic PowerCLI Concepts	35
Using the Get-Command, Get-Help, and Get-Member cmdlets	35
Using Get-Command	36
Using Get-VICommand	38
Using Get-Help	38
Using Get-PowerCLIHelp	40

Using Get-PowerCLICommunity	41
Using Get-Member	42
Using providers and PSDrives	44
Using providers	44
Using PSDrives	45
Using the vSphere PowerCLI Inventory Provider	46
Using the vSphere PowerCLI Datastore Provider	47
Copying files between a datastore and your PC	48
Using arrays and hash tables	49
Creating calculated properties	50
Using raw API objects with ExtensionData or Get-View	52
Using the ExtensionData property	52
Using the Get-View cmdlet	53
Using Managed Object References	55
Using the Get-VIObjectByVIView cmdlet	56
Extending PowerCLI objects with the New-VIProperty cmdlet	57
Working with vSphere folders	59
Summary	61
Chapter 3: Working with Objects in PowerShell	63
Using objects, properties, and methods	64
Using methods	67
Expanding variables and subexpressions in strings	68
Understanding what expands a string	70
Expanding a string when it is used	70
Using here-strings	71
Using the pipeline	71
Using the ByValue parameter binding	71
Using the ByPropertyName parameter binding	73
Using the PowerShell object cmdlets	75
Using the Select-Object cmdlet	76
Using the Where-Object cmdlet	78
Using the ForEach-Object cmdlet	79
Using the Sort-Object cmdlet	81
Using the Measure-Object cmdlet	82
Rounding a value Using the Group-Object cmdlet	84 85
Using the Compare-Object cmulet	86
Using the Tee-Object condiet	87
Creating your own objects	88
Using the New-Object cmdlet	88
Osing the New-Object officiet	00

Chapter 5: Managing Virtual Machines with PowerCLI	137
Creating a virtual machine	138
Creating a virtual machine from scratch	140
Creating a virtual machine from a template	142
Cloning a virtual machine	142
Registering a virtual machine	143
Using OS customization specifications	144
Starting and stopping a virtual machine	147
Starting a virtual machine	147
Suspending a virtual machine	148
Shutting down a virtual machine's guest operating system	148
Stopping a virtual machine	149
Modifying the settings of a virtual machine	150
Using the VMware vSphere API	152
Adding devices to a virtual machine	153
Adding a hard disk	154
Adding a SCSI controller	155
Adding a network adapter Adding a floppy drive	156 157
Adding a CD drive	157
Modifying devices added to a virtual machine	159
Modifying a hard disk	159
Modifying a SCSI controller	161
Modifying a floopy drive	162 164
Modifying a floppy drive Modifying a CD drive	164
Removing devices from a virtual machine	165
Removing a hard disk	165
Removing a network adapter	166
Removing a floppy drive	166
Removing a CD drive	167 167
Converting a template into a virtual machine	168
Converting a template into a virtual machine Modifying the name of a template	169
, ,	169
Removing a template Moving a virtual machine to another folder, host, cluster,	109
resource pool, or datastore	169
Updating the VMware Tools	170
Using the Update-Tools cmdlet	170
Enabling the "Check and upgrade VMware Tools before each	17.1
power on" checkbox	172
Upgrading virtual machine compatibility	172
Using snapshots	173
oanig anapanota	1/5

Creating snapshots	175
Retrieving snapshots	177
Reverting to a snapshot	178
Modifying snapshots	179
Removing snapshots	179
Running commands on the guest OS	180
Configuring Fault Tolerance	181
Turning Fault Tolerance on	182
Turning Fault Tolerance off	182
Opening the console of a virtual machine	182
Removing a virtual machine	184
Summary	184
Chapter 6: Managing Virtual Networks with PowerCLI	185
Using vSphere Standard Switches	186
Creating vSphere Standard Switches	186
Configuring vSphere Standard Switches	188
Adding network adapters to a switch	191
Removing vSphere Standard Switches	191
Using host network adapters	192
Creating host network adapters	192
Retrieving host network adapters	193
Configuring host network adapters	194
Configuring network speed and the duplex setting	194
Configuring the management network	195
Configuring vMotion	195
Removing host network adapters	196
Configuring NIC Teaming	196
Using standard port groups	199
Creating standard port groups	199
Configuring standard port groups	200
Removing standard port groups	201
Using vSphere Distributed Switches	202
Creating vSphere Distributed Switches	203
Creating a new vSphere Distributed Switch from scratch Cloning a vSphere Distributed Switch	203 204
Creating a vSphere Distributed Switch from an export	204
Retrieving vSphere Distributed Switches	205
Configuring vSphere Distributed Switches	206
Rolling back the configuration of a vSphere Distributed Switch	208
Importing the configuration of a vSphere Distributed Switch from a backup	209
Upgrading a vSphere Distributed Switch	210
Adding hosts to vSphere Distributed Switches	210

Adding host physical network adapters to a vSphere	
Distributed Switch	211
Removing host physical network adapters from a vSphere	
Distributed Switch	212
Removing hosts from a vSphere Distributed Switch	212
Exporting the configuration of vSphere Distributed Switches	213
Removing vSphere Distributed Switches	213
Using distributed virtual port groups	214
Creating distributed virtual port groups	214
Creating distributed virtual port groups from a reference group	215
Creating distributed virtual port groups from an export	215
Configuring distributed virtual port groups	216
Renaming a distributed virtual port group Rolling back the configuration of a distributed virtual port group	217 218
Restoring the configuration of a distributed virtual port group	218
Configuring Network I/O Control	219
Enabling Network I/O Control	219
Disabling Network I/O Control	219
Exporting the configuration of distributed virtual port groups	219
Migrating a host network adapter from a standard port group	
to a distributed port group	220
Removing distributed virtual port groups	220
Configuring host networking	221
Configuring the network of a virtual machine	223
Summary	225
Chapter 7: Managing Storage with PowerCLI	227
Rescanning for new storage devices	228
Creating datastores	228
Creating NFS datastores	229
Getting SCSI LUNs	229
Creating VMFS datastores	230
Creating software iSCSI VMFS datastores	230
Retrieving datastores	233
Setting the multipathing policy	233
Configuring the vmhba paths to a SCSI device	235
Retrieving the vmhba paths to a SCSI device	235
Modifying the vmhba paths to a SCSI device	235
Working with Raw Device Mappings	236
Configuring Storage I/O Control	238
Retrieving Storage I/O Control settings	239
Configuring Storage DRS	240
Creating a Datastore Cluster	240

	Table of Contents
Retrieving Datastore Clusters	241
Modifying Datastore Clusters	241
Adding datastores to a Datastore Cluster	243
Retrieving the datastores in a Datastore Cluster	243
Removing datastores from a Datastore Cluster	244
Removing Datastore Clusters	244
Upgrading datastores to VMFS-5	245
Removing datastores	247
Summary	248
Chapter 8: Managing High Availability and Clustering	
with PowerCLI	249
Creating vSphere HA and DRS clusters	250
Retrieving clusters	252
Retrieving the HA master or primary hosts	252
Retrieving cluster configuration issues	253
Modifying cluster settings	254
Disabling HA	255
Disabling or enabling host monitoring	255
Associating a host profile with a cluster	256
Enabling VM and application monitoring	256
Configuring the heartbeat datastore selection policy	258
Moving hosts to clusters	262
Moving clusters	263
Using DRS rules	263
Creating VM-VM DRS rules	264
Creating VM-Host DRS rules	266
Creating virtual machines DRS groups	266
Creating hosts DRS groups	267
Retrieving DRS groups	267
Modifying DRS groups	268
Removing DRS groups Creating virtual machines to hosts DRS rules	270 270
Retrieving DRS rules	272
Modifying DRS rules	274
Removing DRS rules	274
Using DRS recommendations	275
Using resource pools	276 276
Creating resource pools	
Retrieving resource pools	277
Modifying resource pools Moving resource pools	278 279
IVIOVITO TESOUTCE DOOIS	//9

Configuring resource allocation between virtual machines	280
Removing resource pools	281
Using Distributed Power Management (DPM)	282
Enabling DPM	282
Configuring hosts for DPM	284
Testing hosts for DPM	284
Putting hosts in standby mode	284
Starting hosts	285
Retrieving the DPM configuration of a cluster	285
Disabling DPM	286
Removing clusters	286
Summary	286
Chapter 9: Managing vCenter with PowerCLI	287
Working with roles and permissions	287
Retrieving privileges	288
Using roles	290
Creating roles	290
Retrieving roles	291
Modifying roles	292
Removing roles	293 29 3
Using permissions Creating permissions	293
Retrieving permissions	295
Modifying permissions	296
Removing permissions	296
Managing licenses	297
Adding license keys to the license inventory	297
Retrieving license keys from the license inventory	298
Removing license keys from the license inventory	299
Assigning licenses to hosts	299
Retrieving assigned licenses	300
Removing assigned license keys from hosts	301
Using the LicenseDataManager	301
Associating license keys with host containers	302
Applying the associated license key to all the hosts in the container	303
Retrieving license key associations	303
Modifying license key associations	305 305
Removing license key associations Configuring alarms	306
<u> </u>	
Retrieving alarm definitions	307
Modifying alarm definitions	308
Creating alarm actions Configuring the vCenter Server mail server and sender settings	308 311
Comigating the vocated octive that server and schiel settings)।।

Retrieving alarm actions Removing alarm actions Creating alarm action triggers Retrieving alarm action triggers Removing alarm action triggers	
Creating alarm action triggers Retrieving alarm action triggers	312
Creating alarm action triggers Retrieving alarm action triggers	313
Retrieving alarm action triggers	313
	314
5 55	315
Retrieving events	316
Summary	319
Chapter 10: Reporting with PowerCLI	321
Retrieving log files	321
Creating log bundles	325
Performance reporting	325
Retrieving the statistical intervals	326
Retrieving performance statistics	328
Retrieving metric IDs	330
Exporting reports to CSV files	331
Generating HTML reports	333
Sending reports by e-mail	336
Reporting the health of your vSphere environment with vCheck	338
Using PowerGUI	339
Summary	340
Index	343

Preface

VMware vSphere PowerCLI is a command-line automation and scripting tool that provides a Windows PowerShell interface to the VMware vSphere and vCloud products.

Learning PowerCLI shows you how to install and use PowerCLI to automate the management of your VMware vSphere environment. With lots of examples, this book will teach you how to manage vSphere from the command line and how to create advanced PowerCLI scripts.

What this book covers

Chapter 1, Introduction to PowerCLI, gets you started using PowerCLI. First, you will see how to download and install PowerCLI. Then, you will learn to connect to and disconnect from the vCenter and ESXi servers and retrieve a list of all of your hosts and virtual machines.

Chapter 2, Learning Basic PowerCLI Concepts, introduces the Get-Help, Get-Command, and Get-Member cmdlets. It explains the difference between PowerShell Providers and PSDrives. You will see how you can use the raw vSphere API objects from PowerCLI and how to use the New-VIProperty cmdlet to extend a PowerCLI object.

Chapter 3, Working with Objects in PowerShell, concentrates on objects, properties, and methods. This chapter shows how you can use the pipeline to use the output of one command as the input of another command. You will learn how to use the PowerShell object cmdlets and how to create your own PowerShell objects.

Chapter 4, Managing vSphere Hosts with PowerCLI, covers the management of the vSphere ESXi servers. You will see how to add hosts to the vCenter server and how to remove them. You will work with host profiles, host services, Image Builder, and Auto Deploy, as well as with the esxcli command and the vSphere CLI commands from PowerCLI.

Chapter 5, Managing Virtual Machines with PowerCLI, examines the lifecycle of virtual machines — from creating to removing them. Creating templates, updating VMware Tools and upgrading virtual hardware, running commands in the guest OS, and configuring fault tolerance are some of the topics discussed in this chapter.

Chapter 6, Managing Virtual Networks with PowerCLI, walks you through vSphere Standard Switches and vSphere Distributed Switches, port groups, and network adapters. It shows you how to configure host networking and how to configure the network of a virtual machine.

Chapter 7, Managing Storage with PowerCLI, explores creating and removing datastores and Datastore Clusters, working with Raw Device Mapping, configuring software iSCSI initiators, Storage I/O Control, and Storage DRS.

Chapter 8, Managing High Availability and Clustering with PowerCLI, covers HA and DRS clusters, DRS rules and DRS groups, resource pools, and Distributed Power Management.

Chapter 9, Managing vCenter with PowerCLI, shows you how to work with privileges, work with roles and permissions, manage licenses, configure alarm definitions, alarm action triggers, and retrieve events.

Chapter 10, Reporting with PowerCLI, concentrates on retrieving log files and log bundles, performance reporting, exporting reports to CSV files, generating HTML reports, sending reports by e-mail, and reporting the health of your vSphere environment with the vCheck script.

What you need for this book

To run the example PowerCLI scripts given in this book, you need the following software:

- VMware vSphere PowerCLI
- Windows PowerShell 2.0 or Windows PowerShell 3.0
- VMware vCenter Server
- VMware ESXi

The scripts in this book are tested using VMware vSphere PowerCLI 5.5 Release 1, VMware vCenter Server 5.5, and VMware ESXi 5.5.

Windows PowerShell and VMware vSphere PowerCLI are free. You can download a free 60-day evaluation of VMware vCenter Server and VMware ESXi from the VMware website. It is not possible to modify the settings on the free VMware vSphere Hypervisor using PowerCLI.

Who this book is for

This book is written for VMware vSphere administrators who want to automate their vSphere environment using PowerCLI. It is assumed that you have at least a basic knowledge of VMware vSphere. If you are not a vSphere administrator, but you are interested in learning more about PowerCLI, then this book will also give you some basic knowledge of vSphere.

Conventions

In this book, you will find a number of styles of text that distinguish between different kinds of information. Here are some examples of these styles, and an explanation of their meaning.

Code words in text are shown as follows: "The -Name parameter is required."


A block of code is set as follows:

```
$Cluster = Get-Cluster -Name Cluster01
New-VM -Name VM1 -ResourcePool $Cluster
```

Any command-line input or output is written as follows:

PowerCLI C:\> New-VM -Name VM1 -ResourcePool (Get-Cluster -Name Cluster01)

New terms and **important words** are shown in bold. Words that you see on the screen, in menus or dialog boxes for example, appear in the text like this: "clicking the **Next** button moves you to the next screen".



Reader feedback

Feedback from our readers is always welcome. Let us know what you think about this book—what you liked or may have disliked. Reader feedback is important for us to develop titles that you really get the most out of.

To send us general feedback, simply send an e-mail to feedback@packtpub.com, and mention the book title via the subject of your message. If there is a topic that you have expertise in and you are interested in either writing or contributing to a book, see our author guide on www.packtpub.com/authors.

Customer support

Now that you are the proud owner of a Packt book, we have a number of things to help you to get the most from your purchase.

Downloading the example code

You can download the example code files for all Packt books you have purchased from your account at http://www.packtpub.com. If you purchased this book elsewhere, you can visit http://www.packtpub.com/support and register to have the files e-mailed directly to you.

Errata

Although we have taken every care to ensure the accuracy of our content, mistakes do happen. If you find a mistake in one of our books—maybe a mistake in the text or the code—we would be grateful if you would report this to us. By doing so, you can save other readers from frustration and help us improve subsequent versions of this book. If you find any errata, please report them by visiting http://www.packtpub.com/submit-errata, selecting your book, clicking on the errata submission form link, and entering the details of your errata. Once your errata are verified, your submission will be accepted and the errata will be uploaded on our website, or added to any list of existing errata, under the Errata section of that title. Any existing errata can be viewed by selecting your title from http://www.packtpub.com/support.

Piracy

Piracy of copyright material on the Internet is an ongoing problem across all media. At Packt, we take the protection of our copyright and licenses very seriously. If you come across any illegal copies of our works, in any form, on the Internet, please provide us with the location address or website name immediately so that we can pursue a remedy.

Please contact us at copyright@packtpub.com with a link to the suspected pirated material.

We appreciate your help in protecting our authors, and our ability to bring you valuable content.

Questions

You can contact us at questions@packtpub.com if you are having a problem with any aspect of the book, and we will do our best to address it.

1 Introduction to PowerCLI

Have you ever had to create 100 virtual machines in a really short period of time, change a setting on all of your hosts, or make an advanced report for your boss to show how full the hard disks of your virtual machines are? If you have, you know that performing these tasks using the vSphere client will take a lot of time. This is where automation can make your job easier. **VMware vSphere PowerCLI** is a powerful tool that can perform these tasks and much more. And the best thing is that it is free!

VMware vSphere PowerCLI is a **command-line interface** distributed as a Microsoft Windows PowerShell snap-in. You can use PowerCLI to automate your vSphere hosts, virtual machines, virtual networks, storage, clusters, vCenter Servers, and more.

In this chapter, you will learn:

- Downloading and installing PowerCLI
- Modifying the PowerShell execution policy
- Connecting and disconnecting servers
- Using the credential store
- Retrieving a list of all of your virtual machines
- Retrieving a list of all of your hosts


Downloading and installing PowerCLI

Before you can install PowerCLI, you have to download the PowerCLI installer from the VMware website. You will need a My VMware account to do this.


Downloading PowerCLI

Perform the following steps to download PowerCLI:

1. Visit http://www.vmware.com/go/powercli. On this page, you will find a **Resources** section.



- 2. Click on the **vSphere PowerCLI 5.5** link in the **Resources** section to go to the download page.
- 3. Click on the **Download** button to download PowerCLI.
- 4. You have to log in with a My VMware account. If you don't have a **My VMware** account, you can register for free.



- 5. After you log in, you will be taken to the **vSphere PowerCLI 5.5** download page. Click on the **Download Now** button to start downloading PowerCLI.
- 6. You have to agree to and accept the terms and conditions outlined in the VMware End User License Agreement. Check the tick box in front of I agree to the terms and conditions outlined in the End User License Agreement and click on Accept to download the PowerCLI installer.




7. Save the PowerCLI installation file on your local hard disk.

Installing PowerCLI

Perform the following steps to install PowerCLI:

- 1. Run the PowerCLI installer that you just downloaded.
- 2. Click on Yes in the User Account Control window to accept the Do you want to allow the following program to make changes to this computer? option.


3. PowerCLI requires VMware Remote Console Plug-In and VMware VIX to be installed on your computer. Click on **Install** to install these products.




4. Click on **Next** on the **Welcome to the InstallShield Wizard for VMware vSphere PowerCLI** window.




5. Select **I accept the terms in the license agreement** and click on **Next**.



 If you are using VMware vCloud Director, you can select This feature will be installed on local hard drive for vCloud Director PowerCLI. (If you want, you can change the installation directory by clicking on Change....) Click on Next.



7. Click on **Install** to begin the installation.







After installing PowerCLI, you will have a **VMware vSphere PowerCLI** icon on your desktop. If you installed PowerCLI on a 64-bit computer, you will also have a **VMware vSphere PowerCLI** (32-Bit) icon. Some PowerCLI commands only work in the 32-bit version of PowerCLI. So install both versions.

Besides starting PowerCLI from the icon on your desktop, you can also start PowerCLI from the Start menu. Go to **All Programs** | **VMware** | **VMware vSphere PowerCLI** to launch **VMware vSphere PowerCLI** or **VMware vSphere PowerCLI** (32-Bit).

When you start PowerCLI, you will get the following screen:

```
Welcome to the UMware vSphere PowerCLI!

Log in to a vCenter Server or ESX host:

To find out what commands are available, type:

Get-UICommand
To show searchable help for all PowerCLI commands:

Get-PowerCLIHelp
Once you've connected, display all virtual machines:

Get-UM
If you need more help, visit the PowerCLI community:

Get-PowerCLICommunity

Copyright (C) 1998-2013 UMware, Inc. All rights reserved.

PowerCLI C:\Program Files (x86)\UMware\Infrastructure\vSphere PowerCLI>
```

If you didn't get the text from the screenshot but got some red error messages saying that files **cannot be loaded because running scripts is disabled on this system**, read the following section to solve this problem. The following screenshot shows the error message that will be displayed:

Modifying the PowerShell execution policy

If this is the first time that you are using Windows PowerShell on the computer on which you installed PowerCLI, you have to change the **execution policy** to be able to start PowerCLI.

The Windows PowerShell execution policies define when you can run scripts or load configuration files. The possible values for the execution policy are: Restricted, AllSigned, RemoteSigned, Unrestricted, Bypass, and Undefined.

Policy	Description
Restricted	This is the default execution policy. It allows you to run commands at the command prompt but disables the execution of scripts. It will also disable the start of PowerCLI.
AllSigned	With the AllSigned execution policy, scripts can run but must be signed by a trusted publisher. If you run a script by a publisher that is not trusted yet, you will see a prompt asking whether you trust the publisher of the script.
RemoteSigned	The RemoteSigned execution policy allows you to run scripts that you have written on the local computer. Any script downloaded from the Internet must be signed by a trusted publisher or must be unblocked.
Unrestricted	When the execution policy is set to Unrestricted, unsigned scripts can run. If you run a script that has been downloaded from the Internet, you will get a security warning saying that this script can potentially harm your computer and asking whether you want to run this script.
Bypass	The Bypass execution policy blocks nothing and displays no warnings or prompts. This execution policy is designed for configurations in which a Windows PowerShell script is built into a larger application that has its own security model.
Undefined	The Undefined execution policy removes the execution policy from the current scope. If the execution policy in all scopes is Undefined, the effective execution policy is Restricted, which is the default execution policy. The Undefined execution policy will not remove an execution policy that is set in a Group Policy scope.

You can check the current execution policy setting with the following command:

PowerCLI C:\> Get-ExecutionPolicy

Get-ExecutionPolicy is a Windows PowerShell **commandlet** (**cmdlet**). Cmdlets are commands built into PowerShell or PowerCLI. They follow a verb-noun naming convention. The **get cmdlets** receives information about the item that is specified as the noun part of the cmdlet.

Set the execution policy to RemoteSigned to be able to start PowerCLI and run scripts written on the local computer with the Set-ExecutionPolicy -ExecutionPolicy RemoteSigned command, as shown in the next screenshot.




You have to run the Set-ExecutionPolicy -ExecutionPolicy RemoteSigned command from a PowerShell or PowerCLI session that you started using the **Run as Administrator** option, or you will get the following error message:

Set-ExecutionPolicy: Access to the registry key 'HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\PowerShell\1\ShellIds\Microsoft.PowerShell' is denied.

If you are using both the 32-bit and the 64-bit versions of PowerCLI, you have to run this command in both versions.

In the next screenshot of the PowerCLI console, you will see the output of the Set-ExecutionPolicy -ExecutionPolicy RemoteSigned command if you run this command in a PowerCLI session started with "Run as Administrator".



You can get more information about execution policies by typing the following command:

PowerCLI C:\> Get-Help about_Execution_Policies

To get more information about signing your scripts, type the following command:

PowerCLI C:\> Get-Help about_signing

Connecting and disconnecting servers

Before you can do useful things with PowerCLI, you have to connect to a vCenter Server or an ESXi server. And if you are finished, it is a good practice to disconnect your session. We will discuss how to do this in the following sections.

Connecting to a server

If you are not connected to a vCenter or an ESXi server, you will get an error message if you try to run a PowerCLI cmdlet. Let's try to retrieve a list of all of your datacenters using the following command:

```
PowerCLI C:\> Get-Datacenter
```

The output of the preceding command is as follows:

You see that this gives an error message. You first have to connect to a vCenter Server or an ESXi server using the Connect-VIServer cmdlet. If you have a vCenter Server, you only need to connect to the vCenter Server and not to the individual ESXi servers. It is possible to connect to multiple vCenter Servers or ESXi servers at once. The Connect-VIServer cmdlet has the following syntax:

As you can see, the Connect-VIserver cmdlet has two parameter sets: Default and Menu. In the Default parameter set, the -Server parameter is required. In the Menu parameter set, the -Menu parameter is required. You cannot combine parameters from the Default parameter set with the Menu parameter set.

Let's first try to connect to a vCenter Server with the following cmdlet:

```
PowerCLI C:\> Connect-VIServer -Server 192.168.0.132
```

192.168.0.132 is the IP address of the vCenter Server in my home lab. Replace this IP address with the IP address or DNS name of your vCenter or ESXi server.

The preceding command will pop up a window in which you have to specify server credentials to connect to your server if your Windows session credentials don't have rights on your server. Enter values for **User name** and **Password** and click on **OK**.

If you specified valid credentials, you will get output similar to the following:

Name	Port	User
192.168.0.132	443	root

You can also specify a username and password on the command line as follows:

PowerCLI C:\> Connect-VIServer -Server 192.168.0.132 -User admin -Password pass

You can also save the credentials in a variable with the following command:

PowerCLI C:\> \$Credential = Get-Credential

The preceding command will pop up a window in which you can type the username and password.



You can now use the \$Credential variable to connect to a server using the - Credential parameter, as follows:

```
PowerCLI C:\> Connect-VIServer -Server 192.168.0.132 -Credential
$Credential
```

You can also use the PowerCLI **credential store**. This will be discussed in a later section in this chapter.

The default protocol that the Connect-VIServer cmdlet uses is HTTPS. If you want to make a connection with the HTTP protocol, you can do that with the following command:

```
PowerCLI C:\> Connect-VIServer -Server 192.168.0.132 -Protocol http
```

If you have multiple vCenter Servers in **Linked Mode**, you can use the Connect-VIServer -AllLinked parameter to connect all of these vCenter Servers at once, as follows:

```
PowerCLI C:\> Connect-VIserver -Server 192.168.0.132 -Credential $Credential -AllLinked
```

The Connect-VIServer -Menu command gives you a list of previously connected servers from which you can pick one, as shown in the following command line:

```
PowerCLI C:\> Connect-VIServer -Menu
Select a server from the list (by typing its number and pressing Enter):
[1] 192.168.0.132
[2] 192.168.0.133
```

Type the number of the server you want to connect to.

Connecting to multiple servers

It is possible in PowerCLI to connect to multiple servers at once. You can do this by specifying more than one server, as follows:

PowerCLI C:\> Connect-VIServer -Server vCenter1, vCenter2

The first time you try to do this, you will get the following message:

Working with multiple default servers?

Select [Y] if you want to work with more than one default servers. In this case, every time when you connect to a different server using Connect-VIServer, the new server connection is stored in an array variable together with the previously connected servers. When you run a cmdlet and the target servers cannot be determined from the specified parameters, the cmdlet runs against all servers stored in the array variable.

Select [N] if you want to work with a single default server. In this case, when you run a cmdlet and the target servers cannot be determined from the specified parameters, the cmdlet runs against the last connected server.

WARNING: WORKING WITH MULTIPLE DEFAULT SERVERS WILL BE ENABLED BY DEFAULT IN A FUTURE RELEASE. You can explicitly set your own preference at any time by using the DefaultServerMode parameter of Set-PowerCLIConfiguration.

```
[Y] Yes [N] No [S] Suspend [?] Help (default is "Y"):
```

Press *Enter* or type Y to work with multiple default servers.

As the message says, you can always connect to multiple servers but your commands will only work against the last server you connected to unless you have enabled working with multiple servers.

You can see the current value of DefaultServerMode with the Get-PowerCLIConfiguration cmdlet:

PowerCLI C:\> Get-PowerCLIConfiguration

If you want to change the DefaultServerMode from single to multiple, you can do that with the Set-PowerCLIConfiguration cmdlet. The cmdlet has the following syntax:

```
Set-PowerCLIConfiguration [-ProxyPolicy <ProxyPolicy>]
[-DefaultVIServerMode <DefaultVIServerMode>]
[-InvalidCertificateAction <BadCertificateAction>]
[-DisplayDeprecationWarnings [<Boolean>]]
[-WebOperationTimeoutSeconds <Int32>]
[-VMConsoleWindowBrowser <String>]
[-Scope <ConfigurationScope>] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

Change the DefaultServerMode from single to multiple with the following command:


PowerCLI C:\> Set-PowerCLIConfiguration -DefaultVIServerMode Multiple -Scope User

All of the servers that you are currently connected to are stored in the variable \$global:DefaultVIServers. If DefaultVIServerMode is set to multiple, your PowerCLI cmdlets will run against all servers stored in the \$global:DefaultVIServers variable.

The last server you are connected to is stored in the variable \$global:DefaultVIServer. If DefaultVIServerMode is set to single, your PowerCLI cmdlets will only run against the server stored in the \$global:DefaultVIServer variable.

Suppressing certificate warnings

If your vCenter Server does not have valid server certificates, the Connect-VIserver cmdlet will display some warning messages, as shown in the following screenshot:



It is a good practice is to supply your vCenter Server and ESXi servers with valid certificates. You can find information on how to do this in the VMware Knowledge Base article, *Implementing CA signed SSL certificates with vSphere 5.x* (2034833) at http://kb.vmware.com/kb/2034833.

If you don't have valid certificates, you can easily suppress the warning messages using the Set-PowerCLIConfiguration cmdlet with the following command:

```
PowerCLI C:\ > Set-PowerCLIConfiguration -InvalidCertificateAction Ignore
```

This will modify InvalidCertificationAction in the Allusers scope. You have to run this command using the **Run as Administrator** PowerCLI session. Otherwise, you will get the following error message:

Set-PowerCLIConfiguration: Only administrators can change settings for all users.

Disconnecting from a server

To disconnect from a vSphere server, you have to use the Disconnect-VIServer cmdlet. The Disconnect-VIServer cmdlet has the following syntax:

```
Disconnect-VIServer [[-Server] <VIServer[]>] [-Force] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

To disconnect all of your server connections, type the following command:

```
PowerCLI C:\> Disconnect-VIServer -Server * -Force
```

The output of the preceding command is as follows:

```
Confirm
```

```
Are you sure you want to perform this action?

Performing operation "Disconnect VIServer" on Target "User: root, Server: 192.168.0.132, Port: 443".

[Y] Yes [A] Yes to All [N] No [L] No to All [S] Suspend [?] Help (default is "Y"):
```

Type *Y* or *Enter* to disconnect from the server.

If you don't want to be prompted with **Are you sure you want to perform this action?**, you can use the <code>-Confirm:\$false</code> option as follows:

```
PowerCLI C:\> Disconnect-VIServer -Server * -Force -Confirm:$false
```

It may be that you want to disconnect only one session and not all. In that case, specify the server name or IP address of the server you want to disconnect. The following command only disconnects the latest session from server 192.168.0.132:

```
PowerCLI C:\> Disconnect-VIServer -Server 192.168.0.132
```

Disconnecting one or more sessions will also change the value of the \$global:DefaultVIServers and \$global:DefaultVIServer variables.

Retrieving the PowerCLI configuration

To see the current setting of InvalidCertificationAction, you can use the Get-PowerCLIConfiguration cmdlet. The syntax of this cmdlet is as follows:

```
Get-PowerCLIConfiguration [-Scope <ConfigurationScope>]
[<CommonParameters>]
```

The following example will retrieve the PowerCLI configuration and shows the InvalidCertificateAction value for all scopes:

As you can see in the output, there are three different scopes for which you can modify the PowerCLI configuration: Session, User, and AllUsers. The Set-PowerCLIConfiguration cmdlet will modify the AllUser scope if you don't specify a scope.

The DisplayDeprecationWarnings property shown in the preceding output will be discussed in a later section in this chapter.

Using the credential store

If you are logged in to your computer with a domain account, you can use your Windows session credentials to connect to a vCenter or ESXi server. If you are not logged in to your computer with a domain account or your domain account has no rights in vSphere, you have to supply account information every time you connect to a vCenter or ESXi server.

To prevent you from having to do this, you can store credentials in the credential store. These stored credentials will be used as default if you connect to a server that is stored in the credential store. You can use the <code>-SaveCredentials</code> parameter of the <code>Connect-VIServer</code> cmdlet to indicate that you want to save the specified credentials in the local credential store, as follows:

```
PowerCLI C:\> Connect-VIServer -Server 192.168.0.132 -User admin -Password pass -SaveCredentials
```

You can also create a new entry in the credential store with the New-VICredentialStoreItem cmdlet:

```
PowerCLI C:\> New-VICredentialStoreItem -Host 192.168.0.132 -User Admin -Password pass
```

You can not only store credentials for vCenter Servers but also for ESXi servers, using the following command:

```
PowerCLI C:\> New-VICredentialStoreItem -Host ESX1 -User root -Password vmware
```

To get a listing of all of your stored credentials, type the following command:

```
PowerCLI C:\> Get-VICredentialStoreItem
```

And to remove a stored credential you can use the following command:

```
PowerCLI C:\> Remove-VICredentialStoreItem -Host ESX1 -User root
```

The stored credentials are stored in a file on your computer. The default credential store file location is: %APPDATA%\VMware\credstore\vicredentials.xml. But it is also possible to create other credential store files. You can see the contents of the default credential store file with the following command:

```
PowerCLI C:\> Get-Content -Path $env:APPDATA\VMware\credstore\
vicredentials.xml
```

The passwords stored in a credential store file are encrypted. But you can easily retrieve the stored passwords with the following command:

```
PowerCLI C:\> Get-VICredentialStoreItem |
>> Select-Object -Property Host,User,Password
```

So, if your computer is also used by other users and you are not sure that the information in the credential store file cannot be read by other people, it might be better not to use this feature.

Retrieving a list of all of your virtual machines

Now that we know how to connect to a server, let's do something useful with PowerCLI. Most of the people who begin using PowerCLI create reports, so create a list of all of your virtual machines as your first report. You have to use the <code>Get-VM</code> cmdlet to retrieve a list of your virtual machines. The syntax of the <code>Get-VM</code> cmdlet is as follows:

```
Get-VM [[-Name] <String[]>] [-Server <VIServer[]>]
[-Datastore <StorageResource[]>] [-Location <VIContainer[]>]
  [-Tag <Tag[]>] [-NoRecursion] [<CommonParameters>]

Get-VM [[-Name] <String[]>] [-Server <VIServer[]>]
[-DistributedSwitch <DistributedSwitch[]>] [-Tag <Tag[]>]
  [<CommonParameters>]

Get-VM [-Server <VIServer[]>] -Id <String[]> [<CommonParameters>]

Get-VM -RelatedObject <VmRelatedObjectBase[]> [<CommonParameters>]
```

As you can see, the Get-VM cmdlet has four different parameter sets. The names of these parameter sets are: Default, DistributedSwitch, ById, and RelatedObject. You can use these parameter sets to filter the virtual machines based on name, server, data store, location, distributed switch, ID, or related object.

Create your first report with the following command:

PowerCLI C:\> Get-VM

This will create a list of all of your virtual machines. You will see the name, power state, number of CPU's, and the amount of memory in GB for each virtual machine, as shown in the following command-line output:

Name	PowerState	Num CPUs	MemoryGB
Dc1	PoweredOn	2	8.000
VM1	PoweredOn	1	0.250
DNS1	PoweredOn	2	8.000

The Name, PowerState, NumCPU, and MemoryGB properties are the properties that you will see by default if you use the Get-VM cmdlet. However, the virtual machine object in PowerCLI has a lot of other properties that are not shown by default. You can see them all by piping the output of the Get-VM cmdlet to the Format-List cmdlet using the pipe character '|'. The Format-List cmdlet displays object properties and their values in a list format, as shown in the following command-line output:

PowerCLI C:\> Get-VM -Name DC1 | Format-List -Property *

PowerState : PoweredOn Version : v10 Description : Domain controller Notes : Domain controller Guest : DC1: Microsoft Windows Server 2012 (64-bit) : 2 NumCpu MemoryMB : 8192 MemoryGB : {Hard disk 1, Hard disk 2} HardDisks : {Network adapter 1} NetworkAdapters UsbDevices : {} : {CD/DVD drive 1} **CDDrives** FloppyDrives Host : ESX1.blackmilktea.com HostId : HostSystem-host-10

: HostSystem-host-10

: ESX1.blackmilktea.com

VApp :

VMHostId

VMHost

FolderId : Folder-group-v9

Folder : Discovered virtual machine

ResourcePoolId : ResourcePool-resgroup-8

ResourcePool : Resources

PersistentId : 50289ad0-a545-1299-5a75-811049f98276

UsedSpaceGB : 71.268582795746624469757080078 ProvisionedSpaceGB : 78.204129670746624469757080078

DatastoreIdList : {Datastore-datastore-14}

HARestartPriority : ClusterRestartPriority

HAIsolationResponse : AsSpecifiedByCluster

DrsAutomationLevel : AsSpecifiedByCluster

VMSwapfilePolicy : Inherit

VMResourceConfiguration : CpuShares:Normal/2000 MemShares:Normal/81920

Name : DC1

CustomFields : {[Application code,], [CreatedBy, Unknown],

[CreatedOn, Unknown], [Function,]...}

ExtensionData : VMware.Vim.VirtualMachine

Id : VirtualMachine-vm-16

Uid : /VIServer=blackteamilk\admin@192.168.0.132:443/

VirtualMachine=Virtual

Machine-vm-16/

Client

VMware.VimAutomation.ViCore.Impl.V1.VimClient

You can select specific properties with the Select-Object cmdlet. Say you want to make a report that shows the Name, Notes, VMHost, and Guest properties for all your virtual machines. You can do that with the following command:

PowerCLI C:\> Get-VM | Select-Object -Property Name, Notes, VMHost, Guest

The output of the preceding command is as follows:

Name	Notes	VMHost	Guest
DC1		192.168.0.133	DC1:
VM1		192.168.0.134	VM1:
DNS1	DNS Server	192.168.0.134	DNS1:

Suppressing displaying deprecated warnings

You will probably have also seen the following warning messages:

WARNING: The 'Description' property of VirtualMachine type is deprecated. Use the 'Notes' property instead.

WARNING: The 'HardDisks' property of VirtualMachine type is deprecated. Use 'Get-HardDisk' cmdlet instead.

WARNING: The 'NetworkAdapters' property of VirtualMachine type is deprecated. Use 'Get-NetworkAdapter' cmdlet instead.

WARNING: The 'UsbDevices' property of VirtualMachine type is deprecated. Use 'Get-UsbDevice' cmdlet instead.

WARNING: The 'CDDrives' property of VirtualMachine type is deprecated. Use 'Get-CDDrive' cmdlet instead.

WARNING: The 'FloppyDrives' property of VirtualMachine type is deprecated. Use 'Get-FloppyDrive' cmdlet instead.

WARNING: The 'Host' property of VirtualMachine type is deprecated. Use the 'VMHost' property instead.

WARNING: The 'HostId' property of VirtualMachine type is deprecated. Use the 'VMHostId' property instead.

WARNING: PowerCLI scripts should not use the 'Client' property. The property will be removed in a future release.

These warning messages show the properties that should not be used in your scripts because they are deprecated and might be removed in a future PowerCLI release. Personally, I like these warnings because they remind me of the properties that I should not use anymore. But if you don't like these warnings, you can stop them from appearing with the following command:

PowerCLI C:\> Set-PowerCLIConfiguration -DisplayDeprecationWarnings \$false -Scope User

Using wildcard characters

You can also use **wildcard characters** to select specific virtual machines. To display only the virtual machines that have names that start with an "A" or "a", type the following command:

PowerCLI C:\> Get-VM -Name A*

Parameter values are not case-sensitive. The asterisk (*) is a wildcard character that matches zero or more characters, starting at the specified position. Another wildcard character is the question mark (?) which matches any character at the specified position. To get all virtual machines with a three-letter name that ends with an "e", use the following command:

```
PowerCLI C:\> Get-VM -Name ??e
```

You can also specify some specific characters, as shown in the following command:

```
PowerCLI C:\> Get-VM -Name [bc] *
```

The preceding command displays all the virtual machines that have names starting with "b" or "c". You can also specify a range of characters, as shown in the following command:

```
PowerCLI C:\> Get-VM -Name *[0-4]
```

The preceding command lists all the virtual machines that have names ending with 0, 1, 2, 3, or 4.

Filtering objects

If you want to filter properties that don't have their own <code>Get-VM</code> parameter, you can pipe the output of the <code>Get-VM</code> cmdlet to the <code>Where-Object</code> cmdlet. Using the <code>Where-Object</code> cmdlet, you can set the filter on any property. Let's display a list of all of your virtual machines that have more than one virtual CPU using the following command:

```
PowerCLI C:\> Get-VM | Where-Object {$_.NumCPU -gt 1}
```

In this example, the Where-Object cmdlet has a PowerShell scriptblock as a parameter. A **scriptblock** is a PowerShell script surrounded by braces. In this scriptblock, you see \$_. When using commands in the pipeline, \$_ represents the current object. In the preceding example, \$_ represents the virtual machine object that is passed through the pipeline. \$_ .NumCPU is the NumCPU property of the current virtual machine in the pipeline. -gt means greater than, so the preceding command shows all virtual machines' objects where the NumCPU property has a value greater than 1.

PowerShell v3 introduced a new, easier syntax for the Where-Object cmdlet. You don't have to use a scriptblock anymore. You can now use the following command:

```
PowerCLI C:\> Get-VM | Where-Object NumCPU -gt 1
```

Isn't the preceding command much more like simple English?



In the rest of this book, the PowerShell v2 syntax will be used by default because the v2 syntax will also work in PowerShell v3. If PowerShell v3 syntax is used anywhere, it will be specifically mentioned.

Using comparison operators

In the previous section, you saw an example of the -gt comparison operator. In the following table, we will show you all of the PowerShell comparison operators:

Operator	Description
-eq, -ceq, and -ieq	Equals
-ne, -cne, and -ine	Not equals
-gt, -cgt, and -igt	Greater than
-ge, -cge, and-ige	Greater than or equal to
-lt, -clt, and-ilt	Less than
-le, -cle, and-ile	Less than or equal to

In the preceding table, you see three different operators for all functions. So what is the difference? The c variant is case-sensitive. The two-letter variant and the \mathtt{i} variant are case-insensitive. The \mathtt{i} variant is made to make it clear that you want to use the case-insensitive operator.

Using aliases

The Where-Object cmdlet has an alias, ?. Therefore, both the following commands will display a list of all your virtual machines that have more than one virtual CPU:

- PowerCLI C:\> Get-VM | ? {\$_.NumCPU -gt 1}
- PowerCLI C:\> Get-VM | Where-Object NumCPU -gt 1

Using aliases will save you from the trouble of typing in the PowerCLI console. However, it is good practice to use the full cmdlet names when you write a script. This will make the script much more readable and easier to understand. To see a list of all of the aliases that are defined for cmdlets, type the following command:

```
PowerCLI C:\> Get-Alias
```

You can create your own aliases using the New-Alias cmdlet. For example, to create an alias childs for the Get-ChildItem cmdlet, you can use the following command:

```
PowerCLI C:\> New-Alias -Name childs -Value Get-ChildItem
```

Retrieving a list of all of your hosts

Similar to the Get-VM cmdlet, which retrieves your virtual machines, is the Get-VMHost cmdlet, which displays your hosts. The Get-VMHost cmdlet has the following syntax:

You see that there are four different parameter sets. They are named: Default, DistributedSwitch, SecondaryParameterSet, and ById. Don't mix parameters from different sets or you will get an error as follows:

+ FullyQualifiedErrorId :

AmbiguousParameterSet,

VMware.VimAutomation.ViCore.Cmdlets.Commands.GetVMHost

To get a list of all of your hosts, type the following command:

PowerCLI C:\> Get-VMHost

By default, only the Name, ConnectionState, PowerState, NumCPU, CpuUsageMhz, CpuTotalMhz, MemoryUsageGB, MemoryTotalGB, and Version properties are shown. To get a list of all of the properties, type the following command:

PowerCLI C:\> Get-VMHost | Format-List -Property *

State : Connected
ConnectionState : Connected
PowerState : PoweredOn

VMSwapfileDatastoreId:

VMSwapfilePolicy : Inherit

ParentId : ClusterComputeResource-domain-c7

IsStandalone : False

Manufacturer : VMware, Inc.

Model : VMware Virtual Platform

NumCpu : 2
CpuTotalMhz : 4588
CpuUsageMhz : 54

LicenseKey : 00000-00000-00000-00000

MemoryTotalMB : 2047.48828125

MemoryTotalGB : 1.999500274658203125

MemoryUsageMB : 965

MemoryUsageGB : 0.9423828125

ProcessorType : Intel(R) Core(TM) i5-2415M CPU @ 2.30GHz

HyperthreadingActive : False
TimeZone : UTC
Version : 5.5.0
Build : 1331820
Parent : Cluster01

VMSwapfileDatastore :

StorageInfo : HostStorageSystem-storageSystem-22

NetworkInfo : localhost:sitecomwl306

DiagnosticPartition : mpx.vmhba1:C0:T0:L0

FirewallDefaultPolicy: VMHostFirewallDefaultPolicy:HostSystem-host-22

ApiVersion : 5.5

Name : 192.168.0.133

CustomFields : { [AutoDeploy.MachineIdentity,] }

ExtensionData : VMware.Vim.HostSystem

Id : HostSystem-host-22

Uid : /VIServer=root@192.168.0.132:443/

VMHost=HostSystem-host-22/

Client : VMware.VimAutomation.ViCore.Impl.V1.VimClient

DatastoreIdList : {Datastore-datastore-23}


You can use the Get-VMHost parameters or the Where-Object cmdlet to filter the hosts you want to display, as we did with the Get-VM cmdlet.

Displaying the output in a grid view


Instead of displaying the output of your PowerCLI commands in the PowerCLI console, you can also display the output in a grid view. A grid view is a pop up that looks like a spreadsheet with rows and columns. To display the output of the Get-VMHost cmdlet in a grid view, type the following command:

PowerCLI C:\> Get-VMHost | Out-GridView

The preceding command opens the window of the following screenshot:



You can create filters to display only certain rows, and you can sort columns by clicking on the column header. You can also reorder columns by dragging and dropping them. In the next screenshot, we created a filter to show only the hosts with a CpuUsageMhz value greater than or equal to 70. We also changed the order of the **ConnectionState** and **PowerState** columns.



Isn't that cool?

Summary

In this chapter, we looked at downloading and installing PowerCLI and modified the PowerShell execution policy to be able to start PowerCLI. Then we covered how to connect to and disconnect from a server and introduced the credential store to save you from having to specify credentials when you connect to a server. You also learned how to get a list of your virtual machines or hosts and how to stop deprecated warnings. You learned all of the PowerShell comparison operators and found out about aliases for cmdlets. Finally, we concluded the chapter with grid views.

In the next chapter, we will introduce some basic PowerCLI concepts.

Learning Basic PowerCLI Concepts

While learning something new, you always have to learn the basics first. In this chapter, you will learn some basic PowerShell and PowerCLI concepts. Knowing these concepts will make it easier for you to learn the advanced topics. We will cover the following topics in this chapter:

- Using the Get-Command, Get-Help, and Get-Member cmdlets
- Using providers and PSDrives
- Using arrays and hash tables
- Creating calculated properties
- Using raw API objects with ExtensionData or Get-View
- Extending PowerCLI objects with the New-VIProperty cmdlet
- Working with vSphere folders

Using the Get-Command, Get-Help, and Get-Member cmdlets

There are some PowerShell cmdlets that everyone should know. Knowing these cmdlets will help you to discover other cmdlets, their functions, parameters, and returned objects.


Using Get-Command

The first cmdlet that you should know is Get-Command. This cmdlet returns all of the commands that are installed on your computer. The Get-Command cmdlet has the following syntax:

```
Get-Command [[-ArgumentList] <Object[]>] [-All] [-ListImported]
[-Module <String[]>] [-Noun <String[]>] [-ParameterName <String[]>]
[-ParameterType <PSTypeName[]>] [-Syntax] [-TotalCount <Int32>] [-Verb <String[]>] [<CommonParameters>]
```

```
Get-Command [[-Name] <String[]>] [[-ArgumentList] <Object[]>] [-All]
[-CommandType <CommandTypes>] [-ListImported] [-Module <String[]>]
[-ParameterName <String[]>] [-ParameterType <PSTypeName[]>] [-Syntax]
[-TotalCount <Int32>] [<CommonParameters>]
```

Downloading the example code



The first parameter set is called CmdletSet and the second parameter set is called AllCommandSet.

If you type the following command then you will get a list of commands installed on your computer including cmdlets, aliases, functions, workflows, filters, scripts, and applications:

```
PowerCLI C:\> Get-Command
```

You can also specify the name of a specific cmdlet to get information about that cmdlet as shown in the following command:

```
PowerCLI C:\> Get-Command -Name Get-VM
```

This will return the following information about the Get-VM cmdlet:

```
CommandType Name ModuleName
-----
Cmdlet Get-VM VMware.VimAutomation.Core
```

You see that the command returns the command type and the name of the module that contains the Get-VM cmdlet. CommandType, Name, and ModuleName are the properties that the Get-VM cmdlet returns by default. You will get more properties if you pipe the output to the Format-List cmdlet:

```
PowerCLI C:\> Get-Command -Name Get-VM | Format-List *
HelpUri
                    : http://www.vmware.com/support/developer/PowerCLI/
PowerCLI55R1/html/Get-VM.html
                    : C:\Program Files (x86)\VMware\Infrastructure\
vSphere PowerCLI\VMware.VimAutomation.ViCore.Cmdlets.dll
Verb
                    : Get
Noun
                    : VM
HelpFile
                    : VMware.VimAutomation.ViCore.Cmdlets.dll-Help.xml
PSSnapIn
                    : VMware.VimAutomation.Core
ImplementingType
                    : VMware.VimAutomation.ViCore.Cmdlets.Commands.GetVM
Definition
                      Get-VM [[-Name] <string[]>] [-Server <VIServer[]>]
[-Datastore <StorageResource[]>] [-Location <VIContainer[]>] [-Tag
<Tag[]>] [-NoRecursion] [<CommonParameters>]
                      Get-VM [[-Name] <string[]>] [-Server
<VIServer[]>] [-DistributedSwitch <DistributedSwitch[]>] [-Tag <Tag[]>]
[<CommonParameters>]
                      Get-VM [-Server <VIServer[]>] [-Id <string[]>]
[<CommonParameters>]
                      Get-VM -RelatedObject <VmRelatedObjectBase[] >
[<CommonParameters>]
DefaultParameterSet : Default
OutputType
                    : { VMware.VimAutomation.ViCore.Types.V1.Inventory.
VirtualMachine }
Options
                    : ReadOnly
Name
                    : Get-VM
CommandType
                    : Cmdlet
                    : Public
Visibility
ModuleName
                    : VMware.VimAutomation.Core
```

```
Module :
RemotingCapability : PowerShell

Parameters : { [Name, System.Management.Automation.
ParameterMetadata], [Server, System.Management.Automation.
ParameterMetadata], [Datastore,

System.Management.Automation.ParameterMetadata], [DistributedSwitch,
System.Management.Automation.ParameterMetadata]...}

ParameterSets : { [[-Name] < string[] >] [-Server < VIServer[] >]
[-Datastore < StorageResource[] >] [-Location < VIContainer[] >] [-Tag
<Tag[] >] [-NoRecursion] [< CommonParameters >], [[-Name] < string[] >]
[-Server < VIServer[] >] [-DistributedSwitch < DistributedSwitch[] >]
[-Tag <Tag[] >] [< CommonParameters >], [-Server < VIServer[] >] [-Id
<string[] >] [< CommonParameters >], -RelatedObject < VmRelatedObjectBase[] >
[< CommonParameters >] }
```

You can use the Get-Command cmdlet to search for cmdlets. For example, if you want search for the cmdlets that are used for vSphere hosts, type:

```
PowerCLI C:\> Get-Command -Name *VMHost*
```

If you are searching for the cmdlets to work with networks, type:

```
PowerCLI C:\> Get-Command -Name *network*
```

Using Get-VICommand

PowerCLI has a cmdlet Get-VICommand that is similar to the Get-Command cmdlet. The Get-VICommand cmdlet is actually a function that creates a filter on the Get-Command output and returns only PowerCLI commands. Type the following command to list all of the PowerCLI commands:

```
PowerCLI C:\> Get-VICommand
```

The Get-VICommand cmdlet has only one parameter -Name. So you can also type, for example, the following command to get information only about the Get-VM cmdlet

```
PowerCLI C:\> Get-VICommand -Name Get-VM
```

Using Get-Help

To discover more information about cmdlets, you can use the Get-Help cmdlet. For example:

```
PowerCLI C:\> Get-Help Get-VM
```

will display the following information about the Get-VM cmdlet:

```
VMware vSphere PowerCLI 5.1 Release 2

PowerCLI C:\> Get-Help Get-UM

NAME
Get-UM

SYNOPSIS
This cmdlet retrieves the virtual machines on a vCenter Server system.

SYNTAX
Get-UM [[-Name] \(String[])] [-Server \(\text{VIServer[]})] \( [-Datastore \( String[])] \) [-Location \( \text{VUIContainer[]})] [-DistributedSwitch \( (DistributedSwitch[])] \( [-DistributedSwitch \( (DistributedSwitch[])] \) [\( (CommonParameters)] \( (CommonParameters)] \)


Get-UM [[-Server \( (VIServer[]))] -Id \( (String[]) \) [\( (CommonParameters)] \( (CommonParameters)] \)

Get-UM -RelatedObject \( (UmRelatedObjectBase[]) \) [\( (CommonParameters)] \)

DESCRIPTION
This cmdlet retrieves the virtual machines on a vCenter Server system. Returns a set of virtual machines that correspond to the filter criteria provided by the cmdlet parameters. For virtual machines with multiple NICs and multiple IP addresses, the IPAddress property of the UMGuest object contains all IP addresses of the virtual machine. The IP at position \( \text{0} \) is the primary IP address.
```


The Get-Help cmdlet has some parameters that you can use to get more information. The -examples parameter shows examples of the cmdlet. The -detailed parameter adds parameter descriptions and examples to the basic help display. The -full parameter displays all of the information available about the cmdlet. And the -online parameter retrieves online help information available about the cmdlet and displays it in a web browser. In PowerShell v3, there is a new Get-Help parameter - ShowWindow. This displays the output of Get-Help in a new window.

The Get-Help Get-Help -ShowWindow command opens the following screenshot:



Using Get-PowerCLIHelp

The PowerCLI Get-PowerCLIHelp cmdlet opens a separate help window for PowerCLI cmdlets, PowerCLI objects, and articles. This is a very useful tool if you want to browse through the PowerCLI cmdlets or PowerCLI objects.



Using Get-PowerCLICommunity

If you have a question about PowerCLI and you can't find the answer in this book, use the <code>Get-PowerCLICommunity</code> cmdlet to open the VMware vSphere PowerCLI section of the VMware VMTN Communities. You can log in to the VMware VMTN Communities using the same <code>My VMware</code> account that you used to download PowerCLI. First, search the community for an answer to your question. If you still can't find the answer, go to the <code>Discussions</code> tab and ask your question by clicking on the <code>Start a discussion</code> button. You might receive an answer to your question in a few minutes.



Using Get-Member

In PowerCLI, you work with objects. Even a string is an object. An object contains properties and methods; these are called members in PowerShell. To see which members an object contains, you can use the <code>Get-Member</code> cmdlet. To see the members of a string, type:

```
PowerCLI C:\> "Learning PowerCLI" | Get-Member
```

Pipe an instance of a PowerCLI object to Get-Member to retrieve the members of that PowerCLI object. For example, to see the members of a virtual machine object, you can type:

```
PowerCLI C:\> Get-VM | Get-Member
```

TypeName:

VMware.VimAutomation.ViCore.Impl.V1.Inventory.VirtualMachineImpl

Name	${\tt MemberType}$	Definition
ConvertToVersion	Method	T VersionedObjectInterop.Conver
Equals	Method	bool Equals(System.Object obj)
GetHashCode	Method	<pre>int GetHashCode()</pre>
GetType	Method	<pre>type GetType()</pre>
IsConvertableTo	Method	bool VersionedObjectInterop.IsC
LockUpdates	Method	<pre>void ExtensionData.LockUpdates()</pre>
ObtainExportLease	Method	VMware.Vim.ManagedObjectReferen
ToString	Method	string ToString()
UnlockUpdates	Method	<pre>void ExtensionData.UnlockUpdates()</pre>
CDDrives	Property	VMware.VimAutomation.ViCore.Typ
Client	Property	VMware.VimAutomation.ViCore.Int
CustomFields	Property	System.Collections.Generic.IDic
DatastoreIdList	Property	string[] DatastoreIdList {get;}
Description	Property	string Description {get;}
DrsAutomationLevel	Property	System.Nullable[VMware.VimAutom
ExtensionData	Property	<pre>System.Object ExtensionData {get;}</pre>
FloppyDrives	Property	VMware.VimAutomation.ViCore.Typ
Folder	Property	VMware.VimAutomation.ViCore.Typ
FolderId	Property	string FolderId {get;}

		·
Guest	Property	VMware.VimAutomation.ViCore.Typ
HAIsolationResponse	Property	System.Nullable[VMware.VimAutom
HardDisks	Property	VMware.VimAutomation.ViCore.Typ
HARestartPriority	Property	System.Nullable[VMware.VimAutom
Host	Property	VMware.VimAutomation.ViCore.Typ
HostId	Property	string HostId {get;}
Id	Property	string Id {get;}
MemoryGB	Property	<pre>decimal MemoryGB {get;}</pre>
MemoryMB	Property	<pre>decimal MemoryMB {get;}</pre>
Name	Property	string Name {get;}
NetworkAdapters	Property	VMware.VimAutomation.ViCore.Typ
Notes	Property	string Notes {get;}
NumCpu	Property	<pre>int NumCpu {get;}</pre>
PersistentId	Property	string PersistentId {get;}
PowerState	Property	VMware.VimAutomation.ViCore.Typ
ProvisionedSpaceGB	Property	<pre>decimal ProvisionedSpaceGB {get;}</pre>
ResourcePool	Property	VMware.VimAutomation.ViCore.Typ
ResourcePoolId	Property	string ResourcePoolId {get;}
Uid	Property	string Uid {get;}
UsbDevices	Property	VMware.VimAutomation.ViCore.Typ
UsedSpaceGB	Property	<pre>decimal UsedSpaceGB {get;}</pre>
VApp	Property	VMware.VimAutomation.ViCore.Typ
Version	Property	VMware.VimAutomation.ViCore.Typ
VMHost	Property	VMware.VimAutomation.ViCore.Typ
VMHostId	Property	string VMHostId {get;}
${\tt VMResourceConfiguration}$	Property	VMware.VimAutomation.ViCore.Typ
VMSwapfilePolicy	Property	System.Nullable[VMware.VimAutom

The command returns the full type name of the VirtualMachineImpl object and all its methods and properties. Remember that the properties are objects themselves. You can also use Get-Member to get the members of the properties. For example, the following command line will give you the members of the VMGuestImpl object:

```
PowerCLI C:\> $VM = Get-VM -Name vCenter
PowerCLI C:\> $VM.Guest | Get-Member
```

Using providers and PSDrives

Until now, you have only seen cmdlets. Cmdlets are PowerShell commands. However, PowerShell has another import concept named **providers**. Providers are accessed through named drives or **PSDrives**. In the following sections, providers and PSDrives will be explained.

Using providers

A PowerShell provider is a piece of software that makes data stores look like filesystems. PowerShell providers are usually part of a snap-in or a module-like PowerCLI. The advantage of providers is that you can use the same cmdlets for all of the providers. These cmdlets have the following nouns: Item, ChildItem, Content, and ItemProperty. You can use the Get-Command cmdlet to get a list of all of the cmdlets with these nouns:

PowerCLI C:> Get-Command -Noun Item, ChildItem, Content, ItemProperty

CommandType	Name	ModuleName
Cmdlet	Add-Content	Microsoft.PowerShell.Management
Cmdlet	Clear-Content	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Clear-Item	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Clear-ItemProperty	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Copy-Item	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Copy-ItemProperty	Microsoft.PowerShell.Management
Cmdlet	Get-ChildItem	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Get-Content	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Get-Item	Microsoft.PowerShell.Management
Cmdlet	Get-ItemProperty	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Invoke-Item	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Move-Item	Microsoft.PowerShell.Management
Cmdlet	Move-ItemProperty	Microsoft.PowerShell.Management
Cmdlet	New-Item	${\tt Microsoft.PowerShell.Management}$
Cmdlet	New-ItemProperty	Microsoft.PowerShell.Management
Cmdlet	Remove-Item	Microsoft.PowerShell.Management
Cmdlet	Remove-ItemProperty	Microsoft.PowerShell.Management

Cmdlet	Rename-Item	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Rename-ItemProperty	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Set-Content	Microsoft.PowerShell.Management
Cmdlet	Set-Item	${\tt Microsoft.PowerShell.Management}$
Cmdlet	Set-ItemProperty	Microsoft.PowerShell.Management

To display a list of all of the providers in your PowerCLI session, you can use the Get-PSProvider cmdlet:

PowerCLI C:\> Get-PSProvider

Name	Capabilities	Drives
Alias	ShouldProcess	{Alias}
Environment	ShouldProcess	$\{{\tt Env}\}$
FileSystem	Filter, ShouldProcess, Credentials	{C, H, D}
Function	ShouldProcess	{Function}
Registry	ShouldProcess, Transactions	{HKLM, HKCU}
Variable	ShouldProcess	${\tt Variable}$
Certificate	ShouldProcess	{Cert}
WSMan	Credentials	$\{ {\tt WSMan} \}$
VimDatastore	ShouldProcess	{vmstores, vmstore}
VimInventory	Filter	{vis, vi}

The VimDatastore and VimInventory providers are part of PowerCLI. You will soon learn more about the VimDatastore and VimInventory providers.

Using PSDrives

Each provider has one or more drives. For example, the FileSystem provider has drives named C, H, and D, which are hard disks on my PC. You can use the drives to access the providers. Microsoft calls these drives PSDrives to prevent confusing the drives with physical drives in your computer. For instance, to get a listing of all of the files and folders in the root of C: on your PC, type:

PowerCLI C:\> Get-ChildItem C:\

The Get-ChildItem cmdlet has aliases dir, gci, and ls that give you the same result:

```
PowerCLI C:\> dir C:\
PowerCLI C:\> ls C:\
```

You can use the same Get-ChildItem cmdlet to get a list of all of your cmdlet aliases by typing:

PowerCLI C:\> Get-ChildItem alias:

Using the vSphere PowerCLI Inventory Provider

The **Inventory Provider** gives you a filesystem-like view of the inventory items from a vCenter Server or an ESXi server. You can use this provider to view, move, rename, or delete objects by running PowerCLI commands.

When you connect to a server with the Connect-VIServer cmdlet, two PSDrives are created: vi and vis. The vi PSDrive contains the inventory of the last connected server. The vis PSDrive contains the inventory of all currently connected servers in your PowerCLI session.

You can set the location to the vis PSDrive using the Set-Location cmdlet:

```
PowerCLI C:\> Set-Location vis:
PowerCLI vis:\>
```

Use the Get-ChildItem cmdlet to display the items in the current location of the vis PSDrive:

PowerCLI vis:\> Get-ChildItem

Name	Type	Id
vCenter@443	VIServer	/VIServer=bl

Use the Get-ChildItem -Recurse parameter to display all of the items in the Inventory Provider:

PowerCLI vis:\> Get-ChildItem -Recurse

Using the vSphere PowerCLI Datastore Provider

The **Datastore Provider** gives you access to the content of your vSphere datastores.

When you connect to a server with the Connect-VIServer cmdlet, two PSDrives are created: vmstore and vmstores. The vmstore PSDrive contains the datastores of the last connected server. The vmstores PSDrive contains the datastores of all the currently connected servers in your PowerCLI session. You can use these two default PSDrives or you can create custom PSDrives using the New-PSDrive cmdlet.

Set the location to the vmstore PSDrive with the following command:

```
PowerCLI C:\> Set-Location vmstore:
PowerCLI vmstore:\>
```

Display the content of the root directory of the vmstore PSDrive with the following command:

PowerCLI vmstore:\> Get-ChildItem

Name	Type	Id
YourDatacenter	Datacenter	Datacenter-d

You have to go one level deeper to get a listing of your datastores:

```
PowerCLI vmstore:\> Set-Location YourDatacenter
PowerCLI vmstore:\ YourDatacenter > Get-ChildItem
```

You can also create a custom PSDrive for a datastore using the New-PSDrive cmdlet. Start with getting a datastore object and save it in the \$Datastore variable:

```
PowerCLI C:\> $Datastore = Get-Datastore -Name Datastore1
```

Create a new PowerShell PSDrive named ds that maps to the \$Datastore variable:

```
PowerCLI C:\> New-PSDrive -Location $Datastore -Name ds -PSProvider VimDatastore -Root "\"
```

Now, you can change your location into the PowerShell PSDrive using the Set-Location cmdlet:

PowerCLI C:\> Set-Location ds:

You can get a listing of the files and directories on the datastore using the Get-ChildItem cmdlet:

PowerCLI ds:\> Get-ChildItem

You will see an output similar to:

Datastore path: [Datastore1]

LastWriteTi	ime	Type	Length	Name
12/22/2013 3:14	PM	Folder		.dvsData
12/20/2013 8:14	PM	Folder		.naa.600a0b800011
12/21/2013 10:06	AM	Folder		ISOfiles
12/21/2013 2:05	PM	Folder		vCenter Mobile Ac
12/22/2013 1:24	PM	Folder		.vSphere-HA

Copying files between a datastore and your PC

You can use the vSphere Datastore Provider to copy files between a datastore and your PC using the Copy-DatastoreItem cmdlet.

Change the location to a subfolder using the Set-Location cmdlet with the help of the following command line:

PowerCLI ds:\> Set-Location "virtualmachine1"

Copy a file or directory to the destination using the Copy-DatastoreItem cmdlet as follows:

PowerCLI ds:\virtualmachinel> Copy-DatastoreItem -Item ds:\
virtualmachinel\virtualmachinel.vmx -Destination c:\virtualmachinel\

Now, you can view the content of the virtualmachine1.vmx file with:

PowerCLI C:\> Get-Content c:\virtualmachine1\virtualmachine1.vmx



Files cannot be copied directly between vSphere datastores in different vCenter Servers using Copy-DatastoreItem. Copy the files to the PowerCLI host's local filesystem temporarily, and then copy them to the destination

Using arrays and hash tables

In PowerCLI, you can create a list of objects. For example, "red", "white", "blue" is a list of strings. In PowerShell, a list of terms is called an **array**. An array can have zero or more objects. You can create an empty array and assign it to a variable:

```
PowerCLI C:\> $Array = @()
```

You can fill the array during creation using the following command line:

```
PowerCLI C:\> $Array = @("red","white")
```

You can use the += operator to add an element to an array:

```
PowerCLI C:\> $Array += "blue"
PowerCLI C:\> $Array
red
white
blue
```

If you want to retrieve a specific element of an array, you can use an index starting with 0 for the first element, 1 for the second element, and so on. If you want to retrieve an element from the tail of the array, you have to use -1 for the last element, -2 for the second to last, and so on. You have to use square brackets around the index number. In the next example, the first element of the array is retrieved using the following command line:

```
PowerCLI C:\> $Array[0]
Red
```

If you want to test whether an object is an array, you can use:

```
PowerCLI C:\> $Array -is [array]
True
```

There is a different kind of an array called a **hash table**. In a hash table, you map a set of keys to a set of values. You can create an empty hash table using the following command line:

```
PowerCLI C:\> $HashTable = @{}
```

You can fill the hash table during creation using the following command line:

```
PowerCLI C:\> $HashTable = @{LastName='Doe';FirstName='John'}
```

To add a key-value pair to a hash table, you can use the following command line:

```
PowerCLI C:\> $HashTable["Company"]='VMware'
```

To show the contents of the hash table, just display the variable:

PowerCLI C:\> \$HashTable

Name	Value
Company	VMware
FirstName	John
LastName	Doe

If you want to retrieve a specific key-value pair, you can use:

```
PowerCLI C:\> $HashTable["FirstName"]
```

John

To retrieve all of the hash table's keys, you can use the Keys property:

```
PowerCLI C:\> $HashTable.Keys
```

Company

FirstName

LastName

To retrieve all of the values in the hash table, you can use the Values property:

```
PowerCLI C:\> $HashTable.Values
```

VMware

John

Doe

If you want to test whether an object is a hash table, you can use:

```
PowerCLI C:\> $HashTable -is [hashtable]
```

True

In the next section, hash tables will be used to create calculated properties.

Creating calculated properties

You can use the Select-Object cmdlet to select certain properties of the objects that you want to return. For example, you can use the following code to return the name and the used space, in GB, of your virtual machines:

```
PowerCLI C:\> Get-VM | Select-Object -Property Name, UsedSpaceGB
```

But what if you want to return the used space in MB? The PowerCLI VirtualMachineImpl object has no UsedSpaceMB property. This is where you can use a **calculated property**. A calculated property is a PowerShell hash table with two elements: Name and Expression. The Name element contains the name that you want to give the calculated property. The Expression element contains a scriptblock with PowerCLI code to calculate the value of the property. To return the name and the used space in MB for all of your virtual machines, run the following command:

```
PowerCLI C:\> Get-VM |
>> Select-Object -Property Name,
>> @{Name="UsedSpaceMB";Expression={1KB*$_.UsedSpaceGB}}}
>>
```

The hash table contains two key-value pairs. In the first element, the key is Name and the value is UsedSpaceMB. In the other element, the key is Expression and the value is {1KB*\$_.UsedSpaceGB}. The special variable \$_ is used to represent the current object in the pipeline. 1KB is a PowerShell constant that has the value 1024. In calculated properties, you can abbreviate the Name and Expression names to N and E.

Another example of a calculated property shows you how to return the aliases of all of the cmdlets that are the same for all of the providers:

```
PowerCLI C:\> Get-Command -Noun Item, ChildItem, Content, ItemProperty |
>> Select-Object -Property Name,
>> @{Name="Aliases"; Expression={Get-Alias -Definition $_.Name}}
```

Name	Aliases
Add-Content	ac
Clear-Content	clc
Clear-Item	cli
Clear-ItemProperty	clp
Copy-Item	{copy, cp, cpi}
Copy-ItemProperty	cpp
Get-ChildItem	{dir, gci, ls}
Get-Content	<pre>{cat, gc, type}</pre>
Get-Item	gi
Get-ItemProperty	gp
Invoke-Item	ii

```
Move-Item
                     {mi, move, mv}
Move-ItemProperty
                    mp
New-Item
New-ItemProperty
                     {del, erase, rd, ri...}
Remove-Item
Remove-ItemProperty rp
Rename-Item
                     {ren, rni}
Rename-ItemProperty rnp
Set-Content
Set-Item
                     яi
Set-ItemProperty
```

The first command is the Get-Command statement that you have seen before; this returns the cmdlets that are the same for all of the providers. In the calculated property, the Get-Alias cmdlet is used to get the aliases of these commands.

Using raw API objects with ExtensionData or Get-View

PowerCLI makes it easy to use the VMware vSphere application programming interface (API). There are two ways to do this. The first one is by using the ExtensionData property that most of the PowerCLI objects have. The Extensiondata property is a direct link to the vSphere API object related to the PowerCLI object. The second way is by using the Get-View cmdlet to retrieve the vSphere API object related to a PowerCLI object. Both these ways will be discussed in the following sections.

Using the ExtensionData property

Most PowerCLI objects, such as VirtualMachineImpl and VMHostImpl, have a property called ExtensionData. This property is a reference to a view of a VMware vSphere object as described in the "VMware vSphere API Reference Documentation". For example, the ExtensionData property of the PowerCLI's VirtualMachineImpl object links to a vSphere VirtualMachine object view. ExtensionData is a very powerful property because it allows you to use all of the properties and methods of the VMware vSphere API. For example, to see if the VMware Tools are running in your virtual machines, you can run the following command:

```
PowerCLI C:\> Get-VM |
>> Select-Object -Property Name,
```

```
>> @{Name = "ToolsRunningStatus"
>> Expression = {$_.ExtensionData.Guest.ToolsRunningStatus}
>> }
>>
```

If VMware Tools are not installed in a virtual machine, the ExtensionData.Guest. ToolsStatus property will have the value toolsNotInstalled. You can check the tools' status with:

```
PowerCLI C:\> Get-VM |
>> Select-Object -Property Name,
>> @{Name = "ToolsStatus"
     Expression = {$ .ExtensionData.Guest.ToolsStatus}
>> }
>>
Name
                                   ToolsStatus
                                    -----
VM1
                             toolsNotInstalled
DNS1
                                       toolsOk
DC1
                               toolsNotRunning
WindowsServer2012
                                      toolsOld
```

Using the Get-View cmdlet

Another way to get the vSphere API objects is by using the Get-View cmdlet. This cmdlet returns a vSphere object view, which is the same object you can retrieve via the ExtensionData property. For example, the following two PowerCLI commands will give you the same result:

```
PowerCLI C:\> (Get-VM -Name vCenter).ExtensionData
PowerCLI C:\> Get-VIew -VIObject (Get-VM -Name vCenter)
The Get-View cmdlet has the following syntax:
Get-View [-VIObject] <VIObject[]> [-Property <String[]>]
[<CommonParameters>]
Get-View [-Server <VIServer[]>] [-SearchRoot <ManagedObjectReference>]
-ViewType <Type> [-Filter <Hashtable>] [-Property <String[]>]
[<CommonParameters>]
```

```
Get-View [-Server <VIServer[]>] [-Id] <ManagedObjectReference[]>
[-Property <String[]>] [<CommonParameters>]

Get-View [-Property <String[]>] -RelatedObject <ViewBaseMirroredObject[]>
[<CommonParameters>]
```

The names of the parameter sets are: GetViewByVIObject, GetEntity, GetView, and GetViewByRelatedObject. The second parameter set, GetEntity, is very powerful and will allow you to create PowerCLI commands or scripts that are optimized for speed. For example, the following command will give you the vSphere object views of all virtual machines and templates:

```
PowerCLI C:\> Get-View -ViewType VirtualMachine
```

Possible argument values for the -ViewType parameter are:

ClusterComputeResource, ComputeResource, Datacenter, Datastore, DistributedVirtualPortgroup, DistributedVirtualSwitch, Folder, HostSystem, Network, OpaqueNetwork, ResourcePool, StoragePod, VirtualApp, VirtualMachine, and VmwareDistributedVirtualSwitch.

If you want only the virtual machines and not the templates, you need to specify a filter:

```
PowerCLI C:\> Get-View -ViewType VirtualMachine -Filter @{" Config.
Template" = "false"}
```

The filter is in the form of a hash table in which you specify that the value of the Config. Template property needs to be false to get only the virtual machines.

To make your command run faster, you need to specify the properties that you want to return. Otherwise all of the properties are returned and that will make your command run slower.

Let's retrieve only the name and the overall status of your virtual machines:

```
PowerCLI C:\> Get-View -ViewType VirtualMachine -Filter @{"Config.
Template" = "false"} -Property Name,OverallStatus |
>> Select-Object -Property Name,OverAllStatus
```

This command runs in my test environment about 23 times faster than the equivalent:

```
PowerCLI C:\> Get-VM | Select-Object -Property Name,
@{Name="OverallStatus"; Expression={$ .ExtensionData.OverallStatus}}
```

The conclusion is: if you need your script to run faster, try to find a solution using the Get-View cmdlet.



You should always make a trade-off between the time it takes you to write a script and the time it takes you to run the script. If you spend 10 minutes to create a script that takes one hour to run, you will have your work done in 70 minutes. If you spend two hours to create a faster script that runs in 10 minutes, you will have your work done in 130 minutes. I would prefer the first solution. Of course, if you intend to run the script more than once, the time you spend to improve the speed of your script is spent better.

Using Managed Object References

If you look at a vSphere object view using the Get-Member cmdlet, you will see that a lot of properties are from type VMware.Vim.ManagedObjectReference:

```
PowerCLI C:\> Get-VM -Name vCenter | Get-View | Get-Member |
>> Where-Object {$_.Name -eq 'Parent'}
>>

TypeName: VMware.Vim.VirtualMachine

Name MemberType Definition
```

A **Managed Object Reference** (**MoRef**) is a unique value that is generated by the vCenter Server and is guaranteed to be unique for a given entity in a single vCenter instance.



Parent Property

The vSphere object views returned by the ExtensionData property or by the Get-View cmdlet are not the actual vSphere objects. The objects returned are copies or views of the actual objects that represent the actual objects at the time the view was made.

VMware.Vim.ManagedObjectReference Parent {get;}

Using the Get-VIObjectByVIView cmdlet

The Get-View cmdlet gives you a way to go from a PowerCLI object to a vSphere object view. If you want to go back from a vSphere object view to a PowerCLI object, you can use the Get-VIObjectByVIView cmdlet. For example:

```
PowerCLI C:\> $VMView = Get-VM -Name vCenter | Get-View
PowerCLI C:\> $VM = $VMView | Get-VIObjectByVIView
```

In the previous example, the first line will give you a vSphere object view from a PowerCLI VirtualMachineImpl object. The second line will convert the vSphere object view back to a PowerCLI VirtualMachineImpl object.

The Get-VIObjectByVIView cmdlet has the following syntax:

```
Get-VIObjectByVIView [-VIView] <ViewBase[]> [<CommonParameters>]
Get-VIObjectByVIView [-Server <VIServer[]>] [-MORef]
<ManagedObjectReference[]> [<CommonParameters>]
```

You can see that the <code>Get-VIObjectByVIView</code> cmdlet has two parameter sets. The first parameter set contains the <code>-VIView</code> parameter. The second parameter set contains the <code>-Server</code> and <code>-MORef</code> parameters. Remember that parameters from different parameter sets cannot be mixed in one command.

If you are connected to multiple vCenter Servers, the Get-VIObjectByVIView cmdlet might return objects from multiple vCenter Servers because MoRefs are only unique on a single vCenter Server instance. You can use the -Server parameter of the Get-VIObjectByVIView cmdlet to solve this problem by specifying the vCenter Server for which you want to return objects. Because the -Server parameter is in a different parameter set from the -VIView parameter, you cannot use the -VIView parameter that is used in the pipeline. You have to use the ForEach-Object cmdlet and the-MORef parameter of the Get-VIObjectByVIView cmdlet:

```
PowerCLI C:\> $VMView |
>> ForEach-Object {
>> Get-VIObjectByVIView -Server vCenter1 -MoRef $_.MoRef
>> }
>>
```



In the name of the Get-VIObjectByVIView cmdlet, you can see a piece of the history of PowerCLI. VMware vSphere was named VMware Infrastructure before VMware vSphere 4. The earlier VMware vSphere PowerCLI versions were called VI Toolkit. In the name of this cmdlet, you see that a PowerCLI object is still called a VIObject and a vSphere object view is called a VIView.

Extending PowerCLI objects with the New-VIProperty cmdlet

Sometimes you can have the feeling that a PowerCLI object is missing a property. Although the VMware PowerCLI team tried to include the most useful properties in the objects, you can have the need for an extra property. Luckily, PowerCLI has a way to extend a PowerCLI object using the New-VIProperty cmdlet. This cmdlet has the following syntax:

New-VIProperty [-Name] <String> [-ObjectType] <String[]> [-Value]
<ScriptBlock> [-Force] [-BasedOnExtensionProperty <String[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]

New-VIProperty [-Name] <String> [-ObjectType] <String[]> [-Force]
[-ValueFromExtensionProperty] <String> [-WhatIf] [-Confirm]
[<CommonParameters>]

Let's start with an example. You will add the VMware Tools' running statuses used in a previous example to the VirtualMachineImpl object using the New-VIProperty cmdlet:

PowerCLI C:\> New-VIProperty -ObjectType VirtualMachine -Name ToolsRunningStatus -ValueFromExtensionProperty 'Guest.ToolsRunningStatus'

Name	RetrievingType	DeclaringType	Value
ToolsRunning	VirtualMachine	VirtualMachine	Guest.
ToolsRunningStat	tus		

Now you can get the tools' running statuses of all of your virtual machines with:

PowerCLI C:\> Get-VM | Select-Object -Property Name, ToolsRunningStatus

Isn't this much easier?

In the next example, you will add the vCenterServer property to the VirtualMachineImpl object. The name of the vCenter Server is part of the VirtualMachineImpl Uid property. The Uid property is a string that looks like /VIServer=domain\account@vCenter:443/VirtualMachine=VirtualMachine-vm-239/

You can use the Split() method to split the string. For example, the following command splits the string 192.168.0.1 into an array with four elements:

```
PowerCLI C:\> "192.168.0.1".Split('.')

192

168

0

1
```

The first element is 192, the second element 168, the third element 0, and the fourth and last element 1. If you assign the array to a variable then you can use an index to specify a certain element of the array:

```
PowerCLI C:\> $Array = "192.168.0.1".Split('.')
```

The index is 0 for the first element, 1 for the second element, and so on. If you want to specify the last element of the array, you can use the index -1. For example:

```
PowerCLI C:\> $Array[0]
192
```

In the Uid property, the name of the vCenter Server is between the @ sign and the colon. So you can use those two characters to split the string. First you split the string at the colon and take the part before the colon. That is the first element of the resulting array:

```
PowerCLI C:\> $Uid = '/VIServer=domain\account@vCenter:443/
VirtualMachine=VirtualMachine-vm-239/'
PowerCLI C:\> $Uid.Split(':') [0]
/VIServer=domain\account@vCenter
```

Split the resulting part at the @ sign and take the second element of the resulting array to get the name of the vCenter Server:

```
PowerCLI C:\> $String = '/VIServer=domain\account@vCenter'
PowerCLI C:\> $String.Split('@')[1]
vCenter
```

You can do this splitting with one line of code:

```
PowerCLI C:\> $Uid = '/VIServer=domain\account@vCenter:443/
VirtualMachine=VirtualMachine-vm-239/'
PowerCLI C:\> $Uid.Split(':') [0].Split('@') [1]
vCenter
```

Use the -Value parameter of the New-VIProperty cmdlet to specify a scriptblock. In this scriptblock, \$Args[0] is the object with which you want to retrieve the name of the vCenter Server:

```
PowerCLI C:\> New-VIProperty -Name vCenterServer -ObjectType VirtualMachine -Value {$Args[0].Uid.Split(":")[0].Split("@")[1]} -Force
```

The New-VIProperty -Force parameter indicates that you want to create the new property even if another property with the same name already exists for the specified object type.

Now you can get a list of all of your virtual machines and their vCenter Servers with:

PowerCLI C:\> Get-VM | Select-Object -Property Name, vCenterServer

Working with vSphere folders

In a VMware vSphere environment, you can use folders to organize your infrastructure. In the vSphere web client, you can create folders in the Hosts and Clusters, VMs and Templates, Storage, and Networking inventories. The following screenshot shows an example of folders in the VMs and Templates inventory.



You can browse through these folders using the vSphere PowerCLI Inventory Provider. PowerCLI also has a set of cmdlets to work with these folders: Get-Folder, Move-Folder, New-Folder, Remove-Folder, and Set-Folder.

You can use the Get-Folder cmdlet to get a list of all of your folders:

```
PowerCLI C:\> Get-Folder
```

subfolders or datacenters.

Or you can select specific folders by name using the following command line:

```
PowerCLI C:\> Get-Folder -Name "Accounting"
```

All folders are organized in a tree structure under the root folder. You can retrieve the root folder with:

PowerCLI C:\> Get-Folder -NoRecursion

Name	Туре
Datacenters	Datacenter

The root folder is always called Datacenters. In this folder, you can only create

Folders in vSphere are of a certain type. Valid folder types are VM, HostAndCluster, Datastore, Network, and Datacenter. You can use this to specify the type of folders you want to retrieve. For example, to retrieve only folders of type VM, use:

```
PowerCLI C:\> Get-Folder -Type VM
```

A problem with folders is that you don't get the full path from the root if you retrieve a folder. Using the New-VIProperty cmdlet, you can easily add a Path property to a PowerCLI Folder object:

```
PowerCLI C:\> New-VIProperty -Name Path -ObjectType Folder -Value {
    # $FolderView contains the view of the current folder object
    $FolderView = $Args[0].Extensiondata

# $Server is the name of the vCenter server
    $Server = $Args[0].Uid.Split(":")[0].Split("@")[1]

# We build the path from the right to the left
    # Start with the folder name
    $Path = $FolderView.Name
```

```
# While we are not at the root folder
  while ($FolderView.Parent) {
    # Get the parent folder
    $FolderView = Get-View -Id $FolderView.Parent -Server $Server
    # Extend the path with the name of the parent folder
    $Path = $FolderView.Name + "\" + $Path
  }
  # Return the path
  $Path
} -Force # Create the property even if a property with this name exists
In this example, you see that the # character in PowerShell is used to comment.
Using the new Path property, you can now get the path for all of the folders with:
PowerCLI C:\> Get-Folder | Select-Object -Property Name, Path
You can use the Path property to find a folder by its complete path. For example:
PowerCLI C:\> Get-Folder |
>> Where-Object {$ .Path -eq 'Datacenters\Dallas\vm\Templates'}
>>
```

Summary

In this chapter, you looked at the Get-Help, Get-Command, and Get-Member cmdlets. You learned how to use providers and PSDrives. You also saw how to create a calculated property. Using the raw API objects with the ExtensionData property or the Get-View cmdlet was discussed, and you looked at extending PowerCLI objects with the New-VIProperty cmdlet. At the end, you learned to work with folders and you saw how you can use the New-VIProperty cmdlet to extend the Folder object of PowerCLI with a Path property.

In the next chapter, you will learn more about working with objects in PowerCLI.

Working with Objects in PowerShell

PowerShell is an object-oriented shell. Don't let this scare you because knowing how to work with PowerShell objects will make your life much easier. Objects in PowerShell have properties and methods, just as with objects in real life. For example, let's take a computer and try to see it as an object. It has properties such as the manufacturer, the number of CPUs, the amount of memory, and the computer type (for example, server, workstation, desktop, or laptop). The computer also has methods. For example, you can switch the computer on and off. Properties and methods together are called **members** in PowerShell. In *Chapter 2, Learning Basic PowerCLI Concepts*, you already saw the Get-Member cmdlet that lists the properties and methods of a PowerShell object. In this chapter, you will learn all of the ins and outs of PowerShell objects. We will focus on the following topics:

- Using objects, properties, and methods
- Expanding variables and subexpressions in strings
- Using here-strings
- Using the pipeline
- Using the PowerShell object cmdlets
- Creating your own objects
- Using COM objects

Using objects, properties, and methods

In PowerCLI, even a string is an object. You can list the members of a string object using the Get-Member cmdlet that you have seen before. Let's go back to our example in *Chapter 2*, *Learning Basic PowerCLI Concepts*. First, we create a string "Learning PowerCLI" and put it in a variable called \$string. Then, we take this \$string variable and execute the Get-Member cmdlet using the \$string variable as the input:

```
PowerCLI C:\> $String = "Learning PowerCLI"
PowerCLI C:\> Get-Member -Inputobject $String
```

You can also use the pipeline and do it in a single line, as follows:

```
PowerCLI C:\> "Learning PowerCLI" | Get-Member
```

The output will be the following:

TypeName: System.String

Name	MemberType	Definition
Clone	Method	System.Object Clone(), Syst
CompareTo	Method	<pre>int CompareTo(System.Object</pre>
Contains	Method	bool Contains(string value)
СоруТо	Method	<pre>void CopyTo(int sourceIndex</pre>
EndsWith	Method	bool EndsWith(string value)
Equals	Method	bool Equals(System.Object o
GetEnumerator	Method	System.CharEnumerator GetEn
GetHashCode	Method	int GetHashCode()
GetType	Method	type GetType()
GetTypeCode	Method	System.TypeCode GetTypeCode
IndexOf	Method	<pre>int IndexOf(char value), in</pre>
IndexOfAny	Method	<pre>int IndexOfAny(char[] anyOf</pre>
Insert	Method	string Insert(int startInde
IsNormalized	Method	bool IsNormalized(), bool I
LastIndexOf	Method	<pre>int LastIndexOf(char value)</pre>
LastIndexOfAny	Method	<pre>int LastIndexOfAny(char[] a</pre>
Normalize	Method	string Normalize(), string

PadLeft	Method	string PadLeft(int totalWid
PadRight	Method	string PadRight(int totalWi
Remove	Method	string Remove(int startInde
Replace	Method	string Replace(char oldChar
Split	Method	string[] Split(Params char[
StartsWith	Method	bool StartsWith(string valu
Substring	Method	string Substring(int startI
ToBoolean	Method	bool IConvertible.ToBoolean
ToByte	Method	byte IConvertible.ToByte(Sy
ToChar	Method	char IConvertible.ToChar(Sy
ToCharArray	Method	<pre>char[] ToCharArray(), char[</pre>
ToDateTime	Method	datetime IConvertible.ToDat
ToDecimal	Method	decimal IConvertible.ToDeci
ToDouble	Method	double IConvertible.ToDoubl
ToInt16	Method	<pre>int16 IConvertible.ToInt16(</pre>
ToInt32	Method	<pre>int IConvertible.ToInt32(Sy</pre>
ToInt64	Method	long IConvertible.ToInt64(S
ToLower	Method	string ToLower(), string To
ToLowerInvariant	Method	string ToLowerInvariant()
ToSByte	Method	<pre>sbyte IConvertible.ToSByte(</pre>
ToSingle	Method	float IConvertible.ToSingle
ToString	Method	string ToString(), string T
ТоТуре	Method	System.Object IConvertible
ToUInt16	Method	uint16 IConvertible.ToUInt1
ToUInt32	Method	uint32 IConvertible.ToUInt3
ToUInt64	Method	uint64 IConvertible.ToUInt6
ToUpper	Method	string ToUpper(), string To
ToUpperInvariant	Method	string ToUpperInvariant()
Trim	Method	string Trim(Params char[] t
TrimEnd	Method	string TrimEnd(Params char[
TrimStart	Method	string TrimStart(Params cha
Chars	ParameterizedProperty	<pre>char Chars(int index) {get;}</pre>
Length	Property	<pre>int Length {get;}</pre>

You see that a string has a lot of methods, one property, and a special type of property called ParameterizedProperty. Let's first use the Length property. To use a property, type the object name or the name of the variable containing the object; then type a dot; finally, type the property name. For the string, you could use both of the following command lines:

```
PowerCLI C:\> "Learning PowerCLI".Length
17
PowerCLI C:\> $String.Length
17
```

You see that the Length property contains the number of characters of the string "Learning PowerCLI", 17 in this case.

Property names in PowerShell are not case-sensitive, so you could type the following command and still get the same results:

```
PowerCLI C:\> $String.length
17
```

ParameterizedProperty is a property that accepts a parameter value. The ParameterizedProperty property's Chars can be used to return the character at a specific position in the string. You have to specify the position, also called the index, as a parameter to Chars. Indexes in PowerShell start with 0. Therefore, to get the first character of the string, type the following command:

```
PowerCLI C:\> $String.Chars(0)
L
```

To get the second character of the string, type the following command:

```
PowerCLI C:\> $String.Chars(1)
```

You cannot use -1 to get the last character of the string as you can do with indexing in a PowerShell array. You have to calculate the last index yourself; this is calculated by subtracting 1 from the length of the string. Therefore, to get the last character of the string, you can type the following command:

```
PowerCLI C:\> $String.Chars($String.Length - 1)
I
```

PowerShell has more types of properties, such as AliasProperty, CodeProperty, NoteProperty, and ScriptProperty.

- AliasProperty is an alias name for an existing property
- CodeProperty is a property that maps to a static method on a .NET class
- NoteProperty is a property that contains data
- ScriptProperty is a property whose value is returned from executing a PowerShell scriptblock

Using methods

Using methods is as easy as using properties. You type the object name, or the name of a variable containing the object; then you type a dot; and, after the dot, you type the name of the method. For methods, you always have to use parentheses after the method name. For example, to modify a string to all uppercase letters, type in the following command:

```
PowerCLI C:\> $String.ToUpper()
LEARNING POWERCLI
```

Some methods require parameters. For example, to find the index of the P character in the string, you can use the following command:

```
PowerCLI C:\> $String.IndexOf('P')
9
```

The character P is the tenth character in the "Learning PowerCLI" string. But because indexes in PowerShell start with 0 and not 1, the index of the P character in the string is 9 and not 10.

One very useful method is Replace, which you can use to replace a character or a substring with another character or string or with nothing. For example you can replace all instances of the e characters in the string with the u character, as follows:

```
PowerCLI C:\> $String.Replace('e','u')
Luarning PowurCLI
```

The characters in the method are case-sensitive. If you use an uppercase 'E', it won't find the letter and will replace nothing:

```
PowerCLI C:\> $String.Replace('E','U')
Learning PowerCLI
```

You can also replace a substring with another string. Let's replace the word "PowerCLI" with "VMware vSphere PowerCLI":

```
PowerCLI C:\> $String.Replace('PowerCLI','VMware vSphere PowerCLI')
Learning VMware vSphere PowerCLI
```

There is also a -Replace operator in PowerShell. You can use the -Replace operator to carry out a regular expression-based text substitution on a string or a collection of strings as shown in the following command line:

```
PowerCLI C:\> $string -Replace 'e','u'
Luarning PowurCLI
```

Although both have the same name, the string Replace method and the -Replace operator are two different things. There is no -ToUpper operator; as you can see in the following example, this gives an error message:

```
VMware vSphere PowerCLI 5.5 Release 1 - 

PowerCLI C:\> $String -ToUpper
At line:1 char:9
+ $String -ToUpper
Unexpected token '-ToUpper' in expression or statement.
+ CategoryInfo : ParserError: (:) [1, ParentContainsErrorRecordException
+ FullyQualifiedErrorId : UnexpectedToken
```

You can use more than one method in the same command. Say you want to replace Learning with Gaining and that you want to remove the characters C, L, and I from the end of the string using the TrimEnd method. For this, you can use the following command:

```
PowerCLI C:\> $String.Replace('Learning','Gaining').TrimEnd('CLI')
Gaining Power
```

Expanding variables and subexpressions in strings

In PowerShell, you can define a string with single or double quotes. There is a difference between these two methods. In a string with single quotes, variables and subexpressions are not expanded; while in a string with double quotes, variables and subexpressions are expanded.

Let's look at an example of variable expansion in a double-quoted string:

```
PowerCLI C:\> $Number = 3
PowerCLI C:\> "The number is: $Number"
The number is: 3
```

In the preceding example, the string is defined with double quotes and the \$Number variable is expanded. Let's see what happens if you use single quotes:

```
PowerCLI C:\> $Number = 3
PowerCLI C:\> 'The number is: $Number'
The number is: $Number
```

Using a single-quoted string, PowerShell doesn't expand the \$Number variable. Let's try to put the number of virtual CPUs of a virtual machine in a double-quoted string:

```
PowerCLI C:\> $vm = Get-VM -Name dc1

PowerCLI C:\> "The number of vCPU's of the vm is: $vm.NumCpu"

The number of vCPU's of the vm is: dc1.NumCpu
```

The output is not what you intended. What happened? The \$ in front of a variable name tells PowerShell to evaluate the variable. In the string used in the preceding example, \$vm evaluates the variable vm but does not evaluate \$vm.NumCpu. To evaluate \$vm.NumCpu, you have to use another \$ sign before and parentheses around the code that you want to evaluate, like so: \$ (\$vm.NumCpu). This is called a **subexpression** notation.

In the corrected example, you will get the number of virtual CPUs:

```
PowerCLI C:\> $vm = Get-VM -Name dc1
PowerCLI C:\> "The number of vCPU's of the vm is: $($vm.NumCpu)"
The number of vCPU's of the vm is: 2
```

You can use subexpression evaluation to evaluate any PowerShell code. In the next example, you will use PowerShell to calculate the sum of 3 and 4:

```
PowerCLI C:\> "3 + 4 = $(3+4)"
3 + 4 = 7
```

Understanding what expands a string

A string will be expanded when it is assigned to a variable. It will not be reevaluated when the variable is used later. The following example shows this behavior:

```
PowerCLI C:\> $Number = 3
PowerCLI C:\> $String = "The number is: $Number"
PowerCLI C:\> $String
The number is: 3
PowerCLI C:\> $Number = 4
PowerCLI C:\> $String
The number is: 3
```

As you can see, \$String is assigned before \$Number gets the value 4. The \$String variable stays "The number is: 3".

Expanding a string when it is used

Want to know how to delay the expansion of the string until you use it? PowerShell has a predefined variable called \$ExecutionContext. You can use the InvokeCommand.ExpandString() method of this variable to expand the string:

```
PowerCLI C:\> $Number = 3
PowerCLI C:\> $String = 'The number is: $Number'
PowerCLI C:\> $ExecutionContext.InvokeCommand.ExpandString($String)
The number is: 3
PowerCLI C:\> $Number = 4
PowerCLI C:\> $ExecutionContext.InvokeCommand.ExpandString($String)
The number is: 4
```

The preceding example defines \$String as a single-quoted string, so \$Number is not expanded at the assignment of \$String. The \$ExecutionContext.

InvokeCommand.ExpandString(\$String) command expands the string every time the command is executed.

Using here-strings

Until now, you have only seen single-line strings in this book. PowerShell has a so-called **here-string** that spans multiple lines. You use @" or @' to start the here-string and "@ or '@ to finish the here-string. The @"or @' must be at the end of a line and the "@ or '@ must be at the beginning of the line that terminates the here-string. As in single-line strings, variables and subexpressions are expanded in double-quoted here-strings and are not expanded in single-quoted here-strings.

The following command creates a here-string that spans two lines and puts the here-string in the variable \$s:

```
PowerCLI C:\> $s = @"
>> Learning PowerCLI
>> is a lot of fun!
>> "@
>> $s
>>
Learning PowerCLI
is a lot of fun!
```

Using the pipeline

In PowerShell, you can use the output of one command as input for another command by using the vertical bar (|) character. This is called using the pipeline. The vertical bar character is called the **pipe** character. In PowerShell, complete objects pass through the pipeline. This is different from cmd.exe or a Linux shell where only strings pass through the pipeline. The advantage of passing complete objects through the pipeline is that you don't have to perform string manipulation to retrieve property values.

Using the ByValue parameter binding

You have already seen some examples of using the pipeline in previous sections of this book, for example:

```
PowerCLI C:\> Get-VM | Get-Member
```

In this example, the output of the <code>Get-VM</code> cmdlet is used as the input for the <code>Get-Member</code> cmdlet. This is much simpler than the following command, which gives you the same result:

```
PowerCLI C:\> Get-Member -InputObject (Get-VM)
```

You can see that the Get-Member cmdlet accepts input from the pipeline if you look at the help content for the Get-Member parameter -InputObject parameter using the following command:

PowerCLI C:\> Get-Help Get-Member -Parameter InputObject

The output will be the following:

-InputObject <PSObject>

Specifies the object whose members are retrieved.

Using the InputObject parameter is not the same as piping an object to Get-Member. The differences are as follows:

- -- When you pipe a collection of objects to Get-Member, Get-Member gets the members of the individual objects in the collection, such as the properties of each string in an array of strings.
- -- When you use InputObject to submit a collection of objects, Get-Member gets the members of the collection, such as the properties of the array in an array of strings.

Required? false Position? named

Default value


Accept pipeline input? true (ByValue)

Accept wildcard characters? false

You can see in the preceding output that in the description it says Accept pipeline input? true (ByValue). This means that the Get-Member -InputObject parameter accepts input from the pipeline.

The ByValue parameter binding means that PowerShell binds the entire input object to the parameter.

In the following figure, you will see that the pipeline binds the output of the Get-Member cmdlet to the -InputObject parameter of the Get-Member cmdlet:



Using the ByPropertyName parameter binding

If PowerShell can't find a parameter that accepts pipeline input using ByValue, it tries to find parameters that accept pipeline input using ByPropertyName. When a parameter accepts pipeline input using ByPropertyName, it means that the value of a property of the input object is bound to a cmdlet parameter with the same name as the property.

An example of a PowerShell cmdlet that accepts input from the pipeline using the ByPropertyName parameter binding is the Get-Date cmdlet, which returns a System.DateTime object. The -Date parameter of this cmdlet accepts pipeline input using both ByValue and ByPropertyName. The PowerCLI Get-VIEvent cmdlet retrieves information about the events on a vCenter Server system, for example:

PowerCLI C:\> Get-VIEvent | Select-Object -First 1

ScheduledTask : VMware.Vim.ScheduledTaskEventArgument

Entity : VMware.Vim.ManagedEntityEventArgument

Key : 64835 ChainId : 64835

CreatedTime : 12/28/2013 9:04:01 PM

UserName :
Datacenter :
ComputeResource :
Host :
Vm :
Ds :
Net :
Dys :

FullFormattedMessage: Running task VMware vCenter Update Manager

Check Notification on Datacenters in

datacenter

ChangeTag

DynamicType

DynamicProperty

The output has a property CreatedTime. The value of the CreatedTime property has a DateTime object type.

Let's try to pipe the output of the preceding command into the Get-Date cmdlet:


This gives an error message because the output of the Get-VIEvent cmdlet does not have a Date property that matches the -Date parameter of the Get-Date cmdlet. We will now use a calculated property to rename the CreatedTime property in Date:

```
PowerCLI C:\> Get-VIEvent | Select-Object -First 1 |
>> Select-Object @{Name="Date"; Expression={$_.CreatedTime}} |
>> Get-Date
>>
```

Saturday, December 28, 2013 9:04:01 PM

Because the output of the Select-Object cmdlet has a Date property, and this property matches the Get-Date parameter -Date using the ByPropertyName parameter binding, the pipeline now works.

The following figure shows that the pipeline binds the value of the Date property in the output of the Select-Object cmdlet to the -Date property of the Get-Date cmdlet:



Most PowerCLI cmdlets will accept input from the pipeline using the ByValue parameter binding. However, only a few PowerCLI cmdlets will accept input from the pipeline using the ByPropertyName parameter binding. You can find these cmdlets with the following PowerShell code:

```
PowerCLI C:\> Get-VICommand |
>> Where-Object {$_.ParameterSets.Parameters |
>> Where-Object {
>> $_.ValueFromPipeline -and $_.ValueFromPipelineByPropertyName}}
>>
```

This is the output of the preceding command:

${\tt CommandType}$	Name	ModuleName
Cmdlet	Add-EsxSoftwareDepot	VMware.ImageBuilder
Cmdlet	Add-EsxSoftwarePackage	VMware.ImageBuilder
Cmdlet	Compare-EsxImageProfile	VMware.ImageBuilder
Cmdlet	Export-EsxImageProfile	VMware.ImageBuilder
Cmdlet	New-EsxImageProfile	VMware.ImageBuilder
Cmdlet	Remove-EsxImageProfile	VMware.ImageBuilder
Cmdlet	Remove-EsxSoftwareDepot	VMware.ImageBuilder
Cmdlet	${\tt Remove-EsxSoftwarePackage}$	VMware.ImageBuilder
Cmdlet	Set-EsxImageProfile	VMware.ImageBuilder

The script uses the Get-VICommand cmdlet to get all of the PowerCLI cmdlets. It then filters only those cmdlets that have parameters that accept pipeline input using ByPropertyName. As you see in the preceding output, when writing this book, only cmdlets from the PowerCLI VMware. ImageBuilder module accept pipeline input using ByPropertyName.

Using the PowerShell object cmdlets

PowerShell has some cmdlets that are designed to work with all kinds of objects. You can easily recognize them because they all have -Noun Object. You can use the Get-Command cmdlet's -Noun parameter to find them:

PowerCLI C:\> Get-Command -Noun Object

The output of the preceding command is as follows:

Name	ModuleName
Compare-Object	Microsoft.PowerShell.Utility
ForEach-Object	Microsoft.PowerShell.Core
Group-Object	Microsoft.PowerShell.Utility
Measure-Object	Microsoft.PowerShell.Utility
New-Object	Microsoft.PowerShell.Utility
Select-Object	Microsoft.PowerShell.Utility
Sort-Object	Microsoft.PowerShell.Utility
Tee-Object	Microsoft.PowerShell.Utility
Where-Object	Microsoft.PowerShell.Core
	Compare-Object ForEach-Object Group-Object Measure-Object New-Object Select-Object Sort-Object Tee-Object

In the following section, we will discuss the Object cmdlets.

Using the Select-Object cmdlet

If you want to retrieve a subset of the properties of an object, select unique objects, select a specific number of objects, or select specific objects from an array, you can use the Select-Object cmdlet. You can also use the Select-Object cmdlet to add properties to an object using calculated properties as you have seen in *Chapter 2*, *Learning Basic PowerCLI Concepts*.

The Select-Object cmdlet has the following syntax:

```
Select-Object [[-Property] <Object[]>] [-ExcludeProperty <String[]>]
[-ExpandProperty <String>] [-First <Int32>] [-InputObject <PSObject>]
[-Last <Int32>] [-Skip <Int32>] [-Unique [<SwitchParameter>]] [-Wait
[<SwitchParameter>]] [<CommonParameters>]
```

```
Select-Object [-Index <Int32[]>] [-InputObject <PSObject>] [-Unique
[<SwitchParameter>]] [-Wait [<SwitchParameter>]] [<CommonParameters>]
```

As you can see, the Select-Object cmdlet has two parameter sets: one parameter set contains the -Index parameter and the other doesn't. You can use Select as an alias for the Select-Object cmdlet.

The Get-VM cmdlet returns the Name, PowerState, NumCpu, and MemoryGB properties of the virtual machines by default. But what if you want to return the Name, VMHost, and Cluster properties instead? If you look at the properties of a virtual machine object, you will see the VMhost property, but you will not see a Cluster property. However, if you look at a VMHostImpl object, you will find a Parent property. The Parent property of a VMhostImpl object contains the cluster that the host is a member of.

You can use this information to create a PowerCLI one-liner to get the host and cluster of all of the virtual machines:

```
PowerCLI C:\> Get-VM | Select-Object -Property Name,VMHost,@
{Name="Cluster"; Expression={$.VMHost.Parent}}
```

```
Name VMHost Cluster
---- -----
DC1 192.168.0.133 Cluster01
```

The preceding command uses the Select-Object cmdlet to select the Name and VMHost properties of the virtual machine objects; it creates a calculated property named Cluster that retrieves the cluster via the VMHost.Parent property.



You can create a one-liner from all of your PowerShell scripts by using the semicolon as a separator between the commands. Use this only on the command line. It makes your scripts hard to read.

You can use the Select-Object -First parameter to specify the number of objects to select from the beginning of an array of input objects. For example, to retrieve the first three hosts, type the following command:

```
PowerCLI C:\> Get-VMHost | Select-Object -First 3
```

If you are typing commands at the pipeline, you can also use their aliases. For Select-Object, the alias is Select. Therefore, the next example will give the same result as the previous one:

```
PowerCLI C:\> Get-VMHost | Select -First 3
```

To select a number of objects starting from the end of an array of objects, use the Select-Object -Last parameter. The following command retrieves the last cluster:

```
PowerCLI C:\> Get-Cluster | Select-Object -Last 1
```

You can also skip objects from the beginning or the end of an array using the Select-Object -Skip parameter. The following command returns all of the folder objects except the first two:

```
PowerCLI C:\> Get-Folder | Select-Object -Skip 2
```

A very interesting parameter of the Select-Object cmdlet is the -ExpandProperty parameter. If the property contains an object, you can use this parameter to expand the object. For example, if you want to get the VMHostImpl object of the virtual machine named dcl, you can execute the following command:

PowerCLI C:\> Get-VM -Name dc1 | Select-Object -ExpandProperty VMHost

Using the Where-Object cmdlet

If you only want a subset of all of the objects that a command returns, you can use the Where-Object cmdlet to filter the output of a command and only return the objects that match the criteria of the filter.

The Where-Object cmdlet syntax definition is so long that it would take up too much space in this book. You can easily get the Where-Object cmdlet syntax with the following command:

```
PowerCLI C:\> Get-Help Where-Object
```

PowerShell v3 introduced a new, easier syntax for the Where-Object cmdlet. I will show you both the v2 and the v3 syntaxes. First, let's see the new PowerShell v3 syntax.

Let's try to find all virtual machines that have only one virtual CPU. You can do this by searching for virtual machines that have a NumCPU property with a value of 1:

```
PowerCLI C:\> Get-VM | Where-Object NumCpu -eq 1
```

Name	PowerState	Num CPUs	${\tt MemoryGB}$
DC1	PoweredOff	1	0.250

If you use the alias Where, the command looks more like a natural language:

```
PowerCLI C:\> Get-VM | Where NumCpu -eq 1
```

You can also use the alias? if you want to type less on the command line:

```
PowerCLI C:\> Get-VM | ? NumCpu -eq 1
```

The PowerShell v2 syntax is a bit more obscure. You have to use a script block as the value of the Where-Object -FilterScript parameter:

```
PowerCLI C:\> Get-VM | Where-Object -FilterScript {$_.NumCpu -eq 1}
```

Because the -FilterScript parameter is the first positional parameter of the Where-Object cmdlet, nobody uses the parameter name, and you will always see one of the following command lines being used:

```
PowerCLI C:\> Get-VM | Where-Object {$_.NumCpu -eq 1}
PowerCLI C:\> Get-VM | where {$_.NumCpu -eq 1}
```

The advantage of the PowerShell v2 syntax over the v3 syntax is that you can create complex filtering scripts, for example:

```
PowerCLI C:\> Get-VM |
>> Where-Object {$_.NumCpu -gt 2 -and $_.MemoryGB -lt 16}
>>
```

The preceding command will show you all of the virtual machines with more than two virtual CPUs and less than 16 GB of memory. If you want to create the same filter using the PowerShell v3 syntax, you have to use two filters: one for the number of CPUs and one for the memory. Here is an example command:

```
PowerCLI C:\> Get-VM | Where NumCpu -gt 2 | Where MemoryGB -lt 16
```

Using the ForEach-Object cmdlet

Some cmdlets don't accept properties from the pipeline. On the other hand, you might like to use a cmdlet in the pipeline but the property you want to use in the pipeline doesn't accept pipeline input. This is where the PowerShell ForEach-Object cmdlet will help you.

The ForEach-Object cmdlet has the following syntax:

The names of the parameter sets are ScriptBlockSet and PropertyAndMethodSet. The -Process parameter is required for the ScriptBlockSet parameter set. The -MemberName parameter is required for the PropertyAndMethodSet parameter set. The PropertyAndMethodSet parameter set was introduced in PowerShell v3.

The default first parameter is -Process; it is generally omitted when using the cmdlet. The -Process parameter has a scriptblock as its parameter value and this scriptblock will run for every object that passes the pipeline. The following command will retrieve the names of all of your virtual machines:

```
PowerCLI C:\> Get-VM | ForEach-Object {$ .Name}
```

In the scriptblock, the special variable \$_ is used. The \$_ variable is the current object that passes through the pipeline. Thus, \$_. Name will return the value of the name property of the current object.

You can also use the alias foreach:

```
PowerCLI C:\> Get-VM | foreach {$ .Name}
```

In PowerShell v3, the command is even simpler:

```
PowerCLI C:\> Get-VM | foreach Name
```

If you want the ForEach-Object cmdlet to execute code before the objects start to pass through the pipeline—say to initialize a variable—you can create a scriptblock and use it as an argument value for the <code>-Begin</code> parameter. If you want the ForEach-Object cmdlet to execute code after the objects finish passing through the pipeline—for example, to return the result of a calculation you did on all of the objects in the pipeline—you can create a scriptblock and use it as an argument value for the <code>-End</code> parameter. For example use the following command:

```
PowerCLI C:\> 1,2,3,4 |
>> ForEach-Object -Begin {"Start of the Script"; $Sum = 0} `
>> -Process {$Sum += $_} -End {"Sum of the elements: $Sum"}
>>
Start of the Script
Sum of the elements: 10
```

The preceding example was just to demonstrate the ForEach-Object cmdlet. If you want to take the sum of the objects in the pipeline, it is better to use the Measure-Object cmdlet that will be discussed in one of the following sections.



In the example, you can see that the semicolon character is used to separate PowerShell commands. The **backtick** character (`) used as the last character of a line is used to escape the newline character and treat the newline character as a space. This enables you to break long lines of code and continue them on the next line.

To specify 1, 2, 3, and 4 you can also use the PowerShell range operator (..) as follows:

1..4

The preceding operator is equivalent to the following:

```
1, 2, 3, 4
```

The ForEach-Object -Process scriptblock is run at least once even if the input object is \$null, as you can see in the following example:

```
PowerCLI C:\> $null | ForEach-Object -Process {"Hello world."}
Hello world.
```

You probably don't want to return anything if the input object is \mathfrak{pull} . You can solve this problem by testing with if (\mathfrak{z}) to check whether the input object exists inside the scriptblock:

```
PowerCLI C:\> $null | ForEach-Object -Process {if ($_) {"Hello."}}
```

Using the Sort-Object cmdlet

PowerCLI returns objects in random order. If you want the objects to be sorted, you can use the Sort-Object cmdlet to sort them.

The Sort-Object cmdlet has the following syntax:

```
Sort-Object [[-Property] <Object[]>] [-CaseSensitive
[<SwitchParameter>]] [-Culture <String>] [-Descending
[<SwitchParameter>]] [-InputObject <PSObject>] [-Unique
[<SwitchParameter>]] [<CommonParameters>]
```

The Sort-Object cmdlet sorts objects in ascending or descending order based on the values of the properties of the object.

You can specify a single property or multiple properties (for a multi-key sort), and you can select a case-sensitive or case-insensitive sort. You can also direct Sort-Object to display only the objects with a unique value for a particular property.

The following example will give a list of all of your virtual machines and their hosts sorted in ascending order on the host name and the virtual machine name.

```
PowerCLI C:\> Get-VM | Select-Object -Property VMHost,Name |
>> Sort-Object -Property VMHost,Name
>>
```

Using the aliases select for Select-Object and sort for Sort-Object, and also using positional parameters, the preceding example can be shortened into this:

```
PowerCLI C:\> Get-VM | select VMHost, Name | sort VMHost, Name
```

Using the Measure-Object cmdlet

If you want to count objects or calculate the minimum, maximum, sum, and average of the numeric values of properties, you can use the Measure-Object cmdlet. For text objects, it can count and calculate the number of lines, words, and characters.

The Measure-Object cmdlet has the following syntax:

```
Measure-Object [[-Property] <String[]>] [-Average
[<SwitchParameter>]] [-InputObject <PSObject>] [-Maximum
[<SwitchParameter>]] [-Minimum [<SwitchParameter>]] [-Sum
[<SwitchParameter>]] [<CommonParameters>]

Measure-Object [[-Property] <String[]>] [-Character
[<SwitchParameter>]] [-IgnoreWhiteSpace [<SwitchParameter>]] [-InputObject <PSObject>] [-Line [<SwitchParameter>]] [-Word
[<SwitchParameter>]] [<CommonParameters>]
```

The names of the parameter sets are GenericMeasure and TextMeasure. There are no required parameters.

Let's get back to our example from the ForEach-Object cmdlet, where we counted the sum of the numbers 1, 2, 3, and 4. You can do this more easily using the Measure-Object cmdlet with the following command:

```
PowerCLI C:\> (1..4 | Measure-Object -Sum).Sum
10
```

The only output property that the Measure-Object cmdlet fills by default is the Count property. To count the number of virtual machines in your environment, type the following command:

```
PowerCLI C:\> Get-VM | Measure-Object
```

The output of the preceding command will be as follows:

Count : 1
Average :
Sum :
Maximum :

Minimum : Property :

If you just want the count value, you can specify the Count property:

```
PowerCLI C:\> (Get-VM | Measure-Object).Count
12
```

Alternatively, you can use the Select-Object -ExpandProperty parameter:

```
PowerCLI C:\> Get-VM | Measure-Object |
>> Select-Object -ExpandProperty Count
>>
12
```

You can also use the alias measure for Measure-Object:

```
PowerCLI C:\> (Get-VM | measure).Count
12
```

To get the average, sum, maximum, and minimum values of a property, you have to specify the property name and the parameters for the values that you want to retrieve. The following command will retrieve the average, sum, maximum, and minimum values of the ProvisionedSpaceGB property for all of your virtual machines:

```
PowerCLI C:\> Get-VM \mid Measure-Object -Property ProvisionedSpaceGB -Average -Sum -Maximum -Minimum
```

Count: 12

Average : 60.590376389601

Sum : 727.084516675211

Maximum : 221.090891393833

Minimum : 2.58988594077528

Property : ProvisionedSpaceGB

To count the number of characters, words, and lines in a string, you can use the – Line, –Word, and –Character parameters:

```
PowerCLI C:\> "Learning PowerCLI" |
>> Measure-Object -Line -Word -Character
>>
```

Lines	Words	Characters Property
1	2	17

You can also use the Measure-Object cmdlet to count the number of lines, words, and characters in the here-string:

```
PowerCLI C:\> @"
>> Every vSphere admin should
>> Learn PowerCLI!
>> "@ | Measure-Object -Line -Word -Character
>>
```

Lines	Words	Characters Property
2	6	42

Rounding a value

If you don't want a value to have several fractional digits, you can use the .NET Math.Round method to round a value to the nearest integer or to the specified number of fractional digits. The first parameter of the Math.Round method is the value that you want to round. The optional second parameter is the number of fractional digits that you want the value to round to. If you don't specify the second parameter, the value will be rounded to the nearest integer. For example, use the following command:

```
PowerCLI C:\> [math]::Round(60.590376389601,2)
60.59
```

You can use the Math. Round method in a calculated property. For example:

```
PowerCLI C:\> Get-VM | Measure-Object -Property ProvisionedSpaceGB
-Average -Sum -Maximum -Minimum |
>> Select-Object -Property Count,
>> @{Name="Average";Expression={[math]::Round($_.Average,2)}}
>>
```

Count	Average
12	60.59

Using the Group-Object cmdlet

The Group-Object cmdlet groups objects that contain the same value for the specified properties. Using the Group-Object cmdlet can be very useful, for example, when you want to count the number of instances of a specific value of a property.

The Group-Object cmdlet has the following syntax:

```
Group-Object [[-Property] <Object[]>] [-AsHashTable
[<SwitchParameter>]] [-AsString [<SwitchParameter>]] [-CaseSensitive
[<SwitchParameter>]] [-Culture <String>] [-InputObject <PSObject>] [-NoElement [<SwitchParameter>]] [<CommonParameters>]
```

Let's create a PowerCLI command to count the number of instances of each operating system installed on a virtual machine. In a traditional scripting language, you would have to loop through all of your virtual machines and increment counters for each operating system. In PowerCLI, you can achieve this much easier using the Group-Object cmdlet. The name of the guest operating system is in a virtual machine's Guest .OSFullName property. You can use the Group-Object cmdlet to group the objects on the Guest .OSFullName property using a calculated property. The Group-Object cmdlet will return the Count, Name, and Group properties by default. Using the -NoElement parameter will remove the Group property from the output. The following example groups the virtual machines on the Guest .OSFullname property and returns the Count and Name properties for each Guest .OSFullName property.

```
PowerCLI C:\> Get-VM |
>> Group-Object -Property @{Expression={$_.Guest.OSFullName}} -NoElement
|
>> Format-Table -AutoSize
>>

Count Name
-----
    1 Microsoft Windows Server 2012 (64-bit)
    1 SUSE Linux Enterprise 11 (32-bit)
    3 SUSE Linux Enterprise 11 (64-bit)
    1
    2 Microsoft Windows Server 2008 R2 (64-bit)
    1 CentOS 4/5/6 (32-bit)
```

```
2 Other (64-bit)
1 CentOS 4/5/6 (64-bit)
1 CentOS 4/5/6 (64-bit)
```



The one virtual machine that does not have a guest operating system name is powered off for a long time. The guest operating system is determined using the VMware Tools. **VMware vSphere** can't find the guest operating system for this virtual machine while it is powered off.

The Format-Table -AutoSize command formats the output, so you will get the full operating system name.

Using the Compare-Object cmdlet

If you want to compare two objects or sets of objects, you have to use the Compare-Object cmdlet.

The Compare-Object cmdlet has the following syntax:

```
Compare-Object [-ReferenceObject] <PSObject[]> [-DifferenceObject]
<PSObject[]> [-CaseSensitive [<SwitchParameter>]] [-Culture <String>]
[-ExcludeDifferent [<SwitchParameter>]] [-IncludeEqual
[<SwitchParameter>]] [-PassThru [<SwitchParameter>]] [-Property
<Object[]>] [-SyncWindow <Int32>] [<CommonParameters>]
```

From the sets of objects that the Compare-Object cmdlet compares, one set of objects is called the **reference set** and the other is called the **difference set**.

Let's compare two strings:

The output shows that the strings are not the same. The <= symbol indicates objects from the reference set. The => symbol indicates objects from the difference set. If you use the -IncludeEqual parameter, the Compare-Object cmdlet will also show objects that are equal in both sets. These objects are indicated by the == symbol.

Using the Tee-Object cmdlet

The Tee-Object cmdlet saves the command output in a file or variable and also sends it down the pipeline. It sends the output of a command in two directions, as in the letter "T". If Tee-Object is the last command in the pipeline, the command output is displayed at the prompt.

The Tee-Object cmdlet has the following syntax:

```
Tee-Object [-FilePath] <String> [-Append [<SwitchParameter>]] [-
InputObject <PSObject>] [<CommonParameters>]


Tee-Object [-InputObject <PSObject>] -LiteralPath <String>
[<CommonParameters>]

Tee-Object [-InputObject <PSObject>] -Variable <String>
[<CommonParameters>]
```

The following example retrieves all of your virtual machines and saves the virtual machine objects in a variable named VMs. It also sends the objects down the pipeline and displays the Name and PowerState properties of the virtual machines.

```
PowerCLI C:\> Get-VM | Tee-Object -Variable VMs |
>> Select-Object -Property Name, PowerState
>>
```

The following figure shows that the Tee-Object cmdlet writes its output to the variable \$VMs and pipes its output to the next command in the pipeline:



VM1

Creating your own objects

There are several ways to create new objects in PowerCLI. In fact, you have already been creating new objects by using the Select-Object -Property command. In this section, you will learn more ways to create new objects.

Using the New-Object cmdlet

PowerShell has its own cmdlet for creating objects: New-Object. You can use this cmdlet to create a Microsoft .NET Framework or COM object.

The New-Object cmdlet has the following syntax:

```
New-Object [-TypeName] <String> [[-ArgumentList] <Object[]>] [-
Property <IDictionary>] [<CommonParameters>]

New-Object [-ComObject] <String> [-Property <IDictionary>] [-Strict [<SwitchParameter>]] [<CommonParameters>]
```

Using a hash table to create an object

The easiest way to create a Microsoft .NET Framework object as the output of your PowerCLI scripts is to create a PSObject type object using a hash table. The following example creates an object with two members of member type NoteProperty—Name and VMHost:

ESX1

If you look at the object with Get-Member, you will see four standard methods and the NoteProperty member types named Name and VMHost:

PowerCLI C:\> \$Object | Get-Member

TypeName: System.Management.Automation.PSCustomObject

Name	MemberType	Definition
Equals	Method	<pre>bool Equals(System.Object obj)</pre>
${\tt GetHashCode}$	Method	<pre>int GetHashCode()</pre>
GetType	Method	<pre>type GetType()</pre>
ToString	Method	string ToString()
Name	NoteProperty	System.String Name=VM1
VMHost	NoteProperty	System.String VMHost=ESX1

The four methods Equals, GetHashCode, GetType, and ToString are methods that every PowerShell object has.

This technique is fast and is easy to use. It has the disadvantage that PowerShell might output the properties in a different order than you added them. You can solve this problem by piping the object to Select-Object and specifying the properties there in the right order as follows:

PowerCLI C:\> \$Object | Select-Object -Property Name, VMHost

Name	VMHost
VM1	ESX1

Creating objects using the Select-Object cmdlet

If you use the Select-Object cmdlet to select only specific properties of an object, you are creating a new object type. For example, the objects returned by the Get-VM cmdlet are of type VMware.VimAutomation.ViCore.Impl.V1.Inventory. VirtualMachineImpl. However, if you pipe the output of the Get-VM cmdlet to Select-Object, you will get the following output:

PowerCLI C:\> Get-VM | Select-Object -Property Name | Get-Member

TypeName: Selected.VMware.VimAutomation.ViCore.Impl.V1.Inventory .VirtualMachineImpl

In the TypeName output, you can see that the original type name is prefixed by Selected. You can create a new object from scratch if you pipe an empty string to Select-Object, as in the following example:

```
PowerCLI C:\> $Report = "" | Select-Object -Property VM,VMHost
PowerCLI C:\> $Report.VM = "VM1"

PowerCLI C:\> $Report.VMHost = "ESX1"

PowerCLI C:\> $Report

VM VMHost
-- ------
VM1 ESX1
```

In the first line, you have created a new object \$Report that has two blank properties: VM and VMHost. In the second and third lines, values are assigned to these properties. In the last line, the \$Report object is returned.

This technique was used a lot in PowerShell v1 and you still see it used often. In PowerShell v2 and above, I prefer using a hash table.

Adding properties to an object with Add-Member

If you want to add one or more properties to an existing object, you can use the Add-Member cmdlet.

The Add-Member cmdlet has the following syntax:

```
Add-Member [-PassThru [<SwitchParameter>]] -InputObject <PSObject> -
TypeName <String> [<CommonParameters>]

Add-Member [-MemberType] <PSMemberTypes> [-Name] <String> [[-Value]
<Object>] [[-SecondValue] <Object>] [-Force [<SwitchParameter>]] [-
PassThru [<SwitchParameter>]] [-TypeName <String>] -InputObject
<PSObject> [<CommonParameters>]

Add-Member [-NotePropertyName] <String> [-NotePropertyValue] <Object>
[-Force [<SwitchParameter>]] [-PassThru [<SwitchParameter>]] [-
TypeName <String>] -InputObject <PSObject> [<CommonParameters>]
```

```
Add-Member [-NotePropertyMembers] <IDictionary> [-Force [<SwitchParameter>]] [-PassThru [<SwitchParameter>]] [-TypeName <String>] -InputObject <PSObject> [<CommonParameters>]
```

You can create a new object with the New-Object cmdlet and then use the Add-Member cmdlet to add properties, as follows:

This technique was also common in PowerShell v1. Because it is the slowest option, it is rarely used anymore.

The Add-Member cmdlet adds properties to the input object and does not generate output unless you specify the -PassThru parameter. If you want to use more than one Add-Member command in a pipeline, don't forget to use the -PassThru parameter.

Using type declarations

PowerShell v3 introduced a new way to create an object using a type declaration of a pscustomobject object. The advantage over the technique using a hash table is that the properties come out in the same order in which you added them. If you use PowerShell v3, this becomes a very clean and fast technique to use.

Using COM objects

You can also use the New-Object cmdlet to create an instance of a COM object. COM objects were used a lot in VBScript. In PowerShell, you can still use them to do things that you cannot do in native PowerShell. The following example will use the SAPI. SpVoice COM object to output a text as voice. It will say "The script is finished." Append this piece of code at the end of your PowerCLI script and you will hear your computer say that the script is finished. This way, you don't have to keep watching your computer screen. Isn't this cool?

```
PowerCLI C:\> $Voice = New-Object -ComObject SAPI.SpVoice
PowerCLI C:\> $Voice.Speak("The script is finished.") | Out-Null
```

You can get a list of all of the COM objects on your computer with the following PowerShell code:

```
Get-ChildItem -Path HKLM:\Software\Classes -ErrorAction `
SilentlyContinue |
Where-Object {$_.PSChildName -match '^\w+\.\w+$' -and `
    (Get-Itemproperty "$($_.PSPath)\CLSID" -ErrorAction `
SilentlyContinue)} |
Format-Table -Property PSChildName
```

The script lists all of the subkeys in the HKEY_LOCAL_MACHINE\Software\Classes registry key. It then uses a regular expression to select only the subkeys with a PSChildName property that contains two words separated by a dot. The subkeys must themselves have a subkey, named CLSID. Finally, the value of the PSChildName property is shown in table format.

The script uses the backtick or "grave accent" (`), the Windows PowerShell continuation character, to continue commands on the next line.

You cannot use all of the COM objects in a PowerShell script. Some COM objects are not compatible with PowerShell.

Summary

In this chapter, you learned how to use PowerShell objects, their properties, and methods. You saw variable and subexpression expansion in strings and herestrings. You learned about the PowerShell pipeline and parameter binding using the ByValue or ByPropertyName parameter binding types. You learned how to use the PowerShell object cmdlets: Select-Object, Where-Object, ForEach-Object, Sort-Object, Measure-Object, Group-Object, Compare-Object, Tee-Object, and New-Object. We looked at different methods to create new objects. Finally, you saw an example of how to use COM objects.

In the next chapter, you will learn how to manage VMware vSphere hosts with PowerCLI.

4

Managing vSphere Hosts with PowerCLI

In a VMware vSphere environment, the hosts are the work horses; they provide the power on which the virtual machines run. So before you can deploy your virtual machines, you first have to deploy your hosts.

In this chapter, you will learn how to manage your hosts using PowerCLI. We will focus on:

- Adding a host to a VMware vCenter Server
- Enabling and disabling maintenance mode
- Working with host profiles
- Working with host services
- Configuring the host firewall
- Configuring vSphere Image Builder and Auto Deploy
- Using esxcli from PowerCLI
- Using the vSphere CLI commands from PowerCLI
- Removing a host from the VMware vCenter Server

Adding a host to a VMware vCenter Server

The VMware vCenter Server provides a centralized platform to manage your VMware vSphere environments. In this section, you will learn how to add a host to a VMware vCenter Server.

Creating a datacenter

After deploying a new vCenter Server, you cannot add a host to a vCenter Server until you have created a datacenter. So we will start with creating a datacenter. To create a datacenter, you have to use the New-Datacenter cmdlet. This cmdlet has the following syntax:

New-Datacenter [-Location] <VIContainer> [-Name] <String> [-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]

The -Location and -Name parameters are required.

When you create a datacenter, you have to specify a value for the location parameter. This location has to be a folder. You can create the datacenter in the root of your vCenter Server environment. This root is actually a folder called Datacenters. You can also create a subfolder in the Datacenters folder and create the datacenter in this subfolder. It is not possible to create a datacenter in a folder inside another datacenter. You can use the next command to find all of the folders that can be used to create datacenters in:

PowerCLI C:\> Get-Folder -Type Datacenter

Name Type ---Datacenters Datacenter

The next screenshot shows how you can create a datacenter in the vSphere Web Client. This is different from PowerCLI because you can specify the vCenter Server as the location in the vSphere Web Client.



In the following example, we will create a datacenter called New York in the Datacenters folder. First we use the Get-Folder cmdlet to get the Datacenters folder. Then we use the pipeline to pass the Datacenters folder to the -Location parameter of the New-Datacenter cmdlet. The -Location parameter accepts the pipeline input ByValue.


```
PowerCLI C:\> $Datacenter = Get-Folder -Name Datacenters |
>> New-Datacenter -Name "New York"
>>
PowerCLI C:\> $Datacenter

Name
----
New York
```

Creating a cluster

You probably want to create a cluster in which you place your hosts so you can take advantage of **High Availability** (**HA**) and **Dynamic Resource Scheduling** (**DRS**). In *Chapter 8, Managing High Availability and Clustering with PowerCLI*, you will learn all about clusters. However, we will show you how to create a default cluster here, so you can make your hosts a member of the cluster.

The next screenshot shows how you can create a cluster in the vSphere Web Client.



You have to use the New-Cluster cmdlet to create a cluster. The New-Cluster cmdlet has the following syntax:

```
New-Cluster [-HARestartPriority <HARestartPriority>]
[-HAIsolationResponse <HAIsolationResponse>] [-VMSwapfilePolicy
<VMSwapfilePolicy>] [-Name] <String> -Location <VIContainer> [-HAEnabled]
[-HAAdmissionControlEnabled] [-HAFailoverLevel <Int32>] [-DrsEnabled]
[-DrsMode <DrsMode>] [-DrsAutomationLevel <DrsAutomationLevel>]
[-VsanDiskClaimMode <VsanDiskClaimMode>] [-VsanEnabled [<Boolean>]]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

To create a default cluster, you only have to specify the name and location. The -Name and -Location parameters are required.

Adding a host

To add a host to a VMware vCenter Server, you need to use the Add-VMHost cmdlet. This cmdlet has the following syntax:

```
Add-VMHost [-Name] <String> [-Port <Int32>] [-Location] <VIContainer> [-Credential <PSCredential>] [-User <String>] [-Password <String>] [-Force] [-RunAsync] [-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Name and -Location parameters are required.

The next screenshot shows how you can add a host to a cluster in the vSphere Web Client:



While adding a host to a vCenter Server, you have to supply the username and the password for the user you want to use, to authenticate with the host. You can specify the username and password as a string or you can use the <code>-Credential</code> parameter and pass a PSCredential object created with the <code>Get-Credential</code> cmdlet. You also have to specify the DNS name or IP address of the host and the location where you want to add the host. Let's try to add the host to the cluster we created in the previous section.

As you can see from the error message, the command failed because the host is using a self-signed SSL certificate. You have to give the host a trusted certificate or you can use the -Force parameter to skip the certificate check.

```
PowerCLI C:\> Add-VMHost -Name 192.168.0.133 -Location $Cluster `>> -User root -Password vmware -Force >>
```

Name	ConnectionState	PowerState	${\tt NumCpu}$	CpuUsageMhz
192.168.0.133	Connected	PoweredOn	2	0

The host is now added to the cluster. You can check this with:

```
PowerCLI C:\> $Cluster | Get-VMHost
```

Name	ConnectionState	PowerState	${\tt NumCpu}$	CpuUsageMhz
192.168.0.133	Connected	PoweredOn	2	49

Enabling and disabling maintenance mode

If you want to shut down, patch, upgrade, or reconfigure a host, you do not want any virtual machines running on the host. If you put a host in **maintenance mode**, you are sure that no virtual machines will be moved to or started on the host. If the host is running on a fully automated DRS-enabled cluster, the DRS will move the running virtual machines from the host to other hosts in the cluster using vMotion.

The next screenshot of the vSphere Web Client shows the different DRS automation levels that a cluster can have:

 Manual vCenter Server will suggest migration recommendations for virtual machines.
 Partially Automated Virtual machines will be automatically placed onto hosts at power on and vCenter Server will suggest migration recommendations for virtual machines.
 Fully Automated Virtual machines will be automatically placed onto hosts when powered on, and will be automatically migrated from one host to another to optimize resource usage.

To put a host in maintenance mode, you have to use the Set-VMHost cmdlet.

This cmdlet has the following syntax:

```
Set-VMHost [-VMHost] <VMHost[] > [[-State] <VMHostState>]
[-VMSwapfilePolicy <VMSwapfilePolicy>] [-VMSwapfileDatastore <Datastore>]
[-Profile <VMHostProfile>] [-Evacuate] [-TimeZone <VMHostTimeZone>]
[-LicenseKey <String>] [-Server <VIServer[]>] [-RunAsync] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

The -VMHost parameter is required.

To put a host in maintenance mode, you have to set the state to Maintenance. To disable maintenance mode, you have to set the state to Connected. The Set-VMHost -State parameter has a third possible value, which is Disconnected. You can use Disconnected to disconnect a host from the vCenter Server.


So let's put the host in maintenance mode first:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.133
PowerCLI C:\> $VMHost | Set-VMHost -State Maintenance
Name
           ConnectionState PowerState NumCpu CpuUsageMhz
            -----
192.168.0.133 Maintenance
                         PoweredOn
                                      2
                                                47
To disable maintenance mode, you have to use:
PowerCLI C:\> $VMHost | Set-VMHost -State Connected
Name
           ConnectionState PowerState NumCpu CpuUsageMhz
            -----
192.168.0.133 Connected
                         PoweredOn
                                               139
```

Working with host profiles

A host profile is a collection of all of the configuration settings for an ESXi host, such as storage and networking configurations and security settings. You can create a host profile from a reference host or import an existing host profile. After attaching a host profile to a host, the host can be checked for compliance with the host profile. If the host is compliant, you know the settings of the host are the same as the settings of the host profile. If the host is not compliant, the host profile can be applied to the host to make the host compliant.

The next screenshot of the vSphere Web Client shows you some of the settings that you can configure in a host profile:



Common Information Model (CIM) Indication Subscriptions are subscriptions to the notifications for hardware-related events, such as problems with the cooling, battery, processor, memory, or power of an ESXi server.

Creating a host profile


To get started, you first need to configure a reference host. You have to configure general system settings, such as date and time configuration; network configuration, such as switches, portgroups and NICs; security and services; and storage and advanced configuration settings such as DirectPath I/O configuration. Once you are happy with the configuration of the reference host, you create a new host profile using the configuration of the reference host as a base. You need to use New-VMHostProfile to create the host profile.

The New-VMHostProfile cmdlet has the following syntax:

```
New-VMHostProfile [-Name] <String> [-ReferenceHost] <VMHost>
[-Description <String>] [-CompatibilityMode] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

Let's create a host profile called Cluster-Profile using host 192.168.0.133 as a reference host.

The next screenshot shows how you can create a host profile in the vSphere Web Client:



PowerCLI C:\> New-VMHostProfile -Name Cluster-Profile -ReferenceHost 192.168.0.133 -Description "Host Profile for cluster"

Name	Description			
Cluster-Profile	Host Profile for cluster			

Attaching the host profile to a cluster or a host


After creating the host profile, you have to attach the host profile to a cluster or a host. You can attach a profile using the PowerCLI Apply-VMHostProfile - AssociateOnly command.

The Apply-VMHostProfile cmdlet has the following syntax:

```
Apply-VMHostProfile [-Entity] <InventoryItem[]> [-Profile
<VMHostProfile>] [-Variable <Hashtable>] [-AssociateOnly]
[-ApplyOnly] [-RunAsync] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -Entity parameter is required and accepts pipeline input.

The next screenshot shows you how to attach a host profile in the vSphere Web Client.



Let's attach the host profile to cluster Cluster01 we created earlier in this chapter.

```
PowerCLI C:> Get-Cluster -Name Cluster01 |
>> Apply-VMHostProfile -Profile Cluster-Profile -AssociateOnly
-Confirm:$false>>
```

Name	HAEnabled	${\tt HAFailoverLevel}$	DrsEnabled	${\tt DrsAutomationLevel}$
Cluster01	False	1	False	FullyAutomated



The -Confirm: \$false parameter suppresses the prompt for confirmation before executing the command.

Testing the host profile for compliance

After attaching a host profile to a cluster or a host, you can use the Test-VMHostProfileCompliance cmdlet for compliance with the profile.

The Test-VMHostProfileCompliance cmdlet has the following syntax:

```
Test-VMHostProfileCompliance [-VMHost] <VMHost[]> [-UseCache] [[-Server]
<VIServer[]>] [<CommonParameters>]
```

```
Test-VMHostProfileCompliance [-Profile] <VMHostProfile[]> [-UseCache]
[[-Server] <VIServer[]>] [<CommonParameters>]
```

The -VMHost or -Profile parameter is required. The cmdlet has two parameter sets named VMHostCompliance and ProfileCompliance. You can use the first parameter set to specify a host to test for compliance with the attached profile. The second parameter set can be used to specify a host profile. All of the clusters and hosts attached to the profile will be tested for compliance against the host profile. There is no parameter set in which you can specify a cluster to check for compliance. If you want to check a cluster for compliance against a host profile, you either have to specify the host profile or all of the hosts in the cluster.

Let's test the Cluster-Profile host profile for compliance against all attached clusters and hosts:

```
PowerCLI C:\> Test-VMHostProfileCompliance -Profile Cluster-Profile
```

If the command returns nothing, it means that the host profile is compliant against all attached clusters and hosts. In this case, you could expect that the Cluster-Profile host profile is compliant because we used the host 192.168.0.133 as a reference host and this host is the only host in the cluster.

Let's add a second host to the cluster and test it for compliance:

```
PowerCLI C:\> Add-VMHost -Name 192.168.0.134 -Location $Cluster `
>> -User root -Password vmware -Force
>>
```

I made some changes to the configuration of the new host, so let's check if the Test-VMHostProfileCompliance cmdlet finds them:

```
PowerCLI C:\> Test-VMHostProfileCompliance -Profile Cluster-Profile |
>> Select-Object -ExpandProperty IncomplianceElementList
>>
```

```
PropertyName Description
-----
network.ipRo... Number of IPv4 routes did not match
network-vswi... Additional vSwitch(es) vSwitch1 found
network-port... Additional portgroup(s) vMotion found
```

As you can see, the command found three things that are not compliant with the host profile.

Applying a host profile to a host or cluster

You can apply a host profile to a host or cluster so that the configuration of this host or cluster becomes compliant with the host profile. To apply a host profile, you have to use the Apply-VMHostProfile cmdlet that we have used before to attach a host profile to a cluster or a host. The host or cluster must be in maintenance mode before you can apply a host profile to it.

We will set the host in maintenance mode first and then apply the host profile that is attached to the cluster:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.134
PowerCLI C:\> $VMHost | Set-VMHost -State Maintenance
Name
                ConnectionState PowerState NumCpu CpuUsageMhz
                -----
                                       2
192.168.0.134
               Maintenance
                           PoweredOn
                                                 45
PowerCLI C:\> $VMHost | Apply-VMHostProfile -Confirm:$false
Name
                ConnectionState PowerState NumCpu CpuUsageMhz
                -----
192.168.0.134
               Maintenance PoweredOn
```

You can now test the host for compliance with the host profile:

```
PowerCLI C:\> Test-VMHostProfileCompliance -VMHost $VMHost
```

If the command returns nothing, the host is compliant.

Using host profile answer files

If you apply a host profile and the host profile requires additional information, because settings are configured as Prompt the user ..., the Apply-VMHostProfile cmdlet will return a hash table with the settings that need to be answered. For example:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.134
PowerCLI C:\> $VMHost | Apply-VMHostProfile -Confirm:$false
Name
                               Value
network.hostPortGroup["key-... 00:0c:29:4a:aa:55 network.
hostPortGroup["key-...
network.hostPortGroup["key-...
network.dnsConfig.HostNameP...
You can save the hash table in a $HashTable variable:
PowerCLI C:\> $HashTable = $VMHost |
>> Apply-VMHostProfile -Confirm:$false
You can get the full key names of the hash table elements with:
PowerCLI C:\> $HashTable.Keys
network.hostPortGroup["key-vim-profile-host-HostPortgroupProfile-Ma
nagementNetwork"].MacAddressPolicy.mac
network.hostPortGroup["key-vim-profile-host-HostPortgroupProfile-Ma
nagementNetwork"].ipConfig.IpAddressPolicy.address
network.hostPortGroup["key-vim-profile-host-HostPortgroupProfile-Ma
nagementNetwork"].ipConfig.IpAddressPolicy.subnetmask
network.dnsConfig.HostNamePolicy.hostName
```

For every empty value in the hash table, you have to specify a value:

```
PowerCLI C:\> $HashTable['network.hostPortGroup["key-vim-profile-hos
t-HostPortgroupProfile-ManagementNetwork"].ipConfig.IpAddressPolicy.
address'] = '192.168.0.134'
PowerCLI C:\> $HashTable['network.hostPortGroup["key-vim-profile-hos
t-HostPortgroupProfile-ManagementNetwork"].ipConfig.IpAddressPolicy.
subnetmask'] = '255.255.255.0'
PowerCLI C:\> $HashTable['network.dnsConfig.HostNamePolicy.hostName'
] = 'Esx001'
```

You are now ready to apply the host profile to the host with the answers you provided in the hash table using the \$HashTable variable as the value of the -Variable parameter:

```
PowerCLI C:\> $HashTable = $VMHost |
>> Apply-VMHostProfile -Variable $HashTable -Confirm:$false
>>
```

Exporting a host profile

You can use the Export-VMHostProfile cmdlet to export a host profile to a file that is in the VMware profile format (.vpf). This can be useful if you want to transfer a host profile to another vCenter Server. Just export the host profile on the first vCenter Server and then import the host profile on the second vCenter Server.

When exporting, a host profile administrator and user profile passwords are not exported for security reasons. When a host profile is imported and applied to a host, you will be prompted to enter values for the passwords.

The syntax of the Export-VMHostProfile cmdlet is:

```
Export-VMHostProfile [-FilePath] <String> [-Profile] <VMHostProfile>
[-Force] [-Server <VIServer>] [<CommonParameters>]
```

Let's export the Cluster-Profile host profile to a .vpf file:

```
PowerCLI C:\> Get-VMHostProfile -Name Cluster-Profile |
>> Export-VMHostProfile -FilePath ~\Cluster-Profile.vpf
>>
```

Mode	LastWriteTime	Length	n Name
-a	12/29/2013 11:	35 AM 911587	Cluster-Profile.vpf

The ~ character in the file path is a PowerShell way to specify the default directory of the current user account.

The Cluster-Profile.vpf file is an XML file that contains the configuration of the reference host that was used to create the host profile. This is a huge file. If you are wondering what is in this file, take a look at the content with Notepad or another editor.

Importing a host profile

You can use the Import-VMHostProfile cmdlet to import a host profile from a file.

The Import-VMHostProfile cmdlet has the following syntax:

```
Import-VMHostProfile [-FilePath] <String> [-Name] <String>
[[-ReferenceHost] <VMHost>] [-Description <String>] [-Server
<VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Let's import the Cluster-Profile.vpf file that we just created to create a new host profile called New-Profile:

```
PowerCLI C:\> Import-VMHostProfile -Name New-Profile `
>> -FilePath C:\Users\Robert\Cluster-Profile.vpf `
>> -ReferenceHost 192.168.0.133 -Description "New profile"
>>
```

Name	Description
New-Profile	New profile

You can now attach New-Profile to a cluster or to a host.



When writing this book, the Import-VMHostProfile cmdlet did not understand the ~ character in the value of the -FilePath parameter. This is why I used the full path for the Cluster-Profile.vpf file.

Working with host services

PowerCLI has a number of cmdlets to work with host services. You can easily find these cmdlets using the Get-Command cmdlet:

PowerCLI C:\> Get-Command -Noun VMHostService

${\tt CommandType}$	Name	ModuleName
Cmdlet	Get-VMHostService	${\tt VMware.VimAutomation.Core}$
Cmdlet	Restart-VMHostService	${\tt VMware.VimAutomation.Core}$
Cmdlet	Set-VMHostService	${\tt VMware.VimAutomation.Core}$
Cmdlet	Start-VMHostService	${\tt VMware.VimAutomation.Core}$
Cmdlet	Stop-VMHostService	VMware.VimAutomation.Core

Retrieving information about host services

You can use the Get-VMHostService cmdlet to retrieve information about the services running on a host.

The syntax of the Get-VMHostService cmdlet is:

Get-VMHostService [-VMHost] <VMHost[]> [-Refresh] [-Server <VIServer[]>]
[<CommonParameters>]

Let's retrieve a list of all the services of one of the hosts:

PowerCLI C:\> Get-VMHostService -VMHost 192.168.0.133

Key	Label	Policy	Running
DCUI	Direct Console UI	on	True
TSM	ESXi Shell	off	False
TSM-SSH	SSH	off	False
lbtd	lbtd	on	True

lsassd	Local Security Authenticati	off	False
lwiod	I/O Redirector (Active Dire	off	False
netlogond	Network Login Server (Activ	off	False
ntpd	NTP Daemon	off	False
sfcbd-watchdog	CIM Server	on	True
snmpd	snmpd	on	False
vmware-fdm	$vSphere\ High\ Availability\ A\dots$	off	False
vprobed	vprobed	off	False
vpxa	vpxa	on	True
xorg	xorg	on	False



The default output of the Get-VMHostService cmdlet also shows the values of the Required property. I removed the Required column to fit the output to the page width of this book.

Starting a host service

Starting a host service can be useful to temporarily enable a service. For example, if you want to enable the ESXi shell to login into an ESXi server, you need to start the TSM service. The Start-VMHostService cmdlet will start a host service. The syntax of this cmdlet is:

Start-VMHostService [-HostService] <HostService[] > [-WhatIf] [-Confirm]
[<CommonParameters>]

The -HostService parameter is required.

For example, to start the TSM service, you can use:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-VMHostService |
>> Where-Object {$_.Key -eq "TSM"} | Start-VMHostService
>>
```

Key	Label	Policy	Running
TSM	ESXi Shell	off	True

Stopping a host service

After you have temporarily enabled a service, you should stop the service if you don't plan to use it anymore. Some services, such as the SSH service, produce a warning if you keep them running. To stop a service, you need to use the Stop-VMHostService cmdlet. The syntax is similar to the Start-VMHostService cmdlet's syntax:

```
Stop-VMHostService [-HostService] <HostService[]> [-WhatIf] [-Confirm]
[<CommonParameters>]
```

To stop the TSM service we started in the previous section, use the following command line:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-VMHostService |
>> Where-Object {$ .Key -eq 'TSM'} |
>> Stop-VMHostService -Confirm:$false
>>
                                                Policy
                                                        Running
                    Label
Key
                                                         -----
                    ----
                                                -----
---
                                                off
                    ESXi Shell
                                                        False
TSM
```

Restarting a host service

If you want to restart a host service because it is not running well or you modified the settings of the service, you can use the Restart-VMHostService cmdlet.

The syntax of this cmdlet is:


```
Restart-VMHostService [-HostService] <HostService[] > [-WhatIf] [-Confirm]
[<CommonParameters>]
```

In the next example, we will restart the TSM service. I modified this example, in comparison with the previous start and stop host services examples, to show you that in PowerCLI there are different ways you can use to perform a task.

Modifying the startup policy of a host service

You can use the Set-VMHostService cmdlet to modify the startup policy of a host service.

The next screenshot shows you how to edit the startup policy of a host service in the vSphere Web Client:



The syntax of the Set-VMHostService cmdlet is:

```
Set-VMHostService [-HostService] <HostService[]> [-Policy]
<HostServicePolicy> [-WhatIf] [-Confirm] [<CommonParameters>]
```

Possible values for the -Policy parameter are: automatic, on, and off. These values correspond with the following values in the VMware vSphere Client:

VMware vSphere Client service startup policy	Set-VMHostService -Policy value
Start and stop with port usage	automatic
Start and stop with host	on
Start and stop manually	off

TSM

TSM

Let's modify the startup policy of the TSM service and set it to on. We will use the \$HostService variable from the previous example:

PowerCLI C:\> Set-VMHostService -HostService \$HostService -Policy on

Key	Label	Policy	Running	Required
TSM	ESXi Shell	on	True	False

In the next example, the startup policy of the TSM service for all of your hosts will be set to off:

```
PowerCLI C:\> Get-VMHost | Get-VMHostService |
>> Where-Object {$_.Key -eq 'TSM'} |
>> Set-VMHostService -Policy Off
>>

Key Label Policy Running Required
```

Configuring the host firewall

ESXi Shell

ESXi Shell

A host firewall is a VMware vSphere feature to protect the host against attacks. The host firewall allows or blocks traffic to and from specific host services. You can use PowerCLI to configure the host firewall.

off

off

True

False

False

False

To get a list of all of the PowerCLI cmdlets that you can use to configure a host firewall, type:

PowerCLI C:\> Get-Command -Noun VMHostFirewall*

CommandType	Name
Cmdlet	Get-VMHostFirewallDefaultPolicy
Cmdlet	Get-VMHostFirewallException
Cmdlet	Set-VMHostFirewallDefaultPolicy
Cmdlet	Set-VMHostFirewallException

Getting the host firewall default policy

To get the host firewall default policy of a host, you have to use the Get-VMHostFirewallDefaultPolicy cmdlet.

The syntax of the Get-VMHostFirewallDefaultPolicy cmdlet is:

```
Get-VMHostFirewallDefaultPolicy [-VMHost] <VMHost[]> [[-Server]
<VIServer[]>] [<CommonParameters>]
```

Let's first get the host firewall default policy for a host:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.133
PowerCLI C:\> Get-VMHostFirewallDefaultPolicy -VMHost $VMHost
IncomingEnabled OutgoingEnabled
```

```
False False
```

In the given example, the default policy is that the incoming and outgoing traffic is disabled. This is, of course, the most secure policy and it is recommended to keep this policy unless you have a very good reason to change it.

Modifying the host firewall default policy

You can change the host firewall default policy using the Set-VMHostFirewallDefaultPolicy cmdlet.

The Set-VMHostFirewallDefaultPolicy cmdlet has the following syntax:

```
Set-VMHostFirewallDefaultPolicy [[-AllowIncoming] [<Boolean>]]
[[-AllowOutgoing] [<Boolean>]] [-Policy] <VMHostFirewallDefaultPolicy[]>
[-WhatIf] [-Confirm] [<CommonParameters>]
```

If your host firewall default policy enables incoming or outgoing traffic, you can set it to be disabled for both with:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.133
PowerCLI C:\> $Policy = $VMHost | Get-VMHostFirewallDefaultPolicy
PowerCLI C:\> $Policy | Set-VMHostFirewallDefaultPolicy `
>> -AllowIncoming $false -AllowOutgoing $false
>>

IncomingEnabled OutgoingEnabled
```

```
IncomingEnabled OutgoingEnabled
-----
False False
```

Getting the host firewall exceptions

You can specify exceptions from the host firewall default policy. To get a list of all of the exceptions for a specific host, you have to use the Get-VMHostFirewallException cmdlet.

This cmdlet has the following syntax:

```
Get-VMHostFirewallException [[-Name] <String[]>] [-VMHost] <VMHost[]>
[-Port <Int32[]>] [-Enabled [<Boolean>]] [-Server <VIServer[]>]
[<CommonParameters>]
```

To get a list of all of the exceptions, you can use:

PowerCLI C:\> \$VMHost | Get-VMHostFirewallException

Name	Enabled	IncomingPorts	OutgoingPorts	Protocols
CIM Server	True	5988		TCP
CIM Secure Server	True	5989		TCP
CIM SLP	True	427	427	UDP, TCP
DHCPv6	True	546	547	TCP, UDP
DVFilter	False	2222		TCP
DVSSync	False	8301, 8302	8302, 8301	UDP
HBR	True		31031, 44046	TCP
IKED	False	500	500	UDP
NFC	True	902	902	TCP
WOL	True		9	UDP
Active Directory All	False		88, 123, 13	UDP, TCP
DHCP Client	True	68	68	UDP
DNS Client	True	53	53	UDP, TCP
Fault Tolerance	True	8100, 8200,	80, 8100, 8	TCP, UDP
vSphere High Avai	False	8182	8182	TCP, UDP
FTP Client	False	20	21	TCP
gdbserver	False	1000-9999,		TCP
httpClient	False		80, 443	TCP
Software iSCSI Cl	False		3260	TCP
NFS Client	False		0-65535	TCP
NTP Client	False		123	UDP
VM serial port co	False	23, 1024-65535	0-65535	TCP

SNMP Server	True	161		UDP
SSH Client	False		22	TCP
SSH Server	True	22		TCP
syslog	False		514, 1514	UDP, TCP
vCenter Update Ma	False		80, 9000-9100	TCP
vMotion	True	8000	8000	TCP
VM serial port co	False		0-65535	TCP
vSphere Client	True	902, 443		TCP
vprobeServer	False	57007		TCP
VMware vCenter Agent	True		902	UDP
vSphere Web Access	True	80		TCP

You can use the -Name or -Port parameters to filter for a specific exception. For example, to get all of the exceptions for port number 22, use:

PowerCLI C:\> \$VMHost | Get-VMHostFirewallException -Port 22

Name	Enabled	IncomingPorts	OutgoingPorts	Protocols
NFS Client	False		0-65535	TCP
VM serial port co	False	23, 1024-65535	0-65535	TCP
SSH Client	False		22	TCP
SSH Server	True	22		TCP
VM serial port co	False		0-65535	TCP

Modifying a host firewall exception

Sometimes it is necessary to make changes to the host firewall exceptions, for example, when you want to configure an external syslog server. In this section, I will show you how to do this.

To modify the host firewall exceptions, you have to use the Set-VMHostFirewallException cmdlet. This cmdlet has the following syntax:

```
Set-VMHostFirewallException [-Enabled] [<Boolean>] [-Exception]
<VMHostFirewallException[]> [-WhatIf] [-Confirm] [<CommonParameters>]
```

Let's assume that we have configured a syslog server on a vCenter Server 192.168.0.132. To configure the syslog server on the host, you can use the Set-VMHostSysLogServer cmdlet. The syntax of this cmdlet is:

Set-VMHostSysLogServer [[-SysLogServer] <NamedIPEndPoint>] [-VMHost]
<VMHost[]> [-SysLogServerPort <Int32>] [-Server <VIServer[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]

First you need to set the remote syslog server:

After this, you have to enable the host firewall exception for the syslog server:

```
PowerCLI C:\> $VMHost | Get-VMHostFirewallException -Name syslog | `
>> Set-VMHostFirewallException -Enabled $true
>>
```

Name	Enabled	IncomingPorts	OutgoingPorts	Protocols
syslog	True		514, 1514	UDP, TCP

Configuring vSphere Image Builder and Auto Deploy

VMware vSphere Auto Deploy is a cool feature introduced in VMware vSphere 5.0 that enables you to provide physical hosts with the ESXi software via the PXE boot instead of installing an ESXi server from a CD-ROM. Auto Deploy can be useful if you need to deploy many ESXi servers. If you only have a few ESXi servers, Auto Deploy is probably not the best solution for you because of the amount of work you have to do to set up Auto Deploy. To enable Auto Deploy, you need a vCenter Server, an Auto Deploy server, a DNS server, a DHCP server, a TFTP server, and PowerCLI. Yes, you have seen it right. PowerCLI is a core component of Auto Deploy. All the information you need to enable and configure Auto Deploy can be found in the VMware document, "vSphere Installation and Setup Guide". You can download this document from the VMware vSphere documentation page: https://www.vmware.com/support/pubs/vsphere-esxi-vcenter-server-pubs.html

Because this is a PowerCLI book, we will focus on the PowerCLI cmdlets that you can use to create and deploy a host image.

Configuring Image Builder

Before you can deploy an image using Auto Deploy, you first have to create the image using Image Builder. In PowerCLI, the Image Builder cmdlets are in a separate module called VMware.ImageBuilder. This module is loaded by default if you start PowerCLI. Let's get a list of all of the Image Builder cmdlets:

PowerCLI C:\> Get-Command -Module VMware.ImageBuilder

CommandType	Name	ModuleName
Cmdlet	Add-EsxSoftwareDepot	VMware.ImageBuilder
Cmdlet	Add-EsxSoftwarePackage	VMware.ImageBuilder
Cmdlet	Compare-EsxImageProfile	VMware.ImageBuilder
Cmdlet	Export-EsxImageProfile	VMware.ImageBuilder
Cmdlet	Get-EsxImageProfile	VMware.ImageBuilder
Cmdlet	Get-EsxSoftwareDepot	VMware.ImageBuilder
Cmdlet	Get-EsxSoftwarePackage	VMware.ImageBuilder
Cmdlet	New-EsxImageProfile	VMware.ImageBuilder
Cmdlet	Remove-EsxImageProfile	VMware.ImageBuilder
Cmdlet	Remove-EsxSoftwareDepot	VMware.ImageBuilder
Cmdlet	Remove-EsxSoftwarePackage	VMware.ImageBuilder
Cmdlet	Set-EsxImageProfile	VMware.ImageBuilder

First, you have to add an ESXi software depot to your PowerCLI session. An ESXi software depot contains image profiles and **vSphere Installation Bundle** (**VIB**) files. An image profile is a list of VIBs. If you want to know what is in a VIB, you can find out at http://blogs.vmware.com/vsphere/2011/09/whats-in-a-vib.html.

Use the Add-EsxSoftwareDepot cmdlet to add an ESXi software depot to your PowerCLI session. You can use an ESXi software depot provided on the VMware website or you can download the ESXi installable from the VMware website in the depot.zip format. For example, for ESXi 5.5, this file is called VMware-ESXi-5.5.0-1331820-depot.zip.

The Add-EsxSoftwareDepot cmdlet has the following syntax:

Add-EsxSoftwareDepot [-DepotUrl] <String[]> [-WarningAction <ActionPreference>] [-WarningVariable <String>] [<CommonParameters>]

To add the official VMware software depot to your PowerCLI session, use:

PowerCLI C:\> Add-EsxSoftwareDepot -DepotUrl https://hostupdate.vmware.com/software/VUM/PRODUCTION/main/vmw-depot-index.xml

```
Depot Url
```

https://hostupdate.vmware.com/software/VUM/PRODUCTION/main/vmw-d...

If you want to deploy HA modules for your ESXi servers, you also have to connect to the HA depot on your vCenter Server. For example:

To add the software depot from a depot.zip file that you downloaded from the VMware website, use:

PowerCLI C:\> Add-EsxSoftwareDepot -DepotUrl 'C:\users\robert\Downlo ads\VMware vSphere 5.5\VMware-ESXi-5.5.0-1331820-depot.zip'

```
Depot Url
```

zip:C:\users\robert\Downloads\VMware vSphere 5.5\VMware-ESXi-5.5...

After adding an ESXi software depot to your PowerCLI session, you can use the Get-EsxImageProfile cmdlet to see the contents of the ESXi software depot.

The Get-EsxImageProfile cmdlet has the following syntax:

```
Get-EsxImageProfile [[-Name] <String[]>] [[-Vendor] <String[]>]
[[-AcceptanceLevel] <AcceptanceLevels[]>] [-WarningAction
<ActionPreference>] [-WarningVariable <String>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

For example:

PowerCLI C:\> Get-EsxImageProfile

Name	Vendor		Last Modi:	fied		Accepta
						nce Lev
ESXi-5.5.0-1331820-standard	VMware,	Inc.	9/19/2013	6:07:00	AM	Partner
ESXi-5.5.0-1331820-no-tools	VMware.	Inc.	9/19/2013	6:07:00	ΑМ	Partner

Configuring Auto Deploy

The Auto Deploy cmdlets are in the PowerCLI module VMware.DeployAutomation. You can use the Get-Command cmdlet to list all the Auto Deploy cmdlets:

PowerCLI C:\> Get-Command -Module VMware.DeployAutomation

${\tt CommandType}$	Name	ModuleName
Cmdlet	Add-DeployRule	VMware.DeployAutomation
Cmdlet	Apply-ESXImageProfile	VMware.DeployAutomation
Cmdlet	Copy-DeployRule	VMware.DeployAutomation
Cmdlet	Get-DeployOption	VMware.DeployAutomation
Cmdlet	Get-DeployRule	VMware.DeployAutomation
Cmdlet	Get-DeployRuleSet	VMware.DeployAutomation
Cmdlet	Get-VMHostAttributes	VMware.DeployAutomation
Cmdlet	Get-VMHostImageProfile	VMware.DeployAutomation
Cmdlet	Get-VMHostMatchingRules	VMware.DeployAutomation
Cmdlet	New-DeployRule	VMware.DeployAutomation
Cmdlet	Remove-DeployRule	VMware.DeployAutomation
Cmdlet	Repair-DeployImageCache	VMware.DeployAutomation
Cmdlet	Repair-DeployRuleSetCompliance	VMware.DeployAutomation
Cmdlet	Set-DeployOption	VMware.DeployAutomation
Cmdlet	Set-DeployRule	VMware.DeployAutomation
Cmdlet	Set-DeployRuleSet	VMware.DeployAutomation
Cmdlet	Switch-ActiveDeployRuleSet	VMware.DeployAutomation
Cmdlet	Test-DeployRuleSetCompliance	VMware.DeployAutomation

Now that we have the image profiles created with Image Builder, we need to create deploy rules to specify the image to be deployed to the hosts. You can create a deploy rule using the New-DeployRule cmdlet that has the following syntax:

```
New-DeployRule [-Name] <String> -Pattern <String[]> -Item
<VIObjectCore[]> [<CommonParameters>]
```

```
New-DeployRule [-Name] <String> -AllHosts -Item <VIObjectCore[]>
[<CommonParameters>]
```

Let's create a deploy rule that will deploy the ESXi-5.5.0-1331820-standard image to all hosts:

```
PowerCLI C:\> New-DeployRule -Name ImageRule `
>> -Item ESXi-5.5.0-1331820-standard -AllHosts
>>
```

The preceding command generates too much output to show in this book.

You also need to create a deploy rule that specifies the location for the hosts. Let's locate the hosts in the datacenter New York:

```
PowerCLI C:\> New-DeployRule -Name LocationRule -Item "New York" >> -AllHosts
```

Name : LocationRule

PatternList:

ItemList : {New York}

Now, we have to add the newly created rules to the working ruleset using the Add-DeployRule cmdlet. The Add-DeployRule cmdlet has the following syntax:

```
Add-DeployRule [-DeployRule] <DeployRule[]> [[-At] <UInt32>] [-NoActivate] [<CommonParameters>]
```

To add both rules to the working ruleset, use:

PowerCLI C:\> Add-DeployRule -DeployRule ImageRule

Name : ImageRule

PatternList:

ItemList : {ESXi-5.5.0-1331820-standard}

PowerCLI C:\> Add-DeployRule -DeployRule LocationRule

Name : ImageRule

PatternList:

ItemList : {ESXi-5.5.0-1331820-standard}

Name : LocationRule

PatternList:

ItemList : {New York}

To check which rulesets are active, you can use the Get-DeployRuleSet cmdlet. This cmdlet has the following syntax:

```
Get-DeployRuleSet [-Active] [-Working] [<CommonParameters>]
```

The cmdlet has two parameters -Active and -Working. The -Active parameter will retrieve the active ruleset. The active ruleset shows how new hosts are to be deployed. The -Working parameter will retrieve the working ruleset. This ruleset can be used to test changes before making them active.

Let's retrieve the active deploy ruleset:

PowerCLI C:\> Get-DeployRuleSet -Active

Name : ImageRule

PatternList:

ItemList : {ESXi-5.5.0-1331820-standard}

Name : LocationRule

PatternList :

ItemList : {New York}

Now, you are almost ready to deploy hosts using Auto Deploy. The hosts only need configuration, which will be done using host profiles. You have to connect the host profiles to Auto Deploy using deploy rules. Let's assume you have a host profile called Cluster-Profile. You can connect this host profile to Auto Deploy using the New-DeployRule and Add-DeployRule cmdlets that you have seen before. Let's create a deploy rule named HostProfileRule, which connects the host profile Cluster-Profile to all hosts:

```
PowerCLI C:\> New-DeployRule -Name HostProfileRule `
>> -Item Cluster-Profile -AllHosts
>>
```

Name : HostProfileRule

PatternList:

ItemList : {Cluster-Profile}

PowerCLI C:\> Add-DeployRule -DeployRule HostProfileRule

Name : ImageRule

PatternList :

ItemList : {ESXi-5.5.0-1331820-standard}

Name : LocationRule

PatternList :

ItemList : {New York}

Name : HostProfileRule

PatternList :

ItemList : {Cluster-Profile}

To configure the host name and IP addresses, the preferred way is to use static DHCP entries. An alternative is to use static IP addresses in the host profile and use answer files for each host.

Using esxcli from PowerCLI

VMware offers more command-line interfaces for vSphere than PowerCLI. One of them is the **vSphere Command-Line Interface** (**vSphere CLI**). The vSphere CLI has a command called <code>esxcli</code>. PowerCLI has built-in support for this <code>esxcli</code> command in the <code>Get-EsxCli</code> cmdlet.



There are no New-EsxCli, Set-EsxCli, and Remove EsxCli cmdlets. The Get-EsxCli cmdlet exposes the esxcli functionality for a host. You cannot create a new one, modify, or remove it.

The syntax of the Get-EsxCli cmdlet is:

```
Get-EsxCli -VMHost <VMHost[]> [[-Server] <VIServer[]>]
[<CommonParameters>]
```

Use the Get-EsxCli cmdlet to connect to the esxcli functionality of a host and save the connection in a variable \$esxcli:

```
PowerCLI C:\> $esxcli = Get-EsxCli -VMHost 192.168.0.133
```

In the vSphere CLI, the command to get information about the CPUs in your host is:

```
C:\>esxcli --server=192.168.0.133 hardware cpu list
Enter username: root
Enter password:
```

In PowerCLI, the command becomes a little different. The <code>Get-EsxCLI</code> cmdlet returns a PowerShell object and you have to use the properties and methods of this object to create the commands. This is why you have to put dots between all of the words in the command. And if the last word is a method, you have to specify parentheses for a parameter list even if there are no parameters. The command from the preceding example becomes the following in PowerCLI:

```
PowerCLI C:\> $esxcli.hardware.cpu.list()
```

You can, of course, use the vSphere documentation to find the available <code>esxcli</code> commands. But you can also use PowerCLI for help. If you type in a partial command, you will get a list of elements and methods that are possible for this command. Let's start with <code>\$esxcli</code> itself:

```
PowerCLI C:\> $esxcli
========
EsxCli: 192.168.0.133
```

Elements: -----device esxcli fcoe graphics hardware iscsi network sched software storage system vm

You see that one of the elements is hardware. Let's try hardware as the next command:

You now have all the command elements you can use after hardware. Let's try cpu:

```
PowerCLI C:\> $esxcli.hardware.cpu
_____
EsxCliElement: cpu
  Elements:
  _____
  cpuid
  global
  Methods:
  _____
  Cpu[] list()
And now you have obtained the list() method that we used in the previous example.
A lot of the esxcli commands also provide a help() method that gives information
about the command. To get help about the $esxcli.hardware.cpu command, type:
PowerCLI C:\> $esxcli.hardware.cpu.help()
_____
vim.EsxCLI.hardware.cpu
______
CPU information.
ChildElement
-----
- hardware.cpu.cpuid | Information from the CPUID instruction on ea
                ch CPU.
- hardware.cpu.globa | Information and configuration global to all
 1
                CPUs.
```

| List all of the CPUs on this host.

Method

- list

If you want to know what the parameters for an esxcli method are, you can use the vSphere documentation or you can use the Get-Member cmdlet:

PowerCLI C:\> \$esxcli.hardware.cpu | Get-Member

TypeName:

VMware.VimAutomation.ViCore.Impl.V1.EsxCli.EsxCliElementImpl

Name	MemberType	Definition
list	${\tt CodeMethod}$	<pre>vim.EsxCLI.hardware.cpu.list.Cpu[]</pre>
cpuid	CodeProperty	VMware.VimAutomation.Sdk.Util10Ps
global	CodeProperty	VMware.VimAutomation.Sdk.Util10Ps
ConvertToVersion	Method	T VersionedObjectInterop.ConvertTo
Equals	Method	bool Equals(System.Object obj)
GetHashCode	Method	<pre>int GetHashCode()</pre>
GetType	Method	<pre>type GetType()</pre>
help	Method	VMware.VimAutomation.ViCore.Types
IsConvertableTo	Method	<pre>bool VersionedObjectInterop.IsConv</pre>
ToString	Method	string ToString()
Client	Property	VMware.VimAutomation.ViCore.Intero
FullName	Property	string FullName {get;}
Id	Property	string Id {get;}
Name	Property	string Name {get;}
Uid	Property	string Uid {get;}



The relevant information in the Definition column is abbreviated because of the limited width of a book page. You will get more information if you run this command in a PowerCLI session with a larger window width.

Listing all of the available esxcli commands

You can use PowerCLI to list all of the available <code>esxcli</code> commands for a host using the <code>Get-EsxcliCommand</code> function. If you save the function in a file called <code>Get-EsxcliCommand.psl</code>, you can load the function into your PowerCLI session by dotsourcing the file:

PowerCLI C:\> . .\Get-EsxCliCommand.ps1

Dot-sourcing is the PowerShell way to load the functions of a PowerShell script into your PowerShell session. You have to specify a dot and a space in front of the path to a PowerShell script file. If you just run the PowerShell script without dot-sourcing, after the script is finished the functions defined in the script will not be available in your PowerShell session.

Now that you have loaded the Get-ESXCliCommand function into your PowerCLI session, you can call the function with the \$esxcli variable as the -EsxCli parameter value to list all the available esxcli commands:

PowerCLI C:\> Get-EsxCliCommand -EsxCli \$esxcli

Showing the output of the preceding command is beyond the scope of this book. If you want to see the output and all of the possible <code>esxcli</code> commands, take a look at my blogpost at http://rvdnieuwendijk.com/2012/08/19/how-to-list-all-the-powercli-esxcli-commands/ where you can also download the <code>Get-EsxCliCommand</code> function.

```
function Get-EsxCliCommand {
```

The Get-EsxCliCommand function starts with the comment-based function help. This makes it possible that, after defining the function in your PowerCLI session, you can use the Get-Help cmdlet to get help about the function:

```
#
.SYNOPSIS
Lists all the possible PowerCLI ESXCLI commands.

.DESCRIPTION
Lists all the possible PowerCLI ESXCLI commands.

.PARAMETER EsxCli
The VMware.VimAutomation.ViCore.Impl.V1.EsxCli.EsxCliImpl or VMware.VimAutomation.ViCore.Impl.V1.EsxCli.EsxCliElementImpl object for which all the possible PowerCLI ESXCLI command must be returned.

.PARAMETER Name
The top level name of the listed commands. The default is '$esxcli'.

.EXAMPLE
PS C:\> $esxcli = Get-EsxCli -VMhost ESX1.yourdomain.com
PS C:\> Get-EsxCliCommand -EsxCli $esxcli
```

```
Lists all the PowerCLI ESXCLI commands for server
     ESX1.yourdomain.com.
    .EXAMPLE
     PS C:\> $esxcli = Get-EsxCli -VMhost ESX1.yourdomain.com
     PS C:\> Get-EsxCliCommand -EsxCli $esxcli.network `
              -Name '$esxcli.network'
     Lists all the PowerCLI ESXCLI network commands for server
     ESX1.yourdomain.com.
    .INPUTS
     VMware.VimAutomation.ViCore.Impl.V1.EsxCli.EsxCliImpl
     VMware.VimAutomation.ViCore.Impl.V1.EsxCli.EsxCliElementImpl
     System.String
    .OUTPUTS
     System.String
    .NOTES
     Author: Robert van den Nieuwendijk
     Version: 1.0
     Date: 19-8-2012
    .LINK
     http://rvdnieuwendijk.com/
#>
```

The next part of the function defines the output of the function as a string, the <code>-EsxCli</code> parameter as a mandatory parameter, and <code>-Name</code> as a parameter consisting of an array of strings. The <code>-Name</code> parameter is used in recursive calls to the function to specify the name of the current position in the tree:

```
[CmdletBinding()]
[OutputType([string])]
param(
   [parameter(Mandatory=$true,Position=0)]$EsxCli,
   [parameter(Position=1)][String[]]$Name='$esxcli')
```

The next part writes the current esxcli command to the output:

```
# Write the current command to the output stream
[string]::Join('.',$Name)
```

The next part uses recursion to list all of the properties of the current esxcli command. Recursion means that a function calls itself. The Get-Member cmdlet is used to select only the properties:

The next part uses recursion to list all of the methods of the current esxcli command. The Get-Member cmdlet is used to select only the methods:

Using the vSphere CLI commands from PowerCLI

If you installed both VMware vSphere PowerCLI and VMware vSphere CLI on the same computer, you can use the vSphere CLI Perl commands from PowerCLI. Using the VMware vSphere CLI commands, you can perform tasks that you cannot do with PowerCLI natively, such as configuring IPsec on your ESXi host with the <code>vicfg-ipsec</code> command.

The Add-vCLIfunction function creates a function string for each Perl script in the vSphere CLI bin directory. The function strings are executed using the PowerShell Invoke-Expression cmdlet. This creates a PowerShell function for each vSphere CLI Perl script.

```
function Add-vCLIfunction {
  .SYNOPSIS
    Adds the VMware vSphere Command-Line Interface Perl scripts
    as PowerCLI functions.
  .DESCRIPTION
    Adds all the VMware vSphere Command-Line Interface Perl
    scripts as PowerCLI functions.
    VMware vSphere Command-Line Interface has to be installed on
    the system where you run this function.
    You can download the VMware vSphere Command-Line Interface
    from:
http://communities.vmware.com/community/vmtn/server/vsphere/
automationtools/vsphere cli?view=overview
  .EXAMPLE
    Add-vCLIfunction
    Adds all the VMware vSphere Command-Line Interface Perl
    scripts as PowerCLI functions to your PowerCLI session.
  . COMPONENT
    VMware vSphere PowerCLI
```

```
.NOTES
   Author: Robert van den Nieuwendijk
            12/29/2013
   Version: 1.1
  .LINK
   http://rvdnieuwendijk.com/
  #>
  # Test if VMware vSphere Command-Line Interface is installed
  if (${env:ProgramFiles(x86)})
    $ProgramFiles = ${env:ProgramFiles(x86)}
 else
    $ProgramFiles = $env:ProgramFiles
  $vCLIBinDirectory = "$ProgramFiles\VMware\VMware vSphere CLI\Bin\"
  If (-not (Test-Path -Path $vCLIBinDirectory)) {
   Write-Error "VMware vSphere CLI should be installed before running
this function."
 else {
    # Add all the VMware vSphere CLI perl scripts as PowerCLI
    # functions
   Get-ChildItem -Path "$vCLIBinDirectory\*.pl" |
    ForEach-Object {
      $Function = "function global:$($_.Name.Split('.')[0]) { perl
'$vCLIBinDirectory\$($ .Name)'"
      $Function += ' $args }'
      Invoke-Expression $Function
  }
}
```

After you have run the Add-vCLIfunction function, you can use the vSphere CLI Perl scripts from your PowerCLI session. The next example uses the vSphere CLI vicfg-nics -1 command to retrieve all of the NICs from all of the hosts. Although I know that you can do this in PowerCLI as well, using the Get-VMHostNetworkAdapter cmdlet, I use this example to show the power of the combination of PowerCLI and vSphere CLI.

To prevent you from having to enter the username and password for every vSphere CLI command that you run, you can store them in the environment variables VI_USERNAME and VI_PASSWORD:

```
# Example how you can use PowerCLI to run VMware vSphere CLI
# Perl scripts
Add-vCLIfunction
$env:VI_USERNAME="root"
$env:VI_PASSWORD="TopSecret"
Get-VMHost | ForEach-Object {
   vicfg-nics -l --server $_.Name
}
```

You can use the method shown in the Add-vCLIfunction function to extend PowerShell with custom functions from third-party binaries.


Removing a host from the VMware vCenter Server

To remove a host from your vCenter Server inventory, you have to use the Remove-VMHost cmdlet. The Remove-VMHost cmdlet has the following syntax:

```
Remove-VMHost [-VMHost] <VMHost[]> [-Server <VIServer[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

Let's try to remove a host as seen in the following screenshot:

The operation failed because the host should have been in maintenance mode or a disconnected state before you could remove it.



So let's put the host in maintenance mode first and then try to remove it:

PowerCLI C:\> \$VMHost | Remove-VMHost -Confirm:\$false

The preceding command sets the host in maintenance mode and will remove it from the vCenter Server inventory and cluster.

Summary

In this chapter, we covered working with ESXi hosts using PowerCLI. You saw how to add and remove hosts to and from your vSphere vCenter Server inventory. We looked at putting a host in maintenance mode and how to exit maintenance mode. We have seen how PowerCLI commands work with host profiles and host services. You learned to use the PowerCLI commands for Image Builder and Auto Deploy and finally the use of the <code>esxcli</code> command and the vSphere CLI commands from PowerCLI was discussed.

The next chapter will be about managing virtual machines with PowerCLI.

5 Managing Virtual Machines with PowerCLI

As a VMware vSphere administrator, you probably spend a lot of your time creating, modifying, or removing virtual machines. In this chapter, you will learn how to do this with PowerCLI.

The topics that will be covered in this chapter are:

- Creating a virtual machine
- Registering a virtual machine
- Using OS customization specifications
- Starting and stopping a virtual machine
- Modifying the settings of a virtual machine
- Converting a virtual machine into a template
- Moving a virtual machine to another folder, host, cluster, resource pool, or datastore
- Updating VMware Tools
- Upgrading the virtual machine compatibility
- Using snapshots
- Running commands in the guest OS
- Configuring Fault Tolerance
- Opening the console of a virtual machine
- Removing a virtual machine

Creating a virtual machine

There are several ways in which you can create a new virtual machine, such as:

- Deploying a virtual machine from a template
- Cloning another virtual machine
- Using VMware vCenter Converter to convert a physical computer to a virtual machine (P2V)
- Building a new virtual machine from scratch using traditional methods such as an installation CD-ROM or ISO file to install the operating system

To create a new virtual machine using PowerCLI, you have to use the New-VM cmdlet. The New-VM cmdlet has the following syntax containing four parameter sets.

The default parameter set is shown in the following command line:

```
New-VM [-AdvancedOption <AdvancedOption[]>] [[-VMHost] <VMHost>]
[-Version <VMVersion>] -Name <String> [-ResourcePool <VIContainer>]
[-VApp <VApp>] [-Location <Folder>] [-Datastore <StorageResource>]
[-DiskMB <Int64[]>] [-DiskGB <Decimal[]>] [-DiskPath <String[]>]
[-DiskStorageFormat <VirtualDiskStorageFormat>] [-MemoryMB <Int64>]
[-MemoryGB <Decimal>] [-NumCpu <Int32>] [-Floppy] [-CD] [-GuestId <String>] [-AlternateGuestName <String>] [-NetworkName <String[]>]
[-Portgroup <VirtualPortGroupBase[]>] [-HARestartPriority <HARestartPriority>] [-HAIsolationResponse <HAIsolationResponse>]
[-DrsAutomationLevel <DrsAutomationLevel>] [-VMSwapfilePolicy <VMSwapfilePolicy>] [-Server <VIServer[]>] [-RunAsync] [-Notes <String>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The parameter set for creating a virtual machine from a template is as follows:

```
New-VM [-AdvancedOption <AdvancedOption[]>] [[-VMHost] <VMHost>]
-Name <String> [-ResourcePool <VIContainer>] [-VApp <VApp>]
[-Location <Folder>] [-Datastore <StorageResource>] [-Template]
<Template> [-DiskStorageFormat <VirtualDiskStorageFormat>]
[-OSCustomizationSpec <OSCustomizationSpec>] [-HARestartPriority
<HARestartPriority>] [-HAIsolationResponse <HAIsolationResponse>]
[-DrsAutomationLevel <DrsAutomationLevel>] [-Server <VIServer[]>]
[-RunAsync] [-Notes <String>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The parameter set for cloning a virtual machine is as follows:

```
New-VM [-AdvancedOption <AdvancedOption[]>] [[-VMHost] <VMHost>]
[-Name <String>] [-ResourcePool <VIContainer>] [-VApp <VApp>]
[-Location <Folder>] [-Datastore <StorageResource>]
[-DiskStorageFormat <VirtualDiskStorageFormat>] [-OSCustomizationSpec <OSCustomizationSpec>] [-HARestartPriority <HARestartPriority>]
[-HAIsolationResponse <HAIsolationResponse>] [-DrsAutomationLevel <DrsAutomationLevel>] [-LinkedClone] [-ReferenceSnapshot <Snapshot>]
[-Server <VIServer[]>] [-RunAsync] [-Notes <String>] -VM
<VirtualMachine[]> [-WhatIf] [-Confirm] [<CommonParameters>]
```

The parameter set for registering a virtual machine is as follows:

```
New-VM [[-VMHost] <VMHost>] [-Name <String>] [-ResourcePool
<VIContainer>] [-VApp <VApp>] [-Location <Folder>]
[-HARestartPriority <HARestartPriority>] [-HAIsolationResponse
<HAIsolationResponse>] [-DrsAutomationLevel <DrsAutomationLevel>]
-VMFilePath <String> [-Server <VIServer[]>] [-RunAsync] [-Notes
<String>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Name, -Template, -VM, and -VMFilePath parameters are required for creating a virtual machine.

Remember that, if you use parameters, they will all have to come from the same set. How would you find the names of the parameter sets? You can find these names using the Get-Command cmdlet, as shown in the following command:

```
PowerCLI C:\> (Get-Command New-VM).ParameterSets.Name
```

The output of the previous command is as follows:

DefaultParameterSet

Template

CloneVm

RegisterVm

The preceding command is in PowerShell v3 syntax. In PowerShell v2, the command is as follows:

```
PowerCLI C:\> (Get-Command New-VM).ParameterSets |
>> Select-Object -ExpandProperty Name
>>
```

You can see that the PowerShell v3 syntax is shorter and more elegant. If you are still using PowerShell v2, I encourage you to upgrade to v3.

You can find the PowerShell version of your session with the following command:



PowerCLI C:\> \$PSVersionTable.PSVersion

As you can see from the following output, I am using PowerShell v3:

Major	Minor	Build	Revision
3	0	-1	-1

As you can see in the preceding command, Get-Command shows you the names of the four parameter sets, in this case, DefaultParameterSet, Template, CloneVm, and RegisterVm. You can see that there are different parameter sets for creating a virtual machine from a template, cloning a virtual machine, and registering a virtual machine. Registering a virtual machine is not really creating a new virtual machine. It is adding an existing virtual machine to a vSphere inventory. I will show you examples from all of these parameter sets in the following sections: Creating a virtual machine from scratch, Creating a virtual machine from a template, Cloning a virtual machine, and Registering a virtual machine.

Creating a virtual machine from scratch

In this section, we'll start with creating a virtual machine from scratch. For this purpose, you'll need to use the DefaultParameterSet parameter set. You'll need to specify values for the -Name parameter, which is required, and one of these parameters: -ResourcePool, -VMHost, or -VApp. The -ResourcePool parameter accepts VMHost, Cluster, ResourcePool, and VApp objects. All of these objects individually act as a resource pool. We will create a virtual machine named VM1 and add it to the cluster Cluster01 with the following command lines:

```
PowerCLI C:\> $Cluster = Get-Cluster -Name Cluster01
PowerCLI C:\> New-VM -Name VM1 -ResourcePool $Cluster
```

The output of the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM1	PoweredOff	1	0.250

You have now created your first virtual machine with PowerCLI. This virtual machine has the default settings because you only specified the minimum required parameters. For example, the virtual machine has only 256 MB of memory and a 4 GB disk. You probably want to change these figures. To do this, you can use other parameters, such as <code>-Datastore</code>, <code>-DiskGB</code>, <code>-DiskStorageFormat</code>, <code>-MemoryGB</code>, <code>-NumCpu</code>, and <code>-NetworkName</code>, to create a virtual machine that fulfills your needs. After creating a virtual machine, you can modify it using the <code>Set-VM</code> cmdlet, which will be discussed later in this chapter. However, some settings, such as the disk size, you are better off knowing right from the start. This is because increasing the disk size also requires changes to the filesystem. Shrinking the disk size is only possible by making a backup of the disk, removing the disk, creating a smaller disk, and then restoring the backup.

Let's create a more advanced virtual machine named VM2 with the help of the following command:

```
PowerCLI C:\> $DataStoreCluster = Get-DatastoreCluster -Name `
>> DatastoreCluster1
>>
PowerCLI C:\> New-VM -Name VM2 -ResourcePool $Cluster -Datastore `
>> $DataStoreCluster -DiskGB 20 -DiskStorageFormat Thin `
>> -MemoryGB 4 -NumCPU 2 -NetworkName "VM Network"
>>
```

The output of the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM2	PoweredOff	2	4.000

While creating VM2, we specified a datastore cluster so that Storage DRS could provide the best datastore in the datastore cluster for initial placement of the virtual machine. We also specified Thin as the storage format, to **thin provision** the disk, and the memory size in GB, the number of virtual CPUs, and the name of the virtual machine's network.

The virtual machines VM1 and VM2 have no operating system installed. To install an operating system, you can start the virtual machine and connect a CD-ROM or an ISO file containing an operating system installation disk; alternatively, you can use methods such as a PXE boot.

Creating a virtual machine from a template

Deploying a virtual machine from a template is much easier than installing one from scratch. When you deploy a virtual machine from a template, you create a new virtual machine that is a copy of the template.

To create the template, you first have to create a virtual machine. Install the operating system with all of the software and patches to be included for each virtual machine deployed. When the virtual machine is ready, you have to convert it into a template. You will learn how to do this with PowerCLI later in this chapter.

If you have different operating systems that you need to deploy, you can create a template for each one, for example, Microsoft Windows Server 2012, Red Hat Enterprise Linux 6 (64-bit), and so on. After creating the template, you can deploy a virtual machine from this template using the New-VM -Template parameter.

VM1 is a template. We will use this template to deploy virtual machine VM3 with the following command lines:

```
PowerCLI C:\> $Cluster = Get-Cluster -Name Cluster01
PowerCLI C:\> New-VM -Name VM3 -Template VM1 -ResourcePool $Cluster
```

The preceding command lines will give the following output:

```
Name
               PowerState Num CPUs MemoryGB
                -----
VM3
               PoweredOff 1
                               0.250
```



You can also specify other parameters to change settings.

Cloning a virtual machine

If you clone a virtual machine, you will create a duplicate of the virtual machine with the same configuration and installed software as those on the original virtual machine. This can be done while the source virtual machine is powered on. You have to specify the source virtual machine in the value of the -VM parameter.

Let's clone the VM3 virtual machine into a new virtual machine called VM4:

```
PowerCLI C:\> $Cluster = Get-Cluster -Name Cluster01
PowerCLI C:\> New-VM -Name VM4 -VM VM3 -ResourcePool $Cluster
```

The output will be as follows:

Name	PowerState	Num CPUs	MemoryGB
VM4	PoweredOff	1	0.250

Registering a virtual machine

To register an existing virtual machine to your vCenter inventory, you have to specify the path to a .vmx file. A .vmx file contains the configuration for an existing virtual machine. Here are a few lines from a .vmx file:

```
.encoding = "UTF-8"
config.version = "8"
virtualHW.version = "10"
vmci0.present = "TRUE"
displayName = "vm4"
extendedConfigFile = "vm4.vmxf"
floppy0.present = "FALSE"
memSize = "256"
```

You typically don't modify a .vmx file with an editor, because you might break the connection to the virtual machine. The VMware **Knowledge Base** article (available at http://kb.vmware.com/kb/1714) gives tips for editing a .vmx file.

The following example will register a virtual machine named VM4:

```
PowerCLI C:\> $Cluster = Get-Cluster -Name Cluster01
PowerCLI C:\> New-VM -Name VM4 -ResourcePool $Cluster `
>> -VMFilePath "[Datastore2] VM4/VM4.vmx"
>>
```

The output of the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM4	PoweredOff	1	0.250

In the following screenshot of the vSphere Web Client, you will see all of the files of a virtual machine in its datastore folder:

Name	Size	Modified	Туре
∠	4,194,304.00 KB	2/6/2013 4:37 PM	Virtual Disk
₩ VM4.vmx	2.07 KB	2/9/2013 2:09 PM	Virtual Machine
☐ VM4.vmxf	0.25 KB	2/9/2013 7:49 AM	File
☐ VM4.vmsd	0.00 KB	2/6/2013 4:37 PM	File
NM4.flp VM4.flp	1,440.00 KB	2/8/2013 12:32	Floppy Image
➡ VM4.nvram	8.48 KB	2/9/2013 2:09 PM	Non-volatile Memory File
wmware-1.log	91.34 KB	2/9/2013 1:48 PM	VM Log File
wmware-2.log	91.88 KB	2/9/2013 1:51 PM	VM Log File
wmware-3.log	91.79 KB	2/9/2013 1:52 PM	VM Log File
wmware-4.log	91.78 KB	2/9/2013 1:54 PM	VM Log File
wmware-5.log	91.88 KB	2/9/2013 1:56 PM	VM Log File
vmware-6.log	91.79 KB	2/9/2013 1:59 PM	VM Log File
	263,218.33 KB	2/9/2013 2:09 PM	File
vmware.log	94.79 KB	2/9/2013 2:09 PM	VM Log File

Using OS customization specifications

OS customization specifications are XML files that contain guest operating system settings – such as the computer name, network settings, and license settings – for virtual machines.

Let's get a list of all the OS customization specifications cmdlets:

```
PowerCLI C:\> Get-Command -Noun OSCustomization* |
>> Select-Object -Property Name
>>
```

The output of the preceding command is as follows:

Name

Get-OSCustomizationNicMapping

Get-OSCustomizationSpec

New-OSCustomizationNicMapping

New-OSCustomizationSpec

Remove-OSCustomizationNicMapping

Remove-OSCustomizationSpec

Set-OSCustomizationNicMapping

Set-OSCustomizationSpec

To create an OS customization specification or to clone an existing one, you have to use the New-OSCustomizationSpec cmdlet. This cmdlet has the following syntaxes:

```
New-OSCustomizationSpec [-OSType <String>] [-Server <VIServer[]>]
[-Name <String>] [-Type <OSCustomizationSpecType>] [-DnsServer
<String[]>] [-DnsSuffix <String[]>] [-Domain <String>] [-NamingScheme
<String>] [-NamingPrefix <String>] [-Description <String>] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

```
New-OSCustomizationSpec -OSCustomizationSpec <OSCustomizationSpec>
[-Server <VIServer[]>] [-Name <String>] [-Type
<OSCustomizationSpecType>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

```
New-OSCustomizationSpec -FullName <String> -OrgName <String> [-OSType <String>] [-ChangeSid] [-DeleteAccounts] [-Server <VIServer[]>] [-Name <String>] [-Type <OSCustomizationSpecType>] [-DnsServer <String[]>] [-DnsSuffix <String[]>] [-GuiRunOnce <String[]>] [-AdminPassword <String>] [-TimeZone <String>] [-AutoLogonCount <Int32>] [-Domain <String>] [-Workgroup <String>] [-DomainCredentials <PSCredential>] [-DomainUsername <String>] [-DomainPassword <String>] [-ProductKey <String>] [-NamingScheme <String>] [-NamingPrefix <String>] [-Description <String>] [-LicenseMode <LicenseMode>] [-LicenseMaxConnections <Int32>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -OSCustomizationSpec, -FullName, and -OrgName parameters are required to create or clone OS customization specifications.

The cmdlet has three parameter sets: the first one is for Linux operating systems, the second for cloning OS customization specifications, and the third for Windows guest operating systems.

To use the New-OSCustomizationSpec cmdlet, you have to be connected to a vCenter Server and you have to use PowerCLI in 32-bit mode. If you are using a 32-bit computer, PowerCLI will always be 32-bit. However, if you are using a 64-bit computer, you will have both 64-bit and 32-bit versions of PowerCLI installed. To start the 32-bit version of PowerCLI, click on VMware vSphere PowerCLI (32-Bit).



Let's start with creating a Linux OS customization specification called LinuxOSSpec that specifies Linux as the type of operating system, and blackmilktea.com as the domain name using the following command:

```
PowerCLI C:\> New-OSCustomizationSpec -Name LinuxOSSpec `
>> -OSType Linux -Domain blackmilktea.com -Description "Linux spec"
>>
```

The preceding command will give the following output:

```
        Name
        Description Type

        ----
        ----

        LinuxOSSpec
        Linux spec Persistent
```

Now, we can clone this OS customization specification with the following command:

```
PowerCLI C:\ > New-OSCustomizationSpec -Name LinuxOSSpec2 `
>> -OSCustomizationSpec LinuxOSSpec
>>
```

The output to the preceding command is as follows:

```
        Name
        Description Type

        ----
        ----

        LinuxOSSpec2
        Linux spec Persistent
```

Creating a Windows OS customization specification requires some more parameters.

```
PowerCLI C:\> New-OSCustomizationSpec -Name WindowsOSSpec `
>> -OSType Windows `
>> -Domain blackmilktea.com -DomainUsername DomainAdmin `
>> -DomainPassword TopSecret -FullName "Domain administrator"
>> -OrgName "Black Milk Tea Inc." -Description "Windows Spec"
>>
```

The output to the preceding command is as follows:

```
        Name
        Description
        Type

        ----
        -----
        -----

        WindowsOSSpec
        Windows Spec
        Persistent
```

You can now use an OS customization specification if you create a virtual machine from a template or when you clone a virtual machine. For example, you can use the following command:

```
PowerCLI C:\> New-VM -Name VM5 -Template Windows2012Template `>> -OSCustomizationSpec WindowsOSSpec -VMHost 192.168.0.133 >>
```

The output to the preceding command is as follows:

Name	PowerState	Num	CPUs	MemoryGB
VM5	PoweredOff	1		4.000

Starting and stopping a virtual machine

You have created your virtual machine but it is still powered off. In this section, you will learn how to start, suspend, and stop a virtual machine using PowerCLI.

Starting a virtual machine

To start a virtual machine, you can use the Start-VM cmdlet. This cmdlet has the following syntax:

```
Start-VM [-RunAsync] [-VM] <VirtualMachine[]> [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VM parameter is required to start a virtual machine.

In the first example, we will start the virtual machine VM2 using the following command:

```
PowerCLI C:\> Start-VM -VM VM2
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	${\tt MemoryGB}$
VM2	PoweredOn	1	1.000

To start all of your virtual machines that are powered off, you can pipe the output of the Get-VM cmdlet with a where filter to select only those virtual machines that are powered off. Pipe the result to the Start-VM cmdlet using the following command and all of your virtual machines that are powered off will be started:

```
PowerCLI C:\> Get-VM |
>> Where-Object {$_.PowerState -eq 'PoweredOff'} | Start-VM
>>
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM4	Powered0n	1	0.250
VM2	PoweredOn	1	1.000
VM1	PoweredOn	1	0.250
VM3	PoweredOn	1	0.250

Suspending a virtual machine

If you want to put a virtual machine on hold without powering it down, you can suspend it using the Suspend-VM cmdlet. This cmdlet has the following syntax:

```
Suspend-VM [-RunAsync] [-VM] <VirtualMachine[]> [-Server
<VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VM parameter is required.

In the following example, we will suspend the VM4 virtual machine:

```
PowerCLI C:\> Get-VM -Name VM4 | Suspend-VM -Confirm:$false
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM4	Suspended	1	0.250

If you want to restart a virtual machine, you have to use the Start-VM cmdlet.

Shutting down a virtual machine's guest operating system

If you want to shut down the operating system of a virtual machine, you should use the Shutdown-VMGuest cmdlet. This cmdlet uses VMware Tools to ask the guest operating system to perform a graceful shutdown. If the VMware Tools are not running in the virtual machine, the Shutdown-VMGuest cmdlet will not work and generate an error message. The cmdlet returns immediately and does not wait until the guest operating system has been shut down.

The Shutdown-VMGuest cmdlet has the following syntax:

```
Shutdown-VMGuest [[-VM] <VirtualMachine[]>] [[-Server] <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
Shutdown-VMGuest [[-Guest] <VMGuest[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

You must specify either the -Guest or -VM parameter.

In the following example, we will shut down the guest operating system of the VM4 virtual machine:

```
PowerCLI C:\> Shutdown-VMGuest -VM VM4 -Confirm:$false
```

The output to the preceding command is as follows:

```
State IPAddress OSFullName
-----
Running {192.168.0.145, f... Microsoft Windows Server 2012 (64-bit)
```

Stopping a virtual machine

If shutting down a virtual machine is not possible, because VMware Tools is not installed on the guest operating system, you can use the <code>Stop-VM</code> cmdlet to stop a virtual machine. The <code>Stop-VM</code> cmdlet works like the power switch on a physical computer. This will force the virtual machine to power off without gracefully shutting down the guest operating system. The syntax of the <code>Stop-VM</code> cmdlet is as follows:

```
Stop-VM [-Kill] [-RunAsync] [-VM] <VirtualMachine[]> [-Server
<VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VM parameter is required.

In the following example, we will stop the VM3 virtual machine:

```
PowerCLI C:\> Stop-VM -VM VM3 -Confirm:$False
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM3	PoweredOff	1	0.250

Modifying the settings of a virtual machine

To modify the settings of a virtual machine, you can use the Set-VM cmdlet. This cmdlet has the following syntax:

```
Set-VM [-VM] <VirtualMachine[]> [-Name <String>] [-Version
<VMVersion>] [-MemoryMB <Int64>] [-MemoryGB <Decimal>] [-NumCpu
<Int32>] [-GuestId <String>] [-AlternateGuestName <String>] [-
OSCustomizationSpec <OSCustomizationSpec>] [-HARestartPriority
<HARestartPriority>] [-HAIsolationResponse <HAIsolationResponse>] [-
DrsAutomationLevel <DrsAutomationLevel>] [-Server <VIServer[]>] [-
RunAsync] [-VMSwapFilePolicy <VMSwapfilePolicy>] [-Notes <String>] [-
WhatIf] [-Confirm] [<CommonParameters>]
Set-VM [-VM] <VirtualMachine[]> [-Name <String>] [-Snapshot
<Snapshot>] [-OSCustomizationSpec <OSCustomizationSpec>] [-
HARestartPriority <HARestartPriority>] [-HAIsolationResponse
<HAIsolationResponse>] [-DrsAutomationLevel <DrsAutomationLevel>] [-
Server <VIServer[]>] [-RunAsync] [-VMSwapFilePolicy
<VMSwapfilePolicy>] [-WhatIf] [-Confirm] [<CommonParameters>]
Set-VM [-VM] <VirtualMachine[]> [-Name <String>] [-Server
<VIServer[]>] [-RunAsync] [-ToTemplate] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -VM parameter is required.

The first parameter set is the default. The second parameter set is for reverting a virtual machine to a snapshot. The third parameter set converts a virtual machine into a template.

Using the preceding parameter sets, you can modify the name, hardware version, amount of memory, number of virtual CPUs, guest operating system, high availability settings, DRS settings, swap file policy, and the description of the virtual machine. You can also use the Set-VM cmdlet to apply an OS customization specification to a virtual machine.

In this example, we will rename the virtual machine VM7 to DNS1 and give the virtual machine two CPUs and 8 GB of memory. If CPU hot plug and memory hot plug are not enabled, you have to power off the virtual machine before executing the next command or the command will fail and generate the following message:

"CPU hot plug is not supported for this virtual machine."


To perform the renaming and memory allocation, use the following command:

```
PowerCLI C:\> Set-VM -VM VM7 -Name DNS1 -NumCpu 2 -MemoryGB 8 -Confirm:$false
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
DNS1	PoweredOff	2	8.000

In the following screenshot of the vSphere Web Client, you will see the **Virtual Hardware** tab in the **Edit Settings** window for the virtual machine DNS1 after running the preceding PowerCLI command:



In this next example, we will configure the DNS1 virtual machine as a Microsoft Windows Server 2012 (64-bit) server using the -GuestId parameter. We will also modify the description of the virtual machine to "DNS Server".

```
PowerCLI C:\> Set-VM -VM DNS1 -GuestID windows8Server64Guest `
>> -Notes "DNS Server" -Confirm:$false
```

The output to the preceding command is as follows:


Name	PowerState	Num CPUs	MemoryGB
DNS1	PoweredOff	2	8.000



Go to the following website and click on vSphere API Reference: http://www.vmware.com/support/developer/vc-sdk/
You will find a list of valid GuestId values for specific ESXi versions in the description of the VirtualMachineGuestOsIdentifier enumeration type.

Using the VMware vSphere API

You cannot use the Set-VM cmdlet to modify all virtual machine settings. Sometimes, you have to use the VMware vSphere API, for example, if you want to enable the **Force BIOS setup** feature. In the following screenshot of the vSphere Web Client, you will see the **VM Options** tab in the **Edit Settings** window for the virtual machine **VM2**. As you can see, the **Force BIOS setup** checkbox is unchecked:



In the following example, I will show you how to enable **Force BIOS setup** for the virtual machine VM2:

```
$spec = New-Object Vmware.Vim.VirtualMachineConfigSpec
$spec.bootOptions = New-Object `
Vmware.Vim.VirtualMachineBootOptions
$spec.bootOptions.enterBIOSSetup = $true
$vm = Get-VM -Name VM2
$vm.ExtensionData.ReconfigVM Task($spec)
```

In the preceding example, we first created a Vmware. Vim.

VirtualMachineConfigSpec object. Then, we created a Vmware.Vim. VirtualMachineBootOptions object and added it to the bootOptions property to the VirtualMachineConfigSpec object. The bootOptions.enterBIOSSetup property is set to \$true. Finally, the ReconfigVM_Task method is run for the virtual machine to reconfigure the virtual machine asynchronously.



If you are unsure of how to write VMware vSphere API code, take a look at the VMware Onyx Fling. Onyx is a code generator. It can generate PowerCLI code for tasks that you perform in the VMware vSphere client. You can download Onyx and other VMware Flings at http://labs.vmware.com/flings.Unfortunately, Onyx does not support the vSphere Web Client.

Adding devices to a virtual machine

There are several cmdlets that you can use to add devices to your virtual machines:

- New-HardDisk
- New-NetworkAdapter
- New-FloppyDrive
- New-ScsiController
- New-CDDrive

We will discuss these cmdlets in this section.



While writing this book, there are no PowerCLI cmdlets to add serial ports, parallel ports, USB controllers, USB devices, or PCI devices to a virtual machine or to remove them. If you want to perform any of these tasks, you have to use the VMware vSphere API.

Adding a hard disk

The New-HardDisk cmdlet has the following syntax:

```
New-HardDisk [-AdvancedOption <AdvancedOption[]>] [[-Persistence]
<String>] [-Controller <ScsiController>] [[-DiskType] <DiskType>]
[-CapacityKB <Int64>] [-CapacityGB <Decimal>] [-Split]
[-ThinProvisioned] [-StorageFormat <VirtualDiskStorageFormat>]
[-DeviceName <String>] [-Datastore <StorageResource>] [-VM]
<VirtualMachine[]> [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
New-HardDisk [[-Persistence] <String>] [-Controller <ScsiController>]
-DiskPath <String> [-VM] <VirtualMachine[]> [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The first parameter set is to create a new hard disk, and the second parameter set is to use an existing hard disk. The -VM and -DiskPath parameters are required.

Some of the parameters are obsolete and scheduled for removal in a future PowerCLI version. These parameters are: -CapacityKB, -Split, and -ThinProvisioned. You should avoid using these parameters in your scripts if you want your scripts to be compatible with future PowerCLI versions.

Let's add a 20 GB, thin-provisioned hard disk drive to the VM2 virtual machine:

```
PowerCLI C:\> Get-VM -Name VM2 |
>> New-HardDisk -CapacityGB 20 -StorageFormat Thin
>>
```

The output to the preceding command is as follows:

CapacityGB	Persistence	Filename
20.000	Persistent	[Datastore1] VM2/VM2 1.vmdk

You don't have to power off a virtual machine to add a hard disk. This can be done while the virtual machine is running.

The hard disk will be created on the same datastore as the virtual machine because the -Datastore parameter is not specified.

Adding a SCSI controller

To add a new SCSI controller to a virtual machine, you can use the New-ScsiController cmdlet. The syntax of this cmdlet is as follows:

```
New-ScsiController [-HardDisk] <HardDisk[]> [[-Type]
<ScsiControllerType>] [[-BusSharingMode] <ScsiBusSharingMode>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -HardDisk parameter is required. The valid values for the -Type parameter are: ParaVirtual, VirtualBusLogic, VirtualLsiLogic, and VirtualLsiLogicSAS. The valid values for the -BusSharingMode parameter are: NoSharing, Physical, and Virtual.

Did you notice that the New-ScsiController cmdlet doesn't have a -VM parameter? You have to specify a new or existing hard disk for which you want to add a new SCSI controller. Because the hard disk is connected to a virtual machine, you automatically connect the new SCSI controller to this virtual machine through the hard disk.

A virtual machine must be powered off before you add a SCSI controller to it. For example, you can use the following command:

```
PowerCLI C:\> Get-VM -Name VM3 |
>> New-HardDisk -CapacityGB 10 -StorageFormat Thin |
>> New-ScsiController -Type ParaVirtual
>>
```

The output to the preceding command is as follows:

Type	BusSharingMode	UnitNumber
ParaVirtual	NoSharing	5

In the preceding example, we added a new SCSI controller for a new, 10 GB, thin-provisioned hard disk to the VM3 virtual machine.

Adding a network adapter

The syntax of the New-NetworkAdapter cmdlet is as follows:

```
New-NetworkAdapter [-MacAddress <String>] -NetworkName <String> [-StartConnected] [-WakeOnLan] [-Type <VirtualNetworkAdapterType>] [-VM] <VirtualMachine[]> [-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]

New-NetworkAdapter [-MacAddress <String>] [-StartConnected] [-WakeOnLan] [-Type <VirtualNetworkAdapterType>] -PortId <String> -DistributedSwitch <DistributedSwitch> [-VM] <VirtualMachine[]> [-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]

New-NetworkAdapter [-MacAddress <String>] [-StartConnected] [-WakeOnLan] [-Type <VirtualNetworkAdapterType>] -Portgroup <VirtualPortGroupBase> [-VM] <VirtualMachine[]> [-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The first parameter set is the default one, the second parameter set is the advanced one, and the third parameter set is for connecting to a port group.


The -VM, -NetworkName, -PortId, -DistributedSwitch, and -Portgroup parameters are required. The valid virtual network adapter types for the -Type parameter are e1000, Flexible, Vmxnet, EnhancedVmxnet, Vmxnet3, and Unknown. If no value is given to the -Type parameter, the new network adapter will be of the type recommended by VMware for the given guest OS.

The following example will add a network adapter of type Vmxnet3 to the VM2 virtual machine. The network adapter will be connected to "VM network" when the virtual machine is started.

```
PowerCLI C:\> Get-VM -Name VM2 |
>> New-NetworkAdapter -NetworkName "VM Network" `
>> -StartConnected -Type Vmxnet3
>>
```

The output to the preceding command is as follows:

In the following screenshot of the vSphere Web Client, you see the **Virtual Hardware** tab in the **Edit Settings** window for the virtual machine VM2. It shows the new network adapter that has just been added to the virtual machine.



Adding a floppy drive

You can use the New-FloppyDrive cmdlet to connect a virtual machine to a floppy disk drive in an ESXi server or to connect a virtual machine to a floppy image file. Modern server hardware doesn't include floppy disk drives anymore. This is why I will show you only how to connect to a floppy image.

The New-FloppyDrive cmdlet has the following syntax:

New-FloppyDrive [-FloppyImagePath <String>] [-NewFloppyImagePath
<String>] [-HostDevice <String>] [-StartConnected] [-VM]
<VirtualMachine[]> [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]

The -VM parameter is required.

The following example adds a floppy image file to the VM3 virtual machine and the floppy drive starts connected when the virtual machine is powered on. You can only add a floppy drive to a virtual machine while the virtual machine is powered off. The value of the <code>-NewFloppyImagePath</code> parameter has to be a path to a file on a datastore. Let's do it with the following command:

```
PowerCLI C:\> New-FloppyDrive -VM VM3 -StartConnected `
>> -NewFloppyImagePath '[Datastore2] VM3/VM3.flp'
>>
```

The output to the preceding command is as follows:

FloppyImage	HostDevice	RemoteDevice

The command returns property names with no values. This is because the default output of the New-FloppyDrive cmdlet shows the FloppyImage, HostDevice, and RemoteDevice properties, which are empty when you add a floppy image file to a virtual machine. These properties are only used when you connect a floppy drive to a floppy disk drive in an ESXi server.

Adding a CD drive

The New-CDDrive cmdlet creates a new virtual CD drive. This cmdlet has the following syntax:

```
New-CDDrive [-IsoPath <String>] [-HostDevice <String>]
[-StartConnected] [-VM] <VirtualMachine[]> [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VM parameter is required.

This cmdlet looks a lot like the New-FloppyDrive cmdlet. You can connect to the CD drive on the virtual machine's host or you can connect to an ISO file on a datastore.

In the following example, we will connect a new CD drive to the VM4 virtual machine. The CD drive will start connected when the virtual machine is powered on and will be connected to a Windows Server 2012 ISO file located in the ISOs folder in Datastore2:

```
PowerCLI C:\> New-CDDrive -VM VM4 -StartConnected `
>> -IsoPath '[Datastore2] ISOs\WindowsServer2012.iso'
>>
```

The output to the preceding command is as follows:

IsoPath	HostDevice	RemoteDevice
[Datastore2] ISOs		

You can use the vSphere PowerCLI Datastore Provider to search for files in datastores. Datastore Provider was introduced in *Chapter 2*, *Learning Basic PowerCLI Concepts*.

Modifying devices added to a virtual machine

After having added devices to your virtual machines, you might want to change the settings for these devices. The reason may be a hard disk that needs to grow or a network adapter that must move to another virtual network. To modify a device, you can use the Set-* cmdlets: Set-HardDisk, Set-ScsiController, Set-NetworkAdapter, Set-FloppyDrive, and Set-CDDrive.

Modifying a hard disk

To modify a hard disk, you can use the Set-HardDisk cmdlet. This cmdlet has four parameter sets. They are as follows:

```
Set-HardDisk [-HardDisk] <HardDisk[]> [[-CapacityKB] <Int64>]
[-CapacityGB < Decimal>] [[-Persistence] < String>] [[-Datastore]
<Datastore>] [-StorageFormat <VirtualDiskStorageFormat>] [-Controller
<ScsiController>] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
Set-HardDisk [-HardDisk] <HardDisk[]> [[-CapacityKB] <Int64>]
[-CapacityGB < Decimal >] [[-Persistence] < String >] [[-Datastore]
<Datastore>] [-StorageFormat <VirtualDiskStorageFormat>] [-Controller
<ScsiController>] [-Server <VIServer[]>] [-HostCredential
<PSCredential>] [-HostUser <String>] [-HostPassword <SecureString>]
[-GuestCredential <PSCredential>] [-GuestUser <String>]
[-GuestPassword <SecureString>] [-ToolsWaitSecs <Int32>] [-HelperVM
<VirtualMachine>] [-Partition <String>] [-ResizeGuestPartition]
[-WhatIf] [-Confirm] [<CommonParameters>]
Set-HardDisk [-HardDisk] <HardDisk[] > [-Inflate] [-WhatIf] [-Confirm]
[<CommonParameters>]
Set-HardDisk [-HardDisk] <HardDisk[]> [-ZeroOut] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -HardDisk parameter is required.

The first parameter set is for changing the capacity, persistence, datastore, storage format, or SCSI controller of a hard disk. The second parameter set is for resizing a guest partition of a hard disk. The third parameter set is for inflating a hard disk. Lastly, the fourth parameter set is for filling a hard disk with zeroes.

In the following example, we will increase the size of the hard disk for virtual machine VM6 ('Hard Disk 1') to $8\,\mathrm{GB}$:

```
PowerCLI C:\> Get-VM -Name VM6 | Get-HardDisk |
>> Where-Object {$_.Name -eq 'Hard Disk 1'} |
>> Set-HardDisk -CapacityGB 8 -Confirm:$false
>>
```

The output to the preceding command is as follows:

CapacityGB	Persistence		Filename
8.000	Persistent	[Datastore2]	vm6/vm6.vmdk

It is not possible to shrink a hard disk using the Set-HardDisk cmdlet. This prevents you from corrupting a guest operating filesystem after making a disk too small.

In the following example, we will modify the persistence of the hard disk for virtual machine VM6 ("Hard Disk 1") to IndependentPersistent to prevent the disk from participating in virtual machine snapshots:

```
PowerCLI C:\> Get-VM -Name VM6 | Get-HardDisk |
>> Where-Object {$_.Name -eq "Hard Disk 1"} |
>> Set-HardDisk -Persistence IndependentPersistent -Confirm:$false
>>
```

The output to the preceding command is as follows:

CapacityGB	Persistence		Filename
8.000	IndependentPersis	[Datastore2]	vm6/vm6.vmdk

Moving a hard disk to another datastore

You can use the Move-HardDisk cmdlet to move a hard disk to another datastore and modify the storage format of the hard disk. This is useful if a datastore is running out of space or if a datastore has a high I/O load and you want to move a hard disk to another datastore to balance the load. If you want to move all of the disks of a virtual machine to the same datastore, it is better to use the Move-VM cmdlet; it will be discussed later in this chapter. The Move-HardDisk cmdlet has the following syntax:

```
Move-HardDisk [-HardDisk] <HardDisk[]> [-Datastore] <Datastore> [-StorageFormat <VirtualDiskStorageFormat>] [-Server <VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Let's move Hard Disk 2 from the VM2 virtual machine to Datastorel and change the storage format to Thick with the following command:

```
PowerCLI C:\> Get-VM -Name VM2 | Get-HardDisk |
>> Where-Object {$_.Name -eq "Hard Disk 2"} |
>> Move-HardDisk -Datastore Datastorel -StorageFormat Thick -
Confirm:$false
```

The output to the preceding command is as follows:

CapacityGB	Persistence	Filename
20.000	Persistent	[Datastore1] VM2/VM2 1.vmdk

Modifying a SCSI controller

To modify a SCSI controller, you can use the Set-ScsiController cmdlet. This cmdlet has the following syntax:

```
Set-ScsiController [-ScsiController] <ScsiController[]>
[-BusSharingMode <ScsiBusSharingMode>] [-Type <ScsiControllerType>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

You cannot use the -Type and -BusSharing parameters at the same time. First, you have to run the Set-ScsiController cmdlet to set the type and then run the cmdlet again to configure the bus sharing mode. The valid values for the -Type and -BusSharing parameters are the same as the parameters for the New-ScsiController cmdlet. To modify a SCSI controller, the virtual machine needs to be powered off.

First, we will modify the type of SCSI controller for the VM4 virtual machine to type ParaVirtual. Make sure that you have the VMware Tools installed on your virtual machine because the VMware Tools contain the drivers for the **paravirtual** devices.

```
PowerCLI C:\> Get-ScsiController -VM VM4 |
>> Set-ScsiController -Type ParaVirtual -Confirm:$false
>>
```

The output to the preceding command is as follows:

Type	${ t BusSharing Mode}$	UnitNumber
ParaVirtual	NoSharing	3

After this, we modify the SCSI controller's BusSharingMode parameter to Virtual. This enables virtual disks to be shared by virtual machines on the same host. If you set BusSharingMode to Physical, the virtual disks on this SCSI controller can be shared by virtual machines on any vSphere host:

```
PowerCLI C:\> Get-ScsiController -VM VM4 |
>> Set-ScsiController -BusSharingMode Virtual -Confirm:$false
>>
```

The output to the preceding command is as follows:

Туре	${ t BusSharing Mode}$	UnitNumber
ParaVirtual	Virtual	3

Modifying a network adapter

The Set-NetworkAdapter cmdlet modifies the configuration of a virtual network adapter. You can change the MAC address, adapter type, and the network name, and configure the Connected, StartConnected, and WakeOnLan properties of the adapter.

The Set-NetworkAdapter cmdlet has the following syntax:

```
Set-NetworkAdapter [-NetworkAdapter] <NetworkAdapter[]> [-MacAddress
<String>] [-NetworkName <String>] [-StartConnected [<Boolean>]]
[-Connected [<Boolean>]] [-WakeOnLan [<Boolean>]] [-Type
<VirtualNetworkAdapterType>] [-RunAsync] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

```
Set-NetworkAdapter [-NetworkAdapter] <NetworkAdapter[]> [-MacAddress
<String>] [-StartConnected [<Boolean>]] [-Connected [<Boolean>]]
[-WakeOnLan [<Boolean>]] [-Type <VirtualNetworkAdapterType-]
-PortId <String> -DistributedSwitch <DistributedSwitch> [-RunAsync]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Set-NetworkAdapter [-NetworkAdapter] <NetworkAdapter[]> -Portgroup
<VirtualPortGroupBase> [-RunAsync] [-Server <VIServer[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]

The first parameter set is the default one. The second parameter set is for connecting to a port by key. The third parameter set is for connecting to a port group. The required parameters are <code>-NetworkAdapter</code>, <code>-PortId</code>, <code>-DistributedSwitch</code>, and <code>-Portgroup</code>.

If you want to give a network adapter a fixed MAC address, this address has to be in the range 00:50:56:00:00:00 to 00:50:56:3F:FF:FF. In the following example, we'll give the network adapter of the VM4 virtual machine a fixed MAC address of 00:50:56:00:00:01:

```
PowerCLI C:\> Get-VM -Name VM4 | Get-NetworkAdapter |
>> Set-NetworkAdapter -MacAddress 00:50:56:00:00:01 -Confirm:$false
```

The output to the preceding command is as follows:

```
Name Type NetworkName MacAddress WakeOnLanEnabled
```

Network adapter 1 Flexible VM Network 00:50:56:00:00:01 False

We will now modify the adapter type to e1000, the network name to Vlan 7, and enable StartConnected and WakeOnLan for the same network adapter:

```
PowerCLI C:\> Get-VM -Name VM4 | Get-NetworkAdapter |
>> Set-NetworkAdapter -NetworkName "Vlan 7" -Type e1000 `
>> -StartConnected:$true -WakeOnLan:$true -Confirm:$false
>>
```

The output to the preceding command is as follows:

Modifying a floppy drive

You can use the Set-FloppyDrive cmdlet to modify a floppy drive. The syntax of this cmdlet is:

```
Set-FloppyDrive [-Floppy] <FloppyDrive[]> [-FloppyImagePath <String>]
[-HostDevice <String>] [-NoMedia] [-StartConnected [<Boolean>]]
[-Connected [<Boolean>]] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Floppy parameter is required.

To modify the floppy drive of the VM4 virtual machine to StartConnected, you can use the following command:

```
PowerCLI C:\> Get-VM -Name VM3 | Get-FloppyDrive |
>> Set-FloppyDrive -StartConnected:$true -Confirm:$false
>>
```

The output to the preceding command is as follows:

FloppyImage	HostDevice	RemoteDevice


Modifying a CD drive

To modify a virtual CD drive, use the Set-CDDrive cmdlet, which has the following syntax:

```
Set-CDDrive [-CD] <CDDrive[]> [-IsoPath <String>] [-HostDevice
<String>] [-NoMedia] [-StartConnected [<Boolean>]] [-Connected
[<Boolean>]] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -CD parameter is required to modify a CD drive.

You can use the -IsoPath parameter to point the CD to an ISO image. You can enable or disable the StartConnected and Connected flags. If the -NoMedia parameter is set to \$true, it removes the CD drive's media backing and disconnects it.



In the following example, we will mount an ISO image from a datastore to the CD drive of the VM4 virtual machine:

```
PowerCLI C:\> Get-VM -Name VM4 | Get-CDDrive |
>> Set-CDDrive -IsoPath '[Cluster01_Vmfs01] ISOs\CentOS-6.5-x86_64-
LiveCD.iso' -Confirm:$false
>>
```

The output to the preceding command is as follows:

IsoPath	HostDevice	RemoteDevice
[Cluster01 Vmfs01		

In the following example, we will remove the VM4 virtual machine's CD drive's media backing, disconnect it, and disable the StartConnected flag:

```
PowerCLI C:\> Get-VM -Name VM4 | Get-CDDrive |
>> Set-CDDrive -NoMedia:$true -StartConnected:$false -Confirm:$false
>>
```

The output to the preceding command is as follows:

IsoPath	HostDevice	RemoteDevice

Removing devices from a virtual machine

To remove devices from a virtual machine, you can use these Remove-* cmdlets: Remove-HardDisk, Remove-NetworkAdapter, Remove-FloppyDrive, and Remove-CDDrive. However, there is no Remove-ScsiController cmdlet. When you remove the last hard disk from a SCSI controller, the SCSI controller is also removed.

Removing a hard disk

You can use the Remove-HardDisk cmdlet to remove a hard disk from a virtual machine. The Remove-HardDisk cmdlet has the following syntax:

```
Remove-HardDisk [-HardDisk] <HardDisk[]> [-DeletePermanently]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -HardDisk parameter is required. To remove the hard disk not only from the inventory but also from the datastore, you have to use the -DeletePermanently parameter. You can remove a hard disk while the virtual machine is powered on.

The following example removes Hard Disk 3 from the VM2 virtual machine and also deletes the hard disk from the datastore:

```
PowerCLI C:\> Get-VM -Name VM2 | Get-HardDisk |
>> Where-Object {$_.Name -eq "Hard Disk 3"} |
>> Remove-HardDisk -DeletePermanently -Confirm:$false
```

Removing a network adapter

To remove a network adapter from a virtual machine, you can use the Remove-NetworkAdapter cmdlet. This cmdlet has the following syntax:

```
Remove-NetworkAdapter [-NetworkAdapter] <NetworkAdapter[]> [-WhatIf]
[-Confirm] [<CommonParameters>]
```

The -NetworkAdapter parameter is required. You can only remove a network adapter while the virtual machine is powered off.

Let's remove Network Adapter 2 from the VM4 virtual machine using the following command:

```
PowerCLI C:\> Get-VM -Name VM4 | Get-NetworkAdapter |
>> Where-Object {$_.Name -eq "Network adapter 2"} |
>> Remove-NetworkAdapter -Confirm:$false
```

Removing a floppy drive

You can use the Remove-FloppyDrive cmdlet to remove a floppy drive from a virtual machine. The Remove-FloppyDrive cmdlet's syntax is similar to other Remove-* cmdlet syntaxes:

```
Remove-FloppyDrive [-Floppy] <FloppyDrive[] > [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -Floppy parameter is required. You can only remove a floppy drive while the virtual machine is powered off.

The following example removes all of the floppy drives from the VM4 virtual machine:

```
PowerCLI C:\> Get-VM -Name VM4 | Get-FloppyDrive |
>> Remove-FloppyDrive -Confirm:$false
>>
```

Removing a CD drive

Removing a CD drive can be done with the Remove-CDDrive cmdlet, which has the following syntax:

```
Remove-CDDrive [-CD] <CDDrive[]> [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -CD parameter is required. You can only remove a CD drive while the virtual machine is powered off.

The following command will remove 'CD/DVD drive 2' from the VM4 virtual machine:

```
PowerCLI C:\> Get-VM -Name VM4 | Get-CDDrive |
>> Where-Object {$_.Name -eq 'CD/DVD drive 2'} |
>> Remove-CDDrive -Confirm:$false
>>
```

Converting a virtual machine into a template

You have already learned how to deploy a virtual machine from a template. You now need to know how to create a template. You begin with creating a virtual machine and installing the operating system and application software and patches that you need for all of the virtual machines that you want to deploy. After you are finished creating your new virtual machine, you have to convert it into a template using the Set-VM cmdlet, which you have already seen in the previous section. Let's convert the VM1 virtual machine into a template:

```
PowerCLI C:\> Get-VM -Name VM1 | Set-VM -ToTemplate -Confirm:$false
```

The output to the preceding command is as follows:

Name ---VM1

To confirm that VM1 is now a template, you can use the Get-Template cmdlet to view all of the templates:

```
PowerCLI C:\> Get-Template
```

The output to the preceding command is as follows:

```
Name
----
VM1
The Get-Template cmdlet has the following syntax:
Get-Template [-Location <VIContainer[]>] [-Datastore
<StorageResource[]>] [[-Name] <String[]>] [-NoRecursion]
[-Server <VIServer[]>] [<CommonParameters>]
Get-Template -Id <String[]> [-Server <VIServer[]>]
[<CommonParameters>]
```

The parameters of the Get-Template cmdlet are filters to retrieve only templates from a certain location or datastore or with a specific ID. The first parameter set is the default one. The second parameter set is for retrieving templates by ID.

Converting a template into a virtual machine

Now that you have this template, you have to keep it updated with the latest software versions and patches. However, you cannot start a template to modify the installed operating system. You have to convert it into a virtual machine first, then start the virtual machine, install the latest software versions and patches, and finally shut the virtual machine down and convert it back into a template.

To convert a template to a virtual machine, you have to use the Set-Template cmdlet's -ToVM parameter. The Set-Template cmdlet has the following syntax:

```
Set-Template [-Template] <Template[]> [-Name <String>] [-ToVM]
[-Server <VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

Here is an example to convert a template into a virtual machine:

```
PowerCLI C:\> Set-Template -Template VM1 -ToVM
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM1	PoweredOff	1	0.250

Modifying the name of a template

You can also use the Set-Template cmdlet to give your template a more meaningful name. You have to use the -Name parameter to specify the new name:

```
PowerCLI C:\> Set-Template -Template VM1 -Name Windows2012Template
```

The output to the preceding command is as follows:

```
Name
----
Windows2012Template
```

Removing a template

To remove a template, you can use the Remove-Template cmdlet. This cmdlet has the following syntax:

```
Remove-Template [-Template] <Template[]> [-DeletePermanently]
[-RunAsync] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

To remove the template Windows2012Template from the vCenter Server inventory and also from the datastore, you can use the following command:

```
PowerCLI C:\> Remove-Template -Template Windows2012Template `
>> -DeletePermanently -Confirm:$false
>>
```

Moving a virtual machine to another folder, host, cluster, resource pool, or datastore

To move a virtual machine to another folder, host, cluster, resource pool, or datastore, you can use the Move-VM cmdlet. This cmdlet has the following syntax:

```
Move-VM [-AdvancedOption <AdvancedOption[]>] [[-Destination]
<VIContainer>] [-Datastore <StorageResource>] [-DiskStorageFormat
<VirtualDiskStorageFormat>] [-RunAsync] [-VM] <VirtualMachine[]>
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

In the first example, we will move the VM2 virtual machine to host 192.168.0.133:

```
PowerCLI C:\> Get-VM -Name VM2 | Move-VM -Destination 192.168.0.133
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM2	PoweredOn	1	1.000

In the second example, we will move virtual machine DNS1 to folder Infrastructure:

```
PowerCLI C:\> $Folder = Get-Folder -Name Infrastructure
PowerCLI C:\> Get-VM -Name DNS1 | Move-VM -Destination $Folder
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
DNS1	PoweredOff	2	8.000

In the final example, we will move virtual machine DNS1 to datastore Datastore2:

```
PowerCLI C:\> Move-VM -VM DNS1 -Datastore Datastore2
```

The output to the preceding command is as follows:

Name	PowerState	Num CPU	s MemoryGB
DNS1	PoweredOff	2	8.000


Updating the VMware Tools

When there is a new version of the vSphere ESXi software, it normally comes with a new version of the VMware Tools. There are two methods of updating the VMware Tools in a guest operating system:

- Use the Update-Tools cmdlet
- Enable the Check and upgrade VMware Tools before each power on checkbox and reboot the virtual machine

In this section, we will discuss both options.

In the following screenshot of the vSphere Web Client, you will see the VM Options tab in the Edit Settings window for the VM2 virtual machine. The Check and upgrade VMware Tools before each power on checkbox is enabled.



Using the Update-Tools cmdlet

The Update-Tools cmdlet will update the VMware Tools in a guest operating system. The syntax of this cmdlet is:

```
Update-Tools [-NoReboot] [-RunAsync] [[-Guest] <VMGuest[]>]
[<CommonParameters>]
Update-Tools [-NoReboot] [-RunAsync] [[-VM] <VirtualMachine[]>]
[[-Server] <VIServer[]>] [<CommonParameters>]
```

You can use the first parameter set to specify virtual machines by the VMGuest object. The second parameter set is for specifying virtual machines by the VirtualMachine object or name.

Before you can use the Update-Tools cmdlet, you need to have an older version of the VMware Tools installed.

In the following example, we will use the Update-Tools cmdlet to update the VMware Tools in the VM2 virtual machine:

PowerCLI C:\> Get-VM -Name VM2 | Update-Tools

Linux virtual machines require a reboot each time the VMware Tools are upgraded. This is also true for Windows systems with the VMware Tools Version 8 or lower. The Update-Tools cmdlet will perform this reboot unless you specify the -NoReboot parameter. However, the -NoReboot parameter is supported only for Windows operating systems. Even if you use the -NoReboot parameter, the virtual machine might still reboot after updating the VMware Tools. This will depend on the currently installed VMware Tools version, the VMware Tools version to which you want to upgrade, and the vCenter Server/ESXi versions.



VMware Knowledge Base article, *Determining if a VMware Tools upgrade requires a reboot of a Windows guest operating system (2015163)*, gives you more information about when a VMware Tools upgrade requires a reboot. You can find this KB article at http://kb.vmware.com/kb/2015163.

Enabling the "Check and upgrade VMware Tools before each power on" checkbox

In the next example, we will enable the **Check and upgrade VMware Tools before each power on** checkbox for all of the virtual machines in the inventory. Because there is no PowerCLI cmdlet to do this, we have to go back to the VMware vSphere API.

In the first line, we will create a VirtualMachineConfigSpec object. In the second line, we will create a ToolsConfigInfo object and add this object to the tools property of the VirtualMachineConfigSpec object. In the third line, we will set the ToolsUpgradePolicy object to "UpgradeAtPowerCycle". In the last line, we loop through all of our virtual machines and run the ReconfigVM_Task method with the just-created VirtualMachineConfigSpec object as a parameter to reconfigure the virtual machine and enable the Check and upgrade VMware Tools before each power on checkbox.

```
$Spec = New-Object VMware.Vim.VirtualMachineConfigSpec
$Spec.Tools = New-Object VMware.Vim.ToolsConfigInfo
$Spec.Tools.ToolsUpgradePolicy = "UpgradeAtPowerCycle"
Get-VM | ForEach-Object {$ .ExtensionData.ReconfigVM Task($Spec)}
```

To really upgrade the VMware Tools after enabling the **Check and upgrade VMware Tools before each power on** checkbox, you need to restart all of the virtual machines with the following command:

PowerCLI C:\> Get-VM | Restart-VMGuest



Don't try the preceding command in your production environment. It will restart all of your virtual machines!

Upgrading virtual machine compatibility

To upgrade virtual machine compatibility, you can use the Set-VM cmdlet that you have seen before. You have to use the -Version parameter and specify the new compatibility version as a parameter value. At the time of writing this book, the only valid versions are v4, v7, v8, v9, and v10. Virtual machines compatible with Version 10 can no longer be edited with the vSphere C# Client. You will have to use the vSphere Web Client or PowerCLI to edit the configuration for these virtual machines.

The following example will upgrade the VM7 virtual machine to compatibility Version 10:

```
PowerCLI C:\> Get-VM -Name VM7 | `
>> Set-VM -Version V10 -Confirm:$false
>>
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	${\tt MemoryGB}$
VM7	PoweredOn	1	0.250

The virtual machine has to be powered off, or you will get the following error message:

The attempted operation cannot be performed in the current state (Powered on).


It is not possible to downgrade to an earlier compatibility version. If you specify a version lower or equal to the version the virtual machine already has, you will get the following error message:

Virtual machine compatibility is already up-to-date.

The version numbers correspond to the following virtual machine compatibilities:


Virtual machine version	Virtual machines compatible with
v4	ESX/ESXi 3.5 and later
v7	ESX/ESXi 4.0 and later
v8	ESXi 5.0 and later
v9	ESXi 5.1 and later
v10	ESXi 5.5 and later

In the following screenshot of the vSphere Web Client, you will see the VM Hardware window containing the status of a virtual machine with Compatibility showing ESXi 5.5 and later (VM version 10):



Using snapshots

Snapshots are a point-in-time to which you can revert a virtual machine when changes made to the virtual machine after creating the snapshot should be discarded. For example, snapshots are useful when you are installing or upgrading software in a virtual machine. If the installation or upgrade goes wrong, you can easily restore to the time the last snapshot was taken, in order to get back to the state before you started the installation or upgrade. If you have verified that the installation or upgrade was successful, you should remove the snapshot, because snapshots use valuable space on your datastores and decrease the performance of your virtual machine.



In this section, we will discuss the PowerCLI commands to work with snapshots.

Creating snapshots

To create a new snapshot of a virtual machine, you have to use the New-Snapshot cmdlet. This cmdlet has the following syntax:

```
New-Snapshot [-VM] <VirtualMachine[]> [-Name] <String> [-Description <String>] [-Memory] [-Quiesce] [-Server <VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VM, and -Name parameters are required.


In the following example, we will create a snapshot of the VM2 virtual machine before upgrading it. If something goes wrong during the upgrade, we can revert to the snapshot and will have our original virtual machine back.

```
PowerCLI C:\> New-Snapshot -VM VM2 -Name "Before Upgrade" `
>> -Description "Made before upgrading the virtual machine"
>>
```

The output to the preceding command is as follows:

Name	Description	PowerState
Before Upgrade	Made before upgrading the v	PoweredOff

In the following screenshot of the vSphere Web Client, you will see the **Manage VM Snapshots for VM2** window showing the snapshot created in the previous PowerCLI command:



If the virtual machine is powered on, you can use the <code>-Memory</code> parameter to preserve the virtual machine's memory state with the snapshot. In the powered on state, you can also use the <code>-Quiesce</code> parameter to quiesce the filesystem of the virtual machine using the VMware Tools. Quiescing ensures that a snapshot represents a consistent state of the guest filesystems.

In the following example, we will create a new snapshot of the VM2 virtual machine that includes the virtual machine's memory, and we will quiesce the virtual machine's filesystem before creating the snapshot:

```
PowerCLI C:\> New-Snapshot -VM VM2 -Name "Before patching" `
>> -Memory -Quiesce
>>
```

The output to the preceding command is as follows:

Name	Description	PowerState
Before patching		PoweredOn

The value of the snapshot's PowerState property, PoweredOn, indicates that the virtual machine's memory is included in the snapshot.

Retrieving snapshots

To get a list of all of the snapshots that a virtual machine has or to retrieve a specific snapshot, you can use the Get-Snapshot cmdlet. The syntax of this cmdlet is as follows:

```
Get-Snapshot [[-Name] <String[]>] [-Id <String[]>] [-VM]
<VirtualMachine[]> [-Server <VIServer[]>] [<CommonParameters>]
```

The -VM parameter is required.

Let's get a list of all of the snapshots of the VM2 virtual machine using the following command:

```
PowerCLI C:\> Get-VM -Name VM2 | Get-Snapshot
```

The output to the preceding command is as follows:

Name	Description	PowerState
Before Upgrade	Made before upgrading the $v\dots$	PoweredOff
Before patching		PoweredOn

To retrieve the snapshot named Before Upgrade, you can use the following command:

```
PowerCLI C:\> Get-VM -Name VM2 | Get-Snapshot -Name 'Before Upgrade'
```

The output to the preceding command is as follows:

Name	Description	PowerState
Before Upgrade	Made before upgrading the v	PoweredOff

Snapshots can grow to the size of the original disks and can fill a datastore. The following example will show you the snapshot names, virtual machine names, snapshot sizes in GB, and creation dates for all of the snapshots that are larger than 10 GB:

```
PowerCLI C:\> Get-VM | Get-Snapshot |
>> Where-Object {$_.SizeGB -ge 10GB} |
>> Select-Object -Property Name,VM,SizeGB,Created
>>
```

In the next example, we will retrieve a list of all of the snapshots that are older than 3 days:

```
PowerCLI C:\> Get-VM | Get-Snapshot |
>> Where-Object {$_.Created -lt (Get-Date).AddDays(-3)} |
>> Select-Object -Property VM, Name, Description, Created
>>
```

Reverting to a snapshot

To revert a virtual machine to an existing snapshot, you can use the Set-VM cmdlet that we have seen earlier in the *Modifying the settings of a virtual machine* section. In the following example, we will revert the VM2 virtual machine to the snapshot named Before Upgrade:

```
PowerCLI C:\> $vm = Get-VM -Name VM2

PowerCLI C:\> $snapshot = Get-Snapshot -VM $vm -Name 'Before Upgrade'

PowerCLI C:\> Set-VM -VM $vm -Snapshot $snapshot -Confirm:$false
```

The output to the preceding command is as follows:

Name	PowerState	Num CPUs	MemoryGB
VM2	PoweredOff	1	1.000

Modifying snapshots

To modify the name or description of a snapshot, you can use the Set-Snapshot cmdlet. The Set-Snapshot cmdlet has the following syntax:

```
Set-Snapshot [-Snapshot] <Snapshot[]> [-Name <String>] [-Description
<String>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

In the next example, we will modify the name and description of the 'Before patching' snapshot of the VM2 virtual machine:

```
PowerCLI C:\> Get-VM -Name VM2 |
>> Get-Snapshot -Name 'Before patching' |
>> Set-Snapshot -Name 'Before Microsoft patches' `
>> -Description 'Before installing the Microsoft May patches'
>>
```

The output to the preceding command is as follows:

```
Name Description PowerState
----
Before Microsoft ... Before installing the Micro... PoweredOn
```

Removing snapshots

Snapshots can use a considerable amount of disk space. Therefore, it is good practice to remove snapshots on a regular basis. To remove snapshots, you can use the Remove-Snapshot cmdlet. This cmdlet has the following syntax:

```
Remove-Snapshot [-Snapshot] <Snapshot[]> [-RemoveChildren]
[-RunAsync] [-WhatIf] [-Confirm] [<CommonParameters>]
```

You can use the Remove-Snapshot cmdlet to remove a single snapshot or use the -RemoveChildren parameter to remove a snapshot and all its children.

In the following example, we will remove the snapshot named 'Before Upgrade' and its child snapshots for virtual machine VM2:

```
PowerCLI C:\> Get-VM -Name VM2 |
>> Get-Snapshot -Name 'Before Upgrade' |
>> Remove-Snapshot -RemoveChildren -Confirm:$false
```

Running commands on the guest OS

To run a command on the guest operating system of a virtual machine, you can use the Invoke-VMScript cmdlet. To use this cmdlet, the virtual machines must be powered on and must have the VMware Tools installed. You also need network connectivity to the ESXi server hosting the virtual machine on port 902. This cmdlet only supports the following guest operating systems:

- Windows XP 32-bit SP3
- Windows Server 2003 32-bit SP2
- Windows Server 2003 64-bit SP2
- Windows 7 64-bit
- Windows Server 2008 R2 64-bit
- Red Hat Enterprise 5 operating systems

The Invoke-VMScript cmdlet has the following syntax:

```
Invoke-VMScript [-ScriptText] <String> [-VM] <VirtualMachine[]>
[-HostCredential <PSCredential>] [-HostUser <String>] [-HostPassword
<SecureString>] [-GuestCredential <PSCredential>] [-GuestUser
<String>] [-GuestPassword <SecureString>] [-ToolsWaitSecs <Int32>]
[-ScriptType <ScriptType>] [-RunAsync] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -ScriptType parameter specifies the type of script. Valid values are PowerShell, Bat, and Bash. For Windows virtual machines, the default value is PowerShell, while for Linux virtual machines it is Bash.

The following example runs 'ipconfig /all' on the guest operating system of the VM2 virtual machine:

```
Primary Dns Suffix . . . . . : blackmilktea.com
  IP Routing Enabled. . . . . . : No
  WINS Proxy Enabled. . . . . . : No
  DNS Suffix Search List. . . . . : blackmilktea.com
Ethernet adapter Local Area Connection:
  Connection-specific DNS Suffix .:
  Description . . . . . . . . . . . wmxnet3 Ethernet Adapter
  DHCP Enabled. . . . . . . . . . . . . . . . . .
  Autoconfiguration Enabled . . . . : Yes
  IPv4 Address. . . . . . . . . . . . . . . . 192.168.0.202 (Preferred)
  Default Gateway . . . . . . . : 192.168.0.1
  DNS Servers . . . . . . . . . . . . . . . 192.168.0.2
                               192.168.0.3
  NetBIOS over Tcpip. . . . . . : Enabled
```

Configuring Fault Tolerance

VMware Fault Tolerance is a feature that allows you to run a copy of a virtual machine on another host in the same cluster. The primary virtual machine and the secondary virtual machine are synchronized and run in virtual lockstep with each other. When the host of the primary virtual machine fails, the secondary virtual machine takes its place with the minimum possible interruption of service. Detailed instructions for configuring Fault Tolerance in your vSphere environment can be found on the *VMware vSphere Documentation* page at http://www.vmware.com/support/pubs/vsphere-esxi-vcenter-server-pubs.html under ESXi and vCenter Server Product Documentation | vSphere Availability Guide. You can download this guide in .html, .pdf, .epub, and .mobi formats. In this section, we will discuss how to turn Fault Tolerance on and off in a virtual machine.

Turning Fault Tolerance on

There are no PowerCLI cmdlets to turn Fault Tolerance on or off in a virtual machine, so we have to use the VMware vSphere API. In the next example, we will use the CreateSecondaryVM_Task method to create a secondary virtual machine for the VM2 virtual machine. The CreateSecondaryVM_Task method needs one parameter, which is the Managed Object Reference of the host where the secondary virtual machine is to be created and powered on. In this case, we don't specify a host but use \$null as a placeholder. The secondary virtual machine will be created on a compatible host selected by the system.

```
PowerCLI C:\> $vm = Get-VM -Name VM2
PowerCLI C:\> $vm.ExtensionData.CreateSecondaryVM Task($null)
```

The output to the preceding command is as follows:

Туре	Value
Task	task-26

Turning Fault Tolerance off

To turn Fault Tolerance off for a virtual machine, we will use the VMware vSphere API TurnOffFaultToleranceForVM_Task method. In the following example, we will turn off Fault Tolerance for the VM2 virtual machine. The TurnOffFaultToleranceForVM Task method does not have any parameters.

```
PowerCLI C:\> $vm = Get-VM -Name VM2
PowerCLI C:\> $vm.ExtensionData.TurnOffFaultToleranceForVM Task()
```

The output to the preceding command is as follows:

Type	Value
Task	task-373

Opening the console of a virtual machine

PowerCLI 5.5 introduced the Open-VMConsoleWindow cmdlet that you can use to open the console of a virtual machine in a web browser. You can open the console in a new window or fullscreen. This cmdlet uses the **VMware Remote Console** (**VMRC**) browser plugin.

Supported browsers are as follows:

- Microsoft Internet Explorer Version 7 or later
- Mozilla Firefox Version 9 or later
- Google Chrome Version 16 or later

The syntax of the Open-VMConsoleWindow cmdlet is as follows:


```
Open-VMConsoleWindow [-VM] <RemoteConsoleVM[]> [-FullScreen]
[-UrlOnly] [-Server <VIConnection[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -VM parameter is required. The -Fullscreen parameter will open the console in fullscreen mode. The -Urlonly parameter does not open the console but returns the URL needed to open the console. This URL will stay valid for 30 seconds, after which the screen authentication ticket contained in the URL expires.

The command in the following example will open the console of the VM2 virtual machine:

```
PowerCLI C:\> Open-VMConsoleWindow -VM VM2
```

The **VM2** virtual machine has no operating system installed. That is what you will see in the following screenshot as the virtual machine tries to boot from a PXE boot server:



Removing a virtual machine

In the life cycle of a virtual machine, there comes a time when you may want to remove it. This may be because the application running on the virtual machine is not in use anymore or because the operating system running on the virtual machine is obsolete and you have moved the application to a new server. To remove a virtual machine, you can use the Remove-VM cmdlet, which has the following syntax:

Remove-VM [-DeletePermanently] [-RunAsync] [-VM] <VirtualMachine[]>
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]

If you use the <code>-DeletePermanently</code> parameter, the virtual machine will be removed from your vSphere inventory and from the datastores. If you omit the <code>-DeletePermanently</code> parameter, the virtual machine will only be removed from the vSphere inventory. Because the virtual machine's files remain on the datastores, you can register the virtual machine again.

In the following example, we will use the Remove-VM cmdlet to remove the VM6 virtual machine from the inventory and also remove its files from the datastore. A virtual machine must be powered off before you attempt to remove it.

PowerCLI C:\> Remove-VM -VM VM6 -DeletePermanently -Confirm:\$false

Summary

In this chapter, you learned how to create a virtual machine, use OS customization specifications, start and stop a virtual machine, modify the settings of a virtual machine, and convert a virtual machine into a template. We looked at moving a virtual machine to another folder, host, cluster, resource pool, or datastore. You read how to update VMware Tools, and upgrade the virtual hardware. You also learned how to use snapshots, run commands in the guest OS, configure Fault Tolerance, and remove a virtual machine.

In the next chapter, we will look at managing virtual networks with PowerCLI.

Managing Virtual Networks with PowerCLI

ESXi servers need network connections for management, vMotion, fault tolerance logging traffic, iSCSI, and NAS/NFS access. Virtual machines need network connections for communicating with other virtual or physical computers. VMware vSphere provides two types of virtual switches that you can use to configure the networks: vSphere Standard Switches and vSphere Distributed Switches. The vSphere Standard Switches are specific for an ESXi server host. The vSphere Distributed Switches are created and centrally managed on a vCenter Server and are copied to every host that uses this vSphere Distributed Switch.


The topics that will be covered in the chapter are as follows:

- Using vSphere Standard Switches
- Using host network adapters
- Using standard port groups
- Using vSphere Distributed Switches
- Using distributed virtual port groups
- Configuring host networking
- Configuring the network of a virtual machine

Using vSphere Standard Switches

The vSphere Standard Switches are created on a specific host. If you are using vSphere clusters, then normally you will create the same vSphere Standard Switches on all of your hosts in a cluster, and give a switch the same configuration on all of the hosts. You can use PowerCLI to create and configure the switches on all of your hosts.


The next diagram shows two hosts, and each host has a vSphere Standard Switch:



Creating vSphere Standard Switches

After deploying a new ESXi server, one vSphere Standard Switch is already created. This switch, called vSwitch0, has two port groups: **Management Network** and **VM Network**. Also, it is connected to a physical adapter vmnic0. You can use this switch to connect the host to a vCenter Server or to connect directly to this host using the vSphere Client.

The next screenshot of vSphere Web Client shows vSphere Standard Switch vSwitch0 just after deploying the host 192.168.0.133.



To create a new standard switch, you can use the New-VirtualSwitch cmdlet. This cmdlet has the following syntax:

```
New-VirtualSwitch [-VMHost] <VMHost> [-Name] <String> [[-NumPorts]
  <Int32>] [[-Nic] <PhysicalNic[]>] [[-Mtu] <Int32>] [-Server
  <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

Following is the list of parameters that are required while using the New-VirtualSwitch cmdlet:

- The -VMHost parameter is necessary, and it accepts input via the pipeline.
- The -Name parameter is also necessary.
- The -Numports parameter specifies the number of virtual switch ports. The port number displayed in the vSphere Client might differ from the value that you specified for the -NumPorts parameter.



In ESXi 5.5 or later, standard virtual switches are always elastic, so the -NumPorts parameter is no longer applicable and its value is ignored.

The next PowerCLI command creates a new vSphere Standard Switch named vSwitch1 on host 192.168.0.133 and connects the switch to the network interface vmnic2. The **maximum transmission unit (MTU)** size is set to the default value of 1,500:

The following screenshot shows the Standard Switch, vSwitch1, that has been created with the preceding command:



Configuring vSphere Standard Switches

You can use the Get-VirtualSwitch cmdlet to get a list of your virtual switches. As of writing this book, the cmdlet will return vSphere Standard and Distributed switches unless you specify the -Standard parameter to return only vSphere Standard Switches. VMware has the intention to modify this cmdlet to return only vSphere Standard Switches. To get a list of your vSphere Distributed Switches, it is better to use the Get-VDSwitch cmdlet. This will be discussed later in the chapter.

The Get-VirtualSwitch cmdlet has the following syntax:

```
Get-VirtualSwitch [[-VMHost] <VMHost[]>] [[-VM] <VirtualMachine[]>]
[-Datacenter <Datacenter[]>] [-Name <String[]>] [-Standard]
[-Distributed] [-Server <VIServer[]>] [<CommonParameters>]
```

```
Get-VirtualSwitch -Id <String[]> [-Server <VIServer[]>]
[<CommonParameters>]
```

```
Get-VirtualSwitch -RelatedObject <VirtualSwitchRelatedObjectBase[] >
[ <CommonParameters > ]
```

If you use the Get-VirtualSwitch cmdlet without parameters, then you will get a list of all of your switches from your hosts. To retrieve only the switches for a specific host, you have to specify the -VMHost parameter as shown in the following command line:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.133
PowerCLI C:\> Get-VirtualSwitch -VMHost $VMHost
```

The output of the preceding command is as follows:

Name	NumPorts	Mtu	Notes
vSwitch0	1536	1500	
vSwitch1	1536	1500	

If you only want to retrieve a specific virtual switch, you can specify the name of the switch as follows:

PowerCLI C:\> Get-VirtualSwitch -VMHost \$VMHost -Name vSwitch1

The output of the preceding command is as follows:

Name	NumPorts	Mtu	Notes
vSwitch1	1536	1500	

To modify the settings of a vSphere Standard Switch, you can use the Set-VirtualSwitch cmdlet. You can use this cmdlet to change the number of ports, the MTU size, and the network interface cards for the virtual switch. The syntax of the Set-VirtualSwitch cmdlet is as follows:

```
Set-VirtualSwitch [-VirtualSwitch] <VirtualSwitch[]> [[-NumPorts]
  <Int32>] [[-Nic] <String[]>] [[-Mtu] <Int32>] [-Server <VIServer[]>]
  [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VirtualSwitch parameter is required. After changing the number of switch ports using the -NumPorts parameter, the ESXi host must be restarted for the changes to take effect. In ESXi 5.5 or later, standard virtual switches are always elastic, so the -NumPorts parameter is no longer applicable and its value is ignored.

The network interface cards specified as a value of the -Nic parameter will replace the old NICs. For example, you can use the following command to modify the MTU size of a switch to 9,000 for Jumbo Frames, and the network interface cards to vmnic2 and vmnic3:

```
PowerCLI C:\> Get-VirtualSwitch -VMHost $VMHost -Name vSwitch1 |
>> Set-VirtualSwitch -Mtu 9000 -Nic vmnic2,vmnic3 -Confirm:$false
>>
```

WARNING: The 'Nic' parameter of 'Set-VirtualSwitch' cmdlet is deprecated. Use the 'Add-VirtualSwitchPhysicalNetworkAdapter' cmdlet instead.

Name	NumPorts	Mtu	Notes
vSwitch1	1536	9000	

After executing the previous command, both vmnic2 and vmnic3 will be active adapters.

As you can see in the warning message in the output of the preceding command, the -Nic parameter of the Set-VirtualSwitch cmdlet is deprecated. In the next section, we will look at the Add-VirtualSwitchPhysicalNetworkAdapter cmdlet that should be used instead.



Ethernet uses a frame size of 1,500 bytes by default. **Jumbo frames** are Ethernet frames that are larger than 1,500 bytes and are often 9,000 bytes per frame. In a reliable network, Jumbo frames have less overhead than the standard Ethernet frames and a better throughput. In an unreliable network, however, the chance of losing a frame is bigger for Jumbo frames than for the standard frame size. The loss of a frame requires the retransmission of a frame. In an unreliable network, it is better to use the standard frame sizes. If you use Jumbo frames, then all of the switches and routers between two communicating computers must support the Jumbo frame size. If there are switches or routers along the transmission path that have varying frame sizes, then you can end up with fragmentation problems. If a switch or router along the path does not support jumbo frames and it receives one, it will drop the frame.

Adding network adapters to a switch

To add a physical network adapter to a virtual switch, you should use the Add-Virt ualSwitchPhysicalNetworkAdapter cmdlet. This cmdlet has the following syntax:

The -VMHostPhysicalNic and -VirtualSwitch parameters are required.

The next example adds network adapter vmnic3 to the virtual switch vSwitch1 on the host 192.168.0.133:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.133

PowerCLI C:\> $NetworkAdapter = Get-VMHostNetworkAdapter
-VMHost $VMHost -Physical -Name vmnic3

PowerCLI C:\> Get-VirtualSwitch -Name vSwitch1 -VMHost $VMHost |
>> Add-VirtualSwitchPhysicalNetworkAdapter -VMHostPhysicalNic
$NetworkAdapter -Confirm:$false
```

Removing vSphere Standard Switches

To remove a vSphere Standard Switch, you can use the Remove-VirtualSwitch cmdlet. The syntax of this cmdlet is as follows:

```
Remove-VirtualSwitch [-VirtualSwitch] <VirtualSwitch[]>
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
In the next example, we will remove vSwitch1 from the host 192.168.0.133:
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.133
PowerCLI C:\> Get-VirtualSwitch -VMHost $VMHost -Name vSwitch1 |
>> Remove-VirtualSwitch -Confirm:$False
>>
```

vmk1 00:50:56:65:bd:a1 False

Using host network adapters

A vSphere Standard or Distributed Switch can have virtual and physical network adapters. Physical network adapters are used to connect virtual switches to physical switches and have a name starting with vmnic. Virtual network adapters or VMKernel network adapters can be used to set various properties such as management traffic, vMotion, fault tolerance logging, IP address, and subnet mask. Virtual network adapters have a name starting with vmk. You can see virtual and physical network adapters in the screenshot given in the *Creating vSphere Standard Switches* section.

Creating host network adapters

To create a new virtual network adapter or VMkernel port, you can use the New-VMHostNetworkAdapter cmdlet. The cmdlet creates a port group if the -PortGroup parameter is used. The syntax of this cmdlet is as follows:

```
New-VMHostNetworkAdapter [[-VMHost] <VMHost>]
[[-PortGroup] <String>] [-PortId <String>]
[-VirtualSwitch] <VirtualSwitchBase> [[-IP] <String>]
[[-SubnetMask] <String>] [[-Mac] <String>] [-Mtu <Int32>]
[-ConsoleNic] [-VMotionEnabled [<Boolean>]]
[-FaultToleranceLoggingEnabled [<Boolean>]] [-IPv6ThroughDhcp]
[-AutomaticIPv6] [-IPv6 <String[]>] [-ManagementTrafficEnabled
[<Boolean>]] [-VsanTrafficEnabled [<Boolean>]] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

In the next example, we will create a new VMkernel port called vmk1 on the virtual switch vSwitch1 that is present on the host 192.168.0.133. A port group named VMKernelPortGroup1 is also created:

192.168.0.150 255.255.255.0 vmk1



To fit the preceding output to the width of this page, I had to truncate DeviceName into Device. Also, there are other examples in this chapter in which the output is truncated.

Retrieving host network adapters

The Get-VMHostNetworkAdapter cmdlet can be used to retrieve the physical and virtual host network adapters. This cmdlet will retrieve the network adapters for vSphere Standard Switches and also for vSphere Distributed Switches. The syntax of the Get-VMHostNetworkAdapter cmdlet is as follows:

```
Get-VMHostNetworkAdapter [[-VMHost] <VMHost[]>] [-Physical]
[-VMKernel] [-Console] [[-Name] <String[]>] [-Id <String[]>]
[-Server <VIServer[]>] [<CommonParameters>]

Get-VMHostNetworkAdapter [[-VirtualSwitch] <VirtualSwitchBase[]>]
[-PortGroup <VirtualPortGroupBase[]>] [-Physical] [-VMKernel]
[-Console] [[-Name] <String[]>] [-Id <String[]>]
[-Server <VIServer[]>] [<CommonParameters>]
```

The first parameter set is for the vSphere Standard Switches and the second parameter set for the vSphere Distributed Switches.

In the next example, all of the host network adapters of the host 192.168.0.133 are retrieved:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.133
PowerCLI C:\> $VMHost | Get-VMHostNetworkAdapter
```

```
Name
                        DhcpEnabled IP
                                                  SubnetMask
      Mac
                         _________
                                                   -----
vmnic0 00:0c:29:da:a2:1b False
vmnic1 00:0c:29:da:a2:25 False
vmnic2 00:0c:29:da:a2:2f False
vmnic3 00:0c:29:da:a2:39 False
vmnic4 00:0c:29:da:a2:43 False
vmnic5 00:0c:29:da:a2:4d False
vmnic6 00:0c:29:da:a2:57 False
vmnic7 00:0c:29:da:a2:61 False
                                    192.168.0.133 255.255.255.0
vmk0
      00:0c:29:da:a2:1b True
vmk1
      00:50:56:65:bd:a1 False
                                    192.168.0.150 255.255.255.0
```

In the following example, we will retrieve all of the network adapters for the vSphere distributed switch VDSwitch1:

Configuring host network adapters

To modify the settings of a host network adapter, you can use the Set-VMHostNetworkAdapter cmdlet. The syntax of this cmdlet is as follows:

```
Set-VMHostNetworkAdapter -PhysicalNic <PhysicalNic[]>
[-Duplex <String>] [-BitRatePerSecMb <Int32>] [-AutoNegotiate]
[-WhatIf] [-Confirm] [<CommonParameters>]
Set-VMHostNetworkAdapter -VirtualNic <HostVirtualNic[]> [-Dhcp]
[-IP <String>] [-SubnetMask <String>] [-Mac <String>] [-Mtu <Int32>]
[-VMotionEnabled [<Boolean>]] [-FaultToleranceLoggingEnabled
[<Boolean>]] [-ManagementTrafficEnabled [<Boolean>]]
[-VsanTrafficEnabled [<Boolean>]] [-IPv6ThroughDhcp [<Boolean>]]
[-AutomaticIPv6 [<Boolean>]] [-IPv6 <String[]>] [-IPv6Enabled
[<Boolean>]] [-WhatIf] [-Confirm] [<CommonParameters>]
Set-VMHostNetworkAdapter -VirtualNic <HostVirtualNic[]> -PortGroup
<DistributedPortGroup> [-WhatIf] [-Confirm] [<CommonParameters>]
```

The Set-VMHostNetworkAdapter cmdlet has three parameter sets. The first parameter set is for setting the network speed on the physical network adapters to half or full duplex or auto negotiate. The second parameter set is for setting the various properties of a virtual network adapter. The third parameter set is for migrating a host network adapter from a Standard Port Group to a Distributed Port Group.

Configuring network speed and the duplex setting

In the first example of the Set-VMHostNetworkAdapter cmdlet, we will set the speed of the physical network adapter vmnic2 of the host 192.168.0.133 to 1000 MB and full-duplex:

```
PowerCLI C:\> Get-VMHostNetworkAdapter -VMHost 192.168.0.133 -Name vmnic2 |
>> Set-VMHostNetworkAdapter -BitRatePerSecMb 1000 -Duplex full
-Confirm:$false
```

>>

Name	Mac	DhcpEnabled	ΙP	${\tt SubnetMask}$	DeviceName
vmnic2	00:0c:29:da:a2:2f	False			vmnic2

Configuring the management network

To enable a VMkernel port on an ESXi server for management traffic, you have to use the Set-VMHostNetworkAdapter -ManagementTrafficEnabled parameter. Using \$true as the value for this parameter will enable management traffic and \$false will disable it. In the following example, we will enable management traffic for the VMkernel port vmk1 of the host 192.168.0.133:

```
PowerCLI C:\> Get-VMHostNetworkAdapter -VMHost 192.168.0.133 -Name vmk1 |
>> Set-VMHostNetworkAdapter -ManagementTrafficEnabled:$true
-Confirm:$false
>>
```

Name	Mac	DhcpEnabled	IP	SubnetMask	Device
vmk1	00:50:56:65:bd:a1	False	192.168.0.150	255.255.255.0	vmk1

Configuring vMotion

In the following example, we will enable vMotion on the VMkernel network adapter vmk2 for the host 192.168.0.133:

```
PowerCLI C:\> Get-VMHostNetworkAdapter -VMHost 192.168.0.133 -Name
  vmk1 |
>> Set-VMHostNetworkAdapter -VMotionEnabled:$true -Confirm:$false
>>
```

```
        Name
        Mac
        DhcpEnabled
        IP
        SubnetMask
        Device

        ----
        ----
        -----
        -----
        ------

        vmk1
        00:50:56:65:bd:a1
        False
        192.168.0.150
        255.255.255.0
        vmk1
```

To disable vMotion, you have to modify \$true in the preceding example to \$false.

Removing host network adapters

To remove a host network adapter, you can use the Remove-VMHostNetworkAdapter cmdlet, which has the following syntax:

```
Remove-VMHostNetworkAdapter [-Nic] <HostVirtualNic[]> [-WhatIf]
[-Confirm] [<CommonParameters>]
```

In the following example, we will use the Remove-VMHostNetworkAdapter cmdlet to remove the host network adapter vmk1 from the host 192.168.0.133:

```
PowerCLI C:\> Get-VMHostNetworkAdapter -VMHost 192.168.0.133 -Name
  vmk1 |
>> Remove-VMHostNetworkAdapter -Confirm:$false
>>
```

Configuring NIC Teaming

NIC Teaming, also known as Load Balancing and Failover (LBFO), allows you to combine multiple network adapters into one virtual NIC for fault tolerance and better performance. You can configure NIC Teaming for an entire virtual switch or per virtual port group. The Get-NicTeamingPolicy and Set-NicTeamingPolicy cmdlets that we will discuss in this section have two parameter sets, one for NIC Teaming at the virtual switch level and one for NIC Teaming at the virtual port group level. The syntax of the Get-NicTeamingPolicy cmdlet is as follows:

```
Get-NicTeamingPolicy [-VirtualSwitch] <VirtualSwitch[]>
[-Server <VIServer[]>] [<CommonParameters>]
Get-NicTeamingPolicy [-VirtualPortGroup] <VirtualPortGroup[]>
[-Server <VIServer[]>] [<CommonParameters>]
In the following example, we will retrieve the NIC Teaming policy for virtual switch
vSwitch1 of host 192.168.0.133:
PowerCLI C:\> Get-VMHost -Name 192.168.0.133
>> Get-VirtualSwitch -Name vSwitch1 |
>> Get-NicTeamingPolicy
>>
VirtualSwitch ActiveNic StandbyNic UnusedNic FailbackEnabled NotifySw
vSwitch1
            {vmnic2}
                                         True
                                                       True
```

In the following example, we will retrieve the NIC Teaming policy for the virtual port group Management Network of the host 192.168.0.133:

To configure a NIC Teaming policy by using the Set-NicTeamingPolicy cmdlet, you have to use a Teaming policy, retrieved by the Get-NicTeamingPolicy cmdlet, as the input. You can pass this Teaming policy via the pipeline. The syntax of the Set-NicTeamingPolicy cmdlet is as follows:

```
Set-NicTeamingPolicy [-VirtualSwitchPolicy]
<NicTeamingVirtualSwitchPolicy[]> [-BeaconInterval <Int32>]
[-LoadBalancingPolicy <LoadBalancingPolicy>]
[-NetworkFailoverDetectionPolicy < NetworkFailoverDetectionPolicy>]
[-NotifySwitches [<Boolean>]] [-FailbackEnabled [<Boolean>]]
[-MakeNicActive <PhysicalNic[]>] [-MakeNicStandby <PhysicalNic[]>]
[-MakeNicUnused <PhysicalNic[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
Set-NicTeamingPolicy [-VirtualPortGroupPolicy]
<NicTeamingVirtualPortGroupPolicy[]> [-InheritLoadBalancingPolicy
[<Boolean>]] [-InheritNetworkFailoverDetectionPolicy [<Boolean>]]
[-InheritNotifySwitches [<Boolean>]] [-InheritFailback [<Boolean>]]
[-InheritFailoverOrder [<Boolean>]] [-LoadBalancingPolicy
<LoadBalancingPolicy>] [-NetworkFailoverDetectionPolicy
<NetworkFailoverDetectionPolicy>] [-NotifySwitches [<Boolean>]]
[-FailbackEnabled [<Boolean>]] [-MakeNicActive <PhysicalNic[]>]
[-MakeNicStandby <PhysicalNic[]>] [-MakeNicUnused <PhysicalNic[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```


In the next example, we will add the physical network adapter vmnic1 to the virtual switch vSwitch0 on the host 192.168.0.133. Then, we will configure NIC Teaming for the virtual port group Management Network and add vmnic1 to the active NICs:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name 192.168.0.133
PowerCLI C:\> $Switch = $VMHost | Get-VirtualSwitch -Name vSwitch0
```

PowerCLI C:\> \$Switch | Set-VirtualSwitch -Nic vmnic0,vmnic1
-Confirm:\$false

```
Name
                           NumPorts
                                          Notes
                                     Mtu
                           -----
vSwitch0
                           1536
                                     1500
PowerCLI C:\> $Policy = $VMHost |
>> Get-VirtualPortGroup -Name 'Management Network'
>> Get-NicTeamingPolicy
PowerCLI C:\> Set-NicTeamingPolicy -VirtualPortGroupPolicy $Policy
-MakeNicActive vmnic1
VirtualPortGroup ActiveNic
                                StandbyNic UnusedNic FailbackEnab
-----
                                -----
Management Network {vmnic1, vmnic0}
                                                   True
```

In the screenshot of the vSphere Web Client, you can see the teamed **Physical Adapters** vmnic0 and vmnic1 after executing the commands from the previous example:



Using standard port groups

Port groups are collections of ports that have the same properties, such as the same virtual switch, VLAN ID, Teaming policy, policies for filtering, tagging, and traffic shaping. Port groups are identified by a network label name. You should give all port groups in a datacenter, which are connected to the same network, the same network label. This will make virtual machine configurations portable across hosts. Using the vSphere PowerCLI cmdlets, you can only specify a network label name for the port group and a VLAN ID.



A **Virtual Local Area Network (Virtual LAN** or **VLAN**) is a virtual computer network independent of physical location. All the computers in a VLAN can receive broadcasts from the others and are usually in the same IP subnet.

Creating standard port groups

VLAN 10 Port Group key-vim.host.PortGr... 10

The New-VirtualPortGroup cmdlet will create a new port group for a vSphere Standard Switch. The syntax of this cmdlet is as follows:

```
New-VirtualPortGroup [-Name] <String> [-VirtualSwitch]
<VirtualSwitch> [-VLanId <Int32>] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

In the following example, we will create a new standard port group named VLAN 10 Port Group for the virtual switch vSwitch1 on all of the hosts in the cluster Cluster01. The standard port group connected to VLAN 10:

```
PowerCLI C:\> Get-Cluster -Name Cluster01 |
>> Get-VMHost |
>> Get-VirtualSwitch -Name vSwitch1 |
>> New-VirtualPortGroup -Name "VLAN 10 Port Group" -VLanId 10
>>

Name Key VLanId PortBinding NumPorts
--- VLAN 10 Port Group key-vim.host.PortGr... 10
```

Configuring standard port groups

To get a list of all of your standard port groups or to retrieve just one port group, you can use the Get-VirtualPortGroup cmdlet. The syntax of this cmdlet is as follows:

```
Get-VirtualPortGroup [[-VMHost] <VMHost[]>] [-VM <VirtualMachine[]>]
[-VirtualSwitch <VirtualSwitchBase[]>] [-Name <String[]>]
[-Datacenter <Datacenter[]>] [-Standard] [-Distributed]
[-Tag <Tag[]>] [-Server <VIServer[]>] [<CommonParameters>]

Get-VirtualPortGroup -Id <String[]> [-Server <VIServer[]>]
[<CommonParameters>]

Get-VirtualPortGroup -RelatedObject
<VirtualPortGroupRelatedObjectBase[]> [<CommonParameters>]
```

If you use the Get-VirtualPortGroup cmdlet without parameters, then you will get a list of all the port groups in your environment. You can specify a datacenter, host, virtual machine, virtual switch, or the name of a port group to filter for specific port groups.

To retrieve the VLAN 10 Port Group we just created from all of the hosts in cluster Cluster01, you can use the following command line:

```
PowerCLI C:\> Get-Cluster -Name Cluster01 |
>> Get-VMHost |
>> Get-VirtualPortGroup -Name "VLAN 10 Port Group"
>>
Name Key VLanId PortBind
```

```
Name Key VLanId PortBinding NumPorts
--- VLAN 10 Port Group key-vim.host.PortGr... 10

VLAN 10 Port Group key-vim.host.PortGr... 10
```

The Set-VirtualPortGroup cmdlet can be used to change the name and the VLAN ID of a port group.



If you change the name of a port group, any virtual machine using this port group will not be updated. These virtual machines will continue to show the previous network label and will no longer be connected to any virtual port group.

The Set-VirtualPortGroup cmdlet has the following syntax:

```
Set-VirtualPortGroup [-Name <String>] [-VLanId <Int32>]
[-VirtualPortGroup] <VirtualPortGroup[]> [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The next example will rename VLAN 10 Port Group to VLAN 11 Port Group and change the VLAN ID to 11 on all of the hosts in the cluster Cluster 01:

```
PowerCLI C:\> Get-Cluster -Name Cluster01 |

>> Get-VMHost |

>> Get-VirtualPortGroup -Name "VLAN 10 Port Group" |

>> Set-VirtualPortGroup -Name "VLAN 11 Port Group" -VLanId 11

>>

Name Key VLanId PortBinding NumPorts

--- VLAN 11 Port Group key-vim.host.PortGr... 11
```

Removing standard port groups

VLAN 11 Port Group key-vim.host.PortGr... 11

The Remove-VirtualPortGroup cmdlet will remove a standard port group for you. The syntax of this cmdlet is as follows:

```
Remove-VirtualPortGroup [-VirtualPortGroup]] < VirtualPortGroup[] >
[-WhatIf] [-Confirm] [< CommonParameters >]
```

In the next example, we will remove VLAN 11 Port Group from all of the hosts in cluster Cluster01:


```
PowerCLI C:\> Get-Cluster -Name Cluster01 |
>> Get-VMHost |
>> Get-VirtualPortGroup -Name "VLAN 11 Port Group" |
>> Remove-VirtualPortGroup -Confirm:$false
>>
```

Using vSphere Distributed Switches

The vSphere Distributed Switches are virtual switches that span across multiple hosts. This makes it easier to configure hosts that need similar network configurations. It also ensures that virtual machines will get the same network configuration when they migrate to another host. You need a vSphere Enterprise Plus license and a vCenter Server to be able to use vSphere Distributed Switches.

In vSphere PowerCLI, there are separate sets of cmdlets for working with vSphere Standard Switches and vSphere Distributed Switches. In the past, the VMware PowerCLI team tried to integrate both types of switches into one set of cmdlets. This is why, for example, the <code>Get-VirtualSwitch</code> cmdlet has a <code>-Distributed</code> parameter. However, this parameter is now obsolete, and VMware made a new set of cmdlets specific for vSphere Distributed Switches. The vSphere PowerCLI VDS snap-in that provides support for managing Distributed Switches and port groups was introduced in PowerCLI 5.1 Release 2. In this section, you will learn more about these new cmdlets.

In the following diagram, you see a vSphere Distributed Switch that spans two hosts:



Creating vSphere Distributed Switches

The New-VDSwitch cmdlet creates new vSphere Distributed Switches. This cmdlet has the following syntax:

```
New-VDSwitch [-ContactDetails <String>] [-ContactName <String>]
[-LinkDiscoveryProtocol <LinkDiscoveryProtocol>]
[-LinkDiscoveryProtocolOperation <LinkDiscoveryOperation>]
[-MaxPorts <Int32>] [-Mtu <Int32>] [-Notes <String>]
[-NumUplinkPorts <Int32>] [-Version <String>] -Name <String>
-Location <VIContainer> [-RunAsync] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
New-VDSwitch -ReferenceVDSwitch <VDSwitch> -Name <String> -Location <VIContainer> [-WithoutPortGroups] [-RunAsync] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
New-VDSwitch -BackupPath <String> [-KeepIdentifiers] [-Name <String>]
-Location <VIContainer> [-WithoutPortGroups] [-RunAsync]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

If you compare the preceding syntax with the syntax of the New-VirtualSwitch cmdlet, then you will see that the New-VDSwitch cmdlet has many more possibilities to configure the virtual switch during creation. In vSphere 5.1 and later versions, you can even specify a reference vSphere Distributed Switch or a backup profile from where a new switch can be created.

Creating a new vSphere Distributed Switch from scratch

To create a new vSphere Distributed Switch from scratch, you have to specify at least the -Name and the -Location parameters. The location can be a datacenter or a folder.

In the next example, we will create a new vSphere Distributed Switch named VDSwitch1 in datacenter New York:

```
PowerCLI C:\> $Datacenter = Get-Datacenter -Name "New York"
PowerCLI C:\> New-VDSwitch -Name "VDSwitch1" -Location $Datacenter
```

Name	NumPorts	Mtu	Version	Vendor
VDSwitch1	0	1500	5.5.0	VMware

Cloning a vSphere Distributed Switch

We can now clone the VDSwitch1 to a new switch VDSwitch2. Of course, this is not very useful because VDSwitch1 is not configured yet. We will clone the switch just to show you how to do it:

```
PowerCLI C:\> New-VDSwitch -Name "VDSwitch2" `
>> -ReferenceVDSwitch "VDSwitch1" -Location $Datacenter
>>
```

Name	NumPorts	Mtu	Version	Vendor
VDSwitch2	0	1500	5.5.0	VMware

If you want to clone a vSphere distributed switch without cloning the port groups, then you can use the -WithoutPortGroups parameter.



Cloning a vSphere Distributed Switch and the New-VDSwitch -ReferenceVDSwitch parameter are only supported in VMware vSphere 5.1 and later versions.

Creating a vSphere Distributed Switch from an export

Later in this chapter, we will see how to create an export of the configuration of a vSphere Distributed Switch. If you have an export, then you can use it to recreate a switch or to create a new one. The next example will create a new vSphere Distributed Switch named VDSwitch3 in the datacenter New York from an export of the configuration of VDSwitch1:

```
PowerCLI C:\> New-VDSwitch -BackupPath C:\VDSwitchlConfig.zip `
>> -Name VDSwitch3 -Location (Get-Datacenter -Name "New York")
```

Importing vSphere distributed switch - Switch name: 'VDSwitch1', Switch version: 5.5.0, Number of port groups: 1, Number of resource pools: 8, Number of uplinks: 1, Notes: VDSwitch1 Configuration

Name	NumPorts	Mtu	Version	Vendor
VDSwitch3	0	1500	5.5.0	VMware

Also, for importing an export you can use the <code>-WithoutPortGroups</code> parameter to prevent importing the port groups.



Creating a vSphere Distributed Switch from an export and creating the New-VDSwitch -BackupPath parameter are only supported in VMware vSphere 5.1 and later versions.

Retrieving vSphere Distributed Switches

You can retrieve vSphere Distributed Switches with the Get-VDSwitch cmdlet. The syntax of this cmdlet is as follows:

```
Get-VDSwitch [[-Name] <String[]>] [-Location <FolderContainer[]>]
[-VMHost <VMHost[]>] [-VM <VirtualMachine[]>] [-Server <VIServer[]>]
[<CommonParameters>]

Get-VDSwitch -Id <String[]> [-Server <VIServer[]>]
[<CommonParameters>]

Get-VDSwitch -RelatedObject <VDSwitchRelatedObjectBase[]>
[<CommonParameters>]
```

If you use the <code>Get-VDSwitch</code> cmdlet without parameters, then it will return all of the vSphere Distributed Switches in your environment. You can use the <code>-Location</code> parameter to specify a datacenter or folder in which you want to search for vSphere Distributed Switches.

The next example will retrieve all of the vSphere Distributed Switches in the datacenter New York:

PowerCLI C:\> Get-Datacenter -Name "New York" | Get-VDSwitch

Name	NumPorts	Mtu	Version	Vendor
VDSwitch1	0	1500	5.5.0	Vmware
VDSwitch2	0	1500	5.5.0	VMware
VDSwitch3	0	1500	5.5.0	VMware

You can specify a value for the -Name parameter to retrieve a specific vSphere Distributed Switch. In the following example, we will retrieve the vSphere Distributed Switch VDSwitch1:

PowerCLI C:\> Get-VDSwitch -Name VDSwitch1

Name	NumPorts	Mtu	Version	Vendor
VDSwitch1	0	1500	5.5.0	VMware

Configuring vSphere Distributed Switches

The selection you make using <code>Get-VDSwitch</code> can be used as an input of the <code>Set-VDSwitch</code> cmdlet to modify the configuration or version of one or more vSphere Distributed Switches, to roll back the configuration to its previous state, or to import the configuration from a backup profile.



Rolling back the configuration of a vSphere Distributed Switch and importing the configuration of a vSphere Distributed Switch from a backup are available only on vSphere 5.1 and later versions.

The Set-VDSwitch cmdlet has the following syntax:

```
Set-VDSwitch [-Name <String>] [-ContactDetails <String>]
[-ContactName <String>] [-LinkDiscoveryProtocol
<LinkDiscoveryProtocol>] [-LinkDiscoveryProtocolOperation
<LinkDiscoveryOperation>] [-MaxPorts <Int32>] [-Mtu <Int32>]
[-Notes <String>] [-NumUplinkPorts <Int32>] [-Version <String>]
[-VDSwitch] <VDSwitch[]> [-RunAsync] [-Server <VIServer[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]
Set-VDSwitch -BackupPath <String> [-WithoutPortGroups] [-VDSwitch]
<VDSwitch[]> [-RunAsync] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
Set-VDSwitch -RollBackConfiguration [-VDSwitch] <VDSwitch[]>
[-RunAsync] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

In the next example, we will set almost every property for VDSwitch1 that you can set using PowerShell. We will use a PowerShell technique called **splatting** to create a parameter list for the Set-VDSwitch cmdlet. The parameter list will be a hash table called \$Parameters. By using the **splat operator** @, you can add the parameters in the \$Parameters hash table to the Set-VDSwitch cmdlet call.



When you use splatting, you have to use the name of the variable containing the parameter's hash table without the dollar sign, that is, @Parameters and not @\$Parameters.

```
PowerCLI C:\> $VDSwitch = Get-VDSwitch -Name vDSWitch1
PowerCLI C:\> $Parameters = @{
>> NumUplinkPorts = 2
>> MaxPorts = 1024
>> LinkDiscoveryProtocol = 'LLDP'
```

```
>> LinkDiscoveryProtocolOperation = 'Both'
>> ContactName = 'vsphereadmin@blackmilktea.com'
```

>> ContactDetails = 'New York office'

>> Notes = 'VDSwitch for New York datacenter'

>> }

>> \$VDSwitch | Set-VDSwitch @Parameters

>> Get-VDSwitch -Name vDSWitch1 | Format-List -Property *

>>

Name	NumPorts	Mtu	Version	Vendor
VDSwitch1	0	1500	5.5.0	VMware

LinkDiscoveryProtocol : LLDP LinkDiscoveryProtocolOperation : Both

VlanConfiguration :

Name : VDSwitch1 ExtensionData : VMware.Vim.

VmwareDistributedVirtualSwitch

NumPorts : 0

0f bd a7

Mtu : 1500

Notes : VDSwitch for New York datacenter

Datacenter : New York

NumUplinkPorts : 4

ContactName : vsphereadmin@blackmilktea.com

ContactDetails : New York office

Version : 5.5.0
Vendor : VMware
Folder : network
MaxPorts : 1024


Id : VmwareDistributedVirtualSwitch-dvs-182
Uid : /VIServer=root@192.168.0.132:443/Distrib

utedSwitch=VmwareDistributedVirtualSwitch-dvs-49/

Client : VMware.VimAutomation.Vds.Impl.

V1.VDClientImpl

The following screenshot of the vSphere Web Client shows the settings of the Distributed Switch VDSwitch1 after executing the previous commands:



Rolling back the configuration of a vSphere Distributed Switch

If you made a mistake in the configuration of a vSphere Distributed Switch, then you can roll back the configuration to its previous state using the Set-VDSwitch - RollbackConfiguration parameter.

In the following example, we will modify the MTU size of the switch VDSwitch1 to 9,000, and then use the -RollbackConfiguration parameter to revert to the previous value of 1,500:

```
PowerCLI C:\> Get-VDSwitch -Name VDSwitch1 |
>> Set-VDSwitch -MTU 9000
>>
Name
                          NumPorts Mtu
                                              Version Vendor
                                              -----
                                   9000
VDSwitch1
                                              5.5.0 VMware
PowerCLI C:\> Get-VDSwitch -Name VDSwitch1
>> Set-VDSwitch -RollbackConfiguration
>>
Name
                           NumPorts Mtu
                                              Version Vendor
                           -----
                                              -----
```

Importing the configuration of a vSphere Distributed Switch from a backup

VDSwitch1

You can import the configuration of a vSphere Distributed Switch from a backup created with the Export-VDSwitch cmdlet. Later in this chapter, you will learn how to create a backup. In this section, we will show you how to restore the configuration from a backup.

1500

5.5.0

You have to use the Set-VDSwitch -BackupPath parameter to specify the path to the configuration .zip file. You can also use the -WithoutPortGroups parameter if you don't want to restore the port groups.

In the next example, we will import the configuration of VDSwitch1 from a backup file called 'c:\myVDSwitch1Config.zip':

```
PowerCLI C:\> Get-VDSwitch -Name 'VDSwitch1' |
>> Set-VDSwitch -BackupPath 'c:\myVDSwitch1Config.zip'
>>
```

Restoring vSphere distributed switch configuration - Switch name: 'VDSwitch1', Switch version: 5.5.0, Number of port groups: 0, Number of resource pools: 8, Number of uplinks: 1, Notes: My VDSwitch1 configuration

Name	NumPorts	Mtu	Version	Vendor
VDSwitch1	0	1500	5.5.0	VMware

Upgrading a vSphere Distributed Switch

In every new VMware vSphere version, VMware introduces new features to the vSphere Distributed Switch. To be able to use these new features, you have to upgrade your switches to the new version.

In the next example, we will upgrade the version of the VDSwitch4 switch to 5.5.0:

```
PS C:\> $VDSwitch = Get-VDSwitch -Name VDSwitch4
PS C:\> $VDSwitch
```

Name	NumPorts	Mtu	Version	Vendor
VDSwitch4	0	1500	4.1.0	VMware
PS C:\> \$VDSwitch Set-VDSwitch	ch -Version	5.5.0		
Name	NumPorts	Mtu	Version	Vendor
VDSwitch4	0	1500	5.5.0	VMware

Adding hosts to vSphere Distributed Switches

After creating a vSphere Distributed Switch, you have to add hosts to the switch. Normally, you add at least all of the hosts that are in the same cluster. Because a vSphere Distributed Switch is created in a datacenter or a folder, a vSphere Distributed Switch is not limited to one cluster. You can add hosts of multiple clusters to the same switch.

The Add-VDSwitchVMHost cmdlet will add hosts to a vSphere Distributed Switch. The syntax of this cmdlet is as follows:

```
Add-VDSwitchVMHost -VDSwitch <VDSwitch> -VMHost <VMHost[]>
[-Server <VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

In the next example, we will add all of the hosts of the cluster "Cluster01" to the vSphere Distributed Switch "VDSwitch1":

```
PowerCLI C:\> $VMHost = Get-Cluster Cluster01 | Get-VMHost
PowerCLI C:\> Add-VDSwitchVMHost -VDSwitch VDSwitch1 -VMHost $VMHost
```

Adding host physical network adapters to a vSphere Distributed Switch

Adding hosts to a vSphere Distributed Switch does not add physical network adapters to the switch. For each host, you have to add network adapters to the vSphere Distributed Switch to give the switch connectivity to the external network.

The Add-VDSwitchPhysicalNetworkAdapter cmdlet will connect a host's physical network adapter to a vSphere Distributed Switch. The syntax of this cmdlet is as follows:

```
Add-VDSwitchPhysicalNetworkAdapter [-VMHostNetworkAdapter] <PhysicalNic[]> [-DistributedSwitch] <DistributedSwitch> [-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The following example will add the physical network adapter vmnic4 of the host 192.168.0.133 to the vSphere Distributed Switch VDSwitch1:

```
PowerCLI C:\> $NetworkAdapter = Get-VMHost -Name 192.168.0.133 |
>> Get-VMHostNetworkAdapter -Name vmnic4 -Physical
>>
PowerCLI C:\> Add-VDSwitchPhysicalNetworkAdapter `
>> -DistributedSwitch VDSwitch1 `
>> -VMHostNetworkAdapter $NetworkAdapter -Confirm:$false
>>
```

Removing host physical network adapters from a vSphere Distributed Switch

Removing a physical network adapter from a vSphere Distributed Switch can be done using the Remove-VDSwitchPhysicalNetworkAdapter cmdlet. The syntax of this cmdlet is as follows:

```
Remove-VDSwitchPhysicalNetworkAdapter [-VMHostNetworkAdapter]
<PhysicalNic[]> [-WhatIf] [-Confirm] [<CommonParameters>]
```

You have to specify only a network adapter as the value of the -VMHostNetworkAdapter parameter; then the cmdlet will remove that network adapter from the switch to which it is connected.

In the following example, the physical network adapter vmnic4 from the host 192.168.0.133 will be removed from the vSphere Distributed Switch VDSwitch1:

```
PowerCLI C:\> Get-VMhost -Name 192.168.0.133 |
>> Get-VMHostNetworkAdapter -Physical -Name vmnic4 |
>> Remove-VDSwitchPhysicalNetworkAdapter -Confirm:$false
>>
```

Removing hosts from a vSphere Distributed Switch

You can use the Remove-VDSwitchVMHost cmdlet to remove a host from a vSphere Distributed Switch. This cmdlet has the following syntax:

```
Remove-VDSwitchVMHost -VDSwitch <VDSwitch> -VMHost <VMHost[] > [-Server
<VIServer[] >] [-RunAsync] [-WhatIf] [-Confirm] [<CommonParameters>]
```

In the next example, we will remove the host 192.168.0.133 from the vSphere Distributed Switch VDSwitch1:

```
PowerCLI C:\> Get-VDSwitch -Name VDSwitch1 |
>> Remove-VDSwitchVMHost -VMHost 192.168.0.133 -Confirm:$false
>>
```

Exporting the configuration of vSphere Distributed Switches

If you export the configuration of a vSphere Distributed Switch, then you can create a .zip file that can be used as a backup for the configuration of the vSphere Distributed Switch. You can use this .zip file to recreate or clone the vSphere Distributed Switch.

The Export-VDSwitch cmdlet that you can use to create the .zip file has the following syntax:

```
Export-VDSwitch [-VDSwitch] <VDSwitch[]> [-WithoutPortGroups]
[-Description <String>] [-Destination <String>] [-Force]
[-Server <VIServer[]>] [<CommonParameters>]
```

The next PowerCLI example will export the configuration of the vSphere Distributed Switch VDSwitch1 into a file called VDSwitch1Config.zip:

1/9/2014 6:51 PM



-a---

Exporting the configuration of a vSphere Distributed Switch and the Export-VDSwitch cmdlet are only supported in VMware vSphere 5.1 and later versions.

4374 VDSwitch1Config.zip

Removing vSphere Distributed Switches

To remove a vSphere Distributed Switch, you can use the Remove-VDSwitch cmdlet. This cmdlet has the following syntax:

```
Remove-VDSwitch [-VDSwitch] <VDSwitch[]> [-RunAsync]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

In the next example, we will remove the vSphere Distributed Switch VDSwitch1:

```
PowerCLI C:\> Get-VDSwitch -Name VDSwitch1 |
>> Remove-VDSwitch -Confirm:$false
>>
```

Using distributed virtual port groups

In this section, you will learn how to use port groups on Distributed Virtual Switches.

Creating distributed virtual port groups

You can use the New-VDPortgroup cmdlet to create distributed virtual port groups from scratch, from the reference port groups, or from an export of a Distributed Virtual Switch. The syntax of the New-VDPortgroup cmdlet is as follows:

```
New-VDPortgroup [-VDSwitch] <VDSwitch> -Name <String>
[-Notes <String>] [-NumPorts <Int32>] [-VlanId <Int32>]
[-VlanTrunkRange <VlanRangeList>] [-PortBinding
<DistributedPortGroupPortBinding>] [-RunAsync]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
New-VDPortgroup [-VDSwitch] <VDSwitch> [-Name <String>]
-ReferencePortgroup <VDPortgroup> [-RunAsync] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
New-VDPortgroup [-VDSwitch] <VDSwitch> [-Name <String>] -BackupPath
<String> [-KeepIdentifiers] [-RunAsync] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The New-VDPortgroup cmdlet has three parameter sets. The first parameter set is the default one, the second parameter set can be used to create a port group from a reference port group, and the third one can be used to create a port group from an export.

The first example creates a new distributed virtual port group on the vSphere Distributed Switch VDSwitch1 with 64 ports and VLAN ID 10:

```
PowerCLI C:\> Get-VDSwitch -Name VDSwitch1 |
>> New-VDPortgroup -Name "VLAN 10 Port Group" -NumPorts 64 -VLanId 10
>>

Name NumPorts PortBinding
```

VLAN 10 Port Group 64 Static

Creating distributed virtual port groups from a reference group

In the following example, we will create a new distributed virtual port group named VLAN 10 Port group 2 using the port group VLAN 10 Port Group as a reference:

```
PowerCLI C:\> $Portgroup = Get-VDPortgroup -Name 'VLAN 10 Port Group'
PowerCLI C:\> Get-VDSwitch -Name VDSwitch1 |
>> New-VDPortgroup -Name 'VLAN 10 Port group 2' -ReferencePortgroup
$Portgroup
>>
Name NumPorts PortBinding
----
```



VLAN 10 Port group 2

Creating distributed virtual port groups from a reference group and the New-VDPortgroup -ReferencePortgroup parameter are only supported in VMware vSphere 5.1 and later versions.

Static

Creating distributed virtual port groups from an export

This is the last example of this section. In this one, we will create a new distributed virtual port group named VLAN 10 Port group 3 using an export. Later in this chapter, we will show you how to create an export of a distributed virtual port group.

```
PowerCLI C:\> Get-VDSwitch -Name VDSwitch1 |

>> New-VDPortgroup -Name 'VLAN 10 Port group 3' -BackupPath c:\users\
robert\vlan10portgroup.zip

>>

Restoring vSphere distributed port group configuration - Name: VLAN 10
Port Group, VLAN: 'Access: 10', Type: standard, Port binding: static,
Port allocation: elastic, Notes:

Name NumPorts PortBinding
----
VLAN 10 Port group 3 64 Static
```



Creating distributed virtual port groups from an export and the New-VDPortgroup -BackupPath parameter are only supported in VMware vSphere 5.1 and later versions.

Configuring distributed virtual port groups

You can use the Get-VDPortgroup cmdlet to retrieve all of your distributed virtual port groups or to retrieve a specific one. The syntax of this cmdlet is as follows:

```
Get-VDPortgroup [[-Name] <String[]>]
[-NetworkAdapter <NetworkAdapter[]>] [-VDSwitch <VDSwitch[]>]
[-VMHostNetworkAdapter <HostVirtualNic[]>] [-Server <VIServer[]>]
[-Tag <Tag[]>] [<CommonParameters>]

Get-VDPortgroup -Id <String[]> [-Server <VIServer[]>]
[<CommonParameters>]

Get-VDPortgroup -RelatedObject <VDPortgroupRelatedObjectBase[]> [<CommonParameters>]
```

In the following example, we will retrieve all of our distributed virtual port groups:

PowerCLI C:\> Get-VDPortGroup

[<CommonParameters>]

Name	NumPorts	PortBinding
VDSwitch1-DVUplinks-182	4	Static
VLAN 10 Port Group	64	Static
VLAN 10 Port group 2	64	Static
VLAN 10 Port group 3	64	Static

The Set-VDPortgroup cmdlet can be used to modify the configuration of a distributed virtual port group, to roll back the distributed virtual port group to its last valid configuration, or to import the configuration from a .zip file created earlier with the Export-VDPortgroup cmdlet. The syntax of the Set-VDPortgroup cmdlet is as follows:

```
Set-VDPortgroup [-Name <String>] [-Notes <String>] [-NumPorts
<Int32>] [-VlanId <Int32>] [-VlanTrunkRange <VlanRangeList>]
[-PrivateVlanId <Int32>] [-PortBinding
<DistributedPortGroupPortBinding>] [-DisableVlan] [-VDPortgroup]
<VDPortgroup[]> [-RunAsync] [-Server <VIServer[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]

Set-VDPortgroup -RollbackConfiguration [-VDPortgroup] <VDPortgroup[]>
[-RunAsync] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
```

```
Set-VDPortgroup -BackupPath <String> [-VDPortgroup] <VDPortgroup[]>
[-RunAsync] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```


Renaming a distributed virtual port group

In the following example, we will rename distributed virtual port group VLAN 10 Port Group 2 to VLAN 20 Port Group, modify the number of ports to 128, and change the VLAN ID to 20:

```
PowerCLI C:\> Get-VDPortgroup -Name 'VLAN 10 Port Group 2' |
>> Set-VDPortgroup -Name 'VLAN 20 Port Group' -NumPorts 128 -VlanId 20
>>
```

Name	NumPorts	PortBinding
VLAN 20 Port Group	128	Static

In the following screenshot of the vSphere Web Client, the port group is shown after it is renamed to VLAN 20 Port Group:



Rolling back the configuration of a distributed virtual port group

In the following example, we will roll back the configuration of distributed virtual port group VLAN 10 Port Group to its last valid configuration using the following command:

```
PowerCLI C:\> Get-VDPortgroup -Name 'VLAN 10 Port Group' |
>> Set-VDPortgroup -RollbackConfiguration
>>

NumPorts PortBinding
----
VLAN 10 Port Group 64 Static
```



Rolling back the configuration of a distributed virtual port group and the Set-VDPortgroup -RollbackConfiguration parameter are only supported in VMware vSphere 5.1 and later versions.

Restoring the configuration of a distributed virtual port group

In the following example, we will restore the configuration of distributed virtual port group VLAN 10 Port Group from a .zip file created earlier using the Export-VDPortgroup cmdlet:

```
PowerCLI C:\> Get-VDPortgroup -Name 'VLAN 10 Port Group' |
>> Set-VDPortgroup -BackupPath c:\Vlan10PortGroup.zip
>>
Applying vSphere distributed port group configuration - Name: VLAN 10
Port Group, VLAN: 'Access: 10', Type: standard, Port binding: static,
Port allocation: elastic, Notes:

Name NumPorts PortBinding
----
VLAN 10 Port Group 64 Static
```



Restoring the configuration of a distributed virtual port group and the Set-VDPortgroup -BackupPath parameter are only supported in VMware vSphere 5.1 and later versions.

Configuring Network I/O Control

The virtual Distributed Switch cmdlets don't have a method to configure **Network I/O Control**. However, in PowerCLI you can use all of the VMware vSphere public APIs. It is not difficult to use them to enable or disable Network I/O Control.

Enabling Network I/O Control

In the following example, we will enable Network I/O Control for switch VDSwitch1 using the EnableNetworkResourceManagement() method from the API:

```
PowerCLI C:\> $VDSwitch = Get-VDSwitch -Name VDSwitch1
PowerCLI C:\>
$VDSwitch.ExtensionData.EnableNetworkResourceManagement($true)
```

Disabling Network I/O Control

Disabling Network I/O Control for VDSwitch1 can be done by replacing \$true in the previous example with \$false:

```
PowerCLI C:\> $VDSwitch = Get-VDSwitch -Name VDSwitch1
PowerCLI C:\>
$VDSwitch.ExtensionData.EnableNetworkResourceManagement($false)
```

Exporting the configuration of distributed virtual port groups

You can make an export from one or more distributed virtual port groups with the Export-VDPortGroup cmdlet, and later use this export to create new port groups or to restore the configuration of port groups. The syntax of the Export-VDPortGroup cmdlet is as follows:

```
Export-VDPortGroup [-VDPortGroup] <VDPortgroup[]> [-Description
<String>] [-Destination <String>] [-Force] [-Server <VIServer[]>]
[<CommonParameters>]
```

In the next example, we will create an export of VLAN 10 Port Group:

```
PowerCLI C:\> Get-VDPortGroup -Name 'VLAN 10 Port Group' |
>> Export-VDPortGroup -Destination C:\Vlan10PortGroup.zip
>>
```

Mode	${ t LastWriteTime}$	Length Name
-a	1/9/2014 6:57 PM	1865 Vlan10PortGroup.zip



The Export-VDPortGroup cmdlet is supported only in VMware vSphere 5.1 and later versions.

Migrating a host network adapter from a standard port group to a distributed port group

In the next example, we will use the Set-VMHostNetworkAdapter cmdlet, which we have seen before, to migrate the virtual network adapter vmk1 to the distributed port group VLAN 10 Port Group:

```
PowerCLI C:\> Get-VMHostNetworkAdapter -Name vmk1
>> Set-VMHostNetworkAdapter -PortGroup 'VLAN 10 Port Group'
-Confirm:$false
```

```
DhcpEnabled IP
Name Mac
                                         SubnetMask
                                                     Device
                    -----
---- ---
                                          _____
                                                     -----
vmk1 00:50:56:65:bd:a1 False
                            192.168.0.150 255.255.255.0 vmk1
```

Removing distributed virtual port groups

To remove a distributed virtual port group, you can use the Remove-VDPortGroup cmdlet. The syntax of this cmdlet is as follows:

```
Remove-VDPortGroup [-VDPortGroup] <VDPortgroup[]> [-RunAsync]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

In the following example, we will remove the port group named VLAN 10 Port Group:

```
PowerCLI C:\> Get-VDPortGroup -Name 'VLAN 10 Port Group' |
>> Remove-VDPortGroup -Confirm:$false
>>
```

Configuring host networking

The Get-VMHostNetwork cmdlet will retrieve information about the network on a specific host. This cmdlet has the following syntax:

```
Get-VMHostNetwork [-Server <VIServer[]>] [-VMHost] <VMHost[]>
[<CommonParameters>]
```

In the next example, we will retrieve the information about the network on the host 192.168.0.133:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-VMHostNetwork |
>> Format-List *
>>
VMHostId
                       : HostSystem-host-167
VMHost
                       : 192.168.0.133
VMKernelGateway
                       : 192.168.0.1
VMKernelGatewayDevice :
ConsoleGateway
ConsoleGatewayDevice :
DnsAddress
                      : {192.168.0.1}
DnsFromDhcp
                       : True
DnsDhcpDevice
                       : vmk0
DomainName
                        : sitecomwl306
HostName
                       : localhost
                       : {localdomain, sitecomwl306}
SearchDomain
VirtualSwitch
                       : {vSwitch0, vSwitch1}
                        : {vmnic0, vmnic1, vmnic2, vmnic3...}
PhysicalNic
ConsoleNic
                        : {}
VirtualNic
                        : {vmk0, vmk1}
                        : /VIServer=root@192.168.0.132:443/
VMHost=HostSystem-host-167/VMHostNetwork=/
```

IPv6Enabled : True

ConsoleV6GatewayDevice :

VMKernelV6GatewayDevice :

VMKernelV6GatewayDevice :

ExtensionData : VMware.Vim.HostNetworkInfo
ExtensionData2 : VMware.Vim.HostNetworkSystem

Name :

Id : HostNetworkSystem-networkSystem-167

Client : VMware.VimAutomation.ViCore.Impl.V1.VimClient

The hosts I use as examples in this book are all virtual ESXi servers running in my home lab. As you can see from the preceding output, the hostname is still localhost and the domain is sitecomwl306. That is my SiteCom wireless LAN. Let's try to change the hostname and domain.

The Set-VMHostNetwork cmdlet will modify the network settings of a host. The syntax of this cmdlet is as follows:

```
Set-VMHostNetwork [-Network] <VMHostNetworkInfo[]>
[-ConsoleGateway <String>] [-VMKernelGateway <String>]
[-VMKernelGatewayDevice <String>] [-ConsoleGatewayDevice<String>]
[-DomainName <String>] [-HostName <String>] [-DnsFromDhcp
[<Boolean>]] [-DnsDhcpDevice <Object>] [-DnsAddress <String[]>]
[-SearchDomain <String[]>] [-IPv6Enabled [<Boolean>]]
[-ConsoleV6Gateway <String>] [-ConsoleV6GatewayDevice <String>]
[-VMKernelV6Gateway <String>] [-VMKernelV6GatewayDevice <String>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

In this example, we will change the host name of the host 192.168.0.133 into ESX1, and modify the domain name to blackmilktea.com. To be able to do this, we have to disable DnsFromDhcp because the domain name and host name cannot be explicitly set if DnsFromDhcp is enabled:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-VMHostNetwork | 
>> Set-VMHostNetwork -HostName ESX1 -DomainName blackmilktea.com -DnsFromDhcp:$false 
>>
```

HostName	DomainName	DnsFro ConsoleGateway	ConsoleGatewayD Dns
		mDhcp	evice
ESX1	blackmilk	False	

Configuring the network of a virtual machine

To configure the network of a virtual machine guest operating system, you can use the <code>Get-VMGuestNetworkInterface</code> and <code>Set-VMGuestNetworkInterface</code> cmdlets. Both cmdlets are experimental and might be changed or removed in a future PowerCLI release. The cmdlets use the VMware Tools. So, if these tools are not installed inside the guest operating system or when they are not running, the cmdlets will not work. Because the cmdlets use the VMware Tools, you can configure a guest's network even if the network is not running or is disconnected.

In the help of Get-VMGuestNetworkInterface and Set-VMGuestNetworkInterface cmdlets, the following requirements for using these cmdlets are specified:

- This cmdlet supports only Windows XP 32 SP3, Windows Server 2003 32-bit SP2, Windows Server 2003 64-bit SP2, Windows 7 64-bit, Windows Server 2008 R2 64-bit, and the Redhat Enterprise 5 operating systems.
- To run this cmdlet against vCenter Server/ESX/ESXi versions earlier than 5.0, you need to meet the following requirements:
 - ° You must run the cmdlet on the 32-bit version of Windows PowerShell.
 - ° You must have access to the ESX that hosts the virtual machine over TCP port 902.
 - o For vCenter Server/ESX/ESXi versions earlier than 4.1, you need the VirtualMachine.Interact.ConsoleInteract privilege. For vCenter Server/ESX/ESXi 4.1 and later, you need the VirtualMachine. Interact.GuestControl privilege.
- To run this cmdlet against vCenter Server/ESXi 5.0 and later, you need VirtualMachine. GuestOperations. Execute and VirtualMachine. GuestOperations. Modify privileges.

The syntax of the Get-VMGuestNetworkInterface cmdlet is as follows:

```
Get-VMGuestNetworkInterface [-Name <String[]>] [[-VM]
<VirtualMachine[]>] [-VMGuest <VMGuest[]>] [-Server <VIServer[]>]
[-ToolsWaitSecs <Int32>] [-GuestPassword <SecureString>]
[-GuestUser <String>] [-GuestCredential <PSCredential>]
[-HostPassword <SecureString>] [-HostUser <String>]
[-HostCredential <PSCredential>]
```

In the next example, we will retrieve the network configuration for the virtual machine VM1. First, we have to enter a username and password with administrative rights in the guest operating system:

```
PowerCLI C:\> $Credential = Get-Credential
cmdlet Get-Credential at command pipeline position 1
Supply values for the following parameters:
Credential
PowerCLI C:\> $GuestNic = Get-VM -Name VM1 |
>> Get-VMGuestNetworkInterface -GuestCredential $Credential
PowerCLI C:\> $GuestNic
VM Name
                         ΙP
                                       IPPolicy SubnetMask
                                        -----
VM1 Local Area Connection 192.168.0.201 Static 255.255.255.0
The syntax of the Set-VMGuestNetworkInterface cmdlet is as follows:
Set-VMGuestNetworkInterface -VmGuestNetworkInterface
<VMGuestNetworkInterface[]> [-WinsPolicy <DhcpPolicy>]
[-Wins <String[]>] [-DnsPolicy <DhcpPolicy>] [-Dns <String[]>]
[-IPPolicy <DhcpPolicy>] [[-Gateway] <Object>] [[-Netmask] <String>]
[[-Ip] <IPAddress>] [-ToolsWaitSecs <Int32>]
[-GuestPassword <SecureString>] [-GuestUser <String>]
[-GuestCredential <PSCredential>] [-HostPassword <SecureString>]
[-HostUser <String>] [-HostCredential <PSCredential>] [-WhatIf]
[-Confirm] [<CommonParameters>]
In the following example, we will set the IP address of virtual machine VM1 to
192.168.0.251:
PowerCLI C:\> $GuestNic | Set-VMGuestNetworkInterface -IP 192.168.0.251
-GuestCredential $Credential
VM Name
                          ΙP
                                       IPPolicy SubnetMask
                                        -----
VM1 Local Area Connection 192.168.0.251 Static 255.255.255.0
```

Summary

In this chapter, we covered virtual networking. We showed you how to work with vSphere Standard Switches and vSphere Distributed Switches using PowerCLI. You learned to use port groups, to use host network adapters, and how to configure the management network of a host and the network of a virtual machine.

In the next chapter, you will learn all about managing storage with PowerCLI.

Managing Storage with PowerCLI

Your virtual machines need storage for their configuration files, disks, swap files, and snapshot files. These files can be placed on datastores that reside on a host's **local storage**, **Network File System (NFS)**, **Internet Small Computer System Interface** (**iSCSI**), **Fibre Channel (FC)** or **Fibre Channel over Ethernet (FCoE**), and **Storage Area Networks (SANs**). Datastores can be grouped into Datastore Clusters to create pools of datastores for storage aggregation, easy initial placement of disks, and load balancing using **Storage DRS**. In this chapter, we will discuss how to manage storage with PowerCLI.

The topics that will be covered in this chapter are as follows:

- Rescanning for new storage devices
- Creating datastores
- Retrieving datastores
- Setting the multipathing policy
- Configuring the vmhba paths to a SCSI device
- Working with Raw Device Mappings
- Configuring Storage I/O Control
- Configuring Storage DRS
- Upgrading datastores to VMFS-5
- Removing datastores

Rescanning for new storage devices

After creating a **Logical Unit Number** (**LUN**) on your Fibre Channel storage system and presenting the LUN to your ESXi servers, you have to rescan the **HBAs** on the ESXi servers before you can create a datastore on the LUN. An ESXi host will not see a newly attached LUN before a rescan is performed. You can use the <code>Get-VMHostStorage</code> cmdlet to rescan the HBAs of a host. The <code>Get-VMHostStorage</code> cmdlet has the following syntax:

```
Get-VMHostStorage [-VMHost] <VMHost[]> [-Refresh] [-RescanAllHba]
[-RescanVmfs] [-Server <VIServer[]>] [<CommonParameters>]
Get-VMHostStorage -Id <String[]> [-Server <VIServer[]>]
[<CommonParameters>]
```

The -VMHost and -Id parameters are required.

In the next example, we will rescan all of the HBAs of the hosts of the cluster Cluster01:

```
PowerCLI C:\> Get-Cluster -Name Cluster01 |
>> Get-VMHost | Get-VMHostStorage -RescanAllHba
>>
```

The following is the output of the preceding command:

```
SoftwareIScsiEnabled
-----
False
False
```

Creating datastores

You can use the New-Datastore cmdlet to create a new datastore. The New-Datastore cmdlet has two parameter sets, one for creating VMFS datastores and one for creating NFS datastores. The syntax of the New-Datastore cmdlet is as follows:

```
New-Datastore [-Server <VIServer[]>] [-VMHost] <VMHost[]> [-Name]
<String> -Path <String> [-Vmfs] [-BlockSizeMB <Int32>]
[-FileSystemVersion <String>] [-WhatIf] [-Confirm]
[<CommonParameters>]
New-Datastore [-Server <VIServer[]>] [-VMHost] <VMHost[]> [-Name]
<String> -Path <String> [-Nfs] -NfsHost <String> [-ReadOnly]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VMHost, -Name, -Path, and -NfsHost parameters are required.

Creating NFS datastores

In the first example, we will create an NFS datastore. To indicate that we want to create an NFS datastore, we have to use the -Nfs parameter. The datastore will be created on the host 192.168.0.133 with the name Cluster01_Nfs01. The IP address of the NFS server is 192.168.0.201, and the remote path of the NFS mount point is /fs01/cluster01/nfs01:

PowerCLI C:\> New-Datastore -Nfs -VMHost 192.168.0.133 -Name Cluster01 Nfs01 -NfsHost 192.168.0.201 -Path /fs01/cluster01/nfs01

Name	${\tt FreeSpaceGB}$	CapacityGB
Cluster01 Nfs01	976.292	1,000.000

Getting SCSI LUNs

Before we can create a VMFS datastore, we need to know the **canonical name** of the **SCSI logical unit** that will contain the new VMFS datastore.

The Get-ScsiLun cmdlet retrieves the SCSI devices available on the vCenter Server system and their canonical names. The syntax of the Get-ScsiLun cmdlet is as follows:

```
Get-ScsiLun [[-CanonicalName] <String[]>] [-VmHost] <VMHost[]>
[-Key <String[]>] [-LunType <String[]>] [-Server <VIServer[]>]
[<CommonParameters>]

Get-ScsiLun -Id <String[]> [-Server <VIServer[]>]
[<CommonParameters>]

Get-ScsiLun [[-CanonicalName] <String[]>] [-Hba] <Hba[]> [-Key <String[]>] [-LunType <String[]>] [-Server <VIServer[]>]
[<CommonParameters>]

Get-ScsiLun [[-CanonicalName] <String[]>] [-Datastore] <Datastore[]>
[-Key <String[]>] [-LunType <String[]>] [-Server <VIServer[]>]
[<CommonParameters>]
```

The -VmHost, -Id, -Hba, and -Datastore parameters are required. These four parameter sets are needed for retrieving the SCSI LUNs for hosts, SCSI device IDs, storage adapters, and datastores.

In the next example, we will get all of the SCSI LUNs of the host 192.168.0.133 and select the Vendor, Model, RuntimeName, and CanonicalName properties:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-ScsiLun |
```

```
>> Select-Object -Property Vendor, Model, RuntimeName, CanonicalName >>
```

RuntimeNa	ame	CanonicalName	
3PARdata	vv	vmhba0:C0:T3:L54	naa.60002ac000000000000002f400004ca6
HP	HSVX700	vmhba0:C0:T0:L10	naa.600a0b80001111550000f4f44041944d
HP	HSVX700	vmhba0:C0:T0:L2	naa.600a0b8000111155000025315052494d
HP	HSVX700	vmhba0:C0:T0:L25	naa.600a0b8000111155000059ba3f0d204e
3PARdata	vv	vmhba0:C0:T2:L51	naa.60002ac000000000000035000004bee

Creating VMFS datastores

To create a VMFS datastore, we have to use the New-datastore -Vmfs parameter to indicate that we want to create a VMFS datastore. We have to specify a name for the datastore and a host on which we want to create the datastore. Finally, we have to specify the canonical name of the SCSI logical unit that will contain the new VMFS datastore. This is shown in the following code:

```
PowerCLI C:\> New-Datastore -Vmfs -VMHost 192.168.0.133 -Name Cluster01 Vmfs01 -Path naa.600a0b80001111550000d2c418e29350
```

The following is the output of the preceding command:

Name	FreeSpaceGB	CapacityGB
Cluster01 Vmfs01	248,801	249,750

If you create the VMFS datastore on a host that is part of a cluster, the new datastore will be mounted on all hosts of the cluster.

Creating software iSCSI VMFS datastores

To create a datastore on an iSCSI SAN, you can use hardware iSCSI initiators or software iSCSI initiators. Hardware iSCSI initiators are similar to Fibre Channel HBAs. In this section, we will discuss how to create VMFS datastores using software iSCSI initiators. Before you can connect your ESXi hosts to an iSCSI LUN, your storage administrators will have to create a LUN and expose it to your ESXi servers. To set up software iSCSI initiators, you have to enable software iSCSI on your hosts using the Set-VMHostStorage cmdlet.

The syntax of this cmdlet is as follows:

```
Set-VMHostStorage -VMHostStorageInfo[]>
-SoftwareIScsiEnabled [<Boolean>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -VMHostStorage and -SoftwareIScsiEnable parameters are required.

Then, you can create an iSCSI HBA target. First, you have to find the iSCSI HBA using the Get-VMHostHba cmdlet, which has the following syntax:

```
Get-VMHostHba [[-VMHost] <VMHost[]>] [[-Device] <String[]>]
[-Type <HbaType[]>] [-Server <VIServer[]>] [<CommonParameters>]
```

This cmdlet has no required parameters.

To create the iSCSI HBA target, you can use the New-IScsiHbaTarget cmdlet. The syntax for the New-IScsiHbaTarget cmdlet is as follows:

```
New-IScsiHbaTarget -IScsiHba <IScsiHba[] > [-Address] <String[] >
[[-Port] <Int32>] [-Type <IScsiHbaTargetType>] [[-IScsiName]
<String>] [-ChapType <ChapType>] [-ChapName <String>] [-ChapPassword
<String>] [-MutualChapEnabled [<Boolean>]] [-MutualChapName <String>]
[-MutualChapPassword <String>] [-InheritChap [<Boolean>]]
[-InheritMutualChap [<Boolean>]] [-Server <VIServer[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

The -IScsiHba and -Address parameters are required.

After creating the iSCSI HBA target, we have to rescan the HBAs. The iSCSI HBA has to be bound to a VMkernel port group. In the following script, we will create a dedicated switch and VMkernel port group for iSCSI. There are no cmdlets to bind an iSCSI HBA to a VMkernel port group, so we have to fall back to the vSphere API's IscsiManager BindVnic() method.

After the binding, we have an iSCSI LUN that we can use to create a datastore. The following script performs all of the necessary steps. The script first defines the variables we use, and then it retrieves the VMHost object of the host on which the iSCSI datastore will be created. Software iSCSI will be enabled on this host. Then, an iSCSI target will be created and a rescan of the HBAs will be performed on the host. A new virtual switch and a VMkernel port group will be created. The VMkernel port group will be bound to the iSCSI HBA. Finally, the new iSCSI datastore will be created.

```
# Define the variables
$HostName = '192.168.0.133'
$iSCSITarget = '192.168.0.135'
```

```
$VirtualSwitchName = 'vSwitch2'
$NicName = 'vmnic3'
$PortGroupName = 'iSCSI Port group 1'
$ChapType = 'Preferred'
$ChapUser = 'Cluster01User'
$ChapPassword = 'Cluster01Password'
$DatastoreName = 'Cluster01 iSCSI01'
# Retrieve the host to add the iSCSI datastore to
$VMHost = Get-VMHost -Name $HostName
# Enable software iSCSI support on the host
$VMHost | Get-VMHostStorage | Set-VMHostStorage
-SoftwareIScsiEnabled:$true
# Create an iSCSI target
$VMHostHba = $VMHost | Get-VMHostHba -Type iSCSI
$VMHostHba
New-IScsiHbaTarget -Address $iSCSITarget -ChapType $ChapType -ChapName
$ChapUser -ChapPassword $ChapPassword
# Rescan all HBAs
$VMHost | Get-VMHostStorage -RescanAllHba
# Create a new virtual switch and a vmkernel port group
$vSwitch = New-VirtualSwitch -VMHost $VMHost -Name $VirtualSwitchName
-Nic $NicName
$NetworkAdapter = New-VMHostNetworkAdapter -VirtualSwitch $vSwitch
-PortGroup $PortGroupName
# Bind the vmkernel port group to the iSCSI HBA
$IscsiManager = Get-View -Id $vmhost.ExtensionData.Configmanager.
IscsiManager
$IscsiManager.BindVnic($VMHostHba.Device, $NetworkAdapter.Name)
# Create the iSCSI datastore
$ScsiLun = $VMHost |
Get-ScsiLun
Where-Object {$_.RuntimeName -like "$($VMHostHba.Device)*"}
New-Datastore -Vmfs -VMHost $VMHost -Name $DatastoreName -Path
$ScsiLun.CanonicalName
```

Retrieving datastores

You can use the Get-Datastore cmdlet to retrieve a specific datastore or a list of all of your datastores. The syntax of the Get-Datastore cmdlet is as follows:

```
Get-Datastore [-Server <VIServer[]>] [[-Name] <String[]>]
[-Location <VIObject[]>] [-RelatedObject
<DatastoreRelatedObjectBase[]>] [-Refresh] [-Tag <Tag[]>]
[<CommonParameters>]

Get-Datastore [-Server <VIServer[]>] -Id <String[]> [-Refresh]
[<CommonParameters>]
```

The -Id parameter is required.

In the next example, we will retrieve the datastore with the name Cluster01_Vmfs01:

PowerCLI C:\> Get-Datastore -Name Cluster01 Vmfs01

The following is the output of the preceding command:

Name	${ t FreeSpaceGB}$	CapacityGB
Cluster01 Vmfs01	248,801	249,750

Setting the multipathing policy

If you use Fibre Channel or iSCSI storage devices, the use of multipathing and having multiple paths between your hosts and the SAN are highly recommended. Depending on the recommendations made by your storage vendor, you have to set the multipathing policy to either **Fixed**, **Most Recently Used (MRU)**, or **Round Robin (RR)**.



More information about multipathing policies can be found in the VMware Knowledge Base article *Multipathing policies in ESXi 5.x and ESXi/ESX 4.x (1011340)*, at http://kb.vmware.com/kb/1011340.

You can use the Get-ScsiLun cmdlet to retrieve the current multipathing policy for your LUNs as follows:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-ScsiLun |
>> Where-Object {$ .LunType -eq 'disk'} |
```

```
>> Select-Object -Property CanonicalName,LunType,MultipathPolicy
>>
```

The following is the output of the preceding command:

CanonicalName	LunType	${ t MultipathPolicy}$
naa.600a0b80001111550000f35b93e19350	disk	${\tt MostRecentlyUsed}$
naa.600a0b80001111550000a8adc7e19350	disk	${\tt MostRecentlyUsed}$
naa.600a0b80001111550000893247e29350	disk	${\tt MostRecentlyUsed}$
naa.600a0b80001111550000b6182ca14450	disk	${\tt MostRecentlyUsed}$
naa.600a0b80001111550000d2c418e29350	disk	MostRecentlyUsed

If you want to modify the multipathing policy, you can use the Set-ScsiLun cmdlet's -MultipathPolicy parameter to do so. The syntax of the Set-ScsiLun cmdlet is as follows:

```
Set-ScsiLun [[-MultipathPolicy] <ScsiLunMultipathPolicy>]
[[-PreferredPath] <ScsiLunPath>] [-ScsiLun] <ScsiLun[]>
[-CommandsToSwitchPath <Int32>] [-BlocksToSwitchath <Int32>]
[-NoCommandsSwitch] [-NoBlocksSwitch] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -ScsiLun parameter is required. The -MultipathPolicy parameter has four valid parameter values: Fixed, RoundRobin, MostRecentlyUsed, and Unknown.

In the next example, we will set the multipathing policy for all of the disk LUNs of the host 192.168.0.133 to RoundRobin:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-ScsiLun |
>> Where-Object {$_.LunType -eq 'disk'} |
>> Set-ScsiLun -MultipathPolicy RoundRobin |
>> Select-Object -Property CanonicalName, LunType, MultipathPolicy
>>
```

The following is the output of the preceding command:

CanonicalName	LunType	${\tt MultipathPolicy}$
naa.600a0b80001111550000f35b93e19350	disk	RoundRobin
naa.600a0b80001111550000a8adc7e19350	disk	RoundRobin
naa.600a0b80001111550000893247e29350	disk	RoundRobin
naa.600a0b80001111550000b6182ca14450	disk	RoundRobin
naa.600a0b80001111550000d2c418e29350	disk	RoundRobin

Configuring the vmhba paths to a SCSI device

For each vmhba path to a storage device, you can indicate that the path is active or not active. You can also indicate that the path is the preferred path to the SCSI device.

Retrieving the vmhba paths to a SCSI device

You can use the Get-ScsiLunPath cmdlet to retrieve the list of vmhba paths to a specified SCSI device. The syntax of the Get-ScsiLunPath cmdlet is as follows:

```
Get-ScsiLunPath [[-Name] <String[]>] [-ScsiLun] <ScsiLun[]>
[<CommonParameters>]
```

The -ScsiLun parameter is required, and it accepts input from the pipeline.

In the next example, we will retrieve the vmhba paths of the LUN with CanonicalName naa.600a0b80001111550000f35b93e19350 from the host 192.168.0.133:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-ScsiLun |
>> Where-Object {$_.CanonicalName -eq 'naa.600a0b80001111550000f35b9
3e19350'} |
>> Get-ScsiLunPath
>>
```

The following is the output of the preceding command:

Name	SanID	State	Preferred
fc.5001	50:01:43:81:09:CF:CD:40	Standby	False
fc.5001	50:01:43:81:09:CF:CD:24	Active	False
fc.5001	50:01:43:81:09:CF:CD:44	Standby	False
fc.5001	50:01:43:81:09:CF:CD:20	Standby	False

Modifying the vmhba paths to a SCSI device

You can use the Set-ScsiLunPath cmdlet to enable or disable a vmhba path and to set the preferred path. The syntax of the Set-ScsiLunPath cmdlet is as follows:

```
Set-ScsiLunPath [[-Active] [<Boolean>]] [-ScsiLunPath]
<ScsiLunPath[]> [-Preferred] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -ScsiLunPath parameter is required.

In the following example, we will set the vmhba path with SanId 50:01:43:81:09:CF:CD:40 to Active and Preferred:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-ScsiLun |
>> Where-Object {$_.CanonicalName -eq
'naa.600a0b80001111550000f35b93e19350'} |
>> Get-ScsiLunPath |
>> Where-Object {$_.SanId -eq '50:01:43:81:09:CF:CD:40'} |
>> Set-ScsiLunPath -Active:$true -Preferred
>>
```

The following is the output of the preceding command:

```
        Name
        SanID
        State
        Preferred

        ----
        -----
        ------

        fc.5001...
        50:01:43:81:09:CF:CD:40
        Active
        True
```

If you give the -Active parameter the value \$false, you will disable the vmhba path. This is done using the following command line:

Working with Raw Device Mappings

A **Raw Device Mapping (RDM)** is a storage device that is presented directly to a virtual machine. RDMs are available in two compatibility modes: physical and virtual. The most important difference is that the virtual compatibility mode RDMs can be a part of a VMware vSphere snapshot. Snapshots of a physical compatibility-mode RDM can only be taken on the storage array.

There are some use cases for RDMs. The most common use case is the quorum disk in a Microsoft Windows cluster. A quorum disk must be in the physical compatibility mode.



For more information about using Microsoft Windows Clusters on VMware vSphere, you should read the Setup for Failover Clustering and Microsoft Cluster Service guide. You can find this guide on https://www.vmware.com/support/pubs/. VMware Knowledge Base article Microsoft Clustering on VMware vSphere: Guidelines for supported configurations (1037959) can be found at http://kb.vmware.com/kb/1037959.

To add a RDM to a virtual machine, you can use the New-Harddisk cmdlet. You have already seen the syntax of this cmdlet in *Chapter 5, Managing Virtual Machines with PowerCLI*. The value of the -DiskType parameter specifies what type of disk it will be. The valid values are rawVirtual, rawPhysical, flat, and unknown.

You also need to specify a value for the New-Harddisk -DeviceName parameter. You can retrieve the device name from the LUN number by using the Get-ScsiLun cmdlet. In the next example, we will retrieve all of the LUNs of the host 192.168.0.133 and display the RuntimeName and ConsoleDeviceName properties:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 | Get-ScsiLun |
>> Select-Object -Property RuntimeName, ConsoleDeviceName
>>
```

The following is the output of the preceding command:

```
RuntimeName ConsoleDeviceName

-----
vmhba0:C0:T0:L0 /vmfs/devices/genscsi/naa.5001438109cfcd00
vmhba0:C0:T0:L1
/vmfs/devices/disks/naa.600a0b80001111550000b6182ca14450
vmhba0:C0:T0:L2
/vmfs/devices/disks/naa.600a0b80001111550000f35b93e19350
vmhba0:C0:T0:L3
/vmfs/devices/disks/naa.600a0b80001111550000a8adc7e19350
vmhba0:C0:T0:L4
/vmfs/devices/disks/naa.600a0b80001111550000893247e29350
vmhba0:C0:T0:L5
/vmfs/devices/disks/naa.600a0b80001111550000d2c418e29350
```

In the following example, we will add a physical RDM to virtual machine VM1. If the LUN number of the RDM is 4, the device name is /vmfs/devices/disks/naa.600a 0b80001111550000893247e29350:

PowerCLI C:\> New-HardDisk -VM VM1 -DiskType RawPhysical -DeviceName /vmfs/devices/disks/naa.600a0b80001111550000893247e29350

The following is the output of the preceding command:

```
CapacityGB Persistence
                                Filename
500.000
          IndependentPersis... [Cluster01 Vmfs01] VM1/VM1 1.vmdk
```

Configuring Storage I/O Control

Storage I/O Control (SIOC) is a feature of VMware vSphere Enterprise Plus that provides I/O prioritization of virtual machines running on a group of VMware vSphere hosts that have access to the same datastore. If the latencies of a datastore come above a certain threshold, Storage I/O Control will throttle the I/O bandwidth of the virtual machines that use this datastore (according to their respective share value). The default value for the latency threshold is 30 milliseconds. You should keep this default value unless you have a good reason to change it. One good reason can be the use of SSDs, where a latency threshold of 10 - 15 milliseconds is recommended.

You can enable or disable Storage I/O Control using the

[-Confirm] [<CommonParameters>]

-StorageIOControlEnabled parameter of the Set-Datastore cmdlet. You can also specify a value for the threshold with the -CongestionThresholdMillisecond parameter. The syntax of the Set-datastore cmdlet is as follows:

```
Set-Datastore [-Datastore] <Datastore[]> [[-Name] <String>]
[-CongestionThresholdMillisecond <Int32>] [-StorageIOControlEnabled
[<Boolean>]] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
Set-Datastore [-Datastore] <Datastore[]> -MaintenanceMode [<Boolean>]
[-EvacuateAutomatically] [-RunAsync] [-Server <VIServer[]>] [-WhatIf]
```

The -Datastore and -MaintenanceMode parameters are required. The first parameter set is for updating the datastore. The second parameter set is for

- [238] -

In the next example, we will enable Storage I/O Control for the datastore Cluster01 Vmfs01:

```
PowerCLI C:\> Set-Datastore -Datastore Cluster01_Vmfs01
-StorageIOControlEnabled:$true
```

The following is the output of the preceding command:

Name	FreeSpaceGB	CapacityGB
Cluster01 Vmfs01	44.706	99.750

If you want to enable Storage I/O Control for all of your datastores that don't have Storage I/O Control enabled yet, you can use the following command:

```
PowerCLI C:\> Get-Datastore |
>> Where-Object {-not $_.StorageIOControlEnabled} |
>> Set-Datastore -StorageIOControlEnabled:$true
>>
```

To disable Storage I/O Control for the datastore Cluster01_Vmfs01, we have to give the value \$false to the -StorageIOControlEnabled parameter:

```
PowerCLI C:\> Set-Datastore -Datastore Cluster01_Vmfs01
-StorageIOControlEnabled:$false
```

Name	FreeSpaceGB	CapacityGB
Cluster01 Vmfs01	44.706	99.750

Retrieving Storage I/O Control settings

StorageIOControlEnabled and CongestionThresholdMillisecond are properties of the NasDatastoreImpl and VmfsDatastoreImpl objects that are returned by the Get-Datastore cmdlet. It is easy to retrieve these properties by piping the output of the Get-Datastore cmdlet to the Select-Object cmdlet:

```
PowerCLI C:\> Get-Datastore |
>> Select-Object -Property Name,StorageIOControlEnabled,
>> CongestionThresholdMillisecond
>>
```

The following is the output of the preceding command:

Name	${\tt StorageIOControlEnabled}$	${\tt CongestionThresholdMillisec}$
Cluster01_Nfs01	False	30
Cluster01 Vmfs01	True	30

Configuring Storage DRS

vSphere Storage Distributed Resource Scheduler (Storage DRS) is a vSphere feature first introduced in vSphere 5.0. It gives you the possibility to combine datastores in a Datastore Cluster. You can then manage the Datastore Cluster instead of the individual datastores. When you create a new virtual machine and put the disks on a Datastore Cluster, Storage DRS will place the disks on the optimal datastore based on utilized disk space and datastore performance. Storage DRS can also migrate disks to another datastore in the same Datastore Cluster when the utilized disk space or latency of a datastore becomes too high. You can also make Affinity Rules to separate disks and virtual machines over multiple datastores or keep them together on the same datastore. If you put a datastore in Datastore Maintenance Mode, Storage DRS will move all of the disks on this datastore to other datastores in the same Datastore Cluster.

The first thing that you have to do, if you want to use Storage DRS, is to create one or more datastore clusters. If you have multiple types of datastores, such as gold, silver, and bronze, you might want to create a Datastore Cluster for each type.

Creating a Datastore Cluster

You can create a Datastore Cluster with the New-DatastoreCluster cmdlet, which has the following syntax:

```
New-DatastoreCluster [-Name] <String> -Location <VIContainer>
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The New-DatastoreCluster cmdlet has two required parameters: -Name and -Location. The value of the -Location parameter must be a datacenter or a folder. The following command will create a new Datastore Cluster named Gold-Datastore-Cluster in datacenter New York:

PowerCLI C:\> New-DatastoreCluster -Name Gold-Datastore-Cluster
-Location (Get-Datacenter -Name 'New York')

The following is the output of the preceding command:

Name	CapacityGB	FreeSpaceGB	SdrsAutomationLevel
Gold-Datastore-Cluster	0.000	0.000	Disabled

Retrieving Datastore Clusters

The Get-DatastoreCluster cmdlet will retrieve all of your Datastore Clusters or one or more specific Datastore Clusters. The syntax of the Get-DatastoreCluster cmdlet is as follows:

```
Get-DatastoreCluster [-Id <String[]>] [[-Name] <String[]>]
[-Location <VIContainer[]>] [-VM <VirtualMachine[]>] [-Template
<Template[]>] [-Datastore <Datastore[]>] [-Server <VIServer[]>]
[<CommonParameters>]
```

This cmdlet has no required parameters. If you don't specify a parameter, the New-DatastoreCluster cmdlet will retrieve all of your Datastore Clusters. You can use one of the parameters to retrieve Datastore Clusters based on the ID, name, location, virtual machines, templates, datastores, or vCenter Server. In the next example, we will retrieve all of our Datastore Clusters:

PowerCLI C:\> Get-DatastoreCluster

Name	CapacityGB	FreeSpaceGB	SdrsAutomationLevel
Gold-Datastore-Cluster	0.000	0.000	Disabled

Modifying Datastore Clusters

After creating a Datastore Cluster, Storage DRS is disabled. To enable Storage DRS, you have to use the Set-DatastoreCluster cmdlet. The syntax of this cmdlet is as follows:

```
Set-DatastoreCluster -DatastoreCluster (DatastoreCluster[]>
[-IOLatencyThresholdMillisecond <Int32>] [-IOLoadBalanceEnabled
[<Boolean>]] [-Name <String>] [-SdrsAutomationLevel
<DrsAutomationLevel>] [-SpaceUtilizationThresholdPercent <Int32>]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -DatastoreCluster parameter is required.

To enable Storage DRS, you have to use the <code>-SdrsAutomationLevel</code> parameter. This parameter has three possible values: <code>Disabled</code>, <code>Manual</code>, and <code>FullyAutomated</code>. If you use <code>Manual</code>, Storage DRS will give you recommendations for the placement of disks on the datastores. You will have to apply the recommendations to move the disks. If you choose <code>FullyAutomated</code>, Storage DRS will automatically move disks if the utilized disk space or latency of a datastore becomes too high.


If you want to enable load balancing based on I/O metrics, you have to use the -IOLoadBalanceEnabled parameter and pass it the value \$true.

In the following example, we will enable Storage DRS and set the automation level to FullyAutomated for Gold-Datastore-Cluster. We will also enable load balancing based on I/O metrics:

PowerCLI C:\> Set-DatastoreCluster -DatastoreCluster Gold-Datastore-Cluster -SdrsAutomationLevel FullyAutomated -IOLoadBalanceEnabled:\$true

Name	CapacityGB	FreeSpaceGB	SdrsAutomationLevel
Gold-Datastore-Cluster	0.000	0.000	FullyAutomated

In the next screenshot of the vSphere Web Client, you will see the Datastore Cluster **Gold-Datastore-Cluster** after executing the preceding command:



Adding datastores to a Datastore Cluster

The Move-Datastore cmdlet will move datastores into a Datastore Cluster or to a folder or datacenter. The syntax of the Move-Datastore cmdlet is as follows:


Move-Datastore [-Datastore] <Datastore[] > [-Destination] <VIObject>
[-Server <VIServer[] >] [-WhatIf] [-Confirm] [<CommonParameters>]

The -Datastore and -Destination parameters are required.

In the following example, we will move the Cluster01_Vmfs01 datastore into the Datastore Cluster Gold-Datastore-Cluster:

PowerCLI C:\> Move-Datastore -Datastore Cluster01_Vmfs01 -Destination (Get-DatastoreCluster -Name Gold-Datastore-Cluster)

In the following screenshot of the vSphere Web Client, you will see the datastore Cluster01_Vmfs01 after it is moved into the Datastore Cluster Gold-datastore-Cluster:



Retrieving the datastores in a Datastore Cluster

If you want to know which datastores are in a Datastore Cluster, you can use the Get-Datastore -Location parameter. In the following example, we will retrieve all of the datastores in the Gold-Datastore-Cluster Datastore Cluster:

PowerCLI C:\> Get-Datastore -Location (Get-DatastoreCluster -Name
Gold-Datastore-Cluster)

The following is the output of the preceding command:

Name	FreeSpaceGB	CapacityGB
Cluster01 Vmfs01	44.706	99.750

Removing datastores from a Datastore Cluster

To remove a datastore from a Datastore Cluster, you have to move the datastore to a folder or a datacenter. In the next example, we will move the Cluster01_Vmfs01 datastore from the Gold-Datastore-Cluster Datastore Cluster to the New York datacenter:

PowerCLI C:\> Move-Datastore -Datastore Cluster01_Vmfs01 -Destination
(Get-Datacenter -Name 'New York')

The following is the output of the preceding command:

Name	FreeSpaceGB	CapacityGB
Cluster01 Vmfs01	44.706	99.750

To check if the Cluster_Vmfs01 datastore was really removed from the Datastore Cluster, we can use the Get-Datastore cmdlet again as follows:

```
PowerCLI C:\> Get-Datastore -Location (Get-DatastoreCluster -Name
Gold-Datastore-Cluster)
PowerCLI C:\>
```

The preceding command shows no output, so the Gold-Datastore-Cluster Datastore Cluster no longer contains any datastores.

Removing Datastore Clusters

To remove a Datastore Cluster, you can use the Remove-DatastoreCluster cmdlet. The syntax of this cmdlet is as follows:

```
Remove-DatastoreCluster [-DatastoreCluster] < DatastoreCluster[] >
[-Server < VIServer[] >] [-WhatIf] [-Confirm] [< CommonParameters >]
```

The -DatastoreCluster parameter is required.

In the following example, we will remove the Gold-Datastore-Cluster Datastore Cluster:

```
PowerCLI C:\> Remove-DatastoreCluster
-DatastoreCluster Gold-datastore-Cluster -Confirm:$false
```

Upgrading datastores to VMFS-5

With vSphere 5, VMware upgraded the VMFS filesystem to version 5. VMFS-5 came with the following new features: Unified 1MB File Block Size, Large Single Extent Volumes of 64 TB, Smaller 8 KB Sub-Block, Small File Support, Increased File Count limit > 120,000, VMware vSphere Storage APIs for Array Integration (VAAI), primitive Atomic Test & Set (ATS), enhancement for file locking, GUID Partition Table (GPT), and a new starting sector of 2048.

If you upgraded your vSphere environment from version 4 or earlier to version 5, your datastores are probably still on VMFS-3. There are two options for going to VMFS-5. The first option is to create new VMFS-5 datastores and move your virtual machines to the new datastores. When your old VMFS-3 datastores are empty, you can remove them. The advantage of this method is that the new datastores will have all of the new VMFS-5 features. However, it is a lot of work and you need enough free space on your storage system to create at least one new datastore.

The second option is to upgrade your datastores to VMFS-5. Upgrading your datastores can be done online without downtime for your virtual machines. However, upgraded datastores will not have all of the new features. Upgraded datastores will keep the block size they had before the upgrade, still have the old Sub-Block Size of 64 KB, keep the file limit of 30,720, continue to use the **Master Boot Record (MBR)** partition type, and start on sector 128.

You can retrieve the VMFS version of your datastores with the following command:

```
PowerCLI C:\> Get-Datastore |

>> Where-Object {$_.GetType().Name -eq 'VmfsDatastoreImpl'} |

>> Select-Object -Property Name,FileSystemVersion

>>


The following is the output of the preceding command:

Name FileSystemVersion

----

Cluster01 Vmfs01 5.60
```

In the next screenshot of the vSphere Web Client, you will see the datastore **Cluster01_Vmfs01** with filesystem version **VMFS 3.58** before it is upgraded to VMFS-5:



If you want to upgrade your datastores to VMFS-5, you can use the following PowerCLI script to upgrade all of your datastores. The script uses the <code>Get-Datastore</code> cmdlet to retrieve all of your datastores. Then, it uses the <code>Where-Object</code> cmdlet in the pipeline to filter for VMFS datastores that have a version lower than 5. The <code>ForEach-Object</code> cmdlet is used to process all of the datastores that are found. Then, the script retrieves the <code>HostStorageSystem</code> object of a host connected to the datastore. The <code>UpgradeVmfs()</code> method of this <code>HostStorageSystem</code> object is used to upgrade the datastore. The following script is used to update the datastore:

```
Get-Datastore
Where-Object {$_.GetType().Name -eq 'VmfsDatastoreImpl'
-and $ .FileSystemVersion -lt 5} |
ForEach-Object {
  $Datastore = $_
  # Get the HostStorageSystem of the first host that the
  # datastore is connected to
  # The UpgradeVmfs() method of this object is used to
  # upgrade the datastore
  $HostStorageSystem = $Datastore |
    Get-VMHost | Select-Object -First 1 |
    Get-VMHostStorage | Get-View
  # Construct the path to the volume to upgrade
  # For example:
  # /vmfs/volumes/4e97fa06-7fa61558-937e-984be163eb88
  $Volume = '/' + $Datastore.ExtensionData.Info.Url.TrimStart('ds:/').
TrimEnd('/')
```

```
# Upgrade the datastore
$HostStorageSystem.UpgradeVmfs($Volume)
}
```

Removing datastores

To remove a datastore, you can use the Remove-Datastore cmdlet. The syntax of this cmdlet is as follows:

```
Remove-Datastore [-Datastore] <Datastore[]> [-VMHost] <VMHost>
[-Server <VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The required parameters of the Remove-Datastore cmdlet are -Datastore and -VMHost.

In the next example, we will remove the Cluster01_Vmfs01 datastore, which we created at the beginning of this chapter:

```
PowerCLI C:\> Remove-Datastore -Datastore Cluster01_Vmfs01 -VMHost
192.168.0.133 -Confirm:$false
```

If you try to remove a datastore, it is possible that you get an error message similar to the following error message:

```
Remove-datastore: 1/18/2014 7:37:46 PM Remove-Datastore
The resource '51ceb90c-6cb03821-3504-ac162daa6ca0' is in use.
```

Before you can remove a datastore, there are some requirements that must be fulfilled:

- There must be no virtual machines residing on the datastore
- The datastore must not be part of a Datastore Cluster
- The datastore must not be managed by Storage DRS
- Storage I/O Control must be disabled for the datastore
- The datastore must not be used for vSphere HA heartbeat

After fulfilling all of these requirements, you will not get the The resource is in use error anymore when you remove a datastore.

We have not discussed the use of datastores for vSphere HA heartbeat yet. We will do this in *Chapter 8, Managing High Availability and Clustering with PowerCLI*.

Summary

In this chapter, we covered how to manage storage. We showed you how to create and remove datastores, configure software iSCSI initiators, work with RDMs, configure Storage I/O Control, create and remove Datastore Clusters, add datastores to a datastore cluster, and upgrade your datastores to VMFS-5.

In the next chapter, you will learn all about managing High Availability and clustering with PowerCLI.

8

Managing High Availability and Clustering with PowerCLI

Availability of the applications running in your environment is an important advantage of virtualization. In the case of a host or operating system failure, VMware vSphere **High Availability** (**HA**) will restart the affected virtual machines. This ensures that your servers are available as much as possible.

VMware vSphere **Distributed Resources Scheduler** (**DRS**) provides initial placement of a virtual machine on an appropriate host during power on, automated load balancing to maximize performance, and distribution of virtual machines across hosts to comply with affinity and anti-affinity rules.

To save power and money, **Distributed Power Management** (**DPM**) will consolidate your virtual machines on fewer hosts in your cluster and power down the unused hosts when not all of the resources are needed.

To use DRS or DPM, you need a VMware vSphere Enterprise or Enterprise Plus license.

The topics that will be covered in this chapter are:

- Creating vSphere HA and DRS clusters
- Retrieving clusters
- Modifying cluster settings
- Moving hosts to clusters
- Moving clusters
- Using DRS rules

- Using DRS recommendations
- Using resource pools
- Using Distributed Power Management (DPM)
- Removing clusters

Creating vSphere HA and DRS clusters

In Chapter 4, Managing vSphere Hosts with PowerCLI, you already saw how to create a vSphere cluster with the default settings using the New-Cluster cmdlet. In the default settings, HA and DRS are disabled. You will now see how to create a cluster with HA and DRS enabled. First, the syntax of the New-Cluster cmdlet will be repeated so you don't have to look back at Chapter 4, Managing vSphere Hosts with PowerCLI:

```
New-Cluster [-HARestartPriority <HARestartPriority>]
[-HAIsolationResponse <HAIsolationResponse>] [-VMSwapfilePolicy
<VMSwapfilePolicy>] [-Name] <String> -Location <VIContainer> [-HAEnabled]
[-HAAdmissionControlEnabled] [-HAFailoverLevel <Int32>] [-DrsEnabled]
[-DrsMode <DrsMode>] [-DrsAutomationLevel <DrsAutomationLevel>]
[-VsanDiskClaimMode <VsanDiskClaimMode>] [-VsanEnabled] [-Server
<VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Name and -Location parameters are required.

In the next example, an HA- and DRS-enabled cluster named Cluster02 will be created in the New York datacenter. The new cluster will have the DRS migration automation level as "fully automated". The HA admission control will be enabled and the cluster will have a configured failover capacity of one host. The VM restart priority will be high and the host isolation response will be "leave powered on". The swap file location for virtual machines will be the virtual machine directory.

Because you will use almost every parameter of the New-Cluster cmdlet, you will use splatting to create a hash table with all of the parameters and their values. Splatting was explained in *Chapter 6, Managing Virtual Networks with PowerCLI*, so I hope you still remember this great PowerShell feature. It makes your code more readable because you don't have to create a single long command. Consider the following command lines:

```
PowerCLI C:\> $Parameters = @{
>> Name = 'Cluster02'
>> Location = (Get-Datacenter -Name 'New York')
>> DrsEnabled = $true
>> DrsAutomationLevel = 'FullyAutomated'
>> HAEnabled = $true
>> HAAdmissionControlEnabled = $true
```

In the next image, you will see a screenshot from the vSphere Web Client showing the HA and DRS settings of Cluster02 after running the preceding PowerCLI commands to create the cluster:



Retrieving clusters

To retrieve one or more of the clusters available on your vCenter Server system, you can use the Get-Cluster cmdlet. The syntax of the Get-Cluster cmdlet is:

```
Get-Cluster [-VM <VirtualMachine[]>] [-VMHost <VMHost[]>] [-Location
<VIContainer[]>] [[-Name] <String[]>] [-NoRecursion] [-Server
<VIServer[]>] [<CommonParameters>]
Get-Cluster -Id <String[]> [-Server <VIServer[]>] [<CommonParameters>]
```

The -Location parameter enables you to filter for clusters in a specific location such as a datacenter or folder. The -Name, -Id, -VM, and -VMHost parameters specify filters that you can use to retrieve clusters with a specific name or ID, or clusters containing the specified virtual machines or hosts.

In the first example, you will retrieve the cluster named Cluster02 that you created in the preceding section of this chapter.

PowerCLI C:\> Get-Cluster -Name Cluster02

Name	HAEnabled	HAFailover	${\tt DrsEnabled}$	${\tt DrsAutomationLevel}$
			Level	
Cluster02	True	1	True	FullyAutomated

In the second example, you will retrieve the cluster on which virtual machine VM1 runs:

```
PowerCLI C:\> Get-Cluster -VM VM1
```

Name	HAEnabled	HAFailover	$ exttt{HAFailover}$ $ exttt{DrsEnabled}$ $ exttt{DrsAutomationLe}$		
			Level		
Cluster01	True	1	False	FullyAutomated	

Retrieving the HA master or primary hosts

In a vSphere HA cluster, one of the hosts is the master host and all other hosts are slave hosts. The master host monitors the state of the slave hosts and the power state of all the protected virtual machines, manages the lists of cluster hosts and protected virtual machines, acts as a vCenter Server management interface to the cluster, and reports the cluster health state.

The Get-HAPrimaryVMHost cmdlet will retrieve the master host on a vCenter 5.0 or later HA cluster and will retrieve the primary HA hosts on an earlier than vCenter 5.0 cluster. The syntax of the Get-HAPrimaryVMHost cmdlet is:

```
Get-HAPrimaryVMHost [[-Cluster] <Cluster[]>] [-Server <VIServer[]>]
[<CommonParameters>]
```


In the example, the master host on the cluster Cluster01 is retrieved using the following command lines:

PowerCLI C:\> Get-Cluster -Name Cluster01 | Get-HAPrimaryVMHost

Name	${\tt ConnectionState}$	PowerState	${\tt NumCpu}$	${\tt CpuUsageMhz}$
192.168.0.133	Connected	PoweredOn	2	69

Retrieving cluster configuration issues

If your cluster is incorrectly configured, the vSphere Web Client will show you the issues in the **Summary** tab. In the next screenshot of the vSphere Web Client, you will see two cluster configuration issues: **Insufficient capacity in cluster Cluster01** to satisfy resource configuration in New York and vCenter Server is unable to find a master vSphere HA agent in cluster Cluster01 in New York:



You can easily find any cluster configuration issues with PowerCLI. The next PowerCLI script displays the cluster name, creation time, and the full formatted message of all of the cluster configuration issues in your environment.

The script uses the Get-Cluster cmdlet to retrieve all of the clusters. It pipes the output to the Get-View cmdlet to return the vSphere View objects of the clusters. The vSphere View objects are piped to the Select-Object cmdlet to expand the ConfigIssue property. Another Select-Object cmdlet is used in the pipeline to retrieve the cluster name using a calculated property, the creation time, and the full formatted message. Finally, the output is piped to Format-Table -AutoSize to display it in a compact table format:

Modifying cluster settings

To modify the settings of a cluster, you can use the Set-Cluster cmdlet. This cmdlet has basically the same parameters as the New-Cluster cmdlet with the addition of the -Profile parameter that enables you to associate a host profile with a cluster. The syntax of the Set-Cluster cmdlet is:

```
Set-Cluster [-HARestartPriority <HARestartPriority>]
[-HAIsolationResponse <HAIsolationResponse>] [-VMSwapfilePolicy
<VMSwapfilePolicy>] [-Cluster] <Cluster[]> [[-Name] <String>]
[-HAEnabled [<Boolean>]] [-HAAdmissionControlEnabled [<Boolean>]]
[-HAFailoverLevel <Int32>] [-DrsEnabled [<Boolean>]] [-DrsMode
<DrsMode>] [-DrsAutomationLevel <DrsAutomationLevel>] [-VsanEnabled
[<Boolean>]] [-VsanDiskClaimMode <VsanDiskClaimMode>] [-Profile
<VMHostProfile>] [-Server <VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

Disabling HA

The next example will disable HA for Cluster02. This might be useful when you perform network maintenance that may cause isolation responses.

PowerCLI C:\> Get-Cluster -Name Cluster02 | Set-Cluster -HAEnabled \$false -Confirm:\$false

Name	HAEnabled	HAFailover DrsEnabled DrsAutomationLevel			
			Level		
Cluster02	False	1	True	FullyAutomated	

Disabling or enabling host monitoring

To disable host monitoring, you have to use the vSphere API. The next script will disable host monitoring for Cluster02. In the script, a ClusterConfigSpecEx object is created. Also, a ClusterDasConfigInfo object for the dasConfig property of the ClusterConfigSpecEx object is created. The hostMonitoring property of the ClusterDasConfigInfo object is set to disabled. Finally, the ReconfigureComputeResource_Task() method is called using the ClusterConfigSpecEx object as the first parameter.

The second parameter of the ReconfigureComputeResource_Task() method is named modify. If the value of the modify parameter is set to \$true, the changes specified in the ClusterConfigSpecEx object will be applied incrementally to the cluster object. If the value of the modify parameter is \$false, the configuration of the cluster will match the specification exactly. In this case, any unset properties of the specification will result in unset or default properties of the configuration of the cluster.

The $ReconfigureComputeResource_Task()$ method creates a vSphere task and runs asynchronously:

```
# Disabling host monitoring
$Cluster = Get-Cluster -Name Cluster02
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.dasConfig = New-Object VMware.Vim.ClusterDasConfigInfo
$spec.dasConfig.hostMonitoring = "disabled"
$Cluster.ExtensionData.ReconfigureComputeResource_Task($spec, $true)
```

If you want to enable host monitoring, you have to modify "disabled" in line 5 of the preceding script to "enabled".

Associating a host profile with a cluster

In Chapter 4, Managing vSphere Hosts with PowerCLI, you already saw how to attach or associate a host profile to a cluster using the Apply-VMHostProfile cmdlet. The next example will show you how to associate a host profile to a cluster using the Set-Cluster cmdlet:

PowerCLI C:\> Set-Cluster -Cluster Cluster02 -Profile Cluster-Profile -Confirm:\$false

If you want to remove the association, you can use \$null as the value for the -Profile parameter.

Enabling VM and application monitoring


VM and application monitoring will restart a virtual machine if VMware Tools' heartbeats are not received for a specific time frame. This time frame, called the failureInterval, is configurable. You can also specify the minimum time the virtual machine must be up, called minUpTime, the maximum number of times, called maxFailures, and a virtual machine will be restarted in a certain time window, called maxFailureWindow. In the vSphere client, there are three predefined settings to monitor sensitivity called low, medium, and high.

The preset values for the low, medium, and high monitoring sensitivities are:

Monitoring Sensitivity	Low	Medium	High
failureInterval	120	60	30
minUpTime	480	240	120
maxFailures	3	3	3
maxFailureWindow	604800	86400	3600

Of course, you can use your own custom values. If you don't want to use **Maximum** resets time window, you have to use the value -1 for the maxFailureWindow property.

In the next screenshot of the vSphere Web Client, you will see the VM Monitoring settings of a cluster with **VM and Application Monitoring** enabled and **Monitoring Sensitivity** set to **High**.



You cannot use the Set-Cluster cmdlet to enable or disable VM and application monitoring. You have to use the vSphere API again to do this. In the next script, you will create the ClusterConfigSpecEx and ClusterDasConfigInfo objects as you have seen before. The vmMonitoring property of the ClusterDasConfigInfo object will get the value vmAndAppMonitoring. You will also create a ClusterDasVmSettings object as the value of the defaultVmSettings property of the ClusterDasConfigInfo object. A ClusterVmToolsMonitoringSettings object is created as the value of the vmToolsMonitoringSettings property of the ClusterDasVmSettings object. The properties of the ClusterVmToolsMonitoringSettings object will get a value that corresponds with the medium monitoring sensitivity. Finally, the ReconfigureComputeResource Task() method is called to reconfigure the cluster.

```
# Enabling VM and application monitoring
$Cluster = Get-Cluster -Name Cluster02
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
```

```
$spec.dasConfig = New-Object VMware.Vim.ClusterDasConfigInfo
$spec.dasConfig.vmMonitoring = "vmAndAppMonitoring"
$spec.dasConfig.defaultVmSettings = New-Object VMware.Vim.
ClusterDasVmSettings
$spec.dasConfig.defaultVmSettings.vmToolsMonitoringSettings = New-
Object VMware.Vim.ClusterVmToolsMonitoringSettings
$spec.dasConfig.defaultVmSettings.vmToolsMonitoringSettings.enabled =
$spec.dasConfiq.defaultVmSettings.vmToolsMonitoringSettings.
vmMonitoring = "vmAndAppMonitoring"
$spec.dasConfig.defaultVmSettings.vmToolsMonitoringSettings.
failureInterval = 60
$spec.dasConfig.defaultVmSettings.vmToolsMonitoringSettings.minUpTime
$spec.dasConfig.defaultVmSettings.vmToolsMonitoringSettings.
maxFailures = 3
$spec.dasConfig.defaultVmSettings.vmToolsMonitoringSettings.
maxFailureWindow = 86400
$Cluster.ExtensionData.ReconfigureComputeResource_Task($spec, $true)
```

The possible values for the vmMonitoring property are vmMonitoringDisabled (the default value), vmMonitoringOnly, or vmAndAppMonitoring.

Configuring the heartbeat datastore selection policy

Datastore heartbeating is a vSphere HA feature introduced in vSphere 5.0. In the case of a lost network connection between the HA master and the slaves, datastore heartbeating is used to validate whether a host has failed or just the network between the hosts is lost. If the master concludes that a slave host has failed because there are no datastore heartbeats, the virtual machines of the failed host will be restarted on other hosts in the cluster. If a host still has datastore heartbeats, the master concludes that the slave is **isolated** or **partitioned**. Depending on the configured host isolation response for the cluster, the virtual machines on the isolated host will be left powered on, shut down, or powered off.

vCenter Server selects two datastores per host for datastore heartbeating, according to the datastore heartbeating policy defined for the cluster. The policy can be one of the following: automatically select datastores accessible from the host, use datastores only from the specified list, or use datastores from the specified list and complement automatically if needed.

In the next table, you will see the three datastore heartbeating policies and the possible values for the HBDatastoreCandidatePolicy property used by the vSphere API:

HBDatastoreCandidatePolicy	Description
allFeasibleDs	Automatically select datastores accessible from the host
userSelectedDs	Use datastores only from the specified list
allFeasibleDsWithUserPreference	Use datastores from the specified list and complement automatically if needed

In the first example, you will retrieve the datastore heartbeating policy for Cluster01:

```
PowerCLI C:\> $Cluster = Get-Cluster -Name Cluster01
PowerCLI C:\> $Cluster.ExtensionData.Configuration.DasConfig.
HBDatastoreCandidatePolicy
allFeasibleDsWithUserPreference
```

In the following example, you will retrieve the datastores used for datastore heartbeating in cluster Cluster01:


```
PowerCLI C:\> $cluster.ExtensionData.RetrieveDasAdvancedRuntimeInfo().
HeartbeatDatastoreInfo |
>> Select-Object -ExpandProperty Datastore |
>> Get-VIObjectByVIView
>>
```

There are no PowerCLI cmdlets to configure datastore heartbeating, so you have to use the vSphere API. In the next example, you will configure the "automatically select datastores accessible from the host" datastore heartbeating policy for cluster ClusterOl. First, you create the ClusterConfigSpecEx and ClusterDasConfigInfo objects as a value of the dasConfig property of the ClusterConfigSpecEx object. Then, you give the hBDatastoreCandidatePolicy property of the ClusterDasConfigInfo object the allFeasibleDs value. Finally, you call the ReconfigureComputeResource Task() method to reconfigure the cluster.

```
# Automatically select datastores accessible from the host
# for datastore heartbeating
$Cluster = Get-Cluster -Name Cluster01
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.dasConfig = New-Object VMware.Vim.ClusterDasConfigInfo
```

```
$spec.dasConfig.hBDatastoreCandidatePolicy = "allFeasibleDs"
$Cluster.ExtensionData.ReconfigureComputeResource_Task($spec, $true)
```

The next screenshot of the vSphere Web Client will show you the **Datastore Heartbeating** settings of Cluster01 set to **Automatically select datastores accessible from the host** after running the preceding PowerCLI commands:



In the next example, you will configure the "use datastores only from the specified list" datastore heartbeating policy for ClusterO1. The new thing in this example is that you have to specify the Managed Object References of the datastores that you selected for the datastore heartbeating. Therefore, an array of two ManagedObjectReference objects is specified as the value of the heartbeatDatastore property of the ClusterDasConfigInfo object. The array is filled with the MoRefs of the selected datastores. The hbDatastoreCandidatePolicy property of the ClusterDasConfigInfo object is given the userSelectedDs value. Finally, the ReconfigureComputeResource_Task() method is called to reconfigure the cluster.

```
# Use datastores only from the specified list
# for datastore heartbeating
$Cluster = Get-Cluster -Name Cluster01
$Datastore1 = Get-Datastore -Name Datastore1
$Datastore2 = Get-Datastore -Name Datastore2
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.dasConfig = New-Object VMware.Vim.ClusterDasConfigInfo
$spec.dasConfig.heartbeatDatastore = New-Object VMware.Vim.
ManagedObjectReference[] (2)
$spec.dasConfig.heartbeatDatastore[0] = New-Object VMware.Vim.
ManagedObjectReference
$spec.dasConfig.heartbeatDatastore[0].type = "Datastore"
```

```
$spec.dasConfig.heartbeatDatastore[0].Value = $Datastore1.
ExtensionData.MoRef.Value
$spec.dasConfig.heartbeatDatastore[1] = New-Object VMware.Vim.
ManagedObjectReference
$spec.dasConfig.heartbeatDatastore[1].type = "Datastore"
$spec.dasConfig.heartbeatDatastore[1].Value = $Datastore2.
ExtensionData.MoRef.Value
$spec.dasConfig.hBDatastoreCandidatePolicy = "userSelectedDs"
$Cluster.ExtensionData.ReconfigureComputeResource Task($spec, $true)
```

In the last example of configuring datastore heartbeating, you will configure the "use datastores from the specified list and complement automatically if needed" datastore heartbeating policy for ClusterO1. The example is almost the same as the preceding example. The difference is that you now give the hBDatastoreCandidatePolicy property of the ClusterDasConfigInfo object the allFeasibleDsWithUserPreference value:

```
# Use datastores from the specified list and complement
# automatically if needed for datastore heartbeating
$Cluster = Get-Cluster -Name Cluster01
$Datastore1 = Get-Datastore -Name Datastore1
$Datastore2 = Get-Datastore -Name Datastore2
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.dasConfig = New-Object VMware.Vim.ClusterDasConfigInfo
$spec.dasConfig.heartbeatDatastore = New-Object VMware.Vim.
ManagedObjectReference[] (2)
$spec.dasConfig.heartbeatDatastore[0] = New-Object VMware.Vim.
ManagedObjectReference
$spec.dasConfig.heartbeatDatastore[0].type = "Datastore"
$spec.dasConfig.heartbeatDatastore[0].Value = $Datastore1.
ExtensionData.MoRef.Value
$spec.dasConfig.heartbeatDatastore[1] = New-Object VMware.Vim.
ManagedObjectReference
$spec.dasConfig.heartbeatDatastore[1].type = "Datastore"
$spec.dasConfiq.heartbeatDatastore[1].Value = $Datastore2.
ExtensionData.MoRef.Value
$spec.dasConfig.hBDatastoreCandidatePolicy =
"allFeasibleDsWithUserPreference"
$Cluster.ExtensionData.ReconfigureComputeResource Task($spec, $true)
```

Moving hosts to clusters

You can use the Move-VMHost cmdlet to move a host to a cluster. The host has to already be added to your vSphere inventory. If it isn't, you can use the Add-VMHost cmdlet to add the host to your inventory, as shown in *Chapter 4*, *Managing vSphere Hosts with PowerCLI*. The host also has to be in maintenance mode or you will get the error message: **The operation is not allowed in the current state**.

The syntax of the Move-VMHost cmdlet is:

```
Move-VMHost [-VMHost] <VMHost[]> [-Destination] <VIContainer> [-Server
<VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VMHost and -Destination parameters are required.

You can also use the Move-VMhost cmdlet to move a host to another VIContainer object such as a datacenter or a folder.

In the next example, you will first put host 192.168.0.134 in maintenance mode, move the host to Cluster02, and finally exit maintenance mode:

192.168.0.134 Maintenance PoweredOn 2

PowerCLI C:\> \$VMHost | Set-VMHost -State Connected

Name	ConnectionState	PowerState	NumCpu	CpuUsageMhz
192.168.0.134	Connected	PoweredOn	2	619

226

Moving clusters

You can use the Move-Cluster cmdlet to move a cluster to a folder. The folder must be in the same datacenter as the cluster. The syntax of the Move-Cluster cmdlet is:

```
Move-Cluster [-Cluster] <Cluster[]> [-Destination] <VIContainer> [-Server
<VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Cluster and -Destination parameters are required.

Besides a folder, you can specify the datacenter to which the cluster belongs as the value of the -Destination parameter. In this case, the cluster is moved to the host system folder of the datacenter. It is not possible to move a cluster to another datacenter.

In the next example, Cluster01 is moved to the Accounting folder:

PowerCLI C:\> Move-Cluster -Cluster Cluster01 -Destination Accounting
Name HAEnabled HAFailover DrsEnabled DrsAutomationLevel

		Level			
Cluster01	True	1	True	FullvAutomated	

Using DRS rules

To control the placement of virtual machines on hosts in a cluster, you can use DRS affinity rules or anti-affinity rules. There are two types of affinity rules:

- VM-VM affinity rules: These rules specify affinity or anti-affinity between
 virtual machines. An affinity rule specifies that DRS should or must keep
 a group of virtual machines together on the same host. A use case of the
 affinity rules can be performance, because virtual machines on the same
 hosts have the fastest network connection possible. An anti-affinity rule
 specifies that DRS should or must keep a group of virtual machines on
 separate hosts. This prevents you from losing all of the virtual machines
 in the group if a host crashes.
- VM-Host affinity rules: These rules specify affinity or anti-affinity between a group of virtual machines and a group of hosts. An affinity rule specifies that the group of virtual machines should or must run on the group of hosts. An anti-affinity rule specifies that the group of virtual machines should or must not run on the group of hosts.

In PowerCLI, there are cmdlets to use VM-VM affinity rules. To use VM-Host affinity rules, you have to, unfortunately, use the vSphere API.

Creating VM-VM DRS rules

To create a VM-VM DRS rule, you can use the New-DrsRule cmdlet that has the following syntax:

```
New-DrsRule [-Name] <String> [-Cluster] <Cluster[]> [-Enabled
[<Boolean>]] -KeepTogether [<Boolean>] -VM <VirtualMachine[]> [-RunAsync]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Name, -Cluster, -KeepTogether, and -VM parameters are required.

If the value of the -KeepTogether parameter is \$true, the new DRS rule is an affinity rule. If the value is \$false, the new DRS rule is an anti-affinity rule.


If the value of the -Enabled parameter is \$true, the new DRS rule is enabled. If the value is \$false, it is disabled.

In the next example, you will create a new, enabled DRS VM-VM affinity rule named Keep VM1 and VM2 together for Cluster01. The DRS rule will keep the two virtual machines VM1 and VM2 together on the same host.

PowerCLI C:\> New-DrsRule -Name 'Keep VM1 and VM2 together' -Cluster Cluster01 -VM VM1,VM2 -KeepTogether:\$true -Enabled:\$true

Name	Enabled	Type	VMIDs
<pre>Keep VM1 and VM2 together VirtualMachine-vm-105}</pre>	True	VMAffinity	$\big\{ \texttt{VirtualMachine-vm-129,}$

In the next screenshot, you will see the window of the vSphere Web Client, which you can use to create a DRS rule filled with the same settings as in the preceding PowerCLI command.



In the second example, you will create a new DRS VM-VM anti-affinity rule named Separate VM3 and VM4 for Cluster01:

PowerCLI C:\> New-DrsRule -Name 'Separate VM3 and VM4' -Cluster Cluster01 -VM VM3,VM4 -KeepTogether:\$false -Enabled:\$true

Name Enabled Type VMIDs
---- ---- ---- ---- Separate VM3 and VM4 True VMAntiAffinity {VirtualMachine-vm-107, VirtualMachine-vm-126}

Creating VM-Host DRS rules

Unfortunately, there are no PowerCLI cmdlets to create a VM-Host affinity rule. You have to use the vSphere API to do this. There are three steps involved in creating a VM-Host affinity rule:

- 1. Creating a virtual machines DRS group
- 2. Creating a host DRS group
- 3. Creating a virtual machines to hosts DRS rules

Creating virtual machines DRS groups

While creating a virtual machines DRS group, you have to add at least one virtual machine to this group. In the next example, you will create a virtual machines DRS group called Cluster01 VMs should run on host 192.168.0.133 for Cluster01 and add virtual machine VM1 to this DRS group.

First you create a ClusterConfigSpecEx object. Then you add an array containing one ClusterGroupSpec object to the GroupSpec property of the ClusterConfigSpecEx object. The operation property of the ClusterGroupSpec object is given the value add. A ClusterVmGroup object is assigned to the info property of the ClusterGroupSpec object. The name of the DRS group is assigned to the name property of the ClusterVmGroup object. The MoRef of the virtual machine that will be added to the DRS group is assigned to the vm property of the ClusterVmGroup object. Finally, the cluster's ReconfigureComputeResource_Task() method is called to reconfigure the cluster and to add the DRS group:

```
# Creating a Virtual Machines DRS Group
$Cluster = Get-Cluster -Name Cluster01
$VM = Get-VM -Name VM1 -Location $Cluster
$DRSGroupName = 'Cluster01 VMs should run on host 192.168.0.133'
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.groupSpec = New-Object VMware.Vim.ClusterGroupSpec[] (1)
$spec.groupSpec[0] = New-Object VMware.Vim.ClusterGroupSpec
$spec.groupSpec[0].operation = 'add'
$spec.groupSpec[0].info = New-Object VMware.Vim.ClusterVmGroup
$spec.groupSpec[0].info.name = $DRSGroupName
$spec.groupSpec[0].info.vm += $VM.ExtensionData.MoRef
$Cluster.ExtensionData.ReconfigureComputeResource_Task($spec, $true)
```

Creating hosts DRS groups

Creating a hosts DRS group is similar to creating a virtual machine DRS group. Instead of adding a ClusterVmGroup object to the info property of the ClusterGroupSpec object, you have to add a ClusterHostGroup object. The host property of ClusterHostGroup will get the MoRef of the host you want to add to the DRS group assigned. You have to add at least one host to a hosts DRS group.

In the following example, you will create a hosts DRS group called Cluster01 192.168.0.133 Hosts DRS Group and you will add host 192.168.0.133 to this group:

```
# Creating a Hosts DRS Group
$Cluster = Get-Cluster -Name Cluster01
$VMHost = Get-VMHost -Name 192.168.0.133 -Location $Cluster
$DRSGroupName = 'Cluster01 192.168.0.133 Hosts DRS Group'
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.groupSpec = New-Object VMware.Vim.ClusterGroupSpec[] (1)
$spec.groupSpec[0] = New-Object VMware.Vim.ClusterGroupSpec
$spec.groupSpec[0].operation = "add"
$spec.groupSpec[0].info = New-Object VMware.Vim.ClusterHostGroup
$spec.groupSpec[0].info.name = $DRSGroupName
$spec.groupSpec[0].info.host += $VMHost.ExtensionData.MoRef
$Cluster.ExtensionData.ReconfigureComputeResource Task($spec, $true)
```

Retrieving DRS groups

There are no cmdlets to retrieve DRS groups. You will have to use the vSphere API. The DRS groups are in the ConfigurationEx.Group property of a vSphere ClusterComputeResource object.

The next example will show you how to retrieve the DRS groups of Cluster01:

```
PowerCLI C:\> Get-Cluster -Name Cluster01 |
>> ForEach-Object { $_.ExtensionData.ConfigurationEx.Group }
>>

Vm : {VirtualMachine-vm-129}

LinkedView :
Name : Cluster01 VMs should run on host 192.168.0.133

UserCreated :
DynamicType :
```

DynamicProperty:

DynamicProperty:

```
Host : {HostSystem-host-109}
LinkedView :
Name : Cluster01 192.168.0.133 Hosts DRS Group
UserCreated :
DynamicType :
```

Modifying DRS groups

If you want to modify a DRS group, the only thing you can do is add or remove virtual machines or hosts to or from the DRS group. There are no PowerCLI cmdlets to do this, so you have to use the vSphere API.

Adding virtual machines to a DRS group

In the first example, you will add virtual machines VM2, VM4, and VM7 to the DRS group Cluster01 VMs should run on host 192.168.0.133. Because the structure of the ClusterConfigSpecEx objects is always the same, I will explain only what is unique in this example. In this case, the operation is edit. The DRS group is assigned to the info property. All of the new group members are added to the info.vm property.

```
# Adding virtual machines to a DRS group
$Cluster = Get-Cluster -Name Cluster01
$GroupName = "Cluster01 VMs should run on host 192.168.0.133"
$VMs = Get-VM -Name VM2, VM4, VM7
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.groupSpec = New-Object VMware.Vim.ClusterGroupSpec[] (1)
$spec.groupSpec[0] = New-Object VMware.Vim.ClusterGroupSpec
$spec.groupSpec[0].operation = "edit"
$spec.groupSpec[0].info = $Cluster.ExtensionData.ConfigurationEx.Group
|
Where-Object {$_.Name -eq $GroupName}}
foreach ($VM in $VMs)
{
$spec.groupSpec[0].info.vm += $VM.ExtensionData.MoRef
}
$Cluster.ExtensionData.ReconfigureComputeResource Task($spec, $true)
```

Removing virtual machines from a DRS group

In the second example about modifying DRS groups, the virtual machines VM4 and VM7 will be removed from DRS group Cluster01 VMs should run on host 192.168.0.133.

This example looks a lot like the preceding one. The difference is that virtual machines are removed from the info.vm property using the Where-Object cmdlet and the -notcontains operator. Only the virtual machines that are not in the list of virtual machines to be removed are assigned to the info.vm property.

```
# Removing virtual machines from a DRS group
$Cluster = Get-Cluster -Name Cluster01
$GroupName = "Cluster01 VMs should run on host 192.168.0.133"
$VMs = Get-VM -Name VM4,VM7
$VMsMorefs = $VMs | ForEach-Object {$ .ExtensionData.MoRef}
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.groupSpec = New-Object VMware.Vim.ClusterGroupSpec[] (1)
$spec.groupSpec[0] = New-Object VMware.Vim.ClusterGroupSpec
$spec.groupSpec[0].operation = "edit"
$spec.groupSpec[0].info = New-Object VMware.Vim.ClusterVmGroup
$spec.groupSpec[0].info.name = $GroupName
$spec.groupSpec[0].info.vm = $Cluster.ExtensionData.ConfigurationEx.
Group
  Where-Object {$ .Name -eq $GroupName} |
  Select-Object -ExpandProperty vm |
  Where-Object {$VMsMorefs -notcontains $ }
$Cluster.ExtensionData.ReconfigureComputeResource Task($spec, $true)
```



Remember that you cannot remove all of the virtual machines or hosts from a DRS group. A DRS group needs at least one group member.

Adding and removing hosts to or from a DRS group is similar to adding or removing virtual machines to or from a DRS group. I leave this to you as an exercise to solve (Hint: use Get-VMHost instead of Get-VM).



More information about the VMware.VIM.* objects used in the preceding examples can be found in the VMware vSphere API reference documentation: http://pubs.vmware.com/vsphere-55/topic/com.vmware.wssdk.apiref.doc/right-pane.html

Removing DRS groups

Removing DRS groups is similar to preceding DRS groups operations. To remove a DRS group, the operation is remove and removeKey is the DRS group's name.

```
# Removing a DRS group
$Cluster = Get-Cluster -Name Cluster01
$GroupName = "Cluster01 VMs should run on host 192.168.0.133"
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.groupSpec = New-Object VMware.Vim.ClusterGroupSpec[] (1)
$spec.groupSpec[0] = New-Object VMware.Vim.ClusterGroupSpec
$spec.groupSpec[0].operation = "remove"
$spec.groupSpec[0].removeKey = $GroupName
$Cluster.ExtensionData.ReconfigureComputeResource Task($spec, $true)
```

Creating virtual machines to hosts DRS rules

Finally, you have to relate the virtual machines DRS group to the hosts DRS group in a virtual machines to hosts DRS rule. There are four possible relations:

- Must run on hosts in group
- Should run on hosts in group
- Must not run on hosts in group
- Should not run on hosts in group

In the example given, you will create a Should run on hosts in group virtual machines to hosts DRS rule to give preference to virtual machine VM1 to run on host 192.168.0.133.

First, a ClusterConfigSpecEx object is created. An array of one ClusterRuleSpec object is assigned to the rulesSpec property of the ClusterConfigSpecEx object. The operation property of rulesSpec is set to add. A ClusterVmHostRuleInfo object is assigned to the info property of rulesSpec. The enabled property of the ClusterVmHostRuleInfo object is set to \$true. The name property is given the name of the DRS rule. Because it is a "should run on hosts in group" DRS rule, the mandatory property is set to \$false. The userCreated property is set to \$true. The vmGroupName and affineHostGroupName properties are assigned the names of the related DRS groups. Finally, the cluster's ReconfigureComputeResource_Task() method is called to create the DRS rule:

```
# Creating a Virtual Machines to Hosts DRS rule
$Cluster = Get-Cluster -Name Cluster01
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
```


```
$spec.rulesSpec = New-Object VMware.Vim.ClusterRuleSpec[] (1)
$spec.rulesSpec[0] = New-Object VMware.Vim.ClusterRuleSpec
$spec.rulesSpec[0].operation = "add"
$spec.rulesSpec[0].info = New-Object VMware.Vim.ClusterVmHostRuleInfo
$spec.rulesSpec[0].info.enabled = $true
$spec.rulesSpec[0].info.name = "Cluster01 VM1 should run on host
192.168.0.133 DRS Rule"
$spec.rulesSpec[0].info.mandatory = $false
$spec.rulesSpec[0].info.userCreated = $true
$spec.rulesSpec[0].info.vmGroupName = "Cluster01 VMs should run on
host 192.168.0.133"
$spec.rulesSpec[0].info.affineHostGroupName = "Cluster01 192.168.0.133
Hosts DRS Group"
$Cluster.ExtensionData.ReconfigureComputeResource_Task($spec, $true)
```

If you want to create a "must run on hosts in group" DRS rule, you only have to change the line <code>\$spec.rulesSpec[0].info.mandatory = \$false</code> in the preceding code to the following:

```
$spec.rulesSpec[0].info.mandatory = $true
```

If you want to create a "must not run on hosts in group" or "should not run on hosts in group" DRS group, you have to assign the DRS hosts group name to \$spec.rulesSpec[0].info.antiAffineHostGroupName instead of \$spec.rulesSpec[0].info.affineHostGroupName.

In the next screenshot of the vSphere Web Client, you will see the virtual machines to hosts DRS rule Cluster01 VM1 should run on host 192.168.0.133 DRS Rule created with the preceding PowerCLI commands:



Retrieving DRS rules

You can use the Get-DrsRule cmdlet to retrieve the DRS rules of the specified clusters. The syntax of this cmdlet is:

```
Get-DrsRule [[-Name] <String[]>] [-Cluster] <Cluster[]> [[-VM]
<VirtualMachine[]>] [-Type <ResourceSchedulingRuleType[]>] [-Server
<VIServer[]>] [<CommonParameters>]
Get-DrsRule [[-Name] <String[]>] [-Cluster] <Cluster[]> [[-VM]
<VirtualMachine[]>] [-VMHost <VMHost[]>] [-Server <VIServer[]>]
[<CommonParameters>]
```

The -Cluster parameter is required. You cannot use the -Type and -VMHost parameters in the same command, because they are in different parameter sets.

If you don't specify the -Type or -Host parameters, you will only retrieve the VM-VM affinity or VM-VM anti-affinity rules:

PowerCLI C:\> Get-DrsRule -Cluster Cluster01

Name	Enabled	Type	VMIDs
<pre>Keep VM1 and VM2 together VirtualMachine-vm-105}</pre>	True	VMAffinity	$\label{eq:continuous} \big\{ \texttt{VirtualMachine-vm-129} ,$
Separate VM3 and VM4 VirtualMachine-vm-126}	True	VMAntiAffinity	{VirtualMachine-vm-107,

If you also want to retrieve the VM-Host DRS rules, you have to specify all of the possible types as a value of the -Type parameter:

PowerCLI C:\> Get-DrsRule -Cluster Cluster01 -Type VMAffinity,VMAntiAffinity,VMHostAffinity

Name	Enabled	Type	VMIDs
<pre>Keep VM1 and VM2 together VirtualMachine-vm-105}</pre>	False	VMAffinity	{VirtualMachine-vm-129,
Keep VMs on Host	True	${\tt VMHostAffinity}$	$\big\{ \texttt{VirtualMachine-vm-129} \big\}$
Seperate VM1 and DC1 VirtualMachine-vm-129}	True	VMAntiAffinity	{VirtualMachine-vm-111,

You can also retrieve all of the DRS rules that involve certain virtual machines using the -VM parameter:

PowerCLI C:\> Get-DrsRule -Cluster Cluster01 -VM VM2

Name	Enabled	Type	VMIDs
<pre>Keep VM1 and VM2 together VirtualMachine-vm-105}</pre>	False	VMAffinity	{VirtualMachine-vm-129,

To retrieve all of the DRS rules that involve specific hosts, use the -VMHost parameter using the following command:

PowerCLI C:\> Get-DrsRule -Cluster Cluster01 -VMHost 192.168.0.133

```
Name Enabled Type VMIDs
---- --- ---- ----
Keep VMs on Host True VMHostAffinity {VirtualMachine-vm-129}
```

Modifying DRS rules

To modify a DRS rule, you can use the Set-DrsRule cmdlet. The syntax of this cmdlet is:

```
Set-DrsRule [[-Enabled] [<Boolean>]] [-Rule] <DrsRule[]> [-Name <String>]
[-VM <VirtualMachine[]>] [-RunAsync] [-Server <VIServer[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

The -Rule parameter is required.

In the following example, the DRS rule Keep VM1 and VM2 together of Cluster01 will be disabled:

```
PowerCLI C:\> Get-DrsRule -Name 'Keep VM1 and VM2 together' -Cluster Cluster01 |
>> Set-DrsRule -Enabled:$false
>>
Name Enabled Type VMIDs
```

```
Keep VM1 and VM2 together False VMAffinity {VirtualMachine-vm-129,
VirtualMachine-vm-105}
```

Removing DRS rules

The Remove-DrsRule cmdlet can be used to remove a DRS rule. The syntax of the Remove-DrsRule cmdlet is:

```
Remove-DrsRule [-Rule] <DrsRule[]> [-RunAsync] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -Rule parameter is required.

In the next example, the DRS rule Keep VM1 and VM2 together of Cluster01 is removed:

```
PowerCLI C:\> Get-DrsRule -Cluster Cluster01 -Name 'Keep VM1 and VM2
together' |
>> Remove-DrsRule -Confirm:$false
```

Using DRS recommendations

To retrieve the available DRS recommendations from the provided clusters, you can use the Get-DrsRecommendation cmdlet. This is useful if you configured DrsAutomationLevel on your cluster as Manual or PartiallyAutomated. The syntax of the Get-DrsRecommendation cmdlet is:

```
Get-DrsRecommendation [[-Cluster] <Cluster[]>] [-Refresh] [-Priority
<Int32[]>] [-Server <VIServer[]>] [<CommonParameters>]
```

In the next example, you will retrieve all of the DRS recommendations for all of the clusters:

PowerCLI C:\ > Get-DrsRecommendation

```
Priority Recommendation Reason
------
2 Migrate VM 'VM1' from host... Fix soft VM/host affinity r...
```

To apply a DRS recommendation, you can use the Apply-DrsRecommendation cmdlet. This cmdlet has the following syntax:

```
Apply-DrsRecommendation [-DrsRecommendation] <DrsRecommendation[] > [-RunAsync] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -DrsRecommendation property is required.

In the following example, all of the DRS recommendations will be applied:

```
PowerCLI C:\> Get-DrsRecommendation | Apply-DrsRecommendation
```

If you have several DRS recommendations and you don't want to apply them all, you can use a filter to select the DRS recommendations you want to apply:

```
PowerCLI C:\> Get-DrsRecommendation |
>> Where-Object {$_.Recommendation -like "*VM1*" } |
>> Apply-DrsRecommendation
```

Using resource pools

The virtual machines in a vSphere cluster share the resources of the ESXi hosts in the cluster. Resource pools are a way to divide the resources of the cluster into different pools. Virtual machines in a resource pool share the resources of their resource pool. This can be useful to always give a group of virtual machines the resources they need or to limit the amount of resources for a group of virtual machines.

Each cluster has a root resource pool called Resources. The resource pools you create are children of the Resources root resource pool or of other resource pools in the cluster.

Resource pools and virtual machines have settings that will be explained in the next table:

Setting	Description
Shares	A relative importance against sibling resource pools or virtual machines. Shares can have a level (Custom, High, Low, or Normal) or an amount.
Limit	The maximum allowed resources.
Reservation	The minimum available resources.
Expandable reservation (resource pool only)	If a resource pool has expandable reservation, it can use resources of the parent resource pool, if the parent resource pool has unreserved resources.

You already saw the Move-VM cmdlet that can be used to move virtual machines into resource pools in *Chapter 5, Managing Virtual Machines with PowerCLI*.

Creating resource pools

You can use the New-ResourePool cmdlet to create a resource pool. The syntax of the New-ResourcePool cmdlet is:

```
New-ResourcePool -Location <VIContainer> -Name <String>
[-CpuExpandableReservation [<Boolean>]] [-CpuLimitMhz <Int64>]
[-CpuReservationMhz <Int64>] [-CpuSharesLevel <SharesLevel>]
[-MemExpandableReservation [<Boolean>]] [-MemLimitMB <Int64>]
[-MemLimitGB <Decimal>] [-MemReservationMB <Int64>] [-MemReservationGB <Decimal>] [-MemSharesLevel <SharesLevel>] [-NumCpuShares <Int32>]
[-NumMemShares <Int32>] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -Location and -Name parameters are required. The value of the -Location parameter can be a resource pool, cluster, or host.

In the following example, a new resource pool called ResourcePool2 will be created for Cluster 01. Because the parameter list is quite long, splatting is used to make the code more readable.

```
PowerCLI C:\> $Parameters = @{
>> Location = (Get-Cluster -Name Cluster01)
>> Name = 'ResourcePool2'
>> CpuExpandableReservation = $true
>> CpuReservationMhz = 500
>> CpuSharesLevel = 'normal'
>> MemExpandableReservation = $true
>> MemReservationMB = 512
>> MemSharesLevel = 'high'
>> New-ResourcePool @Parameters
>>
```

Name	CpuShares	CpuReser	CpuLimit	MemShares	MemReser	MemLi
	Level	${\tt vationMHz}$	MHz	Level	vationGB	mitGB
ResourcePool2	Normal	500	-1	High	0.500	-1.000

Retrieving resource pools

To retrieve resource pools, you can use the Get-ResourcePool cmdlet. The syntax of the Get-ResourcePool cmdlet is:

```
Get-ResourcePool [-VM <VirtualMachine[]>] [-Location <VIContainer[]>]
[[-Name] <String[]>] [-NoRecursion] [-Server <VIServer[]>]
[<CommonParameters>]
Get-ResourcePool -Id <String[]> [-Server <VIServer[]>]
[<CommonParameters>]
Get-ResourcePool -RelatedObject <ResourcePoolRelatedObjectBase[]>
[<CommonParameters>]
```

If you don't specify parameters, all of the resource pools in your environment will be retrieved. You can use the different parameters to filter the resource pools. In the next example, you will retrieve all of the resource pools of Cluster01:

PowerCLI C:\> Get-Cluster -Name Cluster01 | Get-ResourcePool

Name	CpuShares	CpuReser	CpuLimit	MemShares	MemReser	MemLi
	Level	${\tt vationMHz}$	MHz	Level	${\tt vationGB}$	mitGB
Resources	Normal	6560	6560	Normal	0.753	0.753
ResourcePool2	Normal	500	-1	High	0.500	-1.000

Modifying resource pools

The Set-ResourcePool cmdlet can be used to modify the settings of a resource pool. The syntax of this cmdlet is:

```
Set-ResourcePool [-ResourcePool] <ResourcePool[]> [-Name <String>]
[-CpuExpandableReservation [<Boolean>]] [-CpuLimitMhz <Int64>]
[-CpuReservationMhz <Int64>] [-CpuSharesLevel <SharesLevel>]
[-MemExpandableReservation [<Boolean>]] [-MemLimitMB <Int64>]
[-MemLimitGB <Decimal>] [-MemReservationMB <Int64>] [-MemReservationGB <Decimal>] [-MemSharesLevel <SharesLevel>] [-NumCpuShares <Int32>]
[-NumMemShares <Int32>] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -ResourcePool parameter is the only required parameter.

You cannot specify a new location for a resource pool using the Set-ResourcePool cmdlet, but the rest of the parameters of the Set-ResourcePool cmdlet are the same as for the New-ResourcePool cmdlet.

In the next example, the ResourcePool2 memory limit and CPU limit will be modified:

PowerCLI C:\> Set-ResourcePool -ResourcePool Resourcepool2 -MemLimitGB 4 -CpuLimitMhz 6000

Name	CpuShares	CpuReser	CpuLimit	MemShares	MemReser	MemLi
	Level	${\tt vationMHz}$	MHz	Level	vationGB	mitGB
ResourcePool2	Normal	500	6000	High	0.500	4.000

Moving resource pools

To move a resource pool to a new location, you can use the Move-ResourcePool cmdlet, which has the following syntax:

```
Move-ResourcePool [-ResourcePool] <ResourcePool[]> [-Destination]
<VIContainer> [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -ResourcePool and -Destination parameters are required. You cannot move a resource pool between different hosts or clusters.

In the next example, a new resource pool named ResourcePool1 is created and then the existing resource pool ResourcePool2 is relocated and made a child of the ResourcePool1 resource pool:

PowerCLI C:\> New-ResourcePool -Name ResourcePool1 -Location (Get-Cluster -Name Cluster01)

Name	CpuShares	CpuReser	CpuLimit	${\tt MemShares}$	${\tt MemReser}$	MemLi
	Level	${\tt vationMHz}$	MHz	Level	${\tt vationGB}$	mitGB
ResourcePool1	Normal	0	-1	Normal	0.000	-1.000

PowerCLI C:\> Move-ResourcePool -ResourcePool ResourcePool2 -Destination
(Get-ResourcePool -Name ResourcePool1)

Name	CpuShares Level	CpuReser vationMHz	-	MemShares Level	MemReser vationGB	
ResourcePool2	Normal	500	6000	High	0.500	4.000

If you want to see the hierarchy of the resource pools, you can look at the Parent property of the resource pools:

```
PowerCLI C:\> Get-ResourcePool -Location (Get-Cluster -Name Cluster01) |
>> Select-Object -Property Name, Parent | Format-Table-AutoSize
>>
```

Name	Parent
Resources	Cluster01
ResourcePool1	Resources
ResourcePool2	ResourcePool1

In the example output, you can see that the Resources resource pool is a child of the Cluster01 cluster, the ResourcePool1 resource pool is a child of the ResourcePool1 resource pool is a child of the ResourcePool1 resource pool.

Configuring resource allocation between virtual machines

You can also specify shares, limits, and reservations for virtual machines. You can use the Get-VMResourceConfiguration cmdlet to retrieve the current resource configuration of virtual machines. The syntax of the Get-VMResourceConfiguration cmdlet is:

```
Get-VMResourceConfiguration [-Server <VIServer[]>] [-VM]
<VirtualMachine[]> [<CommonParameters>]
```

The -VM parameter is required.

In the next example, the resource configuration of virtual machine VM1 is retrieved and piped to the Format-List -Property * command to list all of the property values. The output of the example is in the following screenshot:

The Set-VMResourceConfiguration cmdlet can be used to modify the resource configuration of a virtual machine. The syntax of the Set-VMResourceConfiguration cmdlet is:

```
Set-VMResourceConfiguration [-Configuration] <VMResourceConfiguration[]>
[-HtCoreSharing <HTCoreSharing>] [-CpuAffinity <CpuAffinity>]
[-CpuAffinityList <Int32[]>] [-CpuReservationMhz <Int64>] [-CpuLimitMhz <Int64>] [-CpuSharesLevel <SharesLevel>] [-NumCpuShares <Int32>]
[-MemReservationMB <Int64>] [-MemReservationGB <Decimal>] [-MemLimitMB <Int64>] [-MemLimitGB <Decimal>] [-MemSharesLevel <SharesLevel>]
[-NumMemShares <Int32>] [-Disk <HardDisk[]>] [-NumDiskShares <Int32>]
[-DiskSharesLevel <SharesLevel>] [-DiskLimitIOPerSecond <Int64>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Configuration parameter is the only required parameter. Most of the parameters are similar to the parameters of the Set-ResourcePool cmdlet. New parameters are -Disk, -NumDiskShares, -DiskSharesLevel, and -DiskLimitIOPerSecond. These parameters allow you to set a disk I/O limit, disk shares, and a disk shares level per disk.

In the following example, the CPU and memory shares level of virtual machine VM1 are set to high:

```
PowerCLI C:\> Get-VMResourceConfiguration -VM VM1 |
>> Set-VMResourceConfiguration -CpuSharesLevel High -MemSharesLevel High
>>
```

VM	NumCpuShares	CpuSharesLevel	NumMemShares	MemSharesLevel
VM1	2000	High	5120	High

Removing resource pools

The Remove-ResourcePool cmdlet will remove a resource pool for you. This cmdlet has the following syntax:

```
Remove-ResourcePool [-ResourcePool] <ResourcePool[]> [-Server
<VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -ResourcePool parameter is required.

In the next example, the resource pool named ResourcePool1 is removed:

```
PowerCLI C:\> Remove-ResourcePool -ResourcePool1
-Confirm:$false
```

Using Distributed Power Management (DPM)

The load of your virtual machines is probably not always the same. Sometimes they need more resources and sometimes they need fewer resources. **Distributed Power Management (DPM)** will use DRS to consolidate virtual machines on fewer ESXi hosts during periods of low resource utilization. The unused ESXi hosts will be powered off. If more resources are needed, DPM will power on ESXi hosts and DRS will move virtual machines to these hosts. DPM will save you or your company money in power and cooling costs.




VMware has created a fling called "Proactive DRS" that uses the historical data gathered by VMware vCenter Operations Manager to proactively power on hosts before a predicted increase in resource demands. You can find Proactive DRS at: http://labs.vmware.com/flings/proactive-drs

Enabling DPM

DPM has two modes: manual and automatic. In manual mode, DPM will give recommendations to evacuate virtual machines from hosts and power off or power on the hosts. You will have to apply the recommendations manually. In the automatic mode, DPM will automatically apply DPM recommendations above a certain threshold.

In the next screenshot of the vSphere Web Client, you will see the DPM settings of a cluster with **Automation Level** set to **Manual** and **DPM Threshold** set in the middle:



There are no cmdlets to configure DPM, so you have to use the vSphere API again. You start with creating a ClusterConfigSpecEx object. Assign a new ClusterDpmConfigInfo object to the dpmConfig property of the ClusterConfigSpecEx object. Assign \$true to the enabled property, and assign manual or automated to the defaultDpmBehavior property. If you choose automated, you can assign an integer value from 1 to 5 to the hostPowerActionRate property, where 1 is the most aggressive threshold and 5 is the most conservative threshold:

```
# Enabling Distributed Power Management
$Cluster = Get-Cluster -Name Cluster01
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.dpmConfig = New-Object VMware.Vim.ClusterDpmConfigInfo
$spec.dpmConfig.enabled = $true
$spec.dpmConfig.defaultDpmBehavior = "manual"
$spec.dpmConfig.hostPowerActionRate = 3
$Cluster.ExtensionData.ReconfigureComputeResource_Task($spec, $true)
```

Configuring hosts for DPM

For DPM to be able to power on hosts, you have to configure the **Intelligent Platform Management Interface (IPMI)** / **Integrated Lights-Out (iLO)** settings for power management. You have to specify the username, password, BMC IP address, and BMC MAC address of the IPMI interface in your host.

The next example will configure the IPMI information for host 192.168.0.133 using the UpdateIpmi() method:

```
# Updating IPMI info
$VMHost = Get-VMHost -Name 192.168.0.133
$ipmiInfo = New-Object VMware.Vim.HostIpmiInfo
$ipmiInfo.bmcIpAddress = "192.168.0.201"
$ipmiInfo.bmcMacAddress = "d4:85:64:52:1b:49"
$ipmiInfo.login = "IPMIuser"
$ipmiInfo.password = "IPMIpassword"
$VMHost.ExtensionData.UpdateIpmi($ipmiInfo)
```

Testing hosts for DPM

Before enabling DPM on a cluster or before adding a host to a DPM-enabled cluster, it is a good practice to test the IPMI settings of all of the hosts. You would be in trouble if DPM stopped a host and couldn't start it, wouldn't you? You can test a host for IPMI by putting it in standby mode first and starting it afterwards.

Putting hosts in standby mode

You can use the Suspend-VMHost cmdlet to put a host in standby mode. The syntax of the Suspend-VMHost cmdlet is:

```
Suspend-VMHost [-VMHost] <VMHost[]> [-TimeoutSeconds <Int32>]
[-Evacuate] [-Server <VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -VMHost parameter is required.

In the next example, host 192.168.0.133 will be put into standby mode:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 |
>> Suspend-VMHost -Confirm:$false
>>
```

Starting hosts

To start a host in the standby mode, you can use the Start-VMHost cmdlet. The syntax of this cmdlet is:

```
Start-VMHost [-VMHost] <VMHost[]> [-TimeoutSeconds <Int32>] [-Server
<VIServer[]>] [-RunAsync] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -VMHost parameter is required.

The host 192.168.0.133 that was put in standby mode in the preceding example will be started in the next example:

```
PowerCLI C:\> Get-VMHost -Name 192.168.0.133 |
>> Start-VMHost -Confirm:$false
>>
```

After a successful start from standby mode, your host is ready for DPM.

Retrieving the DPM configuration of a cluster

To check if DPM is enabled on a cluster and to see the DPM settings, you can look at the ExtensionData.ConfigurationEx.DpmConfigInfo property of the cluster.

In the next example, the DPM configuration of Cluster01 is retrieved:

```
PowerCLI C:\> Get-Cluster -Name Cluster01 |
>> ForEach-Object {$_.ExtensionData.ConfigurationEx.DpmConfigInfo}
>>
```

Enabled : True

DefaultDpmBehavior : automated

HostPowerActionRate : 5
Option :
DynamicType :
DynamicProperty :

Disabling DPM

To disable DPM, you can use almost the same script as to enable DPM. Just modify \$spec.dpmConfig.enabled = \$true into \$spec.dpmConfig.enabled = \$false.

You don't have to specify values for the defaultDpmBehavior or hostPowerActionRate properties.

```
# Disabling Distributed Power Management
$Cluster = Get-Cluster -Name Cluster01
$spec = New-Object VMware.Vim.ClusterConfigSpecEx
$spec.dpmConfig = New-Object VMware.Vim.ClusterDpmConfigInfo
$spec.dpmConfig.enabled = $false
$Cluster.ExtensionData.ReconfigureComputeResource Task($spec, $true)
```

Removing clusters

The Remove-Cluster cmdlet will remove a cluster from your vSphere inventory. The Remove-Cluster cmdlet has the following syntax:

```
Remove-Cluster [-Cluster] <Cluster[]> [-Server <VIServer[]>] [-RunAsync]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The next example will remove the Cluster02 cluster that was created at the beginning of this chapter:

PowerCLI C:\> Remove-Cluster -Cluster Cluster02 -Confirm:\$false



Be careful. Removing a cluster will also remove all of the hosts and virtual machines in the cluster!

Summary

In this chapter, you learned all about managing vSphere HA and DRS clusters, retrieving HA master or primary hosts, retrieving cluster configuration issues, disabling HA, disabling or enabling host monitoring, associating a host profile with a cluster, enabling VM and Application Monitoring, configuring the heartbeat datastore selection policy, moving hosts to clusters, moving clusters, using DRS rules and DRS groups, using resource pools, configuring resource allocation between virtual machines, and using DPM.

The next chapter will be about managing vCenter from PowerCLI.

Managing vCenter with PowerCLI

If you have more than one ESXi server, a vCenter Server will make your ESXi servers much easier to manage. A vCenter Server will also add a lot of additional features, such as HA and DRS clusters, to your vSphere environment,. In this chapter, we will discuss some topics that will help you manage your vSphere environment.

The following topics are covered in this chapter:

- Working with roles and permissions
- Managing licenses
- Configuring alarms
- Retrieving events

Working with roles and permissions

In a VMware vSphere environment, you might want to give certain **permissions** to users or administrators, who are not a part of the vSphere administrator's team, to perform specific tasks. For example, you might want to give the administrators of a server the permission to power on and off the server. You don't want to give these administrators all of the privileges in your environment because then you will lose control over it. There are many privileges you can give to somebody, and you probably want to give only a few. If you assigned privileges to users directly, it would be hard to see who has which privileges.

VMware vSphere has a nice feature called **roles**. Roles are a collection of privileges that you will need to perform a certain task. You can create a role called Server administrator and assign the Power On and Power Off privileges to this role. Every time you want to give an administrator the rights to power on and off a server, you can assign the Server administrator role to the administrator.

Permissions can be granted for every object in your vSphere environment, such as the root of your vSphere environment, datacenters, folders, clusters, and virtual machines. Permissions can be propagated to child objects of the main object to which you added a permission.

In the previous Server administrator example, you might want to create a folder for all of the servers assigned to the administrator. You can grant the Server administrator role to the administrator in the folder and propagate this permission to all of the child objects of the folder. This will give the administrator power on and off privileges for all of the servers in the folder.

Retrieving privileges

At the time of writing this book, using vSphere 5.5, there are 319 different privilege items you can grant to somebody. These privileges are arranged in 46 privilege groups. To get a list of all the privilege items or the privilege groups and their descriptions, you can use the Get-VIPrivilege cmdlet. This cmdlet has the following syntaxes:

The Get-VIPrivilege cmdlet without parameters will retrieve all of the privilege items and the privilege groups.

In the first example, we will retrieve all of the privilege items that have a name starting with Power:

```
PowerCLI C:\> Get-VIPrivilege -Name "Power*" -PrivilegeItem
```

The output of the preceding command is as follows:

Name	Description	Server
Power	Power system operations	192.168.0.132
Power On	Power On or resume a virtual machine	192.168.0.132
Power Off	Power Off a virtual machine	192.168.0.132
Power On	Power On a vApp	192.168.0.132
Power Off	Power Off a vApp	192.168.0.132

In the second example, we will use the Get-VIPrivilege -Role cmdlet to retrieve the privileges of the ReadOnly role:

PowerCLI C:\> Get-VIPrivilege -Role ReadOnly

The output of the preceding command is as follows:

Name	Description	Server
Anonymous	The only privilege held by sessions which \hdots	192.168.0.132
View	Visibility without read access to an entity	192.168.0.132
Read	Grants read access to an entity	192.168.0.132

In the third example, we will retrieve a list of the privilege groups using the following command:

PowerCLI C:\> Get-VIPrivilege -PrivilegeGroup

The output of the preceding command is too long to show in this book. Try the command yourself and see what it does.

In the fourth and last example of the Get-VIPrivilege cmdlet, we will use the -Group parameter to retrieve all of the privilege items of the Alarms group:

PowerCLI C:\> Get-VIPrivilege -Group Alarms

The output of the preceding command is as follows:

Name	Description	Server
Create alarm	Create an alarm	192.168.0.132
Remove alarm	Remove an alarm	192.168.0.132
Modify alarm	Modify an alarm	192.168.0.132
Acknowledge alarm	Acknowledge an alarm	192.168.0.132
Set alarm status	Set status for an alarm	192.168.0.132
Disable alarm action	Disable actions for an alarm	192.168.0.132

Using roles

Now that you know how to retrieve the vSphere privilege items and groups, you can start using the predefined roles or creating custom roles.

Creating roles

You can use the New-VIRole cmdlet to create a new role. The syntax of the New-VIRole cmdlet is as follows:

```
New-VIRole [-Name] <String> [[-Privilege] <Privilege[]>]
[-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Name parameter is required to create a new role.


In the following example, you will create the Server administrator role with the Power on and Power off privileges:

```
PowerCLI C:\> $Privileges = Get-VIPrivilege -Name "Power On", "Power Off"
PowerCLI C:\> New-VIRole -Name "Server administrator" -Privilege
$Privileges
```

The output of the preceding commands is as follows:

Name		IsSystem
Server	administrator	False

In the next screenshot of the vSphere Web Client, you will see the privileges of the **Server administrator** role under **Privileges** after executing the preceding PowerCLI commands to create the role:



Retrieving roles

The Get-VIRole cmdlet retrieves all the roles on your server. The syntax of this cmdlet is as follows:

```
Get-VIRole [[-Name] <String[]>] [-Id <String[]>]
[-Server <VIServer[]>] [<CommonParameters>]
```

The Get-VIRole cmdlet without parameters retrieves all of the roles in your environment:

PowerCLI C:\> Get-VIRole

The output of the preceding command is as follows:

Name	IsSystem
NoAccess	True
Anonymous	True
View	True
ReadOnly	True
Admin	True
VirtualMachinePowerUser	False
VirtualMachineUser	False
ResourcePoolAdministrator	False
VMwareConsolidatedBack	False
DatastoreConsumer	False
NetworkConsumer	False
Server administrator	False

You can also use the -Name parameter to retrieve specific roles:

```
PowerCLI C:\> Get-VIRole -Name "Server administrator"
```

The output of the preceding command is as follows:

```
Name IsSystem
----
Server administrator False
```

If you combine the Get-VIRole and Get-VIPrivilege cmdlets, you will get the privileges of a role. If you look at the privileges of the Server administrator role, you will see that it has not only the Power On and Power Off privileges, but also the Anonymous, View, and Read privileges. These three privileges are added to all of the roles you create and cannot be removed from the created roles.

PowerCLI C:\> Get-VIRole -Name "Server administrators" | Get-VIPrivilege

The output of the preceding command is as follows:

Name	Description	Server
Anonymous	The only privilege held by sessions which \dots	192.168.0.132
View	Visibility without read access to an entit	192.168.0.132
Read	Grants read access to an entity	192.168.0.132
Power On	Power On or resume a virtual machine	192.168.0.132
Power Off	Power Off a virtual machine	192.168.0.132
Power On	Power On a vApp	192.168.0.132
Power Off	Power Off a vApp	192.168.0.132

Modifying roles

You can use the Set-VIRole cmdlet to give a new name to a role, add privileges to a role, or remove privileges from a role. The syntaxes of the Set-VIRole cmdlet are as follows:

```
Set-VIRole [-Role] <Role[]> [-Name <String>] [-AddPrivilege
<Privilege[]>] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

```
Set-VIRole [-Role] <Role[]> [-Name <String>] [-RemovePrivilege
<Privilege[]>] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -Role parameter is required to modify a role. The Set-VIRole cmdlet has two parameter sets, one for the -AddPrivilege parameter and one for the -RemovePrivilege parameter. This means that you can't use the -AddPrivilege and -RemovePrivilege parameters in the same command.

In the next example, you will modify the Server administrator role into an Alarm operator role. The name will be changed, the power privileges will be removed, and the alarms privileges will be added using the following commands:

```
PowerCLI C:\> Get-VIRole -Name "Server administrator" |
>> Set-VIRole -Name "Alarm operator" -RemovePrivilege (Get-VIPrivilege
-Name "Power On","Power Off") |
>> Set-VIRole -AddPrivilege (Get-VIPrivilege -Group Alarms)
>>
```

The output of the preceding command is as follows:

Name	IsSyster		
Alarm operator	False		

Removing roles

The Remove-VIRole cmdlet can be used to remove roles. This cmdlet has the following syntax:

```
Remove-VIRole [-Role] <Role[]> [-Force] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Role parameter is required to remove a role. By default you cannot remove a role that is associated with a permission. The -Force parameter indicates that you want to remove the role even if it is associated with a permission.

In the following example, we will remove the Alarm operator role:

```
PowerCLI C:\> Remove-VIRole -Role "Alarm operator" -Confirm:$false
```

Using permissions

Now that you know how to create and use roles in PowerCLI, you can start creating permissions. A vSphere permission grants the privileges in a role to users or groups of users on a vSphere inventory item.

Creating permissions

The New-VIPermission cmdlet creates new permissions. The New-VIPermission cmdlet has the following syntax:

```
New-VIPermission [-Entity] <VIObject[]> [-Principal] <VIAccount[]>
[-Role] <Role> [-Propagate [<Boolean>]] [-Server <VIServer[]>]
[-WhatIf] [-Confirm] [<CommonParameters>]
```

The -Entity, -Principal, and -Role parameters are required to create a new permission.

By default, new permissions are propagated to child objects in the vSphere inventory. If you just want to create a permission for an inventory item and not for its child objects, you have to use the <code>-Propagate</code> parameter with the <code>sfalse</code> value.

It is not possible to create new permissions for the following objects:

- Direct child folders of a datacenter
- Root resource pools of clusters and standalone hosts

These objects always inherit the permissions of their parent.



VMware vCenter **Single Sign-On** (**SSO**) was first introduced in vSphere 5.1. In vSphere 5.5, the default Single Sign-On domain is named vsphere.local and the default Single Sign-On administrator account is administrator@vsphere.local. In vSphere 5.1, the default Single Sign-On domain is named System-Domain and the default Single Sign-On administrator account is admin@System-Domain.

In the next example, the vCenter Single-Sign On account VSPHERE.LOCAL\
Administrator is granted the Admin role for the New York datacenter:

PowerCLI C:\> New-VIPermission -Entity (Get-Datacenter -Name 'New York') -Principal VSPHERE.LOCAL\Administrator -Role Admin

The output of the preceding command is as follows:

Role	Principal	Propagate	IsGroup
Admin	VSPHERE.LOCA	True	False

In the following screenshot of vSphere Web Client, you will see the permissions of the **New York** datacenter under the **Permissions** tab after executing the preceding PowerCLI command to grant the **Administrator** role to the **VSPHERE.LOCAL**\ **Administrator** account for the **New York** datacenter:



Retrieving permissions

The Get-VIPermission cmdlet retrieves the permissions defined for inventory objects. The syntax of this cmdlet is as follows:

```
Get-VIPermission [[-Entity] <VIObject[]>] [-Principal <VIAccount[]>]
[-Server <VIServer[]>] [<CommonParameters>]
```

The cmdlet will retrieve all of the permissions in your environment if you don't specify parameters. You can use the <code>-Entity</code> parameter to retrieve only the permissions for the specified inventory objects. Use the <code>-Principal</code> parameter to retrieve permissions for certain users or groups.

In the following example, we will retrieve all of the permissions of the New York datacenter:

```
PowerCLI C:\> Get-VIPermission -Entity (Get-Datacenter -Name 'New
York')
```

The output of the preceding command is as follows:

Role	Principal	Propagate	IsGroup
Admin	VSPHERE.LOCA	True	False
Admin	root	True	False

If you retrieve the permissions, the default output doesn't show you the vSphere object for the permission. You can add this object by piping the output to the Format-Table cmdlet. Use the -Property parameter and specify all of the properties you want to retrieve, as shown in the following command line. The vSphere object is in the Entity property.

PowerCLI C:\> Get-VIPermission | Format-Table -Property Entity, Role, Principal, Propagate, IsGroup -AutoSize

The output of the preceding command is as follows:

Entity	Role	Principal	Propagate	IsGroup
New York	Admin	${\tt VSPHERE.LOCAL} \\ {\tt Administrator}$	True	False
Datacenters	Admin	VSPHERE.LOCAL\Administrator	True	False
Datacenters	Admin	root	True	False

Modifying permissions

You can use the Set-VIPermission cmdlet to change the role of a permission or to modify a permission if it propagates to child objects or vice versa. The Set-VIPermission cmdlet has the following syntax:

```
Set-VIPermission [-Permission] <Permission[]> [-Role <Role>]
[-Propagate [<Boolean>]] [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

The -Permission parameter is required to modify permissions.

In the following example, the permission of the account VSPHERE.LOCAL\
Administrator on datacenter New York is changed into ReadOnly and the propagation of the permission to child objects is disabled:

```
PowerCLI C:\> Get-VIPermission -Entity (Get-Datacenter -Name 'New York') -Principal VSPHERE.LOCAL\Administrator |
>> Set-VIPermission -Role ReadOnly -Propagate:$false
>>
```

The output of the preceding command is as follows:

Removing permissions

The Remove-VIPermission cmdlet will remove the specified permissions from your inventory. The syntax of this cmdlet is as follows:

```
Remove-VIPermission [-Permission] <Permission[]> [-WhatIf] [-Confirm]
[<CommonParameters>]
```

In the following example, the permission for VSPHERE.LOCAL\Administrator is removed from the New York datacenter:

```
PowerCLI C:\> Get-VIPermission -Entity (Get-Datacenter -Name 'New York')
-Principal VSPHERE.LOCAL\Administrator |
>> Remove-VIPermission -Confirm:$false
>>
```

Managing licenses

While writing this book, there are no PowerCLI cmdlets to add, retrieve, update, or remove licenses. You have to use the vSphere API to manage licenses in PowerCLI. There is only one cmdlet in PowerCLI for license management, Get-LicenseDataManager, and the only thing this cmdlet does is expose a hidden vSphere API.


You will use the vSphere API objects LicenseManager, LicenseAssignmentManager, and the hidden LicenseDataManager object to manage licenses.

You need to use LicenseManager to manage licenses in the license inventory on your vCenter Server. You can use LicenseAssignmentManager to manage the assignment of licenses to the ESXi servers. You use LicenseDataManager to associate licenses with containers in your vSphere environment and enable automatic license assignment to hosts that are added to a container.

The following three commands will give you hooks to the vSphere API license objects:

PowerCLI C:\> \$LicenseManager = Get-View -Id 'LicenseManager-LicenseManager'

PowerCLI C:\> \$LicenseAssignmentManager = Get-View -Id 'LicenseAssignmentManager-LicenseAssignmentManager' PowerCLI C: > \$LicenseDataManager = Get-LicenseDataManager



Adding license keys to the license inventory

To add a license to your vSphere license inventory, you have to use the Licensemanager.AddLicense() method. This method has two parameters. The first parameter is the license key that is to be added to your license inventory. The second parameter, called labels, is a pair of key-value labels that are ignored by the ESXi servers. You can use \$null as the second parameter.

PowerCLI C:\> \$LicenseManager = Get-View -Id 'LicenseManager-LicenseManager'

PowerCLI C:\> \$LicenseManager.AddLicense('00000-00000-00000-00000-00000',\$null)



You can also work with a real license key instead of 00000-00000-00000-00000-00000. This is the Product Evaluation license key used for the 60-day evaluation period of new ESXi servers.

Retrieving license keys from the license inventory

To retrieve license keys from your license inventory, you just have to query the Licenses property of the LicenseManager object, as shown in the following commands:

PowerCLI C:\> \$LicenseManager = Get-View -Id 'LicenseManager-LicenseManager'

PowerCLI C:\> \$LicenseManager.Licenses

The output of the preceding commands is as follows:

LicenseKey : 00000-00000-00000-00000

EditionKey : eval

Name : Product Evaluation

Total : 0
Used : 2
CostUnit :

Properties : {Localized}

Labels :
DynamicType :
DynamicProperty :

Removing license keys from the license inventory

You can use the LicenseManager.RemoveLicense() method to remove a license from your license inventory. The RemoveLicecense() method has only one parameter: the license key. In the following example, you will remove the license key 00000-00000-00000-00000-00000 from your inventory:

```
PowerCLI C:\> $LicenseManager = Get-View -Id 'LicenseManager-
LicenseManager'
PowerCLI C:\> $LicenseManager.
RemoveLicense('00000-00000-00000-00000')
```

Assigning licenses to hosts

Before PowerCLI 5.5 Release 1, in order to assign a license to a host you would have to use the LicenseAssignmentManager.UpdateAssignedLicense() method. This method has three parameters: the ID of the host, the license key, and the display name of the host. You don't have to specify the display name, so you can use \$null for this parameter.

In the following example, you will assign the license key 00000-00000-00000-00000-00000 to the host 192.168.0.133:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name '192.168.0.133'
PowerCLI C:\> $LicenseKey = '00000-00000-00000-00000'
PowerCLI C:\> $LicenseAssignmentManager = Get-View -Id
'LicenseAssignmentManager-LicenseAssignmentManager'
PowerCLI C:\> $LicenseAssignmentManager.UpdateAssignedLicense($VMHost.Id, $LicenseKey, $null)
```

The output of the preceding commands is as follows:

```
LicenseKey : 00000-00000-00000-00000

EditionKey : eval

Name : Product Evaluation

Total : 0

Used : 2

CostUnit :

Properties : {Localized}
```

Labels : {Localized}

DynamicType :
DynamicProperty :

PowerCLI 5.5 Release 1 introduced a new parameter named -LicenseKey to the Set-VMHost cmdlet. You can use this parameter to assign a license key to a host using the following command:

```
PowerCLI C:\> Get-VMHost -Name '192.168.0.133' |
>> Set-VMHost -LicenseKey '00000-00000-00000-00000'
>>
```

The output of the preceding command is as follows:

Name	ConnectionState	PowerState	NumCpu	CpuUsageMhz
192.168.0.133	Connected	PoweredOn	2	1035

Retrieving assigned licenses

The LicenseAssignmentManager.QueryAssignedLicenses() method retrieves the licenses assigned to a host. The method has only one parameter: the ID of the host. After running the method, you will find the license in the AssignedLicense property.

```
PowerCLI C:\> $VMHost = Get-VMHost -Name '192.168.0.133'
PowerCLI C:\> $LicenseAssignmentManager = Get-View -Id
'LicenseAssignmentManager-LicenseAssignmentManager'
PowerCLI C:\> $LicenseAssignmentManager.QueryAssignedLicenses
($VMHost.Id).AssignedLicense
```

The output of the preceding commands is as follows:

```
LicenseKey : 00000-00000-00000-00000
```

EditionKey : eval

Name : Product Evaluation

Total : 0
Used : 2
CostUnit :

Properties : {Localized}

Labels :
DynamicType :
DynamicProperty :

Since PowerCLI 5.5 Release 1, the VMHost object has a LicenseKey property. You can now retrieve the license key of a host with the following command:

```
PowerCLI C:\> Get-VMHost -Name '192.168.0.133' |
>> Select-Object -Property Name, LicenseKey
>>
```

The output of the preceding command is as follows:

Name	LicenseKey
192.168.0.133	00000-00000-00000-00000-00000

Removing assigned license keys from hosts

The LicenseAssignmentManager.RemoveAssignedLicense() method will remove all of the assigned license keys from a host. This method has one parameter: the ID of the host.

In the following example, you will remove all of the licenses from the host 192.168.0.133:

```
PowerCLI C:\> $VMHost = Get-VMHost -Name '192.168.0.133'
PowerCLI C:\> $LicenseAssignmentManager = Get-View -Id
'LicenseAssignmentManager-LicenseAssignmentManager'
PowerCLI C:\>
$LicenseAssignmentManager.RemoveAssignedLicense($VMHost.Id)
```

Using the LicenseDataManager

With the automated deployment of the ESXi hosts by using Auto Deploy, you will also want to automate the assignment of vSphere license keys to hosts. PowerCLI provides an object called LicenseDataManager that you can use to associate license keys with host containers, such as clusters, datacenters, and datacenter folders. The presence of license keys that are associated with host containers makes it possible to automatically assign a license key to a host when an unlicensed host is added to a host container or is reconnected to the vCenter Server. If a host is already licensed, the host keeps the license key it already had.

You have to use the <code>Get-LicenseDataManager</code> cmdlet to get an instance of the <code>LicenseDataManager</code> object. The <code>Get-LicenseDataManager</code> cmdlet is supported only by vCenter Server 5.0 or higher. The use of the <code>Get-LicenseDataManager</code> cmdlet is different from what you are used to in PowerCLI. You have to use this cmdlet to retrieve a <code>LicenseDataManager</code> object, and then use the methods of this object to associate the licenses to the inventory nodes.

The syntax of the Get-LicenseDataManager cmdlet is as follows:

Get-LicenseDataManager [[-Server] <VIServer[]>] [<CommonParameters>]



Be warned that the Get-LicenseDataManager cmdlet is defined in the VMware.VimAutomation.License snapin. If you use PowerCLI by starting PowerShell and adding the PowerCLI snap-ins, don't forget to add the VMware. VimAutomation.License snap-in if you want to use the Get-LicenseDataManager cmdlet.

Associating license keys with host containers

To associate license keys with host containers, you have to use the LicenseDataManager.UpdateAssociatedLicenseData() method. This method needs two parameters: the Managed Object Reference of the container and a LicenseData object. The LicenseData object contains a LicenseKeyEntry object consisting of methods named TypeId and LicenseKey. The only valid TypeId that I know of is vmware-vsphere.

In the next example, we will associate a license key to the New York datacenter:

```
$LicenseDataManager = Get-LicenseDataManager
$LicenseData = New-Object Vmware.VimAutomation.License.Types.
LicenseData
$LicenseKeyEntry = New-Object Vmware.VimAutomation.License.Types.
LicenseKeyEntry
$LicenseKeyEntry
$LicenseKeyEntry.TypeId = 'vmware-vsphere'
$LicenseKeyEntry.LicenseKey = '00000-00000-00000-00000'
$LicenseData.LicenseKeys += $LicenseKeyEntry
$HostContainer = Get-Datacenter -Name 'New York'
$LicenseDataManager.UpdateAssociatedLicenseData($hostContainer.Uid, $LicenseData)
```

Applying the associated license key to all the hosts in the container

After associating a license key to a host container, the hosts that were already in the container before the license key was associated will not automatically get the associated license keys applied. You have to use the LicenseDataManager. ApplyAssociatedLicenseData() method to apply the license key to the hosts.

In the following example, we will apply the license key associated with the New York datacenter to all of the hosts in the datacenter:

```
$LicenseDataManager = Get-LicenseDataManager
foreach ($VMHost in (Get-Datacenter -Name 'New York' | Get-VMHost))
{
    $\text{$LicenseDataManager.ApplyAssociatedLicenseData($VMHost.Uid)}}
}
```

Retrieving license key associations

There are three possible ways to retrieve license key associations. You can do one of the following:

- Retrieve all of the license key associations to the host containers in your environment
- Retrieve the license keys associated with a specific host container
- Retrieve the effective license key of a host container.

In the following three sections, you will see examples of all the three possibilities.

Retrieving all of the license key associations to the host containers in your environment

To retrieve all of the license key associations to the host containers, you can use the LicenseDataManager.QueryEntityLicenseData() method. Before running the next example, I also associated a license to the cluster Cluster01. This cluster is in the New York datacenter.

The following example retrieves all of the license key associations in your environment:

```
VMware vSphere PowerCLI 5.5 Release 1 - 

PowerCLI C:>> $LicenseDataManager = Get-LicenseDataManager PowerCLI C:>> $LicenseDataManager.QueryEntityLicenseData()

Entity
LicenseData
Datacenter-datacenter-21 (vmware-vsphere: 00000-000...
ClusterComputeResource-doma... (vmware-vsphere: 00000-111...

PowerCLI C:>>
```

If you want to know the name of the entity <code>Datacenter-datacenter-39</code> or <code>ClusterComputeResource-domain-c52</code>, you can use the <code>Get-VIObjectByVIView</code> cmdlet to convert the <code>MoRef</code> parameter into a PowerCLI object. For example, to get the name of <code>Datacenter-datacenter-21</code>, you can use the command shown in the following screenshot:

```
VMware vSphere PowerCLI 5.5 Release 1 - 

PowerCLI C:>> Get-UIObjectByUIUiew -MoRef Datacenter-datacent A
er-21

Name
New York

PowerCLI C:>>
```

Retrieving the license keys associated with a specific host container

To retrieve the license keys associated with a specific host container, you have to use the LicenseDataManager.QueryAssociatedLicenseData() method. In the following example, we will retrieve the license keys associated with the New York datacenter:

```
PowerCLI C:\> $LicenseDataManager = Get-LicenseDataManager
PowerCLI C:\> $HostContainer = Get-Datacenter -Name 'New York'
PowerCLI C:\>
$LicenseDataManager.QueryAssociatedLicenseData($HostContainer.Uid)
```

The output of the preceding commands is as follows:

Retrieving the effective license key of a host container

It is possible to associate a license key with a parent container and not with a child container. The license key associated with the parent container is also effective on the child container. If you want to know which is the effective license key of a host container, you have to use the LicenseDataManager.QueryEffectiveLicenseData() method. In the following example, we will retrieve the effective license key associated with the cluster ClusterO2. The cluster ClusterO2 belongs to the New York datacenter and does not have a license key associated with it:

```
PowerCLI C:\> $LicenseDataManager = Get-LicenseDataManager
PowerCLI C:\> $HostContainer = Get-Cluster -Name Cluster02
PowerCLI C:\> $LicenseDataManager.QueryEffectiveLicenseData($HostContain er.Uid)
```

The output of the preceding commands is as follows:

As you can see in the output of the preceding example, the license key associated with the New York datacenter is effective on the Cluster02 cluster.

Modifying license key associations

To associate another license key with a host container, you just have to replace the license key associated with the host container with a new license key. The PowerCLI code that you have to use to associate a new license key is exactly the same as what we used to associate a license key with a host container, as you saw earlier in the *Associating license keys with host containers* section. After modifying a license key association, you have to apply the new license key to all of the hosts in the container, as shown in the *Applying the associated license key to all the hosts in the container* section.

Removing license key associations

To remove the association of a license key with a host container, you have to use the LicenseDataManager.UpdateAssociatedLicenseData() method with \$null as the second parameter. In the following example, we will remove the association of the license key with the datacenter New York:

```
$LicenseDataManager = Get-LicenseDataManager
$HostContainer = Get-Datacenter -Name 'New York'
$LicenseDataManager.UpdateAssociatedLicenseData($HostContainer.Uid,
$null)
```


Configuring alarms

In a vSphere environment, there are conditions (such as datastores running out of space) that you want to know about before things run out of control. In the "datastores running out of space" example, you would want to be warned before the datastore is full, so you can move some disks to another datastore to create extra free space on the datastore that is running out of space.

VMware vSphere provides alarms that trigger warnings and alerts when certain conditions are met. There are a lot of predefined alarms for almost every condition possible in vCenter Server. For example, there is the Datastore usage on disk alarm for datastores that will, by default, give you a warning if a datastore usage is above 75 percent and give you an alert if a datastore usage is above 85 percent. It is also possible to define actions such as Send a notification email that are executed when an alarm is triggered.

In PowerCLI, there are various cmdlets to modify alarm definitions and to create and modify alarm action triggers and alarm actions.

In the following screenshot of the vSphere Web Client, you will see the **Trigger states** notification of the **Datastore usage on disk** alarm:



Retrieving alarm definitions

You can use the Get-AlarmDefinition cmdlet to retrieve the available alarm definitions. The syntax of this cmdlet is as follows:

```
Get-AlarmDefinition [-Id <String[]>] [[-Name] <String[]>] [[-Entity]
<VIObject[]>] [-Enabled [<Boolean>]] [-Server <VIServer[]>]
[<CommonParameters>]
```


There are three possible ways to retrieve alarm definitions. You can do one of the following:

- Get a list of all the available alarm definitions
- Filter the alarm definitions by name or entity
- Retrieve only the enabled alarm definitions

In the following example, we will retrieve the Datastore usage on disk alarm:


PowerCLI C:\> Get-Alarmdefinition -Name 'Datastore usage on disk'

The output of the preceding command is as follows:



Datastore usage on disk Default alarm to monitor datastore... True

In the following screenshot of the vSphere Web Client, you will see the alarm definition for the **Datastore usage on disk** alarm:



Modifying alarm definitions

To modify alarm definitions, you can use the Set-AlarmDefinition cmdlet that gives the ability to change the name and description of an alarm definition, specify how often the alarm actions repeat if the alarm is active, and enable or disable the alarm. The Set-AlarmDefinition cmdlet has the following syntax:

```
Set-AlarmDefinition [-AlarmDefinition] <AlarmDefinition[]>
[-ActionRepeatMinutes <Int32>] [-Description <String>] [-Enabled
[<Boolean>]] [-Name <String>] [-Server <VIServer[]>] [-WhatIf]
[-Confirm] [<CommonParameters>]
```

The -AlarmDefinition parameter is required to modify an alarm definition.

In the following example, we will disable the Datastore usage on disk alarm:

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' |
>> Set-AlarmDefinition -Enabled $false
>>
```

The output of the preceding command is as follows:

Creating alarm actions

If an alarm is triggered, you can send an e-mail notification, generate an SNMP trap, or run a script. These actions can be defined with the New-AlarmAction cmdlet. This cmdlet has the following syntaxes:

```
New-AlarmAction [-AlarmDefinition] <AlarmDefinition> -Email [-Subject
<String>] -To <String[]> [-Cc <String[]>] [-Body <String>] [-Server
<VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

```
New-AlarmAction [-AlarmDefinition] <AlarmDefinition> -Script
-ScriptPath <String> [-Server <VIServer[]>] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

```
New-AlarmAction [-AlarmDefinition] <AlarmDefinition> -Snmp [-Server <VIServer[]>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

As you can see, the New-AlarmAction cmdlet has three parameter sets, one for each type of alarm action you can define. The -AlarmDefinition parameter is always required to create an alarm action. To create a Send a notification email alarm action, the -Email and -To parameters are also required. To create a Send a notification trap alarm action, the -Snmp parameter is required. To create a Run a command alarm action, the -Script and -ScriptPath parameters are required.

In the first example, we will create a Send a notification e-mail alarm action for the Datastore usage on disk alarm:

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' | >> New-AlarmAction -Email -To user@domain.com -Subject 'Datastore usage on disk alarm' -Body 'Datastore {targetName} usage is over its alarm limits'
```

>>

The output of the preceding command lines is as follows:

ActionType	Trigger
SendEmail	

The {targetName} variable in the preceding example will substitute the name of the datastore in the subject and body of the e-mail. The variables that you can use are shown in the following table. The table is copied from the vSphere 5.5 documentation's *Alarm Command-Line Parameters* section at http://pubs.vmware.com/vsphere-55/topic/com.vmware.vsphere.monitoring.doc/GUID-B8DF4E10-89E3-409D-9111-AE405B7E5D2E copy.html:

Variable	Description
{eventDescription}	The text of the alarmStatusChange event. The {eventDescription} variable is supported only for the Condition and State alarms.
{targetName}	The name of the entity on which the alarm is triggered.
{alarmName}	The name of the alarm that is triggered.
{triggeringSummary}	A summary of the alarm trigger values.
{declaringSummary}	A summary of the alarm declaration values.
{oldStatus}	The alarm status before the alarm is triggered.
{newStatus}	The alarm status after the alarm is triggered.
{target}	The inventory object on which the alarm is set.


In the second example, we will create a Send a notification trap alarm action for the Datastore usage on disk alarm:

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' |
>> New-AlarmAction -Snmp
>>
```


The output of the preceding command is as follows:

```
ActionType Trigger
-----
SendSNMP ...
```

In the third example, we will create a Run a command alarm action for the Datastore usage on disk alarm. The c:\Scripts\DatastoreAlarm.cmd script has to run when the alarm is triggered.



In the following screenshot of the vSphere Web Client, you will see the actions that can be taken under the **Action** column when the state of the **Datastore usage on disk** alarm changes from warning to alert:



As mentioned earlier, use the following command to create a Run a command alarm action for the Datastore usage on disk alarm:

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' | >> New-AlarmAction -Script -ScriptPath c:\Scripts\DatastoreAlarm.cmd >>
```

The output of the preceding command is as follows:

```
ActionType Trigger
-----
ExecuteScript ...
```



You cannot specify a PowerShell or PowerCLI script as the value of the <code>-ScriptPath</code> parameter. Rather, you have to specify a batch file. Of course you can call PowerShell from inside the batch file. For example, you can call the script <code>c:\scripts\AlarmAction.ps1</code> from a batch file with the following command:

echo. | powershell -command "&{c:\scripts\AlarmAction.ps1}"

You can find more information in the VMware Knowledge Base article *Unable to invoke PowerShell scripts as alarm action on vCenter Server 5.0* (2039574) at http://kb.vmware.com/kb/2039574.


Configuring the vCenter Server mail server and sender settings

Before you can send an e-mail as an alarm action, you have to specify an SMTP server and the e-mail address that will be used as the sender's address in the e-mails sent by vCenter Server. There are no PowerCLI cmdlets to do this. You have to use the vSphere API.

In the next example, we will configure the vCenter Server with smtpserver. blackmilktea.com as the address of the SMTP server and vcenter@ blackmilktea.com as the sender's e-mail address. The following script uses the VpxSettings UpdateOptions() method to configure the SMTP server and the sender's e-mail address:

```
$OptionValue = New-Object VMware.Vim.OptionValue[] (2)
$OptionValue[0] = New-Object VMware.Vim.OptionValue
$OptionValue[0].key = 'mail.smtp.server'
$OptionValue[0].value = 'smtpserver.blackmilktea.com'
$OptionValue[1] = New-Object VMware.Vim.OptionValue
$OptionValue[1].key = 'mail.sender'
$OptionValue[1].value = 'vcenter@blackmilktea.com'
$VpxSettings = Get-View -Id 'OptionManager-VpxSettings'
$VpxSettings.UpdateOptions($OptionValue)
```

In the following screenshot of the vCenter Server Mail settings (in the vSphere Web Client), you will see the defined SMTP server address and the sender's e-mail address in the Mail server and Mail sender text fields after executing the preceding PowerCLI script:



Retrieving alarm actions

The Get-AlarmAction cmdlet will retrieve the alarm actions of the specified alarm definitions. The syntax of the Get-AlarmAction cmdlet is as follows:

```
Get-AlarmAction [[-AlarmDefinition] <AlarmDefinition[]>] [-ActionType
<ActionType[]>] [-Server <VIServer[]>] [<CommonParameters>]
```

In the following example, we will retrieve the alarm actions of the Datastore usage on disk alarm definition. Because the default output shows only the ActionType and Trigger properties, the output is piped to the Format-List -property * command to show all of the properties.

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' |
>> Get-AlarmAction | Format-List -Property *
>>
```

The output of the preceding command is as follows:

```
Body : Datastore usage is over its alarm limits
Cc : {}
To : {user@domain.com}
Subject : Datastore usage on disk alarm
```

ActionType : SendEmail

AlarmDefinition : Datastore usage on disk Trigger : {Yellow -> Red (Once)}

Uid : /VIServer=root@192.168.0.132:443/Alarm=Alarm-alarm-8/

SendEmailAction=1049345814/

AlarmVersion : 59 Client : ActionType : SendSNMP

AlarmDefinition : Datastore usage on disk

Trigger : {Yellow -> Red (Once)}
Uid : /VIServer=root@192.168.0.132:443/Alarm=Alarm-alarm-8/

SendSNMPAction=-1381748622/

AlarmVersion : 59 Client

ScriptFilePath : c:\Scripts\DatastoreAlarm.cmd

ActionType : ExecuteScript

AlarmDefinition : Datastore usage on disk Trigger : {Yellow -> Red (Once)}

: /VIServer=root@192.168.0.132:443/Alarm=Alarm-alarm-8/

RunScriptAction=307617281/ AlarmVersion : 59

Client : Client

Removing alarm actions

You can use the Remove-AlarmAction cmdlet to remove an alarm action. The Remove-AlarmAction cmdlet has the following syntax:

```
Remove-AlarmAction [-AlarmAction] <AlarmAction[]> [-WhatIf]
[-Confirm] [<CommonParameters>]
```

The -AlarmAction property is required to remove an alarm action.

In the following example, we will remove the SendSNMP alarm action from the Datastore usage on disk alarm definition:

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' |
>> Get-AlarmAction -ActionType SendSNMP
>> Remove-AlarmAction -Confirm:$false
```

Creating alarm action triggers

Every new alarm action will be triggered once the alarm state changes from warning (yellow) to alert (red). If you want to create additional alarm action triggers, you can use the New-AlarmActionTrigger cmdlet to create a new action trigger for the specified alarm action. The syntax of this cmdlet is as follows:

```
New-AlarmActionTrigger [-StartStatus] <InventoryItemStatus>
[-EndStatus] <InventoryItemStatus> -AlarmAction <AlarmAction>
[-Repeat] [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -StartStatus, -EndStatus, and -AlarmAction parameters are required to create an alarm action trigger.

In the next example, we will create a new alarm action trigger for the SendEmail alarm action of the Datastore usage on disk alarm definition. The trigger is started when the alarm state changes from normal (green) to warning (yellow). The alarm action will be repeated once every hour until the alarm is acknowledged.

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' | >> Get-AlarmAction -ActionType SendEmail | >> New-AlarmActionTrigger -StartStatus 'Green' -EndStatus 'Yellow' -Repeat >>
```

The output of the preceding command lines is as follows:

StartStatus	EndStatus	Repeat
Green	Yellow	True

Now, use the following command to set the time intervals between the occurrence of the alarms:

```
PowerCLI C:\> Set-AlarmDefinition 'Datastore usage on disk' -ActionRepeatMinutes 60
```

The output of the preceding command is as follows:

Retrieving alarm action triggers

To retrieve alarm action triggers, you can use the Get-AlarmActionTrigger cmdlet. This cmdlet has the following syntax:

```
Get-AlarmActionTrigger [[-AlarmAction] <AlarmAction[]>]
[<CommonParameters>]
```


In the next example, we will retrieve the alarm action triggers of the SendEmail alarm action of the Datastore usage on disk alarm definition.

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' |
>> Get-AlarmAction -ActionType SendEmail |
>> Get-AlarmActionTrigger
>>
```

The output of the preceding command is as follows:

StartStatus	EndStatus	Repeat
Yellow	Red	False
Green	Yellow	True

In the next screenshot of the vSphere Web Client, you will see the **Trigger states** and **Alarm actions** notifications for the **Datastore usage on disk** alarm:



Removing alarm action triggers

We can remove alarm action triggers using the Remove-AlarmActionTrigger cmdlet. The syntax of the Remove-AlarmActionTrigger cmdlet is as follows:

```
Remove-AlarmActionTrigger [-AlarmActionTrigger]
<AlarmActionTrigger[] > [-WhatIf] [-Confirm] [<CommonParameters>]
```

The -AlarmActionTrigger parameter is required to remove an alarm action trigger.

In the following example, the alarm action trigger with the start status Green will be removed from the SendEmail alarm action of the Datastore usage on disk alarm definition:

```
PowerCLI C:\> Get-AlarmDefinition -Name 'Datastore usage on disk' |
>> Get-AlarmAction -ActionType SendEmail |
>> Get-AlarmActionTrigger |
>> Where-Object {$_.StartStatus -eq 'Green'} |
>> Remove-AlarmActionTrigger -Confirm:$false
```

An alarm action must have at least one alarm action trigger. You cannot remove the last one. If you try to remove the last alarm action trigger, you will get the following error message:

You cannot remove this AlarmActionTrigger. The AlarmAction must have at least one AlarmActionTrigger.

Retrieving events

The Get-VIEvent cmdlet can be used to retrieve information about the events on a vCenter Server system. The syntax of the Get-VIEvent cmdlet is as follows:

```
Get-VIEvent [[-Entity] <VIObject[]>] [-Start <DateTime>] [-Finish <DateTime>] [-Username <String>] [-MaxSamples <Int32>] [-Types <EventCategory[]>] [-Server <VIServer[]>] [<CommonParameters>]
```

There are no required parameters for every command.

If you don't specify a value for the -Start, -End, and -MaxSamples parameters, the default maximum number of objects returned will be 100. If you want to specify the maximum value possible for the -MaxSamples parameter, you can use -MaxSamples ([int]::MaxValue). This is a .NET notation and it is the equivalent of 2,147,483,647.

You can specify Error, Info, or Warning as the value of the -Types parameter in order to retrieve the events of the specified types only. For example, to retrieve a maximum of 50 error events from the error events of the last 24 hours, you can use the following command:

```
PowerCLI C:\> $StartDate = (Get-Date).AddDays(-1)
PowerCLI C:\> Get-VIEvent -Start $StartDate -Types Error -MaxSamples 50 |
>> Select-Object -Property CreatedTime,FullFormattedMessage
>>
```

The output of the preceding command lines is as follows:

The events returned by the Get-VIEvent cmdlet are of different types, depending on the type of the event. To get a sorted list of some of the names of the event types in your environment, you can use the following command lines:

```
PowerCLI C:\> Get-VIEvent -MaxSamples 500 |
>> Select-Object -Property @{
>> Name = "TypeName"
>> Expression = {$_.GetType().Name}
>> }|
>> Sort-Object -Property TypeName -Unique |
>> Format-Wide -Property TypeName -Column 2
>>
```

The output of the preceding command is as follows:

AlarmAcknowledgedEvent AlarmStatusChangedEvent

DatastoreFileDeletedEvent DatastoreIORMReconfiguredEvent

DrsVmMigratedEvent DrsVmPoweredOnEvent
DvsPortLinkDownEvent DvsPortLinkUpEvent
EventEx NoAccessUserEvent

 ${\tt NonVIWorkloadDetectedOnDatastoreEvent} \quad {\tt ScheduledTaskCompletedEvent}$

ScheduledTaskStartedEvent TaskEvent

UserLoginSessionEvent UserLogoutSessionEvent
VmAcquiredTicketEvent VmBeingHotMigratedEvent

VmDasResetFailedEvent VmEmigratingEvent
VmMessageEvent VmPoweredOnEvent

VmReconfiguredEvent VmResettingEvent VmResourceReallocatedEvent

VmStartingEvent

Play with the value of the -MaxSamples parameter to get a large or small number of event type names.

You can use the names of the event types to filter for certain events. For example, to retrieve events related to the creation of a virtual machine, you can filter for the VmBeingDeployedEvent, VmCreatedEvent, VmRegisteredEvent, or VmClonedEvent event type names.

You can use these event type names, to find the person who created the virtual machine. In this case, you have to specify the virtual machine as the value of the - Entity parameter. You have to use the -MaxSamples parameter with a large value, otherwise you might not find the event if the virtual machine was not created recently. The output of the Get-VIEvent cmdlet must be piped to the Where-Object cmdlet to filter for the events related to the creation of the virtual machine. In the following example, the event related to the creation of the virtual machine VM1 will be retrieved:

```
PowerCLI C:\> $VM = Get-VM -Name VM1
PowerCLI C:\> Get-VIEvent -Types Info -Entity $VM -MaxSamples
([int]::MaxValue) |
>> Where-Object {
>> $_.Gettype().Name -eq "VmBeingDeployedEvent" -or
>> $_.Gettype().Name -eq "VmCreatedEvent" -or
>> $_.Gettype().Name -eq "VmRegisteredEvent" -or
>> $_.Gettype().Name -eq "VmClonedEvent" -or
>> $_.Gettype().Name -eq "VmClonedEvent"
>> }
```

The output of the preceding command is as follows:

```
SrcTemplate : VMware.Vim.VmEventArgument
```

Template : True
Key : 2652
ChainId : 2649

CreatedTime : 12/11/2013 6:00:28 PM

UserName : root

Datacenter : VMware.Vim.DatacenterEventArgument

ComputeResource : VMware.Vim.ComputeResourceEventArgument

Host : VMware.Vim.HostEventArgument
Vm : VMware.Vim.VmEventArgument

Ds :

Dvs

FullFormattedMessage: Deploying VM5 on host 192.168.0.134 in New York from template Windows2012Template

ChangeTag :
DynamicType :
DynamicProperty :

Now, you know that the virtual machine VM1 was created by the user root on December 11, 2013, at 6:00:28 P.M.

Summary

In this chapter, you learned how to use PowerCLI to manage your vSphere environment with vCenter Server. Topics such as retrieving privileges, using roles, using permissions, managing licenses, using the LicenseDataManager object, modifying alarm definitions, creating alarm actions, creating alarm action triggers, retrieving events, and configuring the vCenter Server mail server and sender settings were discussed.

In the next chapter, we will learn how to report with PowerCLI.

10Reporting with PowerCLI

Creating reports is the task that most new PowerCLI users start with. Your boss wants a report of all the new virtual machines created last month or a list of all the datastores that are over 90 percent full. PowerCLI will make it easy for you to create such a report and save it as a CSV or HTML file. In this chapter, you will learn some techniques to create reports.

The following topics are covered in this chapter:

- Retrieving log files
- Creating log bundles
- Performance reporting
- Exporting reports to CSV files
- Generating HTML reports
- Sending reports by e-mail
- Reporting the health of your vSphere environment with vCheck
- Using PowerGUI

Retrieving log files

ESXi servers and vCenter Servers generate log files. Some of these log files can be retrieved using PowerCLI. The Get-LogType cmdlet can be used to retrieve information about the available log file types on a virtual machine host or vCenter Server. The syntax of the Get-LogType cmdlet is as follows:

Get-LogType [[-VMHost] <VMHost[]>] [-Server <VIServer[]>]
[<CommonParameters>]

There are no required parameters. If you specify a value for the -VMHost parameter, the available log types on the host will be retrieved. If you omit the -VMHost parameter, the available log types on the default vCenter Server will be retrieved.

In the first example, we will retrieve the available log types on the vCenter Server:

```
PowerCLI C:\> Get-LogType
```

The output of the preceding command is as follows:

```
Key
                                 Summarv
                                 -----
vpxd:vpxd-23.log
                                 vCenter server log in 'plain' format
vpxd:vpxd-alert-21.log
                                 vCenter server log in 'plain' format
                                 vCenter server log in 'plain' format
vpxd:vpxd-alert.log
vpxd:vpxd-profiler-46.log
                                vCenter server log in 'plain' format
vpxd:vpxd-profiler.log
                                 vCenter server log in 'plain' format
vpxd:vpxd.log
                                 vCenter server log in 'plain' format
                                 vCenter server log in 'plain' format
vpxd:vpxd cfg.log
vpxd-profiler:vpxd-profiler-4... vpxd-profiler
vpxd-profiler:vpxd-profiler.log vpxd-profiler
```

In the second example, we will retrieve the available log types on the ESXi server 192.168.0.133:

```
PowerCLI C:\> Get-LogType -VMHost 192.168.0.133
```

The output of the preceding command is as follows:

```
Key Summary
---
hostd Server log in 'plain' format
vmkernel Server log in 'plain' format
vpxa vCenter agent log in 'plain' format
```

Now that you know the available log types, you can use them as input for the Get-Log cmdlet and retrieve entries from these logs or the entire bundle of log files. The Get-Log cmdlet has the following syntaxes:

```
Get-Log [-Key] <String[]> [[-VMHost] <VMHost[]>] [[-StartLineNum]
<Int32>] [[-NumLines] <Int32>] [-Server <VIServer[]>]
[<CommonParameters>]
```

```
Get-Log [[-VMHost] <VMHost[]>] [-Bundle] [-DestinationPath] <String>
[-Server <VIServer[]>] [-RunAsync] [<CommonParameters>]
```

The -Key or -DestinationPath parameter is required to retrieve the log files.

In the next example, we will retrieve the vmkernel log file from the host 192.168.0.133:

```
PowerCLI C:\> Get-Log -Key vmkernel -VMHost 192.168.0.133 |
>> Select-Object -ExpandProperty Entries
>>
```

The output of the preceding command is as follows:

```
2014-01-27T17:52:56.774Z cpu1:32881)ScsiDeviceIO: 2337: Cmd(0x412e8089cf00) 0x1a, CmdSN 0x2f0f from world 0 to dev "mpx.vmhba1:C0:T1:L0" failed H:0x0 D:0x2 P:0x0 Valid sense data: 0x5 0x24 0x0.
```

```
2014-01-27T17:52:56.777Z cpu0:32783)NMP:
nmp_ThrottleLogForDevice:2321: Cmd 0x1a (0x412e8089cf00, 0) to dev
"mpx.vmhba32:C0:T0:L0" on path "vmhba32:C0:T0:L0" Failed: H:0x0
D:0x2 P:0x0 Valid sense data: 0x5 0x20 0x0. Act:NONE
```

VMware Knowledge Base article *Interpreting SCSI sense codes in VMware ESXi and ESX (289902)* at http://kb.vmware.com/kb/289902 will give you a detailed explanation on the SCSI code that are in the output of the preceding command.

If you want to search a log file for certain strings or patterns, you can use the PowerShell Select-String cmdlet to do so. The syntax of this cmdlet is given as follows:

```
Select-String [-Pattern] <String[]> [-Path] <String[]> [-AllMatches]
[-CaseSensitive] [-Context <Int32[]>] [-Encoding <String>] [-Exclude
<String[]>] [-Include <String[]>] [-List] [-NotMatch] [-Quiet]
[-SimpleMatch] [<CommonParameters>]
```

```
Select-String [-Pattern] <String[]> [-AllMatches] [-CaseSensitive]
[-Context <Int32[]>] [-Encoding <String>] [-Exclude <String[]>]
[-Include <String[]>] [-List] [-NotMatch] [-Quiet] [-SimpleMatch]
-InputObject <PSObject> [<CommonParameters>]
```

```
Select-String [-Pattern] <String[]> [-AllMatches] [-CaseSensitive]
[-Context <Int32[]>] [-Encoding <String>] [-Exclude <String[]>]
[-Include <String[]>] [-List] [-NotMatch] [-Quiet] [-SimpleMatch]
-LiteralPath <String[]> [<CommonParameters>]
```

The -InputObject parameter is required in order to search a log file, and it accepts input from the pipeline **ByValue**. The -Pattern or -SimpleMatch parameter is also required. If you want to specify a filename to search through the content of the file, you have to use the -Path or -LiteralPath parameter. If you want to use **wildcards**, you have to use the -Path parameter. The value of the -LiteralPath parameter is used exactly as it is typed. No characters are interpreted as wildcards.

As an example of the preceding Select-String cmdlet syntax, you can use the following command to retrieve all of the lines from the vmkernel log file in the host 192.168.0.133 that contain the word WARNING:

```
PowerCLI C:\> Get-Log -Key vmkernel -VMHost 192.168.0.133 |
>> Select-Object -ExpandProperty Entries |
>> Select-String -SimpleMatch 'WARNING'
>>
```

In the preceding example, the command uses the <code>-SimpleMatch</code> parameter to search for a string. If you want to search for a **regular expression**, you should use the <code>-Pattern</code> parameter instead.

If you want to retrieve a specific number of lines from the log file, you can use a combination of the <code>-StartLineNum</code> and <code>-NumLines</code> parameters. First you might want to know how many lines the log file contains. This number is easily retrieved using the following command:

```
PowerCLI C:\> Get-Log -Key vmkernel -VMHost 192.168.0.133 |
>> Select-Object -Property StartLineNum, LastLineNum
>>
```

The output of the preceding command is as follows:

StartLineNum	LastLineNum
1	3365

To retrieve only the last 100 entries of the log file, you can now use the following command:

```
PowerCLI C:\> Get-Log -Key vmkernel -VMHost 192.168.0.133
-StartLineNum 3266 -NumLines 100 |
>> Select-Object -ExpandProperty Entries
>>
```

If you omit the -VMHost parameter, you will retrieve vCenter Server log files. In the following example, we will retrieve the contents of the vpxd.log file:

```
PowerCLI C:\> Get-Log -Key vpxd:vpxd.log |
>> Select-Object -ExpandProperty Entries
```

Creating log bundles

VMware Technical Support might ask for a log bundle when you submit a support request. You can create a log bundle from the vCenter Server's log files with the following command:

```
PowerCLI C:\> Get-Log -Bundle -DestinationPath c:\
The output of the preceding command is as follows:

Data
----
C:\vcsupport-52387fc8-52de-113b-7f28-1908e9ffa0d7.zip

In the following command, we will create a log bundle from the log files on the host 192.168.0.133:

PowerCLI C:\> Get-Log -VMHost 192.168.0.133 -Bundle -DestinationPath c:\
```

The output of the preceding command is as follows:

```
Data
----
C:\vmsupport-52348fab-b7a7-97f1-bf2a-719b91ab84b3.tgz
```

Performance reporting

If your users complain that their virtual machines are running slow, you may want to find the reason for their complaints. You also want to know how your vSphere environment is performing, to see if additional hosts are necessary to keep your systems running smoothly. In PowerCLI, you can use the Get-Stat cmdlet to retrieve statistical information that is available on the ESXi hosts and vCenter Servers.

VMware vCenter Servers keep statistical information about the performance of the virtual machines, hosts, resource pools, and so on. This statistical information is retrieved by the hosts in real time and aggregated in four **statistical intervals** on the vCenter Servers. The real-time information is collected by the hosts with a collection frequency of 20 seconds and kept for 1 hour. The aggregated information is stored in the database of the vCenter Server.

Retrieving the statistical intervals

Information about the statistical intervals can be retrieved using the Get-StatInterval cmdlet. The syntax of this cmdlet is as follows:

```
Get-StatInterval [[-Name] <String[]>] [[-SamplingPeriodSecs]
<Int32[]>] [-Server <VIServer[]>] [<CommonParameters>]
```

There are no required parameters; without parameters, the <code>Get-StatInterval</code> cmdlet gives information about all of the four statistical intervals. The default output is in seconds. To make the output more useful, we can use calculated properties to convert the output <code>Sampling Period</code> to <code>Minutes</code> and <code>Storage Time</code> to <code>Days</code> using the following command lines:

```
PowerCLI C:\> Get-StatInterval |
>> Select-Object -Property Name,
>> @{Name="Sampling Period (Minutes)"
>> Expression={($_.SamplingPeriodSecs)/60}},
>> @{Name="Storage Time (Days)"
>> Expression={$_.StorageTimeSecs/(60*60*24)}}
```

The output of the preceding command is as follows:

Name	Sampling Period	(Minutes)	Storage	Time	(Days)
Past day		5			1
Past week		30			7
Past month		120			30
Past year		1440			365

The sampling period for the real-time interval is 20 seconds. As you can see in the preceding output, the sampling periods for the statistical intervals increase from 5 minutes in Past day to 30 minutes in Past week, 2 hours in Past month, and 1 day in Past year. This means that, if you retrieve an average CPU usage value in the past day's statistical interval, the value is an average of 5 minutes.

During the aggregation process, the data from the previous statistical interval is taken to create the data for the next statistical interval. For example, to calculate an average value for the past week's statistical interval, the average value calculated is an average of the six average values from the same time period in the past day's statistical interval.

Performance data is retrieved for **metric groups** such as CPU, datastore, disk, memory, network, power, and system.

Depending on the **statistics level** of a statistical interval, the approximate number of metrics is aggregated and stored in the vCenter Server database. Statistics Level 4 stores all metrics, while statistics Level 1 stores the least metrics.

The following screenshot shows the **Statistics intervals** settings in **vCenter Server Settings**, with a different **Statistics Level** for each statistics interval:



A statistics level must have the same value as the statistics level of the previous interval, or a lower one.



The statistics levels in the screenshot are just an example and are not recommended values! Try to keep the statistics levels low, otherwise your vCenter Server database will grow larger and the aggregation rollup jobs will take a lot of time to complete. The default setting is 1 for every statistics level interval! Higher levels include more metrics. Each statistics level includes all of the metrics of the lower statistics levels and includes additional metrics. Statistics Level 4 contains all metrics that are supported by the vCenter Server. More information about the statistics levels and the metrics included in each level can be found in the VMware vSphere documentation at the following link:

http://pubs.vmware.com/vsphere-55/topic/com.vmware.vsphere.monitoring.doc/GUID-25800DE4-68E5-41CC-82D9-8811E27924BC.html

Retrieving performance statistics

The Get-Stat cmdlet retrieves the statistical information available on a vCenter Server system. The syntax of this cmdlet is as follows:

```
Get-Stat [-Entity] <VIObject[]> [-Common] [-Memory] [-Cpu] [-Disk]
[-Network] [-Stat <String[]>] [-Start <DateTime>] [-Finish
<DateTime>] [-MaxSamples <Int32>] [-IntervalMins <Int32[]>]
[-IntervalSecs <Int32[]>] [-Instance <String[]>] [-Realtime]
[-Server <VIServer[]>] [<CommonParameters>]
```

The -Entity parameter is required. The value of this parameter must be the object whose performance statistics you want to retrieve.

In the following example, we will retrieve the performance statistics for the host 192.168.0.133 and for every metric ID only one sample is shown:

```
PowerCLI C:\> Get-Stat -Entity (Get-VMHost -Name 192.168.0.133)
-MaxSamples 1
```

The output of the preceding command is as follows:

MetricId	Timestamp		Value	Unit	Instance
cpu.usage.average	12/14/2013 1:00:0	MA 0	2.9	%	
cpu.usagemhz.average	12/14/2013 1:00:0	MA 0	132	MHz	
mem.usage.average	12/14/2013 1:00:0	MA 0	49.5	%	
disk.usage.average	12/14/2013 1:00:0	MA 0	54	KBps	
net.usage.average	12/14/2013 1:00:0	MA 0	91	KBps	
sys.uptime.latest	12/14/2013 1:00:0	MA 0	646483	second	

In the next example, three samples of the real-time values for the cpu.usage. average metric are shown for the host 192.168.0.133. This host has two CPUs, Instance 0 and Instance 1. The rows in the following output where the instance is empty are average values of the two instances:


```
PowerCLI C:\> Get-Stat -Entity (Get-VMHost -Name 192.168.0.133) -Stat
cpu.usage.average -Realtime -MaxSamples 3 |
>> Sort-Object -Property Timestamp -Descending
>>
```

The output of the preceding command is as follows:

MetricId	Timestamp		Value	Unit	Instance
cpu.usage.average	12/14/2013 12:29:	40 PM	72.88	8	1
cpu.usage.average	12/14/2013 12:29:	40 PM	3.78	8	0
cpu.usage.average	12/14/2013 12:29:	40 PM	8.33	%	
cpu.usage.average	12/14/2013 12:29:	20 PM	38.65	8	0
cpu.usage.average	12/14/2013 12:29:	20 PM	10.27	%	1
cpu.usage.average	12/14/2013 12:29:	20 PM	24.46	%	
cpu.usage.average	12/14/2013 12:29:	00 PM	39.86	%	0
cpu.usage.average	12/14/2013 12:29:	00 PM	8.44	%	1
cpu.usage.average	12/14/2013 12:29:	00 PM	24.15	%	

The preceding output shows a time difference of 20 seconds between the intervals. The times in the Timestamp column are the times when the interval finishes.

The following screenshot shows a Realtime Summary performance graph report from the vSphere Web Client for the CPU usage of the host 192.168.0.133:



Retrieving metric IDs

If you want to know which metric IDs are available for an object in a certain statistical interval, you can use the <code>Get-StatType</code> cmdlet to retrieve them. The syntax of the <code>Get-StatType</code> cmdlet is as follows:

```
Get-StatType [[-Name] <String[]>] [-Entity] <InventoryItem[]> [-Start
<DateTime>] [-Finish <DateTime>] [-Interval <StatInterval[]>]
[-Realtime] [-Server <VIServer[]>] [<CommonParameters>]
```

The -Entity parameter is required to retrieve metric IDs.

In the next example, we will retrieve the available metric IDs for the host 192.168.0.133 in the real-time statistical interval and return them after sorting:

```
PowerCLI C:\> Get-StatType -Entity (Get-VMHost -Name 192.168.0.133)
-RealTime |
>> Sort-Object
>>
```

The output of the preceding command is as follows:

```
cpu.coreUtilization.average
cpu.costop.summation
cpu.demand.average
cpu.idle.summation
cpu.latency.average
cpu.ready.summation
cpu.reservedCapacity.average
cpu.swapwait.summation
cpu.totalCapacity.average
cpu.usage.average
cpu.usagemhz.average
cpu.usagemhz.average
cpu.used.summation
cpu.utilization.average
cpu.wait.summation
```

I have aborted the output of the preceding command after the CPU counter group (or the metric group) in this chapter because the command returned 168 metric IDs in total. The following are other counter groups besides CPU: datastore, disk, mem, net, power, rescpu, storageAdapter, storagePath, and sys.

Exporting reports to CSV files

If your boss asks for a report, he probably wants it in the form of a spreadsheet. The easiest way to create a spreadsheet from a PowerCLI report is to export it to a CSV file. This CSV file can be imported in a spreadsheet. Another use case for CSV files is creating export files of one system that you can use later to import into another system. For example, you can use CSV files to export the settings of vCenter Server and import them in another vCenter Server. PowerShell contains the Export-CSV cmdlet to create CSV files.

The syntax of the Export-CSV cmdlet is as follows:

```
Export-Csv [[-Path] <String>] [[-Delimiter] <Char>] [-Append]
[-Encoding <String>] [-Force] [-LiteralPath <String>] [-NoClobber]
[-NoTypeInformation] -InputObject <PSObject> [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Export-Csv [[-Path] <String>] [-Append] [-Encoding <String>] [-Force]
[-LiteralPath <String>] [-NoClobber] [-NoTypeInformation]
[-UseCulture] -InputObject <PSObject> [-Confirm] [-WhatIf]
[<CommonParameters>]
```

The -InputObject parameter is required and it accepts input from the pipeline ByValue and ByPropertyName. The first parameter set is for the -Delimiter parameter. The second parameter set is for the -UseCulture parameter.

In the following example, we will create a CSV file containing the virtual machines in your environment. The output of this script has some problems that will be discussed later in this section.

```
PowerCLI C:\> Get-VM | Export-CSV -Path c:\VMs.csv
```

If you open the c:\VMs.csv file in Notepad or with the Get-Content cmdlet, you will see that the first line contains the type of the objects in the file:

#TYPE

```
VMware.VimAutomation.ViCore.Impl.V1.Inventory.VirtualMachineImpl
```

Your boss doesn't want to know this. You can prevent the creation of this first line by using the Export-CSV -NoTypeInformation parameter.

The second problem is the comma that is used as a delimiter between the columns in the CSV file. In a lot of cultures, the default delimiter for a CSV file is another character. For example, the default CSV file delimiter in the Netherlands, where I live, is a semicolon. There are two possible solutions for this problem:

• You can use the -Delimiter parameter and specify the delimiter character as a value. For example:

```
PowerCLI C:\> Get-VM |
>> Export-CSV -Path c:\VMs.csv -Delimiter ';'
>>
```

Another and in my opinion better solution is to use the -UseCulture parameter. This creates the CSV file with the correct delimiter for the current culture on the system where the script is running. Combined with the -NoTypeInformation parameter, the command becomes something like this:

```
PowerCLI C:\> Get-VM |
>> Export-CSV -Path c:\VMs.csv -UseCulture -NoTypeInformation
>>
```

The last problem with the Export-CSV cmdlet is that the values of properties that contain array objects are not shown in the CSV file. The file only shows the type of the property. For example, the column HardDisks is filled with the following value:

```
VMware.VimAutomation.ViCore.Types.V1.VirtualDevice.HardDisk[]
```

You can use the .NET [string]::Join() method to solve this problem. This method requires two parameters. The first parameter is a character used as a delimiter. The second parameter is the array of objects you want to join.

The next example shows you how to get the names of the hard disks in the CSV file. You now have to use the Select-Object cmdlet to specify all of the objects that you want to return in the CSV file. For the HardDisks column, you have to create a calculated property. The following example will only return the name of the virtual machines and the hard disks:

```
PowerCLI C:\> Get-VM |
>> Select-Object -Property Name,
>> @{Name="HardDisks"; Expression={ [string]::
Join(',',$_.HardDisks) }} |
>> Export-CSV -Path c:\VMs.csv -UseCulture -NoTypeInformation
>>
```

The next screenshot shows the exported CSV file after it's imported into a spreadsheet. The virtual machines are from my home lab that I used to write this book:

	А	В
1	Name	HardDisks
2	DC1	Hard disk 1
3	DNS1	Hard disk 1
4	test2	Hard disk 1
5	vCenter Mobile Access	Hard disk 1
6	VM1	Hard disk 1
7	VM2	Hard disk 1,Hard disk 2
8	VM4	
9	VM7	
10	WindowsServer2012	Hard disk 1

Generating HTML reports

CSV files are nice, but HTML files are more impressive. This section will show you how to create nice looking HTML files from your reports. PowerShell gives you the ConvertTo-Html cmdlet to do this. The syntax of this cmdlet is as follows:

```
ConvertTo-Html [[-Property] <Object[]>] [[-Head] <String[]>]
[[-Title] <String>] [[-Body] <String[]>] [-As <String>] [-CssUri
<Uri>] [-InputObject <PSObject>] [-PostContent <String[]>]
[-PreContent <String[]>] [<CommonParameters>]
```

```
ConvertTo-Html [[-Property] <Object[]>] [-As <String>] [-Fragment]
[-InputObject <PSObject>] [-PostContent <String[]>] [-PreContent
<String[]>] [<CommonParameters>]
```

There are no required parameters. The first parameter set creates an entire HTML page. The second parameter set creates an HTML fragment.

In the first example, you will create a report about the connection state of the hosts. The ConvertTo-Html cmdlet doesn't have a -Path parameter to specify a filename. This problem can be solved by piping the output to the Out-File cmdlet, as shown in the following code:

```
Get-VMHost |
Select-Object -Property Name, ConnectionState |
Sort-Object -Property Name |
ConvertTo-Html |
Out-File -FilePath c:\VMHosts.html
```

You can open the c:\VMHosts.html file in a browser using the following command:

PowerCLI C:\> Start-Process -FilePath c:\VMHosts.html



Be warned that the first time you use the ConvertTo-Html cmdlet, you might be disappointed because the output doesn't look nice by default.

The following screenshot shows the output of the preceding command:

Name ConnectionState 192.168.0.133 Connected 192.168.0.134 Maintenance

To make the output look nicer, it is better to create an HTML fragment from the script and make the HTML header yourself. To make an HTML fragment, you have to use the ConvertTo-Html -Fragment parameter. To create the HTML header, you can use a PowerShell here-string.

In the next example, an HTML header and tail are created with here-string cmdlets. The table is created using ConvertTo-Html -Fragment. If the host's connection state is Connected, the color of the text is changed to green. If the connection state is Disconnected, the color is changed to red. A **Cascading Style Sheet** or **CSS** is used to provide the background and foreground colors for the HTML body and table. After creating the HTML page, a web browser is started to display the page.

```
# The path to the HTML file
$FilePath = 'c:\VMHostsConnectionState.html'

# Create the HTML header
$Header = @"

<!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"
"http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">
<html xmlns="http://www.w3.org/1999/xhtml" xml:lang="en"
lang="en">
<head>
<title>VMware vSphere Hosts ConnectionState Report</title>
<style type="text/css">
<!--
body {
   background-color: lightgray</pre>
```

```
}
table {
 background-color: white
th {
 color: white;
 background-color: darkgray
tr {
 background-color: white
</style>
</head>
<body>
<h2>VMware vSphere Hosts ConnectionState Report</h2>
# Create the VMHost ConnectionState report table
$Fragment = Get-VMHost |
Select-Object -Property Name, ConnectionState |
Sort-Object -Property Name |
ConvertTo-Html -Fragment
# Create the tail of the HTML page
$Tail = @"
</body>
</html>
# Combine all of the pieces into one HTML page
# Color Connected green and Disconnected red
$HTML = $Header
$HTML += $Fragment.Replace('Connected',
 'Connected').
Replace('Disconnected',
  'Disconnected')
$HTML += $Tail
$HTML | Out-File -FilePath $FilePath
# Open a web browser and display the page
Start-Process -FilePath $FilePath
```

The following screenshot shows the output of the preceding script. Do you agree that it looks much better than the first HTML report?



Using fragments, you can easily create one report with different segments for hosts, virtual machines, networks, and so on.

Sending reports by e-mail

After creating a report, you might want to send it to your boss or to yourself. The PowerShell Send-MailMessage cmdlet can send e-mail messages using an SMTP server. The syntax of this cmdlet is as follows:

```
Send-MailMessage [-To] <String[]> [-Subject] <String> [[-Body]
<String>] [[-SmtpServer] <String>] [-Attachments <String[]>] [-Bcc
<String[]>] [-BodyAsHtml] [-Cc <String[]>] [-Credential
<PSCredential>] [-DeliveryNotificationOption
<DeliveryNotificationOptions>] [-Encoding <Encoding>] [-Port <Int32>]
[-Priority <MailPriority>] [-UseSsl] -From <String>
[<CommonParameters>]
```

The -From, -To, and -Subject parameters are required to send a report by e-mail. You can use the PowerShell \$PSEmailServer preference variable for the SMTP server. If the \$PSEmailServer variable is not set, you have to use the -SmtpServer parameter.

You can send a report by putting it in the body of the e-mail or as an attachment. If the report is an HTML document and you want to send it in the body of the e-mail, you have to use the -BodyAsHtml parameter.

In the first example, the HTML report file that was created in the previous section is sent in the body of an e-mail. In this example, we will use splatting to specify the parameters. The PowerShell Out-String cmdlet is used to create a single string from the HTML content.

The SMTP server used in this environment does not require authentication or SSL and uses the default port 25. Additional parameters may be required in some environments.

```
$Parameters = @{
   From = 'admin@blackmilktea.com'
   To = 'manager@blackmilktea.com'
   Subject = 'VMware vSphere hosts Connection State report'
   Body = Get-Content -Path 'c:\VMHostsConnectionState.html' | Out-String
   BodyAsHtml = $true
   SmtpServer = 'smtpserver.blackmilktea.com'
}
Send-MailMessage @Parameters
```

You don't have to create a file before you can send an e-mail. You can also use the content of a variable. In the second example, we will use the content of the \$HTML variable (created in the previous section of this chapter) as the body of the e-mail:

```
$Parameters = @{
   From = 'admin@blackmilktea.com'
   To = 'manager@blackmilktea.com'
   Subject = 'VMware vSphere hosts Connection State report'
   Body = $HTML
   BodyAsHtml = $true
   SmtpServer = 'smtpserver.blackmilktea.com'
}
Send-MailMessage @Parameters
```

In the third example, we will send the HTML report created in the previous section as an attachment:

```
$Parameters = @{
   From = 'admin@blackmilktea.com'
   To = 'manager@blackmilktea.com'
   Subject = 'VMware vSphere hosts Connection State report'
   Body = 'VMware vSphere hosts Connection State report is attached to
this email.'
   Attachment = 'c:\VMHostsConnectionState.html'
   SmtpServer = 'smtpserver.blackmilktea.com'
}
Send-MailMessage @Parameters
```

Reporting the health of your vSphere environment with vCheck

In this section of the book *Learning PowerCLI*, I want to introduce a PowerCLI script that every vSphere admin should use. The **vCheck** script written by Alan Renouf can check your vSphere environment for various configuration issues and report them in an HTML format. The vCheck script reports several issues such as VMs having CD-ROMs connected, VMs with CPU or memory reservations configured, VMs ballooning or swapping, VMs with less than 100 MB free space on a disk, VMs with an old hardware version, and VMs that have no VMware Tools installed. These are just a few examples. The script reports many more issues.

The script is written in a modular way, and it uses a plugin for every check it performs. It is very easy to write your own plugins and add them to the script. There are plugins created to check other technologies such as Microsoft Exchange. Reading the vCheck plugins is a good way to see how the checks are implemented and learn from PowerCLI scripts created by other people in the community. The vCheck script is meant to run daily as a scheduled task so that you can receive the results in your mailbox.

You can find Alan's blog post about vCheck at the following link:

http://www.virtu-al.net/vcheck-pluginsheaders/vcheck/

The vCheck script is now maintained at GitHub and can be downloaded from the following link:


https://github.com/alanrenouf/vCheck-vSphere

In the next screenshot, you will find some of the issues the vCheck script in my home lab found:

VMs in Inconsistent folders	•
The Following VM's are not store trvina to locate them from the dat	ed in folders consistent to their names, this may cause issues when iastore manually
VM	Path
VM7	[Datastore2] VM3
VM1	[Datastore2] VM5
DNS1	[Datastore2] vm7
test2	[Cluster01_Vmfs01] test1
should be installed	Status
Name DC1	toolsNotInstalled
VM2	toolsNotInstalled
DC1	toolsNotInstalled
VM4	toolsNotInstalled
VM1	toolsNotInstalled
DNS1	toolsNotInstalled
WindowsServer2012	toolsNotInstalled
WindowsServer2012	tooisivotinstalled

Using PowerGUI

PowerGUI is a combination of PowerGUI Script Editor and PowerGUI Administrative Console. You can use the PowerGUI Script Editor to edit your PowerCLI scripts. The script editor will give you syntax highlighting and tab completion features. The PowerGUI Administrative Console is a graphical user interface for running your PowerCLI scripts. You can create your own PowerCLI scripts and add them to the PowerGUI Administrative Console. Also, there are PowerPacks that you can download from the PowerGUI website, and they will extend the PowerGUI Administrative Console. For VMware, PowerPacks are already there for VMware vSphere Management, Image Builder and Auto Deploy, and VMware LabManager Administration. These PowerPacks can be used to create a lot of different reports and to perform actions on vSphere objects just as in the vSphere Client. You can examine the PowerCLI code that is behind a report or an action. So, if you want to know how things work, you can easily find out. You can download PowerGUI for free from http://www.powergui.org/.



Messages

X Clear All

Message

⚠ The 'Host' property of VirtualMachine type is deprecated. Use the

The 'Hostld' property of VirtualMachine type is deprecated. Use

- ₽ X

۸

The next screenshot shows the PowerGUI Administrative Console window:

Summary

2 objects

Resource Pools
Virtual Machines
Templates

Networks

Tasks

Log Files

Datastores Files

Custom Attributes

In this chapter, you learned techniques to create reports with PowerCLI. You saw how to create log files and log bundles using the Get-Log cmdlet. Performance reporting using the Get-Stat cmdlet was discussed. CSV files and HTML reports were created using the Export-CSV and ConvertTo-Html cmdlets, and they were sent by e-mail using the Send-MailMessage cmdlet. Then you were introduced to the vCheck script to report common issues in your vSphere environment, and finally, you learned how to use PowerGUI.

This was the last chapter of the book *Learning PowerCLI*. I hope that you enjoyed reading this book, and I hope that you will use PowerCLI to make your job as a vSphere administrator easier.

If you have questions about PowerCLI or PowerCLI scripts that you are writing, the best place to ask your questions is the PowerCLI community in the VMware VMTN Communities at http://www.vmware.com/go/powercli.

Go to the **Discussions** tab and click on **Start a discussion** in the **Actions** section, or use the PowerCLI command <code>Get-PowerCLICommunity</code> to open the PowerCLI community from your PowerCLI session. You may get an answer in a few minutes.

You can also help other people by answering their questions. Answering questions is a great way to improve your own PowerCLI skills.

Index

Symbols \$esxcli.hardware.cpu command 127 \$HostService variable 114 \$String variable 64 -Address parameter 231 -AlarmDefinition parameter 308 -BodyAsHtml parameter 336 -Cluster parameter 273 -Configuration parameter 281 -Confirm:\$false parameter 104 -Credential parameter 99 -DatastoreCluster parameter 242 -Datastore parameter 238 -DeletePermanently parameter 184 -Destination parameter 279 -DrsRecommendation property 275 -Enabled parameter 264 -Entity parameter 104, 328, 330 {eventDescription} variable 309 -FilterScript parameter 79 -Floppy parameter 164 -FullScreen parameter 183 -HardDisk parameter 165 -HostService parameter 111 -Id parameter 228 -IncludeEqual parameter 87 -InputObject parameter 324, 331 -IScsiHba parameter 231 -KeepTogether parameter 264 -LiteralPath parameter 324 -Location parameter 97, 252

-MaintenanceMode parameter 238

-MultipathPolicy parameter 234

-Name parameter 130, 290

-Name parameters 96

-NetworkAdapter parameter 166 -PassThru parameter 91 -Path parameter 324 -Pattern parameter 324 -Permission parameter 296 -Profile parameter 105 -Replace operator 68 -ResourcePool parameter 140, 279 -ScriptType parameter 180 -ScsiLun parameter 234, 235 -ScsiLunPath parameter 236 -SimpleMatch parameter 324 -SoftwareIScsiEnable parameter 231 {targetName} variable 309 -ToUpper operator 68 -UrlOnly parameter 183 -Vmfs parameter 230 -VMHost parameter 100, 187, 228, 325 -VMHostStorage parameter 231 -VM parameter 183

Α

active adapters 190
Add-EsxSoftwareDepot cmdlet 119
Add-Member
properties, adding to objects 90, 91
Add-vCLIfunction function 133, 134
Add-vDSwitchPhysicalNetworkAdapter
cmdlet 211
Add-VDSwitchVMHost cmdlet 211
Affinity Rules 240
AlarmActionTrigger cmdlet 315
alarms
actions, creating 308-310
actions, removing 313

actions, retrieving 312	CIM Indication Subscriptions 102
action triggers, creating 313, 314	ClusterConfigSpecEx object 255, 270
action triggers, removing 315	ClusterDasConfigInfo object 255-257
action triggers, retrieving 314, 315	clusters
configuring 306	configuration issues, retrieving 253
definitions, modifying 308	DPM configuration, retrieving 285
definitions, retrieving 307	HA master, retrieving 252
AliasProperty 67	hosts, moving to 262
allFeasibleDs 259	moving 263
allFeasibleDsWithUserPreference 259	primary hosts 252
AllSigned execution policy 15	removing 286
arrays	retrieving 252
about 49	settings, modifying 254
using 49	cluster settings
AssignedLicense property 300	Datastore heartbeating, configuring
Atomic Test & Set (ATS) 245	258-261
Auto Deploy	HA, disabling 255
configuring 118-124	host monitoring, disabling 255
0 0	host monitoring, enabling 255
В	host profile, associating with cluster 256
_	modifying 254
backtick character (`) 80	VM and application monitoring,
bootOptions.enterBIOSSetup property 153	enabling 256-258
bootOptions property 153	ClusterVmToolsMonitoringSettings
Bypass execution policy 15	object 257
ByPropertyName parameter binding	cmdlets 16
about 75	CodeProperty 67
using 73-75	command-line interface 7
ByValue parameter binding	commands
about 72	running, on guest OS 180
using 71, 72	Common Information Model (CIM)
	Event 102
C	COM objects
	using 92
calculated properties	Compare-Object cmdlet 86
creating 50-52	Connect-VIserver cmdlet 21
canonical name 229	Connect-VIServer cmdlet 17, 19, 24, 46, 47
Cascading Style Sheet (CSS) 334	Connect-VIServer -Menu command 19
CD drive	ConvertTo-Html cmdlet 333
adding 158, 159	ConvertTo-Html -Fragment parameter 334
modifying 164, 165	Copy-DatastoreItem cmdlet 48
removing 167	credential store
certificate warnings	about 19
suppressing 21	using 24, 25
Check and upgrade VMware Tools before	CSV files
each power on checkbox	reports, exporting to 331, 332
enabling 171, 172	reports, exporting to 331, 332

ט	Distributed Power Management (DPM)
1 0 0 0	cluster configuration, retrieving 285
dasConfig property 255, 259	disabling 286
Datastore Cluster	enabling 282, 283
creating 240	hosts, configuring for 284
datastores, adding 243	hosts, putting in standby mode 284
datastores, removing 244	hosts, starting 285
datastores, retrieving 243	hosts, testing for 284
modifying 241, 242	using 282
removing 244	Distributed Resources Scheduler (DRS) 249
retrieving 241	distributed virtual port groups
Datastore heartbeating 258	configuration, exporting 219
Datastore Maintenance Mode 240	configuration, restoring 218
datastores	configuration, rolling back 218
adding, to Datastore Cluster 243	configuring 216
creating 228	creating 214
NFS datastores, creating 229	creating, from export 215, 216
removing 247	creating, from reference group 215
removing, from Datastore Cluster 244	host network adapter, migrating to 220
retrieving 233	Network I/O Control, configuring 219
retrieving, in Datastore Cluster 243	removing 220
upgrading, to VMFS-5 245, 246	renaming 217
DefaultParameterSet parameter set 140	DRS clusters
devices	creating 250
adding, to virtual machine 153	DRS groups
devices, adding to virtual machine	removing 270
CD drive, adding 158, 159	DRS recommendations
CD drive, modifying 164, 165	using 275
floppy drive, adding 157, 158	DRS rules
floppy drive, modifying 164	modifying 274
hard disk, adding 154	removing 274
hard disk, modifying 159, 160	retrieving 272, 273
hard disk, moving to another datastore 161	using 263
modifying 159	Dynamic Resource Scheduling (DRS) 97
network adapter, adding 156	- y () ()
network adapter, modifying 162, 163	E
SCSI controller, adding 155	_
SCSI controller, modifying 161, 162	EnableNetworkResourceManagement()
devices, removing from virtual machine	method 219
CD drive, modifying 165	esxcli
CD drive, removing 167	using, from PowerCLI 125-128
floppy drive, removing 166	esxcli command
hard disk, removing 165	\$esxcli.hardware.cpu command 127
network adapter, removing 166	about 125-129
Disconnect-VIServer cmdlet 22	using, from PowerCLI 125-127
Distributed Management Task Force, Inc.	events
(DMTF) 102	retrieving 316-319
(= <i>)</i>	3

execution policy, PowerShell	using 36-38
AllSigned 15	Get-DatastoreCluster cmdlet 241
Bypass 15	Get-Datastore cmdlet 233
modifying 15, 16	Get-ESXCliCommand function 128
RemoteSigned 15	Get-ExecutionPolicy cmdlet 16
Restricted 15	Get-HAPrimaryVMHost cmdlet 253
Undefined 15	Get-Help cmdlet
Unrestricted 15	using 38, 39
Export-CSV cmdlet 332	Get-LicenseDataManager cmdlet 302
Export-VDPortgroup cmdlet 218	Get-Log cmdlet 322
Export-VDPortGroup cmdlet 220	Get-LogType cmdlet 321
ExtensionData property	Get-Member cmdlet
raw objects, using with 52	using 42, 43
using 52, 53	Get-PowerCLICommunity cmdlet
F	using 41
Г	Get-PowerCLIConfiguration cmdlet 20, 23
Fault Tolerance	Get-PowerCLIHelp cmdlet using 40
configuring 181	Get-PSProvider cmdlet 45
turning off 182	Get-ScsiLun cmdlet 229, 233
turning on 182	Get-ScsiLunPath cmdlet 235
Fibre Channel (FC) 227	Get-StatInterval cmdlet 326
Fibre Channel over Ethernet (FCoE) 227	Get-StatType cmdlet 330
files	Get-VDSwitch cmdlet 205
copying, between datastore and PC 48	Get-VICommand cmdlet 75
Fixed, Most Recently Used (MRU) 233	using 38
floppy drive	Get-VIEvent cmdlet 316
adding 157, 158	Get-View cmdlet
modifying 164	raw objects, using with 52
removing 166	using 53, 54
ForEach-Object cmdlet 79-81	Get-VIObjectByVIView cmdlet
ForEach-Object -Process scriptblock 81	using 56
Format-List cmdlet 26, 37	Get-VIPermission cmdlet 295
Format-Table -AutoSize 254	Get-VIPrivilege cmdlet 288, 291
	Get-VIPrivilege -Role cmdlet 289
G	Get-VIRole cmdlet 291
C (A1	Get-VM cmdlet 25, 37, 39, 71
Get-AlarmAction cmdlet 312	Get-VMHostStorage cmdlet 228
Get-AlarmActionTrigger cmdlet 314	Group-Object cmdlet 85
Get-AlarmDefinition cmdlet 307	guest operating system, virtual machine
Get-Alias cmdlet 52	shutting down 148, 149
Get-ChildItem cmdlet 31 46	GUID Partition Table (GPT) 245
Get-Cluster cmdlet 252	,
get cmdlets 16	Н
Get-Command cmdlet	
about 36, 44	HA
	disabling 255

HA master	attaching, to host 104
retrieving 252	creating 102, 103
hard disk	exporting 108
adding 154	importing 109
modifying 159, 160	testing, for compliance 105
moving, to another datastore 161	working with 101, 102
removing 165	host profiles answer files
hash table	using 107, 108
about 49	hosts
using 49	assigned license keys, removing 301
using, to create object 88, 89	moving, to clusters 262
HBAs 228	putting, in standby mode 284
HBDatastoreCandidatePolicy 259	retrieving 31-33
hBDatastoreCandidatePolicy property 260,	starting 285
261	testing, for DPM 284
HBDatastoreCandidatePolicy property 259	hosts DRS groups
heartbeatDatastore property 260	creating 267
here-string 71	modifying 268
High Availability (HA) 97, 249	retrieivng 267
host	virtual machines, adding 268
adding, to VMware vCenter server 96-99	virtual machines, removing 269
removing, from VMware vCenter Server	host services
134, 135	host firewall, configuring 114
host containers	host firewall default policy, modifying 115
license keys, associating with 302	host firewall default policy, obtaining 115
hostMonitoring property 255	host firewall exceptions, modifying 117
host network adapters	host firewall exceptions, obtaining 116, 117
configuring 194	information, retrieving from 110
creating 192	restarting 112
NIC Teaming, configuring 196, 197	starting 111
removing 196	startup policy, modifying 113, 114
retrieving 193	stopping 112
using 192	working with 110
host network adapters configuration	HTML reports
about 194	generating 333, 336
duplex setting 194	8
management network, configuring 195	
network speed, configuring 194	•
vMotion, configuring 195	Image Builder
host networking	configuring 119, 120
configuring 221, 222	installation, PowerCLI
host profiles	steps 9-14
answer files, using 107	Internet Small Computer System
applying, to cluster 106	Interface (iSCSI) 227
applying, to host 106	Invoke-VMScript cmdlet 180
associating, with cluster 256	IscsiManager BindVnic() method 231
attaching, to cluster 103, 104	-
5	

J	assigned licenses, retrieving 300
Samuel a Common 100	assigning, to hosts 299
jumbo frames 190	keys, adding to license inventory 297
L	keys, removing from license inventory 299
L	keys, retrieving from license inventory 298
Length property 66	managing 297
LicenseAssignmentManager.Query	list() method 127
AssignedLicenses() method 300	log bundles
LicenseAssignmentManager.Remove	creating 325
AssignedLicense() method 301	log files
LicenseAssignmentManager.Update	retrieving 321-324
AssignedLicense() method 299	Logical Unit Number (LUN) 228
LicenseDataManager	NA.
associated license keys, applying to hosts in	M
container 303	maintenance mode
effective license key of host container,	about 100
retrieving 305	cluster DRS automation levels 100
license key associations, retrieving 303	disabling 100
license key associations, retrieving to host	enabling 100
containers in environment 303	host putting, Set-VMHost cmdlet used 100
license key associations, retrieving with	Managed Object References
specific host container 304	using 55
license keys, associating with host contain-	Master Boot Record (MBR) 245
ers 302	Math.Round method 84
using 301	maxFailureWindow 256
LicenseDataManager.ApplyAssociated	maximum transmission unit (MTU) 188
LicenseData() method 303	Measure-Object cmdlet
LicenseDataManager.QueryEffective	using 82, 83
LicenseData() method 305	value, rounding 84
LicenseDataManager.UpdateAssociated	methods 67, 68
LicenseData() method 302	metric IDs
license inventory	retrieving 330
license keys, adding 297, 298	minUpTime 256
license keys, removing from 299	Move-Cluster cmdlet 263
license keys, retrieving from 298	Move-VMHost cmdlet 262
license key associations	multipathing policy
modifying 305	setting 233, 234
removing 305	multiple servers
retrieving 303	connecting to 19, 20
retrieving, to host containers in	A.
environment 303	N
retrieving, with specific host container 304	naturarly adapter
LicenseManager.RemoveLicense()	network adapter adding 156
method 299 licenses	modifying 162, 163
	removing 166
assigned license keys, removing from hosts 301	Network File System (NFS) 227

Network I/O Control	performance statistics
configuring 219	retrieving 328, 329
disabling 219	permissions
enabling 219	about 288
New-Alias cmdlet 31	creating 293, 294
New-CDDrive cmdlet 158	modifying 296
New-Cluster cmdlet 250, 254	removing 296
New-Datacenter cmdlet 96	retrieving 295
New-DatastoreCluster cmdlet 240	pipeline
New-Datastore cmdlet 228	about 71
New-DrsRule cmdlet 264	ByPropertyName parameter binding,
New-FloppyDrive cmdlet 157, 158	using 73-75
New-HardDisk cmdlet 154	ByValue parameter binding, using 71, 72
New-IScsiHbaTarget cmdlet 231	port groups 199
New-NetworkAdapter cmdlet 156	PowerCLI
New-Object cmdlet	about 7
using 88	certificate warnings, suppressing 22
New-OSCustomizationSpec cmdlet 145	disconnecting, from server 22, 23
New-PSDrive cmdlet 47	downloading, steps 8, 9
New-ScsiController cmdlet 155	esxcli, using from 125
New-VDPortgroup cmdlet 214	installing, steps 9-14
New-VICredentialStoreItem cmdlet 24	multiple servers, connecting to 19, 20
New-VIPermission cmdlet 293	server, connecting to 17-19
New-VIProperty cmdlet	URL, for downloading 8
PowerCLI objects, extending with 57-59	vSphere CLI commands, using 132, 133
New-VIRole cmdlet 290	PowerCLI commands output
New-VM cmdlet 138	displaying, in grid view 33
NFS datastores	PowerCLI Configuration
creating 229	retrieving 23
NoteProperty 67	PowerCLI objects
NoteProperty member 89	extending, with New-VIProperty cmdlet 57-59
0	PowerGUI 339, 340
	PowerShell
objects	about 63
about 64	execution policy, modifying 15, 16
creating 88	PowerShell object cmdlets
creating, hash table used 88, 89	about 75
creating, Select-Object cmdlet 89, 90	Select-Object cmdlet, using 76-78
New-Object cmdlet, using 88	primary hosts
properties adding, with Add-Member 90	retrieving 252
OS customization specifications	privileges
using 144-147	retrieving 288, 289
Out-String cmdlet 336	providers
-	about 44
P	using 44, 45
	PSChildName property 92
ParameterizedProperty property 66	10 childranic property 52

PSDrives	ScriptProperty 67
using 45	SCSI controller
ŭ	adding 155
R	modifying 161, 162
	SCSI device
raw API objects	vmhba paths, configuring to 235
using, with ExtensionData property 52	vmhba paths, modifying to 235
using, with Get-View cmdlet 52	vmhba paths, retrieving to 235
Raw Device Mapping (RDM) 236-238	SCSI logical unit 229
ReconfigureComputeResource_Task()	Select-Object cmdlet
method 255-260, 266, 270	about 27, 76, 77, 239, 332
RemoteSigned execution policy 15	using, to create object 89, 90
Remove-AlarmAction cmdlet 313	Select-String cmdlet 324
Remove-CDDrive cmdlet 167	Send-MailMessage cmdlet 336
Remove-FloppyDrive cmdlet 166	server
Remove-VDSwitch cmdlet 213	connecting to 17-19
Remove-VIPermission cmdlet 296	disconnecting from 22, 23
Remove-VM cmdlet 184	Set-CDDrive cmdlet 164
Remove-VMHost cmdlet 134	
Replace method 68	Set-FloppyDrive cmdlet 164 Set-HardDisk cmdlet 159
reports	Set-Location cmdlet 47
creating 321	
exporting, to CSV files 331-333	Set-NetworkAdapter cmdlet 162 Set-PowerCLIConfiguration cmdlet 20-22
sending, by e-mail 336, 337	Set-ScsiController cmdlet 161
Required property 111	Set-VDSwitch -BackupPath parameter 209
resource pools	Set-VIPermission cmdlet 296
creating 276	Set-VIRole cmdlet 292
mofiying 278	Set-VirtualPortGroup cmdlet 200
moving 279, 280	Set-VM cmdlet 141, 152
removing 281	Set-VM Childret 141, 132 Set-VMGuestNetworkInterface cmdlet 224
resource allocation between virtual	Set-VMHostNetworkAdapter cmdlet 220
machines, configuring 280, 281	
retrieving 277	snapshots about 175
using 276	
Restricted execution policy 15	creating 175, 176
roles	modifying 179 removing 179
about 288	retrieving 177, 178
creating 290	
modifying 292	reverting to 178 software iSCSI VMFS datastores
removing 293	creating 230, 231
retrieving 291	Sort-Object cmdlet 81, 82
using 290	splat operator @ 206
Round Robin (RR) 233	splatting 206
,	
S	standard port groups about 199
_	
SAPI.SpVoice COM object 92	configuring 200, 201 creating 199
scriptblock 29	creating 199

removing 201	vicfg-ipsec command 132
statistical intervals	VimDatastore provider 45
retrieving 326, 327	VimInventory provider 45
Storage Area Networks (SANs) 227	Virtual Local Area Network (Virtual LAN
storage devices	or VLAN) 199
rescanning for 228	virtual machine
Storage Distributed Resource Scheduler.	cloning 139, 142
See Storage DRS	compatibility, upgrading 173, 174
Storage DRS 240	console, opening 182
Storage I/O Control (SIOC)	converting, into template 167, 168
about 238, 239	creating 138-140
settings, retrieving 239	creating, from scratch 140, 141
string	creating, from template 138, 142
expanding 70	creating, to host DRS rules 270-272
expanding, on use 70	devices, adding 153
subexpressions 69	devices, removing from 165
subexpressions	guest operating system, shutting
in strings 68, 69	down 148, 149
_	moving, to another folder 169
T	moving, to cluster 169
	moving, to datastore 169
Tee-Object cmdlet 87	moving, to host 169
template	moving, to resource pool 169
converting, into virtual machine 168	registering 139, 143, 144
name, modifying 169	removing 184
removing 169	removing, from DRS groups 269
virtual machine, creating from 142	retrieving 25-27
TrimEnd method 68	settings, modifying 150, 151
type declarations	starting 147, 148
using 91	stopping 149
11	suspending 148
U	virtual machine network
Undefined execution policy 15	configuring 223, 224
Unrestricted execution policy 15	virtual machines DRS groups
Update-Tools cmdlet	creating 266
using 172	virtual machines, retrieving
userSelectedDs 259	aliases, using 30
4.501.501.601.601.20 2 .5	comparison operators, using 30
V	deprecated warnings display, stopping 28
•	objects, filtering 29
variables	wildcard characters, using 28, 29
expanding 68	VM and application monitoring
vCenter Server mail server	enabling 256
configuring 311	VMFS datastores
vCenter Single Sign-On (SSO) 294	creating 230
vCheck 338	vmhba paths
VDPortgroup -BackupPath parameter 219	about 235

modifying, to SCSI device 235	configuring 206
retrieving, to SCSI device 235	creating 203
VM-Host affinity rules 263	creating, from export 204
VM-Host DRS rules	creating, from scratch 203
creating 266	host physical network adapters,
VMHostNetworkAdapter cmdlet 133	adding to 211
VMHostNetworkAdapter parameter 212	host physical network adapters,
vmkernel log file 323	removing from 212
vmMonitoring property 257	hosts, adding to 210
VM-VM affinity rules 263	hosts, removing from 212
VM-VM DRS rules	removing 213
creating 264	retrieving 205
VMware Flings	upgrading 210
URL 153	vSphere Distributed Switches configuration
VMware Remote Console (VMRC) browser	about 206-208
plugin 182	congiguring, from backup 209
VMware Technical Support 325	rolling back 208, 209
VMware Tools	vSphere folders
Check and upgrade VMware Tools before	working with 59-61
each power on checkbox, enabling	vSphere HA
172, 173	creating 250
Update-Tools cmdlet used 171, 172	vSphere Image Builder
updating 170	configuring 118
VMware vCenter Server	vSphere Installation Bundle (VIB) 119
about 96	vSphere PowerCLI Datastore Provider
cluster, creating 97, 98	using 47
datacenter, creating 96	vSphere PowerCLI Inventory Provider
host, adding to 96	using 46
host, removing from 134, 135	vSphere Standard Switches
VMware vCloud Director 12	about 186
VMware vSphere	configuring 188-190
about 287	creating 186-188
roles 288	image 186
VMware vSphere API	network adapters, adding to 191
using 152, 153	removing 191
VMware vSphere PowerCLI. See PowerCLI	187
VMware vSphere Storage APIs for Array	W
Integration (VAAI) 245	Where Object and let 20 78 70
vSphere CLI 125	Where-Object cmdlet 30, 78, 79 wildcard characters
vSphere CLI commands	about 28
using, from PowerCLI 132, 133	used, for selecting virtual machines 28
vSphere Command-Line Interface.	used, for selecting virtual machines 20
See vSphere CLI	
vSphere Distributed Switches	
about 202	
cloning 204	
configuration, exporting 213	



Thank you for buying Learning PowerCLI

About Packt Publishing

Packt, pronounced 'packed', published its first book "Mastering phpMyAdmin for Effective MySQL Management" in April 2004 and subsequently continued to specialize in publishing highly focused books on specific technologies and solutions.

Our books and publications share the experiences of your fellow IT professionals in adapting and customizing today's systems, applications, and frameworks. Our solution based books give you the knowledge and power to customize the software and technologies you're using to get the job done. Packt books are more specific and less general than the IT books you have seen in the past. Our unique business model allows us to bring you more focused information, giving you more of what you need to know, and less of what you don't.

Packt is a modern, yet unique publishing company, which focuses on producing quality, cutting-edge books for communities of developers, administrators, and newbies alike. For more information, please visit our website: www.packtpub.com.

About Packt Enterprise


In 2010, Packt launched two new brands, Packt Enterprise and Packt Open Source, in order to continue its focus on specialization. This book is part of the Packt Enterprise brand, home to books published on enterprise software – software created by major vendors, including (but not limited to) IBM, Microsoft and Oracle, often for use in other corporations. Its titles will offer information relevant to a range of users of this software, including administrators, developers, architects, and end users.

Writing for Packt

We welcome all inquiries from people who are interested in authoring. Book proposals should be sent to author@packtpub.com. If your book idea is still at an early stage and you would like to discuss it first before writing a formal book proposal, contact us; one of our commissioning editors will get in touch with you.

We're not just looking for published authors; if you have strong technical skills but no writing experience, our experienced editors can help you develop a writing career, or simply get some additional reward for your expertise.






VMware vSphere 5.1 Cookbook

ISBN: 978-1-84968-402-6 Paperback: 466 pages

Over 130 task-oriented recipes to install, configure, and manage various vSphere 5.1 components

- 1. Install and configure vSphere 5.1 core components
- 2. Learn important aspects of vSphere such as administration, security, and performance
- 3. Configure vSphere Management Assistant (VMA) to run commands/scripts without the need to authenticate every attempt



vSphere High Performance Cookbook

ISBN: 978-1-78217-000-6 Paperback: 240 pages

Over 60 recipes to help you improve vSphere performance and solve problems before they arise

- Troubleshoot real-world vSphere performance issues and identify their root causes
- Design and configure CPU, memory, networking, and storage for better and more reliable performance
- 3. Comprehensive coverage of performance issues and solutions including vCenter Server design and virtual machine and application tuning

Please check www.PacktPub.com for information on our titles






Instant VMware vCloud Starter

ISBN: 978-1-84968-996-0 Paperback: 76 pages

A practical, hands-on guide to get started with VMware vCloud

- 1. Learn something new in an Instant! A short, fast, focused guide delivering immediate results
- Deploy and operate a VMware vCloud in your own demo kit
- 3. Understand the basics about the cloud in general and why there is such a hype
- 4. Build and use templates to quickly deploy complete environments



Implementing VMware Horizon View 5.2

ISBN: 978-1-84968-796-6 Paperback: 390 pages

A practical guide to designing, implementing, and administrating an optimized Virtual Desktop solution with VMware Horizon View

- Detailed description of the deployment and administration of the VMware Horizon View suite
- 2. Learn how to determine the resources your virtual desktops will require
- 3. Design your desktop solution to avoid potential problems, and ensure minimal loss of time in the later stages

Please check www.PacktPub.com for information on our titles