Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

# EE 301 Signals and Systems

Department of Electrical and Electronics Engineering Middle East Technical University

October 14, 2018

### Outline

- Signals
- Transformations of the independent variable
- Important properties of signals
- Basic CT & DT signals
- Systems
- Basic System Properties

### General remarks

- Concepts of signals and systems arise everywhere.
- Tools associated with these concepts is continuously yielding new developments in diverse fields:
  - Imaging, communications, biomedical eng, circuit design, energy distribution systems, speech processing, ...
- In this course, we will regard everything as
  - Either signals (functions in math)
  - or systems (devices that change the shapes of functions)
- We will learn how to build useful structures for the representation, processing, and analysis of signals by using the mathematical framework of signals and systems.

Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems

## What is a signal?

Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems

### What is a signal?

Defn: A signal is

Signals

Transformations of the independent variable

Important properties of signals

Basic CT & DT signals

Systems

Basic System Properties

### What is a signal?

 Defn: A signal is the variation of a physical, or non-physical quantity with respect to one or more (independent) variables Basic System Properties

## What is a signal?

- Defn: A signal is the variation of a physical, or non-physical quantity with respect to one or more (independent) variables
- Mathematically, signals are functions of variables, which contain information about the behavior of some process or source.


Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems

# **Examples of Signals**

Basic System Properties

### **Examples of Signals**


Electrical signals: voltage variation over time



Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties


## **Examples of Signals**

Speech signals: air pressure variation over time



## **Examples of Signals**

Speech signals: air pressure variation over space



Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

### **Examples of Signals**

Optical signals: (reflected) light brightness in space



Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

### **Examples of Signals**


Electromagnetic signals: Computed tomography (CT) image of abdomen absorption of x-rays in space



Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

## **Examples of Signals**


• Biological signals: Sequence of bases in a gene





## **Examples of Signals**

Financial signals: Change in import volume over time



Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems

### What is a system?

Defn: A system is

Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

### What is a system?

 Defn: A system is any process that results in the transformation of signals Signals

Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

## What is a system?

- Defn: A system is any process that results in the transformation of signals
- Examples of systems:

## What is a system?

- Defn: A system is any process that results in the transformation of signals
- Examples of systems:
- Our goal in this course: Learn mathematical tools to analyze and design signal processing systems

Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems

### How is signal processing useful in real world?

Basic System Properties

- https://www.youtube.com/watch?v=EErkgr1MWw0 (Search youtube for "What is Signal Processing?")
- https://www.youtube.com/watch?v=mexN6d8QF9o (Search youtube for "Signal Processing and Machine Learning")

### Signals as functions of variables

- We will mostly refer to the (independent) variable as time.
  - It can be other things depending on the application (such as space, distance, location index, and so on).
- Independent variables can be 1-D, 2-D,...

### Signals as functions of variables

- We will mostly refer to the (independent) variable as time.
  - It can be other things depending on the application (such as space, distance, location index, and so on).
- Independent variables can be 1-D, 2-D,...
  - Ex: an image is ...
  - Ex: a video is ...

Important properties of signals

# Types of Signals

Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

## Types of Signals

# Continuous-time (CT) signals

continuous variation

Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties


## Types of Signals

# Continuous-time (CT) signals

- continuous variation
- x(t)
- t : continuous-time variable

# Continuous-time (CT) signals


- continuous variation
- x(t)
- t : continuous-time variable
- x(t) is defined for all real values of t



### Discrete-time (CT) signals

# Continuous-time (CT) signals

- continuous variation
- x(t)
- t : continuous-time variable
- x(t) is defined for all real values of t




### Discrete-time (CT) signals

variation at specified time instants

# Continuous-time (CT) signals

- continuous variation
- x(t)
- *t* : continuous-time variable
- x(t) is defined for all real values of t




### Discrete-time (CT) signals

- variation at specified time instants
- x[n] (sequence of numbers)
- *n* : discrete-time variable


# Continuous-time (CT) signals

- continuous variation
- x(t)
- *t* : continuous-time variable
- x(t) is defined for all real values of t



### Discrete-time (CT) signals

- variation at specified time instants
- x[n] (sequence of numbers)
- n: discrete-time variable
- x[n] is defined only for integer values of n



Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

### Continous-time vs discrete-time

### Examples:

- Voltage in time
- # of people in lectures over time
- Blood pressure recorded every half an hour

### Remarks on DT signals

- DT signals are undefined at all values other than integer values of n
  - ⇒ referred as a discrete-time sequence
- Ex: # of people in lectures
  - No meaning for lecture number 1/2

### Remarks on CT signals

- Most physical signals are CT but not all.
- A DT signal may arise
  - from a process that is inherently discrete, as in ...
  - from the sampling of a CT signal, as in ...
- Sampling is very important due to digital computers/signal processors (EE 430).

### Transformations of the independent variable

We sometimes work with signals after modifying the independent variable (i.e. time axis).

### Example

#### Fast forward

- Time Shift :  $x(t t_0)$
- Time Reversal : x(-t)
- Time Scaling :  $x(\frac{t}{a})$  or x(at), a: real number

Signals

Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

Note that x(at) is always defined for  $a \in \mathbb{R}$ . The same is not true for x[an].

### Example

x[n]: a discrete sequence. Which of the following are

defined:  $x[2n], x[\sqrt{2}n], x[\frac{n}{2}]$ ?

Signals

Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

### Example

Find y(t) = x(2t - 1) for the given x(t).

In general, to find x(at + b),

- First time-shift by ...
- OR ...

Periodic signals
Even and Odd Symmetric Signa

### Periodic signals

#### **Definition**

A CT signal x(t) is said to be periodic if it repeats itself with a period of T, i.e.

## Periodic signals

#### **Definition**

A CT signal x(t) is said to be periodic if it repeats itself with a period of T, i.e.

$$x(t) = x(t + T)$$
 holds for all  $t$ 

Periodicity is defined similarly for DT signals: x[n] is periodic with N if x[n] = x[n + N] for all n where N is an integer.

Signals

Transformations of the independent variable


Important properties of signals

Basic CT & DT signals

Systems

Rasic System Properties

Periodic signals
Even and Odd Symmetric Signals



Note that if x(t) is periodic with T then it is also periodic with 2T, 3T, 4T,....

 Fundamental period T<sub>0</sub> of x(t) (N<sub>0</sub> of x[n]): the smallest positive T (N) for which the above equalities hold.

### Example (Challenge yourself!)

Prove whether  $x_p(t) = \sum_{m=-\infty}^{\infty} x(t - mT)$  is periodic or not, when T: some constant, x(t): arbitrary CT signal.

### Example (Challenge yourself!)

If x(t) is periodic with T, how about  $x(t + t_0)$  and  $x(\frac{t}{a})$ ? Similarly, if x[n] is periodic with N, how about  $x[n + n_0]$  and x[Mn]?

Transformations of the independent variable

Important properties of signals

Basic CT & DT signals

Basic System Properties

Periodic signals

Even and Odd Symmetric Signals

## Even and Odd Signals

A signal is even if

Basic System Properties

## Even and Odd Signals

A signal is even if x(-t) = x(t) for all t. (DT: x[-n] = x[n])


A signal is odd if

Basic System Properties

## Even and Odd Signals

A signal is even if x(-t) = x(t) for all t. (DT: x[-n] = x[n])

A signal is odd if x(-t) = -x(t) for all t. (x[-n] = -x[n])



### Example (Challenge yourself!)

Can we decompose arbitrary signals into a sum of two signals, one of which is even and the other is odd:

$$x(t) = x_{ev}(t) + x_{od}(t)$$

- Is the decomposition unique?
- Closed-form expression for the decomposition?

Check the book for the solution:

$$x_{ev}(t) = \frac{1}{2}(x(t) + x(-t)), \quad x_{od}(t) = \frac{1}{2}(x(t) - x(-t))$$

These are called even and odd parts of x(t).

Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

## CT Complex Exponential & Sinusoidal Signals

[Short digression: Review of complex numbers (Page 71)]

The CT complex exponential signal is generally of the form

## CT Complex Exponential & Sinusoidal Signals

[Short digression: Review of complex numbers (Page 71)]

The CT complex exponential signal is generally of the form

$$x(t) = C e^{at}$$

where C and a are in general complex numbers.

### 1. Real Exponential Signals:

C and a are real numbers

- If a > 0, growing exponential:
- If a < 0, decaying exponential:</li>

Signals
Fransformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

$$x(t) =$$

$$x(t) = Ce^{j\omega_0 t}$$
 ( $\omega_0$ : radians/second)

- ⇒ Verify periodicity:
- Fundamental period T<sub>0</sub> =

$$x(t) = Ce^{j\omega_0 t}$$
 ( $\omega_0$ : radians/second)

- ⇒ Verify periodicity:
- Fundamental period  $T_0 = rac{2\pi}{|\omega_0|}$
- $e^{j\omega_0t}$  and  $e^{-j\omega_0t}$

$$x(t) = Ce^{j\omega_0 t}$$
 ( $\omega_0$ : radians/second)

- ⇒ Verify periodicity:
- Fundamental period  $T_0 = rac{2\pi}{|\omega_0|}$
- $e^{j\omega_0 t}$  and  $e^{-j\omega_0 t}$  have the same fundamental period.
- Euler's relations:
- Harmonically related complex exponentials:
- Does x(t) have finite average power? finite energy?

Signals
Fransformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

### 3. Sinusoidal Signals:

$$x(t) =$$

### 3. Sinusoidal Signals:

$$x(t) = A \cos(\omega_0 t + \theta)$$
 ( $\theta$ : radians)

ullet even signal when heta =

### 3. Sinusoidal Signals:

$$x(t) = A\cos(\omega_0 t + \theta)$$
 ( $\theta$ : radians)

- even signal when  $\theta = k\pi$
- odd signal when  $\theta =$

### 3. Sinusoidal Signals:

$$x(t) = A \cos(\omega_0 t + \theta)$$
 ( $\theta$ : radians)

- even signal when  $\theta = k\pi$
- odd signal when  $\theta = \frac{\pi}{2} + k\pi$

### Example (Challenge yourself!)

How to express x(t) in terms of periodic complex exponentials?

CT Complex Exponential & Sinusoidal Signals

## 4. General Complex Exponential Signals:

Both C and a are complex.

Let us represent C in polar form as  $C = re^{i\theta}$  and a in rectangular form as  $a = \alpha + i\omega_0$ . Then  $x(t) = Ce^{at} =$ 

- $\alpha = 0$ : both real and imaginary parts are
- $\alpha > 0$ : both real and imaginary parts are
- $\alpha$  < 0 : both real and imaginary parts are

### Example

$$x(t) = 2e^{(3+j\omega_0)t}$$

$$x(t) = 2e^{(3+j\omega_0)t}$$
  
 $x(t) = e^{(-1+j\omega_0)t}$ 

## DT Complex Exponential & Sinusoidal Signals

The DT complex exponential signal is generally of the form

$$x[n] = C\alpha^n$$
 or  $x[n] = Ce^{\beta n} (\alpha = e^{\beta})$ 

where C and  $\alpha$  are in general complex numbers.

### 1. Real Exponential Signals:

 $\boldsymbol{C}$  and  $\alpha$  are reals.

### Example

DT real exponential signals with various behaviors

### 2. Sinusoidal Signals:

If  $\beta$  is purely imaginary (i.e.  $|\alpha| = 1$ ), we obtain  $x[n] = Ce^{j\Omega_0 n}$ . This is related to sinusoidal signals:

# 3. General Complex Exponentials (Damped sinusoids):

 $\beta$  is <u>not</u> purely imaginary.

By representing C and  $\alpha$  in polar form,

$$x[n] = C\alpha^n = |C|e^{j\theta}(|\alpha|e^{j\Omega_0})^n = |C||\alpha|^n e^{j(\Omega_0 n + \theta)}$$
$$= |C||\alpha|^n (\cos(\Omega_0 n + \theta) + j\sin(\Omega_0 n + \theta))$$

- $|\alpha| > 1$ : both real and imaginary parts are ...
- $|\alpha|$  < 1 : both real and imaginary parts are ...

## Periodicity Properties of DT Complex Exponentials

Although there are many similarities between CT and DT signals, there are also some important differences. One such difference exists between  $e^{j\omega_0 t}$  and  $e^{j\Omega_0 n}$ .

#### Remember:

• CT signal  $e^{j\omega_0 t}$  is

## Periodicity Properties of DT Complex Exponentials

Although there are many similarities between CT and DT signals, there are also some important differences. One such difference exists between  $e^{j\omega_0 t}$  and  $e^{j\Omega_0 n}$ .

#### Remember:

• CT signal  $e^{j\omega_0 t}$  is periodic for

## Periodicity Properties of DT Complex Exponentials

Although there are many similarities between CT and DT signals, there are also some important differences. One such difference exists between  $e^{j\omega_0 t}$  and  $e^{j\Omega_0 n}$ .

#### Remember:

- CT signal  $e^{j\omega_0 t}$  is periodic for any  $\omega_0$ .
- As  $|\omega_0|$  increases, the rate of oscillation (frequency)

## Periodicity Properties of DT Complex Exponentials

Although there are many similarities between CT and DT signals, there are also some important differences. One such difference exists between  $e^{j\omega_0 t}$  and  $e^{j\Omega_0 n}$ .

#### Remember:

- CT signal  $e^{j\omega_0 t}$  is periodic for any  $\omega_0$ .
- As  $|\omega_0|$  increases, the rate of oscillation (frequency) increases.


Both of the above properties are different for  $e^{j\Omega_0 n}$ .

Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems

Basic System Properties

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

### DT sinusoidal sequences for several frequencies



Signals
Fransformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

### For $e^{j\Omega_0 n}$ :

• As  $|\Omega_0|$  increases, the rate of oscillation

### For $e^{j\Omega_0 n}$ :

- As  $|\Omega_0|$  increases, the rate of oscillation does not increase continuously.
- $e^{j\Omega_0 n}$  is not even distinct for different  $\Omega_0$ ; identical for

### For $e^{j\Omega_0 n}$ :

- As  $|\Omega_0|$  increases, the rate of oscillation does not increase continuously.
- $e^{j\Omega_0 n}$  is not even distinct for different  $\Omega_0$ ; identical for  $\Omega_0 + 2\pi k$
- Periodicity?

### For $e^{j\Omega_0 n}$ :

- As  $|\Omega_0|$  increases, the rate of oscillation does not increase continuously.
- $e^{j\Omega_0 n}$  is not even distinct for different  $\Omega_0$ ; identical for  $\Omega_0 + 2\pi k$
- Periodicity?  $e^{j\Omega_0 n}$  is periodic only if  $\Omega_0$  can be written in the form  $\Omega_0 = 2\pi \frac{k}{N}$  for some integers N > 0 and k.

### Example

Is  $x[n] = e^{jn}$  periodic? If so, find the fundamental period and frequency.

### Example

Is  $x[n] = 5\cos(\frac{3\pi}{4}n)$  periodic? If so, find the fundamental period and frequency.

## Differences between CT and DT complex exponentials

CT: $e^{j\omega_0 t}$	DT: $e^{j\Omega_0 n}$
Distinct signals for distinct $\omega_0$	Same signals for $\Omega_0 + 2\pi k$
Periodic for any $\omega_0$	Periodic only if $\frac{\Omega_0}{2\pi}$ is a rational number
Fundamental period $T_0$	Fundamental period N <sub>0</sub>
$\omega_0 = 0 \Rightarrow undefined$	$\Omega_0 = 0 \Rightarrow undefined$
$\omega_0  eq 0 \Rightarrow T_0 = \frac{2\pi}{ \omega_0 }$	$\Omega_0 \neq 0 \Rightarrow N_0 = k \frac{2\pi}{\Omega_0}$ with min. possible $k$
Fundamental frequency $ \omega_0 $	Fundamental frequency $\frac{2\pi}{N_0}$

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences

## DT Unit Impulse & Unit Step Sequences

• DT unit impulse is defined as

$$\delta[n] = \begin{cases} 1, & n = 0 \\ 0, & n \neq 0. \end{cases}$$

DT unit step is defined as

$$u[n] = \begin{cases} 1, & n \geq 0 \\ 0, & n < 0. \end{cases}$$

• The relation between u[n] and  $\delta[n]$ :

$$\delta[n] = u[n] =$$

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences

## DT Unit Impulse & Unit Step Sequences

DT unit impulse is defined as

$$\delta[n] = \begin{cases} 1, & n = 0 \\ 0, & n \neq 0. \end{cases}$$

DT unit step is defined as

$$u[n] = \begin{cases} 1, & n \geq 0 \\ 0, & n < 0. \end{cases}$$

• The relation between u[n] and  $\delta[n]$ :

$$\delta[n] = u[n] =$$

(Sum of Shifted Impulses / Running Sum Interpretations)

DT Unit Impulse & Unit Step Sequences

## Properties of DT Unit Impulse $\delta[n]$

$$\sum_{n=-\infty}^{\infty} \delta[n] =$$
,  $\sum_{n=n_1}^{n=n_2} \delta[n] =$ 

$$\sum_{n=n_1}^{n=n_2} \delta[n] =$$

•  $x[n]\delta[n] =$  $(x[n]\delta[n-n_0] =$ 

•  $\sum_{\substack{n=-\infty\\n=n_2\\n=n_1}}^{\infty} x[n]\delta[n] = \sum_{\substack{n=n_1\\n=-\infty}}^{\infty} x[n]\delta[n] = (\sum_{n=-\infty}^{\infty} x[n]\delta[n_0-n] = 0$ 


) (Convolution Prop.)

Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

## CT Unit Step & Unit Impulse Functions

The CT unit step function: 
$$u(t) = \begin{cases} 1, & t > 0 \\ 0, & t < 0. \end{cases}$$



Signals
ransformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

## **CT Unit Impulse Function**

The CT unit impulse function  $\delta(t)$  is related to the unit step by:

$$u(t) =$$

## **CT Unit Impulse Function**

The CT unit impulse function  $\delta(t)$  is related to the unit step by:

$$u(t) = \int_{-\infty}^{t} \delta(\tau) d\tau$$

This suggests

$$\delta(t) =$$

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

# **CT Unit Impulse Function**

The CT unit impulse function  $\delta(t)$  is related to the unit step by:

$$u(t) = \int_{-\infty}^{t} \delta(\tau) d\tau$$

This suggests

$$\delta(t) =$$

however, this is problematic in the classical sense since u(t) is formally not differentiable at t=0 ("generalized derivative").

For a more formal development, let us define new functions (approximations to the original step & impulse):

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

That is, more formally, the unit impulse func. is defined as

$$\delta(t) = \lim_{\Delta \to 0} \delta_{\Delta}(t)$$

$$\frac{\delta_{\Delta}(t)}{\frac{1}{\Delta}}$$

- Note that  $\delta_{\Delta}(t)$  is a short pulse of duration  $\Delta$  and with unit area for any value of  $\Delta$ .  $\delta(t)$  should be viewed as an idealization of the short pulse when the duration  $\Delta$  is very small (for any practical purpose).
- In practical terms, you can think of  $\delta(t)$  as any func. of unit area, concentrated very near t = 0.

CT Complex Exponential & Sinusoidal Signals DT Complex Exponential & Sinusoidal Signals DT Unit Impulse & Unit Step Sequences CT Unit Impulse & Unit Step Functions

# Properties of unit impulse function $\delta(t)$

 It is a signal of unit area vanishing everywhere except at origin.

$$\int_{-\infty}^{\infty} \delta(t) dt = \int_{t_1}^{t_2} \delta(t) dt =$$

- It is the (generalized) derivative of the unit step func.
- For any cont. func. x(t),

• 
$$x(t)\delta(t) = x(t)\delta(t-t_0) =$$

• 
$$\int_{-\infty}^{\infty} x(t)\delta(t)dt =$$

$$\int_{t_1}^{t_2} x(t)\delta(t)dt =$$

$$(\int_{-\infty}^{\infty} x(t)\delta(t_0 - t)dt = )$$

T Complex Exponential & Sinusoidal Signals T Complex Exponential & Sinusoidal Signals T Unit Impulse & Unit Step Sequences

CT Unit Impulse & Unit Step Functions

# Example (Challenge yourself!)

Prove the following:

Running Integral Interpretation :  $u(t) = \int_{-\infty}^{t} \delta(\tau) d\tau$ 

## Example

Prove the following:

Moving Impulse Interpretation :  $u(t) = \int_0^\infty \delta(t-\tau) d\tau$ 

# Example (Challenge yourself!)

Example 1.7 in the book (square type signal)

Signals
Transformations of the independent variable
Important properties of signals
Basic CT & DT signals
Systems
Basic System Properties

# Systems

#### **Definition**


System: Any process that results in the transformation of signals.

### Example

Examples of systems

CT and DT systems:

### Interconnection of systems:



# Memory

#### **Definition**

A system is memoryless (instantaneous) if its output at any time instant depends only on the value of the input at that particular instant.

## Example

# Causality

#### **Definition**

A system is causal if its output at any time depends only on the values of the input at present time and/or in the past.

#### Example

### Examples

 Physical systems that process <u>time-domain</u> signals in real-time

# Causality

#### **Definition**

A system is causal if its output at any time depends only on the values of the input at present time and/or in the past.

#### Example

- Physical systems that process <u>time-domain</u> signals in real-time can not respond before they are stimulated. In this case, causality is equivalent to realizability.
- Non-causal systems are of interest when

# Causality

#### **Definition**

A system is causal if its output at any time depends only on the values of the input at present time and/or in the past.

#### Example

- Physical systems that process <u>time-domain</u> signals in real-time can not respond before they are stimulated. In this case, causality is equivalent to realizability.
- Non-causal systems are of interest when the independent variable is not time or offline processing is possible.

# Example (Challenge yourself!)

#### Causal or not:

• 
$$y[n] = x[3n]$$

• 
$$y[n] = \sum_{m=-\infty}^{n} \alpha_m x[n-m]$$

• 
$$y(t) = x(t)^2$$

• 
$$y(t) = \int_{-\infty}^{t} x(\tau) d\tau$$

• a memoryless system

# Invertibility

#### **Definition**

A system is invertible if for distinct inputs,  $x_1(t) \neq x_2(t)$ , it generates distinct outputs,  $y_1(t) \neq y_2(t)$ .

If a system is invertible, then a corresponding inverse system exists.

### Example

# Invertibility

### Definition

A system is invertible if for distinct inputs,  $x_1(t) \neq x_2(t)$ , it generates distinct outputs,  $y_1(t) \neq y_2(t)$ .

If a system is invertible, then a corresponding inverse system exists.

### Example

Examples

## Example (Challenge yourself!)

Invertible or not: y(t) = 5x(t - 1/2)?

# Stability

## Definition (Bounded Input Bounded Output (BIBO) stab.)

A system is stable if bounded inputs lead to bounded outputs.

## Example

# Stability

# Definition (Bounded Input Bounded Output (BIBO) stab.)

A system is **stable** if bounded inputs lead to bounded outputs.

### Example

Examples

## Example (Challenge yourself!)

Stable or not:

• 
$$y(t) = \frac{x(t)}{x(t-1)+1}$$

• 
$$y(t) = e^{\alpha t} x(t), \alpha \in C$$

• 
$$y(t) = \frac{d}{dt}x(t)$$

## Time Invariance

#### **Definition**

A system is time-invariant if a time shift in the input signal causes same amount of time shift in the output signal.

# Example

## Time Invariance

### Definition

A system is time-invariant if a time shift in the input signal causes same amount of time shift in the output signal.

## Example

Examples

## Example (Challenge yourself!)

Time-invariant or not:

• 
$$y(t) = \sin(x(t))$$

• 
$$y(t) = x(2t)$$

• 
$$y(t) = e^t x(t)$$

$$v[n] = nx[n]$$

# Linearity

### Definition

A linear system has the superposition property:

## Example

Examples

## Example (Challenge yourself!)

Linear or not:

• 
$$y[n] = 5x[n] + 2$$

• 
$$y(t) = x^2(t)$$

• 
$$y(t) = \frac{d^n x(t)}{dt^n}$$