User Guide

- Recording Studio — Screen recording, game capture and live streaming
- Video Editor — Video editing, effects and export
- Game Tools — Crosshair and FPS overlay

Open source · Free

This guide contains the same information as the Help > User Guide page inside the programs.

English

Contents

1. **Recording Studio**
    1. Quick start
    2. Scenes
    3. Sources
    4. Game capture
    5. FPS overlay
    6. Editing in the preview
    7. Audio
    8. Recording settings
    9. Cursor and shortcut data for Video Editor
    10. Profiles
    11. Encoders
    12. Live streaming
    13. Shortcuts and screen
    14. Troubleshooting
2. **Video Editor**
    1. Quick start
    2. Timeline
    3. Range selection
    4. Cutting and editing
    5. Picture, color and transition
    6. Text and audio
    7. Transitions, annotations and effects
    8. Keyframes
    9. Zoom and pan
    10. Entrance / exit motion and typewriter
    11. Shadow, corners, border and mask
    12. Spotlight
    13. Cursor highlight, click ring, key overlay
    14. Voice effects
    15. Subtitles
    16. Freeze frame and reverse playback
    17. Applying settings to other clips
    18. Recording from microphone
    19. Export

3. **Game Tools**
    1. Quick start
    2. Running in the background and closing
    3. Start automatically when the computer starts
    4. Crosshair settings
    5. Crosshair profiles
    6. FPS Meter
    7. If temperatures are not read
    8. Hiding from recording and stream
    9. Shortcuts
    10. Theme and appearance
    11. Caution in games

1. Recording Studio

Screen recording, game capture and live streaming

1.1 Quick start

- When the program first opens, a scene with a Screen source is ready; you see your screen in the preview.
- Press "Start Recording" in the Controls section at the bottom right or use Ctrl + F12.
- Press "Stop Recording" to finish. The recording is saved as MP4 in the folder chosen in Settings > Recording.
- To open the recording folder, use File > Open recording folder at the top.
- The Video Editor button at the top right opens the editing program. With Tools > Open last recording in Video Editor, your recording is added straight to the timeline.
- Drag the line between panels to resize them; sizes are saved automatically. In the Appearance menu you can choose ready-made layouts or save your own layout under a name.

1.2 Scenes

- A scene is a layout where sources sit together. For example, you can make two scenes for Game and Waiting screen.
- In the Scenes section at the top left, the plus button adds a scene, the trash can deletes the selected scene and the button next to it renames it.
- Clicking a scene in the list switches to it; you can do this while recording too.
- Choose the look of the transition in Scene Transition: Fade blends smoothly, Cut switches instantly.

1.3 Sources

- A source is what appears in the scene. Add sources with the plus button in the Sources section: Screen, Game capture, FPS overlay, Camera, Image, Video, Text, Social media, Solid color.
- The source at the top of the list appears in front. Change the order with the arrow buttons.
- The checkbox on the left hides a source without deleting it.
- Double-click a source or press the Properties button below the preview to open its settings.

1.4 Game capture

- Add Game capture with the plus in the Sources section. In Properties, choose the game from the list or leave "Find full-screen game automatically" on.
- The game window is captured through Windows; nothing is injected into the game. That makes it safe in games with anti-cheat.
- Other windows on top do not enter the stream. The crosshair and FPS overlay from Game Tools do not appear in this source either. To show FPS in recordings and streams, add the FPS overlay source to the scene.

- Running the game in borderless window mode is the most reliable way. If an exclusive full-screen game gives no picture, the source switches to screen capture automatically.

1.5 FPS overlay

- Add FPS overlay with the plus in the Sources section. It starts with your look from Game Tools and, being part of the scene, appears in recordings and streams.
- Drag it to any position in the preview. Change what is shown and how it looks in the Properties window; these settings do not affect Game Tools.
- The program must run as administrator to read the CPU temperature. Without permission some values are not shown.

1.6 Editing in the preview

- Click a source in the preview to select it and drag to move it. It snaps into place near the edges and center.
- Resize screens, cameras, images, videos and solid colors by dragging the red squares at their corners; the aspect ratio is kept.
- "Fill canvas" in the Properties window stretches the source over the whole area.
- The menu button at the top left closes the left panel and enlarges the preview.

1.7 Audio

- Turn desktop audio and microphone on or off in the Audio Mixer and set their levels with the sliders.
- The green bar shows the current audio level. If it does not move, no sound is coming from that source.
- Choose which audio device to use in Settings > Recording.

1.8 Recording settings

- Resolution: Same as screen gives the sharpest result.
- FPS: choose 60 FPS for games, 30 FPS for smaller files.
- Quality: High means sharper but larger files. Low saves disk space.
- These settings cannot be changed while recording; they take effect for the next recording.
- "Start automatically with Windows" starts the program as a tray icon when you sign in. Recording or streaming does not start on its own.

1.9 Cursor and shortcut data for Video Editor

- If "Record cursor and clicks" is on, the cursor position and click moments are written next to the recording as an ".input.json" file. Video Editor uses it to draw cursor highlights and click rings.
- If "Record shortcut keys" is on, only keys pressed with Ctrl, Alt or Win, the F keys and Esc are recorded; typed text and passwords are never recorded. Video Editor shows them as a key overlay.
- Data is collected only while a screen source is in the scene and is never sent anywhere. If you do not want it, turn the boxes off or delete the file; the video is not affected.

1.10 Profiles

- A profile stores recording or streaming settings together: resolution, FPS, encoder, quality and bitrate. Recording and streaming have separate lists.
- For a quick choice, use Stream Profile and Recording Profile in the top menu. The same choice is in the Controls section at the bottom right: the left list is the stream profile, the right list the recording profile.
- To save, set things up, give the profile a name in Settings > Recording or Streaming and press "Save current settings".
- If the list shows "Custom", the current settings match no profile.
- Stream key, server address, recording folder and audio devices are not stored in profiles. Profiles cannot be changed while recording or streaming.

1.11 Encoders

- Choose the encoder in Settings > Recording > Encoder. Those that do not work on this computer appear dimmed.
- "Choose the best" picks the most suitable encoder and starting settings for this computer.
- Hardware encoders (Windows, Quick Sync, NVENC, AMF) run on the graphics card and affect the game least.
- Software encoders (x264, x265, AOM AV1, VP9) run on the processor. They give smaller files and higher quality but load the processor.
- Constant quality is best for recording: the lower the value, the higher the quality and file size. Streaming always uses CBR.
- The slower the preset, the higher the quality and the processor load. If "Skipped frames" rises at the bottom right, choose a faster preset.
- MKV is the most resistant to corruption during recording. MP4 and MOV are written in fragments, so the recording up to that point opens even if the program closes.

1.12 Live streaming

- Choose your platform in Settings > Streaming and enter your stream key. For Kick, also copy the server address from your dashboard.
- Press "Start Streaming" at the bottom right or use Ctrl + F10. The status appears in the Controls section.
- The stream sends the scene and sound you see in the preview. You can record and stream at the same time.
- "Same as recording" uses the recording's resolution and FPS. With "Custom" you can give the stream its own resolution, FPS and bitrate.
- If your internet slows down, the program keeps streaming by skipping frames; if the connection drops it retries automatically. You see the bitrate and skipped frames at the bottom right.
- The stream key controls your channel; never share it.

1.13 Shortcuts and screen


- Ctrl + F12: Start / stop recording. Ctrl + F11: Pause / resume. Ctrl + F10: Start / stop streaming. These also work while the program is in the background.
- You can change the keys in Settings > Shortcuts.
- F11 switches to full screen, Esc leaves full screen.
- The sun / moon button at the top right switches between dark and light mode. Choose the Classic or Bootstrap theme in Settings > Appearance.

1.14 Troubleshooting

- If the preview is black: check that the Screen source is ticked in the Sources list.
- If the recording has no sound: in the Audio Mixer, check that the box is ticked and the green bar is moving.
- If "Skipped frames" keeps rising at the bottom right, the computer is struggling: lower the FPS to 30, choose a faster preset or a hardware encoder.
- Looking for the crosshair or FPS overlay? They are in the Game Tools program and appear in the recording automatically while it is open.

2. Video Editor

Video editing, effects and export



Screenshot: Video Editor

2.1 Quick start

- Drag files onto the window or use the Add media button. Video, audio and images can be added.
- Drag a file from the media list onto the timeline or double-click it.
- Play with the space bar. When you are done, create your video with File > Export.
- Save your project with Ctrl + S; continue later with File > Open project.
- Drag the line between panels to resize them; sizes are saved automatically. In the Appearance menu you can choose ready-made layouts or save your own layout under a name.

2.2 Timeline

- Click only the ruler at the top to move the time. Clicking a clip selects it; Ctrl-click or draw a box from an empty area to select several clips. Ctrl + A selects all.
- Drag selected clips to move them together. Right-click opens the menu for splitting, duplicating, transitions and copying settings.
- Trim by dragging the left or right edge of a clip. Edges snap like magnets to other clips, the playhead and markers.
- A clip dropped on an occupied place returns to its original position.
- Ctrl + wheel zooms, the wheel scrolls sideways. Add new video and audio tracks with the buttons at the top.

- Icons at the start of a track: the eye hides the track (on audio tracks the speaker mutes it), the lock prevents accidental moves, the chain turns on the magnet. Hover over them to see what they do.
- The Recording Studio button at the top right switches to the recording program. In Recording Studio, Tools > Open last recording in Video Editor adds your recording to the end of the timeline here.

2.3 Range selection

- Hold Shift and drag on the ruler, or press I to set the start and O to set the end at the playhead. The range is shown in green; drag its edges on the ruler to change it.
- Play range (P) plays only that part and stops; with Loop on it starts over again.
- Delete range cuts the range from all tracks and pulls the rest forward. Delete outside range keeps only the range. Locked tracks do not change; Ctrl + Z undoes it.
- In the export window, "Export selected range only" turns just this part of the project into a video. Esc clears the range.

2.4 Cutting and editing

- Select the clip, move the playhead to the cut point and press S.
- Delete removes the clip. Shift + Delete removes it and pulls the following clips forward.
- Ctrl + D duplicates. Copy with Ctrl + C and paste at the playhead with Ctrl + V.
- Ctrl + Z undoes, Ctrl + Y redoes. The M key places a marker at the playhead.

2.5 Picture, color and transition

- Set opacity, scale and position in the Properties panel. You can also move the selected clip by dragging it in the preview.
- Adjust brightness, contrast and saturation or choose the Vivid, Cinematic and Black & white looks.
- Fade in and out open and close the clip slowly. If you overlap two clips on different tracks, one blends into the other.
- Speed can be set between 0.25x and 4x; the audio speed changes with it.

2.6 Text and audio

- Add a title with Add text. Change the font, size, color, outline and background in the Properties panel.
- Volume goes up to 200%. Audio fade in and out open and close music smoothly.
- "Detach audio to its own track" turns the video's sound into a separate clip that you can cut and move independently.
- Volume points: select the clip and double-click the yellow line on it. Drag a point up or down to raise or lower the volume at that moment; ideal for lowering music while talking. Right-click deletes a point.
- Noise reduction removes fan noise, hum and hiss. Leveling raises quiet parts and softens loud ones. Both are audible in the preview.
- When exporting, "Normalize loudness to the YouTube standard" sets the overall loudness to -14 LUFS.
- The audio waveform is shown on clips in the timeline, which makes finding cut points easier.

2.7 Transitions, annotations and effects

- The Library at the top left has Transitions, Annotations and Effects tabs.
- Drag a transition to the start or end of a clip. A transition between two adjacent clips goes directly from one to the other, whichever clip it is on; no black shows behind it. The transition also closes a small gap between them.
- With Magnet on at the start of a track, no gaps remain between clips: when you delete, the following clips move forward, and a moved clip slots in where you drop it.
- The Snap box at the top turns snapping of clips to edges and the playhead on and off; holding Alt turns it off temporarily.
- Annotations: lower third, speech bubble, rectangle, ellipse, highlight frame, highlighter, arrow, line and number badge. Click to add one at the playhead.
- Blur and pixelate areas hide information such as user names, chats or passwords visible on the tracks below. Place the clip on any track and duration, then position it by dragging in the preview.
- Effects apply to the selected clips: slow zoom, blur, vignette, color looks, sepia, negative, green screen, mirror.
- Rotation, flipping and cropping are in the Properties panel.
- Applied transitions and effects appear in the Applied list at the top of Properties; remove them one by one with × or all at once with Remove all. The right-click menu and Library tabs also have remove buttons.

2.8 Keyframes

- Select the clip, move the playhead over it and press "Add keyframe at playhead" in Properties.
- Move the playhead to another moment and change the scale, position, rotation or opacity; a new keyframe is written at that moment and the motion in between is created automatically.
- On an animated clip, dragging it in the preview also changes the keyframe at the playhead.
- Keyframes appear as diamonds under the clip on the timeline: click to jump to that moment, drag to change its time, right-click to delete. Turn Smooth on or off in the list in Properties.

2.9 Zoom and pan

- Open Library > Zoom. Move the playhead to where the zoom should start, press "Select area and zoom" and draw the area in the preview.
- The picture zooms smoothly into that area within the duration you choose. At a later moment, "Zoom out" returns to the full view.
- If no clip is selected, all visuals under the playhead zoom together. Zooms are added as keyframes, so you can edit them later.
- To cancel area selection, press the "Cancel" button in the same place.

2.10 Entrance / exit motion and typewriter

- Motions in the Effects tab apply to both the entrance and exit of the selected clip: rise from below, drop from above, slide in, pop in, wipe from left.

- Typewriter works only on text clips: letters appear one by one and are erased from the end on exit.
- In Properties > Entrance / exit motion you can choose separate motions and durations for entrance and exit.

2.11 Shadow, corners, border and mask

- A shadow can be added to any image, text or shape; set its color, opacity, softness and offset in Properties.
- Rounded corners, border and mask work on video, image and solid color clips. Circle mask suits camera footage.
- Mask size and position are set as a percentage of the clip; Soft edge softens the mask border.

2.12 Spotlight

- Annotations > Spotlight darkens everything outside the selected area. It affects the tracks below, so it should be on the top track.
- Adjust its shape, darkness, soft edge and size in Properties; drag it in the preview to move it.

2.13 Cursor highlight, click ring, key overlay

- Works with recordings made in Recording Studio with "Record cursor and clicks" on; the ".input.json" file next to the recording is read automatically.
- Select a video clip and turn it on in the Effects tab or in Properties > Cursor and keyboard. You can set the highlight's color, size and opacity.
- The key overlay shows the shortcuts pressed at the top of the screen if "Record shortcut keys" was on during recording.

2.14 Voice effects

- Select a clip with sound and choose in the Effects tab or Properties > Audio: deep voice, high voice, robot, telephone, radio, echo, hall.

2.15 Subtitles

- In Library > Subtitles, "Add subtitle at playhead" adds a 3-second subtitle; change its text, start and end in the list.
- SRT files can be imported and exported. Set the text size, color, background and position in the Appearance section.
- If "Burn subtitles into video" is on, subtitles are rendered into the exported video. You can also save an .srt file when exporting.

2.16 Freeze frame and reverse playback

- Select a video clip and move the playhead to the frame you want; Effects > "Add freeze frame" inserts that frame as a 3-second image and moves the following clips.

- Reverse playback plays video and audio clips from end to start. Turn it on with the box in Properties > Speed or from the right-click menu.
- In the preview a reversed clip is read in two-second chunks, so there may be a short stutter; the exported video has none.

2.17 Applying settings to other clips

- When several clips are selected, every change you make in Properties applies to all of them.
- "Copy settings" (Ctrl + Shift + C) takes the clip's look, effect, transition and audio settings; select other clips and apply them with "Paste to selected" (Ctrl + Shift + V).
- You can type a value into the box next to each slider.

2.18 Recording from microphone


- The "Record from microphone" button in the Media tab or Ctrl + R starts recording; press again to stop.
- The recording is added to an audio track starting at the playhead. With "Play the video while recording" on, you can narrate while watching; use headphones for this.

2.19 Export

- The first video you add sets the project size and frame rate, so the video is not rescaled and stays sharp.
- The higher the quality percentage, the closer the picture is to the source. From 90 percent up it is visually indistinguishable.
- In File > Export, choose a preset or set the resolution, encoder and quality yourself.
- The lower the quality value, the better the picture and the larger the file. Hardware encoders are faster; x264 usually looks better at the same size.
- Change the canvas in Project > Project settings; vertical short-video and square formats are available too.
- The preview is in low resolution for smoothness; the exported video is full quality.

3. Game Tools

Crosshair and FPS overlay



Screenshot: Game Tools

3.1 Quick start

- Choose the Crosshair or FPS Meter page on the left and press "Show on screen".
- Even if you close the window with the X, the overlays stay on screen and you can switch to your game.
- Overlays do not block clicks; the mouse passes through them.

3.2 Running in the background and closing

- The X does not close the program: the window hides and the program keeps running among the icons next to the clock.
- If you cannot see the icon, click the up arrow in the taskbar.
- Left-click the icon to open the window. Right-click for a menu to turn the crosshair and FPS meter on and off.
- To close the program completely, use the Exit button at the bottom left or Exit in the tray menu. The overlays close too.

3.3 Start automatically when the computer starts

- Tick "Show automatically when the computer starts" at the top of the Crosshair and FPS Meter pages.
- Windows asks for administrator approval the first time; saying "Yes" once is enough.
- No window opens when the computer starts; the program starts as an icon and only the ticked overlays are shown.
- If you move the program file to another folder, untick the box and tick it again.

3.4 Crosshair settings

- Set the line length, thickness and center gap with the sliders on the right. Changes apply instantly.
- Tick "Adjust each line separately" to open the Top, Bottom, Left and Right tabs. Each line has its own length, thickness and gap. A line with length 0 is hidden.
- The rotation sections of the inner and outer lines are separate and do not affect each other. The square dot rotates with the inner lines.
- "Rotate all" turns that set of lines together; for example 45 degrees makes an X shape.
- In the Top, Bottom, Left and Right rows, each line has its own angle. "Around itself" turns the line in place, "Around the center" moves it around the crosshair. Giving all four the same own angle makes a propeller shape.
- "Reset angles" only sets the rotations of the current section to 0; length and thickness stay unchanged.
- You can turn the dot, outer lines and ring on and off separately.
- Click the color box to pick a color. If it is not visible in a bright game, turn on the Outline option.

3.5 Crosshair profiles

- To save a look you like, type a name in the Profile name field and press Save.
- Clicking a profile in the list applies it immediately. The profile in use is marked in the list.
- Unsaved changes are lost when you choose a profile; save first.
- "Copy code" turns the crosshair into a share code. Your friend copies the code and presses "Import code" to use the same one.

3.6 FPS Meter

- In the Info tab, choose the values you want to show: FPS, graphics card, processor, RAM, disk, battery, clock.
- Set the font, size and colors in the Appearance tab.
- The Warnings tab changes the color when FPS drops or temperature rises.
- Choose which corner of the screen it sits in on the Position / Background tab.
- The FPS shown is the number of frames reaching the screen; it can differ from the game's own FPS and may be limited by the refresh rate.

3.7 If temperatures are not read

- For processor and disk temperatures the program must run as administrator. Use the "Open as administrator" button on the FPS Meter page.
- With autostart on, the program already starts with this permission when the computer starts.
- The processor temperature also needs the free PawnIO driver. If it is not installed, a download button appears on the page.
- A value marked "unreadable" may not be supported on your computer.

3.8 Hiding from recording and stream

- Overlays normally appear in screen recordings and streams.
- If you tick "Hide from recording and stream", the overlay is visible on your screen but not in recordings.

3.9 Shortcuts

- F9: Show / hide crosshair. F10: Close crosshair.
- F7: Show / hide FPS meter. F8: Close FPS meter.
- These also work in game. If your game uses the same keys, change them on the Shortcuts page.

3.10 Theme and appearance

- In Settings, choose the Classic or Bootstrap theme, and below it Dark or Light mode.
- The button at the bottom left quickly switches between dark and light mode.
- Your choice is saved; the program starts with the same look next time.

3.11 Caution in games

- The crosshair and FPS meter are drawn on screen as a separate window and never touch game files.
- Still, the rules of some competitive games may ban on-screen crosshairs. Check the rules of the game you play.
- Overlays may not show in exclusive full-screen mode; switch the game to borderless window mode.
- When the game changes resolution, the crosshair and FPS overlay reposition themselves for the new screen.

License and privacy

- This program is free. The developers do not sell it; there is no license fee, subscription, paid edition or in-app purchase.
- The developers collect no data from you. The program has no account, ads, usage statistics, error reporting or automatic update checks.
- You may study and modify the source code and share the program with others, modified or not.
- To the extent permitted by law, the program is provided as is, without any warranty. It is not guaranteed to be fit for a particular purpose, error-free or uninterrupted.