# 16.3 — std::vector and the unsigned length and subscript problem

learncpp.com/cpp-tutorial/stdvector-and-the-unsigned-length-and-subscript-problem/

In the prior lesson <u>16.2 -- Introduction to std::vector and list constructors</u>, we introduced operator[], which can be used to subscript an array to access an element.

In this lesson, we'll look at other ways to access array elements, as well as a few different ways to get the length of an container class (the number of elements currently in the container class).

But before we can do that, we need to discuss one major mistake that the designers of C++ made, and how it affects all the container classes in the C++ standard library.

The container length sign problem

Let's start with an assertion: the data type used for subscripting an array should match the data type used for storing the length of the array. This is so that all elements in the longest possible array can be indexed, and no more.

As Bjarne Stroustrup <u>recalls</u>, when the container classes in the C++ standard library was being designed (circa 1997), the designers had to choose whether to make the length (and array subscripts) signed or unsigned. They chose to make them unsigned.

The reasons given for this: the subscripts of the standard library array types can't be negative, using an unsigned type allows arrays of greater length due to the extra bit (something that was important in the 16-bit days), and range-checking the subscript requires one conditional check instead of two (since no check was needed to ensure the index was less than 0).

In retrospect, this is generally regarded as having been the wrong choice. We now understand that using unsigned values to try to enforce non-negativity doesn't work due to the implicit conversion rules (since a negative signed integer will just implicitly convert to a large unsigned integer, producing a garbage result), the extra bit of range typically isn't needed on 32-bit or 64-bit systems (since you probably aren't creating arrays with more than 2 million elements), and the commonly used operator[] doesn't do range-checking anyway.

In lesson <u>4.5 -- Unsigned integers</u>, and why to avoid them, we discussed the reasons why we prefer to use signed values to hold quantities. We also noted that mixing signed and unsigned values is a recipe for unexpected behavior. So the fact that the standard library container classes use unsigned values for the length (and indices) is problematic, as it makes it impossible to avoid unsigned values when using these types.

For now, we are stuck with this choice and the unnecessary complexity it causes.

A review: sign conversions are narrowing conversions, except when constexpr

Before we proceed further, let's quickly recap some material from lesson <u>10.4 -- Narrowing conversions</u>, list initialization, and constexpr initializers regarding sign conversions (integral conversions from signed to unsigned or vice-versa) because we'll be talking about these a lot in this chapter.

Sign conversions are considered to be narrowing conversions because a signed or unsigned type cannot hold all the values contained in the range of the opposing type. When such a conversion is attempted at runtime, the compiler will issue an error in contexts where narrowing conversions are disallowed (such as in list initialization), and may or may not issue a warning in other contexts where such a conversion is required.

## For example:

```
#include <iostream>

void foo(unsigned int)
{
}

int main()
{
   int s { 5 };

   [[maybe_unused]] unsigned int u { s }; // compile error: list initialization disallows narrowing conversion
   foo(s); // possible warning: copy initialization allows narrowing conversion
   return 0;
}
```

In the above example, the initialization of variable u produces a compilation error because narrowing conversions are disallowed when doing list initialization. The call to foo() performs copy initialization, which does allow narrowing conversions, and which may or may not produce a warning depending on how aggressive the compiler is in producing sign conversion warnings. For example, both GCC and Clang will produce warnings in this case when compiler flag -Wsign-conversion is used.

However, if the value to be sign converted is constexpr and can be converted to an equivalent value in the opposing type, the sign conversion is *not* considered to be narrowing. This is because the compiler can guarantee that the conversion is safe, or halt the compilation process.

In this case, since s is constexpr and the value to be converted (5) can be represented as an unsigned value, the conversion is not considered to be narrowing and can be performed implicitly without issue.

This non-narrowing constexpr conversion (from constexpr int to constexpr std::size\_t) will be something we make use of a lot.

The length and indices of std::vector have type size\_type

In lesson <u>10.7 -- Typedefs and type aliases</u>, we mentioned that typedefs and type aliases are often used in cases where we need a name for a type that may vary (e.g. because it is implementation-defined). For example std::size\_t is a typedef for some large unsigned integral type, usually unsigned long or unsigned long.

Each of the standard library container classes defines a nested typedef member named size\_type (sometimes written as T::size\_type), which is an alias for the type used for the length (and indices, if supported) of the container.

You'll typically see size\_type appear in documentation and in compiler warnings/error
messages. For example, this documentation for the size() member function of std::vector
indicates that size() returns a value of size\_type.

#### Related content

We cover nested typedefs in lesson 15.3 -- Nested types (member types).

size\_type is almost always an alias for std::size\_t, but can be overridden (in rare cases)
to use a different type.

Key insight

size\_type is a nested typedef defined in standard library container classes, used as the type for the length (and indices, if supported) of the container class.

size\_type defaults to std::size\_t, and since this is almost never changed, we can reasonably assume size\_type is an alias for std::size\_t.

#### For advanced readers

All of the standard library containers except std::array use std::allocator to allocate
memory. For these containers, T::size\_type is derived from the size\_type of the allocator
used. Since std::allocator can allocate up to std::size\_t bytes of memory,
std::allocator<T>::size\_type is defined as std::size\_t. Therefore, T::size\_type defaults to std::size\_t.

Only in cases where a custom allocator whose T::size\_type is defined as something other than std::size\_t will a container's T::size\_type be something other than std::size\_t. This is rare and something done on a per-application basis, so it's generally safe to assume T::size\_type will be std::size\_t unless your application is using such a custom allocator (and you will know if that is the case).

When accessing the size\_type member of a container class, we must scope qualify it with the fully templated name of the container class. For example,

```
std::vector<int>::size_type.
```

Getting the length of a std::vector using the size() member function or std::size()

We can ask a container class object for its length using the size() member function (which returns the length as unsigned size\_type):

```
#include <iostream>
#include <vector>

int main()
{
    std::vector prime { 2, 3, 5, 7, 11 };
    std::cout << "length: " << prime.size() << '\n'; // returns length as type
`size_type` (alias for `std::size_t`)
    return 0;
}</pre>
```

#### This prints:

```
length: 5
```

Unlike std::string and std::string\_view, which have both a length() and a size() member function (that do the same thing), std::vector (and most other container types in C++) only has size(). And now you understand why the length of a container is sometimes

ambiguously called its size.

In C++17, we can also use the std::size() non-member function (which for container classes just calls the size() member function).

```
#include <iostream>
#include <vector>

int main()
{
    std::vector prime { 2, 3, 5, 7, 11 };
    std::cout << "length: " << std::size(prime); // C++17, returns length as type
`size_type` (alias for `std::size_t`)
    return 0;
}</pre>
```

For advanced readers

Because std::size() can also be used on non-decayed C-style arrays, this method is sometimes favored over the using the size() member function (particularly when writing function templates that can accept either a container class or non-decayed C-style array argument).

If we want to use either of the above methods to store the length in a variable with a signed type, this will likely result in a signed/unsigned conversion warning or error. The simplest thing to do here is static cast the result to the desired type:

```
#include <iostream>
#include <vector>

int main()
{
    std::vector prime { 2, 3, 5, 7, 11 };
    int length { static_cast<int>(prime.size()) }; // static_cast return value to int std::cout << "length: " << length;
    return 0;
}</pre>
```

Getting the length of a std::vector using std::ssize() C++20

C++20 introduces the std::ssize() non-member function, which returns the length as a large *signed* integral type (usually std::ptrdiff\_t, which is the type normally used as the signed counterpart to std::size\_t):

```
#include <iostream>
#include <vector>

int main()
{
    std::vector prime{ 2, 3, 5, 7, 11 };
    std::cout << "length: " << std::ssize(prime); // C++20, returns length as a large signed integral type
    return 0;
}</pre>
```

This is the only function of the three which returns the length as a signed type.

If you want to use this method to store the length in a variable with a signed type, you have a couple of options.

First, because the int type may be smaller than the signed type returned by std::ssize(), if you are going to assign the length to an int variable, you should static\_cast the result to int to make any such conversion explicit (otherwise you might get a narrowing conversion warning or error):

```
#include <iostream>
#include <vector>

int main()
{
    std::vector prime{ 2, 3, 5, 7, 11 };
    int length { static_cast<int>(std::ssize(prime)) }; // static_cast return value to int
    std::cout << "length: " << length;
    return 0;
}</pre>
```

Alternatively, you can use auto to have the compiler deduce the correct signed type to use for the variable:

```
#include <iostream>
#include <vector>

int main()
{
    std::vector prime{ 2, 3, 5, 7, 11 };
    auto length { std::ssize(prime) }; // use auto to deduce signed type, as returned by std::ssize()
    std::cout << "length: " << length;
    return 0;
}</pre>
```

Accessing array elements using operator[] does no bounds checking

In the prior lesson, we introduced the subscript operator (operator[]):

```
#include <iostream>
#include <vector>

int main()
{
    std::vector prime{ 2, 3, 5, 7, 11 };

    std::cout << prime[3]; // print the value of element with index 3 (7)
    std::cout << prime[9]; // invalid index (undefined behavior)

    return 0;
}</pre>
```

operator[] does not do bounds checking. The index for operator[] can be non-const. We'll discuss this further in a later section.

Accessing array elements using the at() member function does runtime bounds checking

The array container classes support another method for accessing an array. The at() member function can be used to do array access with runtime bounds checking:

```
#include <iostream>
#include <vector>

int main()
{
    std::vector prime{ 2, 3, 5, 7, 11 };

    std::cout << prime.at(3); // print the value of element with index 3
    std::cout << prime.at(9); // invalid index (throws exception)

    return 0;
}</pre>
```

In the above example, the call to prime.at(3) checks to ensure the index 3 is valid, and because it is, it returns a reference to array element 3. We can then print this value. However, the call to prime.at(9) fails (at runtime) because 9 is not a valid index for this array. Instead of returning a reference, the at() function generates an error that terminates the program.

#### For advanced readers

When the at() member function encounters an out-of-bounds index, it actually throws an exception of type std::out\_of\_range. If the exception is not handled, the program will be terminated. We cover exceptions and how to handle them in chapter 27.

Just like operator[], the index passed to at() can be non-const.

Because it does runtime bounds checking on every call, at() is slower (but safer) than operator[]. Despite being less safe, operator[] is typically used over at(), primarily because it's better to do bounds checking before we call at(), so we don't call it with an invalid index in the first place.

Indexing std::vector with a constexpr signed int

When indexing a std::vector with a constexpr (signed) int, we can let the compiler implicitly convert this to a std::size\_t without it being a narrowing conversion:

Indexing std::vector with a non-constexpr value

The subscripts used to index an array can be non-const:

However, as per our best practices (<u>4.5 -- Unsigned integers</u>, and why to avoid them), we generally want to avoid using unsigned types to hold quantities.

When our subscript is a non-constexpr signed value value, we run into problems:

In this example, index is a non-constexpr signed int. The subscript of operator[] defined as part of std::vector has type size\_type (an alias for std::size\_t). Therefore, when we call prime[index], our signed int must be converted to std::size\_t.

Such a conversion should not be dangerous (because the index of a std::vector is expected to be non-negative, and a non-negative signed value will safely convert to an unsigned value). But when performed at runtime, this is considered to be a narrowing conversion, and your compiler should produce a warning about this being an unsafe conversion (if it doesn't, you should consider modifying your warnings so that it does).

Because array subscripting is common, and each such conversion will generate a warning, this can easily clutter up your compilation log with spurious warnings. Or, if you have "treat warning as errors" enabled, it will halt your compilation.

There are many possible ways to avoid this issue (e.g. static\_cast your int to a std::size\_t every time you index an array), but none that are convenient -- they all inevitably end up cluttering or complicating your code in some way.

The simplest thing to do in this case is use a variable of type std::size\_t as your index, and do not use this variable for anything but indexing.

Author's note

We'll discuss additional options to address such indexing challenges in lesson <u>16.7 -- Arrays</u>, <u>loops</u>, <u>and sign challenge solutions</u>.

Quiz time

Question #1

Initialize a std::vector with the following values: 'h', 'e', 'l', 'o'. Then print the length of the array (use std::size()). Finally, print the value of the element with index 1 using the subscript operator and the at() member function.

The program should output the following:

```
The array has 5 elements.
```

# **Show Solution**

Question #2

a) What is size\_type and what is it used for?

# **Show Solution**

b) What type does size\_type default to? Is it signed or unsigned?

## **Show Solution**

c) Which functions to get the length of a container return size\_type?

### **Show Solution**