Университет ИТМО

Факультет программной инженерии и компьютерной техники

Администрирование вычислительных систем

Лабораторная работа № 5

Выполнили: Дерябин Андрей Глушков Дима

Группа Р3410

Оглавление

Задание 8. Создание сетей IPv6	2		
 Подготовка среды Конфигурирование адресации IPv6 Конфигурирование OSPFv3 	2 2 3		
		4. Настройка DHCPv6 для распределения IPv6 адресов	5

Задание 8. Создание сетей IPv6




Рис. 1. Реализованная топология

1. Подготовка среды

<Huawei>sys
[Huawei]sysname R1
<Huawei>sys
[Huawei]sysname R2
<Huawei>sys
[Huawei]sysname R3

2. Конфигурирование адресации IPv6

Настроим глобальную адресацию одноадресной передачи IPv6 на интерфейсах loopback. Вручную настроим локальную адресацию канала на интерфейсе GI0/0/0 для всех маршрутизаторов.

[R1]ipv6

[R1]int loopback 0

[R1-LoopBack0]ipv6 enable

[R1-LoopBack0]ipv6 address 2001:1::A 64

[R1-LoopBack0]int gi0/0/0

[R1-GigabitEthernet0/0/0]ipv6 enable

[R1-GigabitEthernet0/0/0]ipv6 address fe80::1 link-local

[R2]ipv6

[R2]int loopback 0

[R2-LoopBack0]ipv6 enable

[R2-LoopBack0]ipv6 address 2001:2::B 64

[R2-LoopBack0]int gi0/0/0

[R2-GigabitEthernet0/0/0]ipv6 enable

[R2-GigabitEthernet0/0/0]ipv6 address fe80::2 link-local

[R3]ipv6

[R3]int loopback 0

[R3-LoopBack0]ipv6 enable

[R3-LoopBack0]ipv6 address 2001:3::C 64

[R3-LoopBack0]int gi0/0/0

[R3-GigabitEthernet0/0/0]ipv6 enable

[R3-GigabitEthernet0/0/0]ipv6 address fe80::3 link-local

[R1]disp ipv6 int gi0/0/0

GigabitEthernet0/0/0 current state: UP

IPv6 protocol current state : UP

IPv6 is enabled, link-local address is FE80::1

No global unicast address configured

Joined group address(es):

FF02::1:FF00:1

FF02::2 FF02::1

MTU is 1500 bytes

ND DAD is enabled, number of DAD attempts: 1

ND reachable time is 30000 milliseconds

ND retransmit interval is 1000 milliseconds

Hosts use stateless autoconfig for addresses

3. Конфигурирование OSPFv3

Включим процесс OSPFv3 и укажем его идентификатор маршрутизатора на R1, R2 и R3. Убедимся, что он включен.

[R1]ospfv3 1

[R1-ospfv3-1]router-id 1.1.1.1

[R1-ospfv3-1]q

[R1]int gi0/0/0

[R1-GigabitEthernet0/0/0]ospfv3 1 area 0

[R1-GigabitEthernet0/0/0]q

[R1]int loopback 0

[R1-LoopBack0]ospfv3 1 area 0

[R2]ospfv3 1

[R2-ospfv3-1]router-id 2.2.2.2

[R2-ospfv3-1]q

```
[R2]int gi0/0/0
[R2-GigabitEthernet0/0/0]ospfv3 1 area 0
[R2-GigabitEthernet0/0/0]q
[R2]int loopback 0
[R2-LoopBack0]ospfv3 1 area 0

[R3]ospfv3 1
[R3-ospfv3-1]router-id 3.3.3.3
[R3-ospfv3-1]q
[R3]int gi0/0/0
[R3-GigabitEthernet0/0/0]ospfv3 1 area 0
[R3-GigabitEthernet0/0/0]q
[R3]int loopback 0
[R3-LoopBack0]ospfv3 1 area 0
```

Выполним команду **display ospfv3 peer** на R1 и R3 чтобы убедиться, что установлено одноранговое соединение OSPFv3.

```
[R1]disp ospfv3 peer
OSPFv3 Process (1)
OSPFv3 Area (0.0.0.0)
Neighbor ID
            Pri State
                             Dead Time Interface
                                                       Instance ID
2.2.2.2
            1 Full/Backup
                              00:00:32 GE0/0/0
                                                             0
                                                              0
3.3.3.3
            1 Full/DROther
                              00:00:33 GE0/0/0
[R3]disp ospfv3 peer
OSPFv3 Process (1)
OSPFv3 Area (0.0.0.0)
Neighbor ID
             Pri State
                             Dead Time Interface
                                                       Instance ID
1.1.1.1
            1 Full/DR
                            00:00:37 GE0/0/0
                                                           0
2.2.2.2
            1 Full/Backup
                              00:00:34 GE0/0/0
                                                             0
```

Если бы 1.1.1.1 в данный момент не являлся DR, то для сброса процесса OSPFv3 можно было бы выполнить команду **<R1>reset ospfv3 1 graceful-restart.**

Проверим подключение к локальному адресу однорангового канала и к глобальному адресу одноадресной передачи интерфейса LoopBack 0.

```
[R1]ping ipv6 fe80::3 -i gi0/0/0
PING fe80::3 : 56 data bytes, press CTRL_C to break
Reply from FE80::3
bytes=56 Sequence=1 hop limit=64 time = 50 ms
Reply from FE80::3
bytes=56 Sequence=2 hop limit=64 time = 50 ms
Reply from FE80::3
bytes=56 Sequence=3 hop limit=64 time = 40 ms
Reply from FE80::3
bytes=56 Sequence=4 hop limit=64 time = 60 ms
Reply from FE80::3
bytes=56 Sequence=5 hop limit=64 time = 50 ms
```

--- fe80::3 ping statistics ---5 packet(s) transmitted 5 packet(s) received 0.00% packet loss round-trip min/avg/max = 40/50/60 ms [R1]ping ipv6 2001:3::C PING 2001:3::C: 56 data bytes, press CTRL C to break Reply from 2001:3::C bytes=56 Sequence=1 hop limit=64 time = 40 ms Reply from 2001:3::C bytes=56 Sequence=2 hop limit=64 time = 40 ms Reply from 2001:3::C bytes=56 Sequence=3 hop limit=64 time = 30 ms Reply from 2001:3::C bytes=56 Sequence=4 hop limit=64 time = 50 ms Reply from 2001:3::C bytes=56 Sequence=5 hop limit=64 time = 40 ms --- 2001:3::C ping statistics ---5 packet(s) transmitted 5 packet(s) received 0.00% packet loss round-trip min/avg/max = 30/40/50 ms

4. Настройка DHCPv6 для распределения IPv6 адресов

Включим функцию DHCPv6 Server на R2, чтобы устройствам можно было назначать адреса IPv6 с помощью DHCPv6.

[R2]dhcp enable [R2]dhcpv6 duid II

Warning: The DHCP unique identifier should be globally-unique and stable. Are you sure to change it? [Y/N]y

[R2]dhcpv6 pool pool1

[R2-dhcpv6-pool-pool1]address prefix 2001:FACE::/64

[R2-dhcpv6-pool-pool1]dns-server 2001:444e:5300::1

[R2-dhcpv6-pool-pool1]excluded-address 2001:FACE::1

[R2-dhcpv6-pool-pool1]q

Настроим функции IPv6 на интерфейсе gi0/0/0. Включим функцию DHCPv6-сервера на интерфейсе.

[R2]int gi0/0/0

[R2-GigabitEthernet0/0/0]ipv6 address 2001:FACE::1 64

[R2-GigabitEthernet0/0/0]dhcpv6 server pool1

Включим функцию клиента DHCPv6 на R1 и R3, чтобы устройствам можно было назначать адреса IPv6 с помощью DHCPv6.

[R1]dhcp enable

[R1]dhcpv6 duid II

Warning: The DHCP unique identifier should be globally-unique and stable. Are you sure to change it? [Y/N]y

[R1]int gi0/0/0

[R1-GigabitEthernet0/0/0]ipv6 address auto dhcp

[R3]dhcp enable

[R3]dhcpv6 duid II

Warning: The DHCP unique identifier should be globally-unique and stable. Are you sure

to change it? [Y/N]y [R3]int gi0/0/0

[R3-GigabitEthernet0/0/0]ipv6 address auto dhcp

Выполним команду **display dhcpv6 pool** на R2 для проверки информации о пуле адресов DHCPv6.

[R2]disp dhcpv6 pool

DHCPv6 pool: pool1

Address prefix: 2001:FACE::/64

Lifetime valid 172800 seconds, preferred 86400 seconds

2 in use, 0 conflicts

Excluded-address 2001:FACE::1

1 excluded addresses

Information refresh time: 86400

DNS server address: **2001:444E:5300::1** Conflict-address expire-time: 172800

Active normal clients: 2

Выполним команду display ipv6 interface brief на R1 и R3 для проверки информации об адресе IPv6.

[R1]disp ipv6 int brief

*down: administratively down

(I): loopback (s): spoofing

Interface Physical Protocol

GigabitEthernet0/0/0 up up

[IPv6 Address] **2001:FACE::2**

LoopBack0 up up(s)

[IPv6 Address] 2001:1::A

[R3]disp ipv6 int brief

*down: administratively down

(I): loopback (s): spoofing

Interface Physical Protocol

GigabitEthernet0/0/0 up [IPv6 Address] 2001:FACE::3 LoopBack0 up [IPv6 Address] 2001:3::C up

up(s)