# Translating Three-Address Code to MIPS Assembly Code

Saumya Debray Department of Computer Science The University of Arizona, Tucson

## 1 A Simple Three-Address Instruction Set

This document considers a simple three-address instruction set and describes its translation to MIPS assembly code:

- Assignment and copy statements:
  - 1.  $x := y \ op \ z$  $op \in \{+, -, *, /\}.$
  - 2. x := -y
  - 3. x := y
- Indexed assignments
  - 1. x := y[i]
  - 2. x[i] := y
- Conditional and unconditional jumps:
  - 1. if x relop y goto L

L is a label;  $relop \in \{<=, <, >=, >, ==, !=\}.$ 

- 2. goto L
  - L is a label.
- 3. label L

L is a label; it must be unique in the program.

- Instructions for function calls/returns:
  - 1. enter f

f is (a pointer to the symbol table entry of) a function.

2. leave f

f is (a pointer to the symbol table entry of) a function.

- $3. \ \mathtt{param} \ x$
- 4. call f, n

f is (a pointer to the symbol table entry of) a function; n is the number of arguments being passed.

5. return

return to the caller.

6. return x

return to the caller with return value x.

7. retrieve x

Copy the return value into x.




Figure 1: Structure of a stack frame

### 2 Notes on the MIPS R2000

### 2.1 General Information

This document describes how to translate 3-address intermediate code to assembly code for the MIPS R2000 processor (as implemented by Jim Larus's SPIM simulator).

Assembly code files should end with the suffix '.s'. The SPIM simulator reads in assembly source files, so there is no need to translate to machine code.

Comments can be inserted in the assembler source: a comment is indicated by a '#', and extends to the end of the line. It is recommended that you generate comments giving three-address instructions together with your assembly code to simplify debugging.

### 2.2 The Stack

A stack frame has the structure shown in Figure 1. The stack grows from high addresses towards low addresses.

Two registers are relevant for stack management: the *stack pointer* \$sp (register 29) and the *frame pointer* \$fp (register 30). The stack pointer \$sp points to byte 0 (the high byte) of the top of the stack, i.e., the next available word is at displacement 4(\$sp).

The return address is passed to the callee in register register 31.

### 2.3 General-Purpose Registers and Memory

The MIPS is a simple load/store architecture, i.e., arithmetic instructions typically operate only on registers. It has 32 general-purpose registers of 32 bits each, numbered 0 through 31. In MIPS assembly language, register i is written i. The value of register 0 (i0) is always 0. Registers i1, i26, and i27 are reserved for use by the assembler and the OS kernel. Registers i29 (stack pointer, i39), i30 (frame pointer, i49), and i31 (return address register, i47) are used for managing activation records and function calls/returns. The results of integer-valued functions are returned in register i2 (i20).

Memory is byte addressable in little-endian mode, with 32-bit addresses. All instructions are 32 bits long, and must be aligned.

### 2.4 Byte Order

The SPIM simulator follows the byte order of the underlying processor. This means that on lectura, it is little-endian. That is, byte 0 of a 4-byte word is the rightmost (least significant) byte of that word.

## 3 Code Generation

### 3.1 Data and Text Segments

A set of data declarations must be preceded by the line

.data

A section of code (i.e., assembly instructions) must be preceded by

.text

Figure 2 gives an example of the use of these directives.

### 3.2 Identifiers and Labels

A global identifier id in the source program will translate to essentially the same identifier id in the assembly code generated, though to avoid inadvertent conflicts with SPIM opcodes, it's recommended that you add an underscore ' $\bot$ ' in front of each source identifier (see Section 5). Local variables will not map to identifiers, but will be accessed via displacements off the frame pointer.

In order to print string constants, it will be necessary to first declare the string, as discussed below, then access that string using a label generated for it (note that this means that you have to keep track of which label is associated with . which string).

A label is simply an identifier.

Keep in mind that while you will be compiling your program a function at a time, the simulator will see all the labels and identifiers generated in the assembly code output. For this reason, you should be careful to generate labels such that (i) no two compiler-generated labels will ever be in conflict; and (ii) a compiler-generated label will be unlikely to conflict with an identifier from the user's program. For example, you might consider using a global counter for your labels, so that distinct labels use distinct counter values; and have a leading and trailing pair of underscores on labels—e.g., produce labels such as '\_\_012\_\_'—to avoid conflicts with user-defined identifiers.

### 3.3 Assembler Directives

Space for globals can be generated one identifier at a time. An identifier id that occupies n bytes of storage is allocated as

```
int x;
                    .data
                    x:
                         .space 4
                         .space 1
char y, z
                    у:
                    z:
                         .space 1
                    .align 2
                     .text
foo()
                    foo:
{
                    ( code for foo )
                    .data
int a[10];
                        .space 40
                     .text
bar()
                    bar:
                    ( code for bar )
```

Figure 2: An Example of Code Layout for a Program

```
id : .space n
```

String constants can be defined using the .ascii and .asciiz directives, which store the strings listed in memory as a sequence of characters. String constants declared using .ascii are not terminated with a 0 byte, while those declared using .asciiz are 0-terminated. Thus, the string constant "x = %d,  $y = %d\n"$  can be defined by any of the following:

```
.ascii "x = %d, y = %d\12\0"
.ascii "x = %d, y = %d\n\0"
.asciiz "x = %d, y = %d\12"
.asciiz "x = %d, y = %d\n"
```

Finally, alignment restrictions can be enforced using the directive

```
.align n
```

which causes the next data/code to be loaded at an address divisible by  $2^n$ .

Example: Consider the following source program fragment, which declares several global variables, with the corresponding assembler directives:

```
Source Program
                               Assembler Directive
char w;
                               .data
                               w:
                                   .space 1
                                    .align 2
                                                (the next variable must be 4-byte-aligned)
int x, a[12];
                               x:
                                   .space 4
                                               (12 ints @ 4 bytes each)
                                    .space 48
                               a:
char y;
                                   .space 1
```

Code and data portions can be intermixed (as long as proper care is taken to align everything properly), as shown in Figure 2.

### 3.4 Strings

As mentioned in Section 3.3, strings are defined using '.ascii' or '.asciiz' directives. In order to use such a string, it has to have a label, e.g., something like:

```
__Str07: .asciiz "\n"
```

This example attaches the label \_\_Str07 to the string "\n" (the '\_\_' prefix is used to reduce the possibility of a conflict with user-defined identifiers). When the string is used in the program, we use this label.

SPIM does not require labels to be defined before they are used. This means that it's OK to define all the strings, along with their labels, in a single .data section at the end of the program. The simplest way to handle strings, therefore, is to collect them into a string table, then dump the string table into a .data section at the end of the program. Each string table entry consists of the string and its associated label (an int counter suffices to keep track of the label). Thus, when a string is encountered, it is entered into the string table and a label assigned to it. This label is then used when generating code for that string. Thus, given a function call in the source code:

```
foo("abc", "defg");
```

the strings "abc" and "defg" are added to the string table with labels. Suppose that these labels are \_\_Str17 and \_\_Str18, then the three-address code generated is:

When the string table is written out at the end, these strings will generate:

```
.data
...
__Str17: .asciiz "abc"
__Str18: .asciiz "defg"
```

### 3.5 Size Conversions

To load a 1-byte char variable at address addr into a 32-bit (sign-extended) value in register reg, use the instruction '1b reg, addr'. To store a 32-bit value in register reg into a 1-byte char variable at address addr, use the instruction 'sb addr, reg'.

### 3.6 Accessing Memory

The way in which a memory location is accessed depends on whether it is a global or a local; and if a local, then whether or not it is a formal parameter.

#### 3.6.1 Accessing Globals

A scalar global variable can be accessed directly by name, e.g., to load an int variable x into register 5, we can use

```
lw $5, x
```

An element of a global array can be accessed by computing its address and then accessing the contents of this address. Thus, given a global array A of ints, suppose we want to access the value of the three-address code expression A[i]. To do this, we generate

If we are accessing a global array of char, the load instruction at the very end is '1b' instead of '1w'.

The result is to leave the value of A[i] in  $reg_3$ . Note that scaling is necessary only if the size of each array element is greater than one byte. The code for storing a value into an array is similar, except that at the very end we use a 'sw' or 'sb' ("store word/byte") instruction instead of a 'lw' or 'lb' ("load word/byte") instruction (see Section 3.5).

A string constant can be accessed using the label associated with it.

#### 3.6.2 Accessing Locals: 1. Actual Parameters

The parameter passing convention described here is considerably simpler (but not as efficient) as that described in the SPIM manual. Here, all parameters are passed on the stack, and the  $n^{\text{th}}$  parameter to a function ( $n \ge 1$ , going from left to right) can be accessed from within the called function as k(\$fp), where k = 4n + 4. For example, given a function with three parameters, the leftmost is at 8(\$fp), the middle parameter is at 16(\$fp), and the rightmost is at 20(\$fp). Notice that, in Figure 1, the actuals are at higher addresses than \$fp. Because of this, actuals are accessed using positive offsets from \$fp.

If a parameter is an array, then what is passed is a pointer to the first element of the array. In this case, you have to load the contents of the corresponding memory location, then carry out the appropriate address arithmetic to find the array element being referred to.

#### 3.6.3 Accessing Locals: 2. Non-Parameter Variables

To access a local variable into a register, use the appropriate displacement off the frame pointer fp: a non-parameter local variable at displacement fp from the frame pointer is accessed as '-k(fp)'. Notice that, in Figure 1, the non-parameter local variables are below the frame pointer, i.e., at lower addresses than fp. Because of this, such variables are accessed using negative offsets from fp.

Accessing a local array is analogous to that for global arrays, except that we begin by loading the starting address of the array into a register explicitly, instead of using the name of the array variable. Thus, given a local array A of ints that starts at displacement k from the frame pointer, suppose we want to access the value of the three-address code expression A[i]. To do this, we generate

```
load the value of i into reg_1 la reg_2, -k(\$fp) /* load address of A into reg_2 */ sll\ reg_1, reg_1, 2 /* scale by 4 */ add reg_2, reg_2, reg_1 lw reg_3, (reg_2)
```

### 3.7 Loading Constant Values into Registers

A constant value n that is at most 16 bits wide (i.e., is less than  $2^{16} = 65,536$ ) can be loaded into a register r using the li ("load immediate") instruction:<sup>1</sup>

```
li r, n
```

A constant n that occupies between 16 and 32 bits wide can be loaded into a register r using the pair of instructions

<sup>&</sup>lt;sup>1</sup>Strictly speaking, '1i' is a pseudo-instruction: the actual MIPS hardware doesn't have this instruction; the assembler translates the instruction '1i r, n' to 'addi r, \$0, n'.

```
lui r, n_{16}^{hi} ori r, n_{16}^{lo}
```

where  $n_{16}^{hi}$  denotes the high 16 bits of n and  $n_{16}^{lo}$  denotes the low 16 bits of n. For example, suppose  $r\equiv\$8$  and  $n\equiv \texttt{Oxaabbccdd}$ , then  $n_{16}^{hi}\equiv \texttt{Oxaabb}$  and  $n_{16}^{lo}\equiv \texttt{Oxccdd}$ , and the necessary instruction sequence is:

```
lui $8, Oxaabb
ori $8, Oxccdd
```

### 3.8 Arithmetic Operations

Arithmetic operations are performed on registers. Shown below is a simple translation scheme (the SPIM manual discusses instructions that are able to use immediate operands that are not more than 16 bits wide: this optimization can result in somewhat more efficient code, but complicates the code generation process somewhat):

x := y op z	$load y into reg_1$
	$ \begin{array}{c c} load \ \mathbf{y} \ into \ reg_1 \\ load \ \mathbf{z} \ into \ reg_2 \end{array} $
	$\begin{array}{c} opc \ reg_3, \ reg_1, \ reg_2 \\ store \ reg_3 \ into \ \mathbf{x} \end{array}$
	store reg <sub>3</sub> into x
x := -y	load y into reg <sub>1</sub>
	$\begin{array}{c ccccccccccccccccccccccccccccccccccc$
	$store \ reg_2 \ into \ x$

where, for  $op \in \{+, -, *, /\}$ , opc is, respectively, add, sub, mul, and div.

Note that multiplication by powers of 2, which is common when addressing array elements, can be done using a sl1 (shift-left) instruction rather than the more expensive mul instruction.

### 3.9 Conditional and Unconditional Jumps

Unconditional and conditional control transfers can be implemented as follows:

goto L	j L	the offset of L is at most $\pm 2^{26}$ bytes
if x $op$ y goto L	~ 1	
	$load y into reg_2$	15
	$bcc reg_1$ , $reg_2$ , L	the offset of L is about $\pm 2^{15}$ instructions

where the condition codes are given by the following:

### 3.10 Arrays

The value of the  $i^{th}$  element x[i] of a global array x, whose elements are  $2^n$  bytes wide, can be obtained by

```
load the value of i into reg_1 load the starting address of \mathbf{x} into reg_2 sll reg_1, reg_1, \mathbf{n} (scale for element width: omit if \mathbf{n}=0) add reg_2, reg_1, reg_2 {lw, lb} reg_3, 0(reg_2)
```

```
lw $4, j
la $5, x
                         # $5 := start \ address \ of \ x
sll $4, $4, 2
                         # scale array index (x is an integer array)
add $5, $4, $5
                         # $5 := address of x[j]
                         # $6 := x[j]
lw $6, ($5)
sw $6, -40($fp)
                         # tmp := x[j]
lw -40(\$fp), \$4
                         # $4 := tmp
lw $5, i
la $6, -24($fp)
                         # $6 := start \ address \ of \ y
add $6, $5, $6
                         # 6 := address of y[i]
sb $4, ($6)
                         # y[i] := tmp
```

Figure 3: An Example of Generated Code for Array References

Storing a value is analogous, except that the instruction used at the end is sw or sb instead of {lw, lb}.

For example, suppose x is a global array of integers, and y is a local array of characters starting at displacement -24 from the frame pointer and growing from high to low addresses. Consider an assignment y[i] = x[j] in the source program, where i and j are globals: this translates to the 3-address instruction sequence

```
tmp = x[j]
y[i] = tmp
```

where tmp is a compiler-generated temporary variable (of type int) that resides at a displacement of -40 bytes from the frame pointer. Sample code generated for this sequence is shown in Figure 2.

### 3.11 Pointer Operations

Taking the address of a location is indicated by the operation

```
addr(x)
```

It can be implemented as follows:

addr(x): x a global	la reg, x
addr(x) : x a local at k(fp)	la $reg$ , $k(\$fp)$

Pointer dereferencing is indicated by the operation

```
deref(x)
```

where x is (a pointer to the symbol-table entry of) a location. It can be implemented as follows:

```
load x into reg_1

access (load/store) the location O(reg_1)
```

Thus, loads and stores through pointers are handled as follows:

y := deref(x)	$load x into reg_1$	
	$\{lw,lb\}$ $reg_2$ , $O(reg_1)$	
deref(x) := y	$\{lw,lb\}$ $reg_1$ , y	
	$\{lw,lb\} \ reg_1$ , y $load  ext{ x into } reg_2$	
	$\{sw,sb\}$ $reg_1$ , $O(reg_2)$	

### 3.12 Procedures

As with most RISC processors, the MIPS R2000 passes the first few (actually, four) arguments in a procedure call in registers; remaining arguments, if any, are passed on the stack, with the frame pointer \$fp pointing to the word immediately after the last argument passed on the stack.

For simplicity, we'll adopt a simpler parameter passing convention where all arguments are passed on the stack (if you want you can implement the more efficient scheme described above: the changes necessary to the assembly code described below aren't too hard to figure out). We'll also adopt a convention slightly different from that described in the SPIM manual, and have the \$fp register point at the leftmost actual parameter on the stack.

### 3.12.1 Entering a Procedure

On entering a procedure, it is necessary to update the stack and frame pointers, and save the old frame pointer and the return address. For this, we will use the intermediate code instruction

#### enter f

where f is (a pointer to the symbol table entry of) the procedure being entered. We use the symbol table entry for f to determine the number of bytes n required for its stack frame (and possibly auxiliary information such as any registers that we may want to save on entry to the procedure). The sequence of actions on entry to a procedure are:

- 1. Set up the frame pointer.
- 2. Allocate the stack frame by subtracting the size of the stack frame from \$sp. Since we know that the space occupied by local storage is n bytes, this works out to subtracting n from \$sp.
- 3. Save any registers that need to be saved.
  - In general, you'll need to save \$fp and \$ra.
  - Additionally, if your compiler is doing any sort of register allocation or code optimization that values to be put into callee-saved registers with the expectation that these values will survive across procedure calls, then the callee must save any callee-saved registers it uses at entry, and restore these before returning to its caller (since the project in CSC 453 doesn't do any register allocation, there are no additional registers to be saved/restored in CSC 453, and this part can be ignored).
- 4. Allocate space for the rest of the stack frame (locals and temps).

It simplifies things to have the first two words in the area for saved registers be reserved for \$fp and \$ra; in this case, assuming that \$sp is pointing at the topmost word on the stack, i.e., the leftmost actual parameter, it's simplest to first save \$fp and \$ra; then set up the frame pointer; and finally update \$sp to allocate the stack frame. The resulting assembly code is:

```
la $sp, -8($sp)  # allocate space for old $fp and $ra sw $fp, 4($sp)  # save old $fp sw $ra, 0($sp)  # save return address la $fp, 0($sp)  # set up frame pointer la $sp, -n($sp)  # allocate stack frame: n = space for locals/temps, in bytes
```

### 3.12.2 Calling a Procedure

For C programs, actual parameters are pushed from right to left. The relevant three address instructions translate as follows:

param x (x an int or char)	$load \times into \ reg_1$
	la \$sp, -4(\$sp)
	sw $reg_1$ , $O(\$sp)$
param x (x an array)	load starting address of x into $reg_1$
	la \$sp, -4(\$sp)
	sw $reg_1$ , O( $\$$ sp)

The callee does not pop the actual parameters off the stack on return, so this has to be done by the caller. To handle this, we use a three-address instruction

call 
$$p, n$$

where p is a procedure name and n is the number of arguments. This will translate as follows:

call p, n	jal p	
	la \$sp,	k(\$sp)

where k = 4n is the number of bytes occupied by the actual parameters.

### 3.12.3 Return from a Procedure

The return value of a function is put into register \$v0 by the callee. The relevant instructions therefore translate as follows:

leave $f$	restore callee-saved registers, if any (ignore for CSC 453)	
return	la \$sp, 0(\$fp)	(deallocate locals)
	lw \$ra, 0(\$sp)	(restore return address)
	lw \$fp, 4(\$sp)	(restore frame pointer)
	la \$sp, 8(\$sp)	(restore stack pointer)
	jr \$ra	(return)
return x	load x into \$v0	
	la \$sp, 0(\$fp)	(deallocate locals)
	lw \$ra, 0(\$sp)	(restore return address)
	lw \$fp, 4(\$sp)	(restore frame pointer)
	la \$sp, 8(\$sp)	(restore stack pointer)
	jr \$ra	(return)
retrieve x	store \$v0 into x	

## 4 Printing Out Values

For the purposes of this project we will assume the existence of a special function, println(x), that can be used to print out an integer value. For example, an input program might be:

```
int main() {
   int x;
   x = 123;
   println(x);
}
```

When the MIPS code generated for this program is executed, it should print out

123

To accommodate this, in addition to the code generated for the input program, your compiler should generate the MIPS instructions for println() given below.

Recall that with the convention we're using for parameter passing, (i) all parameters are passed on the stack; and (ii) the stack pointer points at the last word on the stack that is in use. Since println() takes one argument, this means that this argument is pushed on top of the stack and the stack pointer is left pointing at it. Since the SPIM system calls expect the argument in register \$a0, we need to load it from the stack.

The code you should generate is as follows (this is a hard-coded instruction sequence generated for all programs):

println(n): called with integer n pushed on the stack:

```
.align 2
.data
_nl: .asciiz "\n"
.align 2
.text
_println:
    li $v0, 1
    lw $a0, 0(sp)
    syscall
    li $v0, 4
    la $a0, .nl
    syscall
    jr $ra
```

## 5 Some Helpful Hints

- 1. For each three-address instruction that is processed, writing out the three-address instruction as a comment alongside the generated MIPS code can help simplify debugging.
- 2. Append an underscore '\_' in front of each source identifier before writing out assembly code. Thus, a source code identifier 'x' is written out as '\_x' in the MIPS code you generate. This avoids inadvertent name collisions between source program identifiers and MIPS opcodes like 'b' and 'j'. (This is the reason for the underscore at the beginning of the label \_println above.)

If you do this, the function main will get renamed to \_main. Since SPIM begins execution at the label main, you should therefore add the following line to the code you generate:

```
main : j_main
```

## Appendix: Using the SPIM Simulator

## 1. Finding spim

On the CS department server lectura, the executable for SPIM is available at

```
/usr/bin/spim
```

However, this software does not allow us to easily quantify the effects of optimizations. So for the purposes of this class we'll use a variant of spim that keeps track of the number of times various different kinds of instructions are executed. This variant is available at

```
/home/cs553/spring21/bin/spim (executable)
/home/cs553/spring21/spim-stats (source code)
```

Note: If you want to build your own copy of this spim variant, you should proceed as follows:

- 1. Copy over the source code directory mentioned above.
- 2. Install two open-source software packages, flex and bison, that are used by spim's front end.
- 3. cd spim-stats/spim
- 4. Edit Makefile, in particular edit the value of the variable PREFIX.
- 5. Type 'make spim' this will create an executable file spim in that directory. If you want you can copy or move this executable to some other place that you prefer.

## 2. Using spim

To run a MIPS assembly code program that is in a file foo, execute the command

```
spim -f foo
```

To get instruction counts for a run, you will have to use the spim-stats variant mentioned above. With this variant, you can get execution counts using the command:

```
spim -keepstats -f foo
```

A user manual for SPIM is available at http://www2.cs.arizona.edu/classes/cs553/spring21/DOCS/spim.pdf. This user manual contains a description of all the instructions available in the MIPS R2000 ISA.

# 3. Debugging

SPIM has some simple debugging facilities, including setting breakpoints and single-stepping through code, that can be very helpful for identifying problems in the assembly code generated by your compiler. See Section 1.2.1 (Terminal Interface) of the SPIM User Manual.