GammaLoop

Differential cross-sections with Local Unitarity

1 Overview

GammaLoop is alpha-stage research software that computes numerical amplitude integrands and uses Local Unitarity for differential partonic cross sections. Its current external-kinematics path uses fixed momenta and a unit PDF factor; it does not yet provide hadronic PDF convolution or a factorization scale. Begin with the physics scope and method before translating a desired collider observable into a run card.

The primary manual path is written for perturbative-QFT and collider physicists. GammaLoop is an application rather than a thin numerical library: model import, process generation, integrand construction, integration, observables, persistence, and diagnostics meet in one stateful workflow. Rust and Python details become relevant only when structured automation is needed.

> **Primary interface**
> The command-line interface is the primary user interface. A run card creates a state, executes commands, and leaves a reusable working directory. The Rust and Python APIs load the same persisted state and expose selected structured operations; they do not define a second, independent execution model.

1.1 Choose a task

- To build or install the CLI and evaluate a compact one-loop scalar graph, follow the command-line guide.
- To decide whether an initial state, contribution, mass/spin choice, subtraction, and observable are supported, read physics scope and Local Unitarity.
- To define momentum flow, helicity and color ownership, flux, units, and sample weights, use the scientific conventions.
- To follow a maintained run card through the complete persistence lifecycle, use the first-state tutorial.
- To adapt a process specification or generation filters, use the process-generation guide with the generated `generate` reference.
- To inspect and edit a diagram before rendering it, use the live notebook in GammaLoop DOT input.
- To inspect concrete cut events, selectors, and histogram snapshots without a full integration, follow the events and observables guide.
- To automate a loaded state or diagnose a long run, choose the Rust/Python interface guide or logging and diagnostics guide.

1.2 A stateful run

A typical source checkout is built and exercised from the repository root:

```
just build-cli-release
./gammaloop ./examples/cli/gg_hhh/1L/gg_hhh_1L.toml
```

The run card imports a model, generates the requested process, executes its command blocks, and records the resulting state. Resume that directory explicitly for subsequent work:

```
./gammaloop -s ./examples/cli/gg_hhh/1L/state \
  run integrate_physical -c "quit -o"
```

The persisted `run.toml` records how to replay the run. The settings files describe global and default runtime configuration, while `processes/` contains process-specific state. Ordinary runs create `gammaloop_state/` unless a different state path is supplied.

> **A lifecycle example is not a physics benchmark**
> The maintained `gg_hhh` card is useful because it exercises model loading, generation, integration settings, and persistence. It selects a fixed-helicity amplitude contribution with an explicit color projector; running it does not by itself produce an unpolarized, color-averaged cross section or validate a published observable.

1.3 Installation and external tools

For ordinary CLI use, begin with using GammaLoop from the command line. It recommends the packaged Nix application when Nix is available, but does not require it: a copy-and-paste Cargo route is provided for a standard Rust toolchain. Neither installation path requires a source checkout.

A source checkout is still needed to change GammaLoop or to work through repository-owned run cards. Its supported development path is the repository's Nix shell, or a local Rust toolchain together with `just`, a recent GNU toolchain, and Python 3.11 or newer when building bindings. FORM 4.2.1 or newer is needed for analytical integration of integrated UV counterterms. UFO model import also needs Python `ufo-model-loader>=1.0.0` and `symbolica>=3.0.0`.

Built-in model names such as `sm` select bundled JSON; an explicit directory such as `./assets/models/ufo/sm` selects UFO import. Both use the default restriction unless a suffix selects another card. The `-full` suffix skips restrictions.

Diagram rendering is a separate concern and uses Clinnet and Typst. Building the CLI does not imply that these drawing tools are installed. Use the Clinnet DOT-rendering guide for their independent versions, templates, and cache boundary.

1.4 Related crates

> **How the crates fit together**
> Linnet provides the half-edge graph model and graph algorithms. Spenso provides typed tensors, tensor structures, and network execution. Idenso handles symbolic tensor identities and algebraic simplification. Vakint matches and evaluates vacuum-integral topologies. GammaLoop combines these components into a collider-calculation workflow.

For a deeper view of how the command layer, state, integrands, and external components fit together, see the GammaLoop implementation architecture.

1.5 Where to begin

- Use built-in `--help` for the CLI options supported by your installed version.
- Start with the included `gg_hhh` run card for a complete state lifecycle, not as a substitute for a physical normalization and validation plan.
- Record the method scope and every factor from the normalization checklist before launching a production run.
- Use the Rust or Python API only when a program needs structured access to loaded state or sample-evaluation results.
- Check prerequisites before starting an expensive integration; some workflows require a Symbolica license or external tools such as FORM.

2 Your first GammaLoop calculation

Generate the same scalar one-loop bubble through the interface that fits your work. Every route uses GammaLoop's built-in scalar model, disables integrated UV generation, and evaluates the same three-dimensional loop-momentum point. The result is a compact software check rather than a normalized collider prediction.

Command line
Use the executable for run cards, interactive commands, persistent states, and complete calculations. This is the shortest route for most GammaLoop users.

Use GammaLoop from the command line →

Python
Use the stateful Python API from notebooks, scripts, or workflow automation. It drives the same command session and returns structured evaluation records.

Use GammaLoop from Python →

Rust
Embed GammaLoop when a Rust application must own the state lifecycle, issue commands, or retain typed evaluation results without crossing a Python boundary.

Use GammaLoop from Rust →

If you are unsure, begin with the command-line guide. The interface guide explains the longer-term ownership and precision boundaries once the first calculation works.

3 Using GammaLoop from the command line

This guide builds one scalar one-loop topology, saves it as a GammaLoop state, and evaluates one point. It uses a built-in model and does not require a run card, a UFO model, or FORM. Once the executable is available, the example itself takes only a few seconds.

3.1 Get the CLI

> **Nix is recommended, not required**
> If you already use Nix, or want the most reproducible installation, follow the first route. Otherwise skip directly to the Cargo route below. Both routes provide the same `gammaloop` command, and neither requires a GammaLoop source checkout.

3.1.1 Recommended: the Nix package

The repository flake exposes GammaLoop as a packaged application. Install that package directly; a source checkout and development shell are not required:

```
nix profile add github:alphal00p/gammaloop#gammaloop
gammaloop --help
```

Nix downloads the package from a configured binary cache when it is available and otherwise builds the same derivation locally. The flake currently supports x86-64 and ARM64 Linux, plus Apple-silicon macOS.

To try the same packaged CLI without adding it to your profile, run:

```
nix run github:alphal00p/gammaloop#gammaloop -- --help
```

Use `nix run .#gammaloop -- --help` instead when testing the package from an existing source checkout. `nix develop` followed by `just build-cli` remains useful for contributors changing GammaLoop, but it is not the normal installation path.

3.1.2 No Nix: install with Cargo

Install a stable Rust toolchain with rustup, then install the small set of native build tools used by GammaLoop. On Debian or Ubuntu:

```
sudo apt-get update
sudo apt-get install -y build-essential m4 diffutils
```

On macOS, install Apple's command-line build tools if they are absent:

```
xcode-select --install
```

Then install the `gammaloop-api` crate. Its executable is named `gammaloop`:

```
SYMBOLICA_OEM_LICENSE=SYMBOLICA_OEM_GAMMALOOP \
  cargo install --locked gammaloop-api
gammaloop --help
```

This registry command becomes available with the first automated crates.io release. Until then, install the release candidate directly from its tested Git revision, without making a checkout:

```
SYMBOLICA_OEM_LICENSE=SYMBOLICA_OEM_GAMMALOOP \
  cargo install --locked \
  --git https://github.com/alphal00p/gammaloop.git \
  --rev eb1dab23c24345def88226ef10874f0dde6c4aa5 \
  gammaloop-api
```

Cargo compiles the CLI locally, so its first installation takes longer than downloading a cached Nix build. Its default build vendors the required GMP, MPFR, and MPC sources; OpenSSL, Python, FORM, and system copies of those libraries are not prerequisites for this example. On Windows, use WSL 2 and follow the Debian or Ubuntu instructions above. The `SYMBOLICA_OEM_LICENSE` value is GammaLoop's public build selector, not a private license key. Add the `ufo-import` feature and Python development headers only when external UFO model loading is needed. Symbolica's license terms still apply to both installation paths.

> **Cargo install is Nix-free, but it is still a source build**
> The current release workflow publishes crate sources and Python distributions, but not target-specific GammaLoop CLI archives or Cargo Binstall metadata. `cargo binstall` therefore cannot yet provide a supported prebuilt binary and may only fall back to a source build.

3.2 Generate a one-loop graph

Users who installed the Nix package or Cargo crate can run this command as written. Contributors using `just build-cli` in a source checkout should replace `gammaloop` with `./gammaloop`:

> **Choose a disposable state path**
> `--clean-state` removes and replaces the state directory passed with `-s`. Use the fresh `./gammaloop_state/quickstart` path shown below, or substitute another path whose existing contents you are prepared to delete.

```
gammaloop --clean-state -s ./gammaloop_state/quickstart run -c \
  'import model scalars-default.json; set global kv
global.generation.uv.generate_integrated=false; generate amp scalar_1 > scalar_1 [{1}] --
allowed-vertex-interactions V_3_SCALAR_122 -p bubble -i one_loop; display processes; quit -
o'
```

The command imports the built-in scalar model, generates one one-loop bubble amplitude, prints the process named `bubble` and integrand named `one_loop`, and writes a reusable state under `gammaloop_state/quickstart/`. Integrated UV generation is disabled deliberately so that this first topology does not invoke FORM.

Check the result by looking for `bubble` and `one_loop` in the process listing and for `gammaloop_state/quickstart/state_manifest.toml`. This graph is a compact software exercise, not a normalized collider prediction.

3.3 Evaluate one point

Load the state read-only and inspect the integrand at one loop-momentum point:

```
gammaloop --read-only-state -s ./gammaloop_state/quickstart run -c \
  'inspect -p bubble -i one_loop -x 0.1 0.2 0.3; quit'
```

A successful run prints the parameterization Jacobian and a finite complex value without changing the saved state. Continue with the first-state tutorial to use a maintained run card, inspect the complete persistence lifecycle, and prepare a calculation whose physics scope and normalization are explicit.

4 Using GammaLoop from Python

This route generates the same scalar bubble as the command-line example, but keeps the session in a Python object and returns a structured evaluation result. Use Python 3.11 or newer.

4.1 Install the Python package

Create an isolated environment. The ordinary wheel command targets the automated `0.3.4` release and newer:

```
python3.11 -m venv .venv
. .venv/bin/activate
python -m pip install --upgrade pip
python -m pip install "gammaloop>=0.3.4"
```

Until that release is visible on PyPI, build the current package from a source checkout instead:

```
git clone https://github.com/alphal00p/gammaloop.git
cd gammaloop
python3.11 -m venv .venv
. .venv/bin/activate
python -m pip install .
```

The Python library does not activate the CLI's OEM license. Set `SYMBOLICA_LICENSE` to your user license when running Python; no OEM selector is needed to build the library.

4.2 Generate and evaluate

Save this as `first_gammaloop.py`:

```
from pathlib import Path
from tempfile import TemporaryDirectory
```

```python
from gammaloop import GammaLoopAPI

with TemporaryDirectory() as temporary:
    api = GammaLoopAPI(state_folder=Path(temporary) / "state")
    api.run("import model scalars-default.json")
    api.run(
        "set global kv "
        "global.generation.uv.generate_integrated=false"
    )
    api.run(
        "generate amp scalar_1 > scalar_1 [{1}] "
        "--allowed-vertex-interactions V_3_SCALAR_122 "
        "-p bubble -i one_loop"
    )

    result = api.evaluate_sample(
        [0.1, 0.2, 0.3],
        process_id=0,
        integrand_name="one_loop",
    )
    print(result.integrand_result)
```

Run `python first_gammaloop.py`. A successful execution prints a finite complex value. The temporary state is deleted when the script exits; use a normal directory when the state should be persisted and explicitly execute a save command before closing the session.

> **One session owns one mutable state**
> `GammaLoopAPI.run` acts on the same in-memory model, settings, processes, and history as the structured methods. The object does not save automatically. Use separate instances for independent calculations, and inspect the interface guide before building a long-running workflow around mutable state.

The documentation harness syntax-checks this script. Runtime execution additionally needs the native wheel or source build and a Symbolica license mode appropriate for the user.

5 Using GammaLoop from Rust

Embed GammaLoop when a Rust program should own the state, command session, and typed evaluation result directly. This example generates the same scalar bubble as the CLI and Python routes.

5.1 Create a project

The ordinary crates.io command becomes available with the automated `0.3.4` release:

```sh
cargo new first-gammaloop
cd first-gammaloop
cargo add gammaloop-api@0.3.4 ndarray@0.17 eyre@0.6
```

Before that release, replace the `gammaloop-api` line with the tested release revision:

```sh
cargo add gammaloop-api \
  --git https://github.com/alphal00p/gammaloop.git \
  --rev eb1dab23c24345def88226ef10874f0dde6c4aa5
cargo add ndarray@0.17 eyre@0.6
```

5.2 Drive one state and evaluate it

Replace `src/main.rs` with:

```rust
use eyre::Result;
use gammaloop_api::{
    commands::evaluate_samples::{evaluate_sample, EvaluateSamples},
    state::CommandHistory,
    StateLoadOption,
};
use ndarray::arr2;
use std::time::{SystemTime, UNIX_EPOCH};

fn main() -> Result<()> {
    let nonce = SystemTime::now().duration_since(UNIX_EPOCH)?.as_nanos();
    let state_folder = std::env::temp_dir().join(format!("gammaloop-quickstart-{nonce}"));
    let mut loaded = StateLoadOption {
        state_folder: Some(state_folder.clone()),
        ..StateLoadOption::default()
    }
    .load()?;

    for raw in [
        "import model scalars-default.json",
        "set global kv global.generation.uv.generate_integrated=false",
        concat!(
            "generate amp scalar_1 > scalar_1 [{1}] ",
            "--allowed-vertex-interactions V_3_SCALAR_122 ",
            "-p bubble -i one_loop"
        ),
    ] {
        let command = CommandHistory::from_raw_string(raw)?;
        let _ = loaded.cli_session().execute_command(command)?;
    }

    let point = arr2(&[[0.1, 0.2, 0.3]]);
    let result = evaluate_sample(
        &mut loaded.state,
        &EvaluateSamples {
            process_id: Some(0),
            integrand_name: Some("one_loop".into()),
            use_arb_prec: false,
            minimal_output: false,
            return_generated_events: None,
            momentum_space: false,
            points: point.view(),
            integrator_weights: None,
            discrete_dims: None,
            graph_names: None,
            orientations: None,
        },
    )?;

    println!("{result}");
    std::fs::remove_dir_all(state_folder)?;
    Ok(())
}
```

Compile and run with your Symbolica user license available through `SYMBOLICA_LICENSE`. Embedding the Rust API does not activate the GammaLoop CLI's OEM license:

```
cargo run
```

> **The facade owns the supported embedding boundary**
> Prefer `StateLoadOption`, `CliSession`, and the typed request objects from `gammaloop-api`. `gammalooprs` exposes lower-level implementation types, but their presence in Rustdoc is not a stability promise. The interface guide maps the supported workflow to the complete Rust reference.

The docs harness compiles this source against the current workspace. Running it additionally requires the native toolchain and a Symbolica license mode appropriate for the user.

6 Physics scope and Local Unitarity

GammaLoop is alpha-stage research software for perturbative quantum-field-theory calculations. Its present, demonstrable calculation path is partonic: it constructs amplitude integrands and uses Local Unitarity forward-scattering representations for differential cross sections, then evaluates or integrates selected contributions. It is not currently a general hadron-level event generator or a promise that every process allowed by a model is numerically supported.

> **Intended reader**
> This chapter is for physicists deciding whether GammaLoop is appropriate for a calculation. The command-line workflow requires no Rust knowledge. Read the kinematics and normalization contract before interpreting a value, and treat compiled loop-count limits as software bounds rather than demonstrated perturbative reach.

6.1 What Local Unitarity changes

At fixed perturbative order, a conventional calculation separates real-emission and virtual contributions even though their infrared singularities cancel only in the sum. The Local Unitarity representation uses Loop–Tree Duality for each forward-scattering graph to express those degrees of freedom on common integration variables. Contributions that approach the same soft or collinear configuration can then cancel locally, before a Monte Carlo integral relies on cancellations between separately integrated numbers.

The defining Local Unitarity paper proves this representation for processes without initial-state collinear singularities and introduces local ultraviolet counterterms. The raised-propagator and local-renormalization paper extends the formalism with distributional cutting rules and a local R-operation treatment. Those are statements about the method. A method valid at arbitrary perturbative order is not evidence that this release implements every order, process, initial state, or renormalization choice.

For one Monte Carlo point, GammaLoop can produce several cut or counterterm contributions in one or more correlated event groups. The observable layer commits the complete group list as one statistical sample. Treating the members as independent events would discard the local-cancellation relation and underestimate correlations.

6.2 Capability envelope in this release

The labels below are deliberately conservative:

- **Supported** means an explicit implementation path was identified; it does not certify every process or numerical regime.
- **Conditional or experimental** means feature-, backend-, model-, or workflow-dependent.
- **Unsupported** means the accepted value reaches a placeholder, explicit error, or panic.
- **Unverified** means the source does not justify a public scientific guarantee.

Area	Classification	Current boundary
Calculation objects	Supported, scoped	Amplitude integrands and forward-scattering cross-section integrands are generated. Numerical support must still be established for the selected topology and contribution.
Initial states and PDFs	Partonic only	The current external kinematics are fixed momenta and helicities, with a PDF factor of one. There is no PDF convolution or factorization scale. The built-in flux path supports exactly one or two incoming particles.
Orders and selectors	Conditional filters	`{n}` constrains an amplitude graph's loops or the sum on two cut sides, while `{{n}}` constrains forward-graph loops. Outside the bracketed block, unpowered constraints populate the amplitude filter and powered constraints populate the cross-section filter, whose exponent is currently discarded. Bracketed named orders bound model-resolved additional cut content on the cross-section path. These mechanisms are not interchangeable and do not provide a universal LO/NLO/NNLO mapping.
Models	Conditional	Built-in Standard Model, scalar, and scalar-gravity JSON models are available; other JSON models can be imported. UFO import requires the optional Python-backed feature and its loader.
External polarizations	Scoped	Automatic sums are implemented for scalar, spinor, and vector states, with Feynman or light-like axial gauge for vectors. Higher-spin polarization replacement is unsupported.
Masses and widths	Real masses only	Real masses enter evaluation. Complex masses are unsupported. Width names are model metadata, but no finite-width or complex-mass scheme was verified.
Thermal and dense media	Experimental, amplitudes only	Equilibrium media at finite or zero temperature support infrared-safe fixed-order amplitudes without threshold subtraction. See thermal and dense media.
Subtraction and renormalization	Conditional or experimental	Local UV settings and several vacuum-integral backends exist. Threshold subtraction is experimental, and the physical meaning of every exposed prescription still needs a method-author review.
Integration components	Scoped	Real and imaginary components can be integrated separately. The accepted `both` setting is not implemented.
Observables	Supported; requires user validation	Particle and jet quantities, selectors, histograms, and kT-family clustering are available. GammaLoop does not establish the infrared and collinear safety of an arbitrary user-defined observable.
Licenses and tools	Conditional	The Rust crates use MIT or Apache-2.0 terms, while Symbolica has separate license conditions. FORM, vacuum-integral backends, UFO import, and drawing tools have independent availability requirements.

6.3 Decide whether a calculation is in scope

Before generating graphs, write down these physics choices outside the run card:

1. Is the requested quantity partonic with fixed external kinematics, or does it require PDFs, a factorization scale, beam structure, or more than two incoming particles?
2. Is it an amplitude or a differential cross section, and which exact graph, loop, cut, and coupling-order filters define the requested contribution?

3. Does the active model use only supported external spins and real masses? If a width is physically essential, do not infer a finite-width scheme from imported metadata.
4. Which spin and color sums or averages, projectors, flux, symmetry factors, and units belong in the normalization? Record them using the conventions checklist.
5. Is the observable infrared and collinear safe for the selected real/virtual combination? This is a physics precondition, not an automatic validation step.
6. What maintained limit, independent implementation, or published number will be used to validate the result and its Monte Carlo uncertainty?

Method scope versus software evidence
The first-state tutorial proves that a model, generated integrand, settings, and persisted state fit together; it does not validate a physical cross section. Use the partonic cross-section regression card and the scalar-topology targets as concrete implementation sources to inspect. The former still uses a powered selector whose exponent is not enforced, so it is not an audited perturbative-order or normalization exemplar. Publish a number only after recording its contribution definition, normalization, convergence, and an independent comparison.

7 Kinematics, normalization, and weights

This page assembles the source-verifiable scientific conventions needed to interpret a GammaLoop sample. It intentionally separates factors supplied by the runtime from factors that remain the physicist's responsibility. Where the implementation does not establish a universal convention, the text says so instead of filling the gap from customary notation.

7.1 Four-vectors and momentum flow

External four-vectors use component order (E, p_x, p_y, p_z) and metric signature $g = \mathrm{diag}(+1, -1, -1, -1)$, so

$$p \cdot q = E_p E_q - (p_x q_x + p_y q_y + p_z q_z), \quad p^2 = E^2 - p_x^2 - p_y^2 - p_z^2.$$

Stored external momenta are physical, normally positive-energy vectors. A separate process signature marks a particle as initial or final; GammaLoop does not require the user-facing list to store every final momentum with a minus sign. When one momentum is dependent, it is reconstructed to satisfy

$$\sum_i^{\text{initial}} p_i - \sum_j^{\text{final}} p_j = 0.$$

The runtime field `e_cm` is a construction and normalization scale. If it is omitted for fixed momenta, the current fallback is the mean absolute value of their nonzero components, not a physical reconstruction of $\sqrt{s}$. Supply `e_cm` explicitly whenever its physical meaning matters.

7.2 Helicity and polarization

Fixed external helicities use `-1`, `0`, or `+1`. Zero is the physical and documented convention for a scalar card, but the current evaluator ignores rather than enforces a scalar's helicity. The automatic external-momentum generator currently assigns `+1` to every external entry; that is a fixed-polarization default, not an unpolarized calculation.

Use `summed` for a polarization sum and `summed_averaged` for the same replacement with the implemented spin-state average. The setting acts on every external entry explicitly marked that way; incoming particles are not averaged merely because they are incoming. Implemented averaging factors are 1 for a scalar, $\frac{1}{2}$ for a spinor, $\frac{1}{2}$ for a massless vector, and $\frac{1}{3}$ for a massive vector. Automatic higher-spin polarization sums are unsupported.

Color is a separate normalization decision
No general automatic incoming-color average was identified. A maintained calculation may supply a color

projector or global prefactor explicitly. Record that choice rather than assuming that `summed_averaged` includes color.

7.3 Flux and reporting units

With the flux factor enabled, the implemented one-incoming-particle factor is

$$F_{1\text{ in}} = \frac{1}{2E},$$

and the implemented two-incoming-particle factor is

$$F_{2\text{ in}} = \frac{1}{4\sqrt{(p_1 \cdot p_2)^2 - m_1^2 m_2^2}}.$$

Zero or three-or-more incoming particles are not implemented by this default path. Reporting units resolve to `pb`, `fb`, `ab`, `mb`, or `none`; `auto` selects picobarns for more than one incoming particle and no conversion otherwise. The fixed factor $3.89379372171859 \times 10^8$ relative to picobarns is applied only by the two-incoming-particle flux branch. The one-incoming-particle branch returns $F_{1\text{ in}}$ without a reporting-unit conversion. Disabling the flux factor also bypasses the conversion branch.

The code describes input scales as model energy units, while the fixed picobarn conversion is the usual natural-unit form associated with GeV. Until the energy-unit premise is made an explicit model contract, do not claim that arbitrary model units convert correctly to pb.

7.4 From an integrand value to a Monte Carlo sample

For the public sample-evaluation contract, the exact weighting relation is

$$w_{\text{sample}} = I_{\text{returned}} J_{\text{parameterization}} w_{\text{MC}}.$$

`integrand_result` includes the native map Jacobians and channel partition factors. For parameterized samples, the separately reported unapplied `parameterization_jacobian` is unity, including when distinct channel points are summed. Direct momentum inputs can report `None` instead, meaning no additional Jacobian factor. `integrator_weight` is the outer-grid Monte Carlo weight and remains separate until integration. For a cross section, the returned integrand also contains the enabled flux and reporting-unit factor.

When available, `absolute_integrand_result` sums the componentwise absolute physical contributions over the distinct channel points of one outer draw. Its outer-grid weight likewise remains separate.

For amplitudes, `stability.check_on_norm` compares the full complex magnitude independently of `integrator.integrated_phase`, since helicity phases can rotate the real and imaginary components. A private sum of channel-point magnitudes also checks stability when signed channels cancel; it does not replace the reported componentwise absolute values. Cross-section stability retains the selected integration components.

An event group may retain an original contribution, threshold counterterms, and one full multiplicative factor. Its implemented reconstruction is

$$w_{\text{event}} = \left(w_{\text{Original}} + \sum_i w_{\text{CT,i}} \right) w_{\text{FullMultiplicativeFactor}}.$$

Sample-evaluation event weights and `FullMultiplicativeFactor` exclude the outer Monte Carlo weight. Observable accumulation receives that weight explicitly, so it can also apply a stratum mask and conditional probability without changing the evaluated sample. The native integrator's exported event lists include the outer weight.

All groups originating from one Monte Carlo point are combined before one statistical sample is committed to a histogram bin. They are correlated contributions, not independent events. The events and observables guide shows the corresponding Python and Rust records.

7.5 Normalization ownership checklist

Factor	Usual owner here	What to record
Polarization sum and spin average	Run card	The explicit helicity mode for every external particle and the vector gauge choice.
Color sum or average	Physicist / projector	The projector or prefactor and its normalization; do not infer a universal automatic average.
Graph multiplicity and signs	Generated graph factor	Automorphism, fermion-loop, external-ordering, and grouping contributions visible in the generated state.
Flux and output units	Runtime when enabled	Incoming momenta and masses, the selected unit, and whether the flux branch was disabled.
Parameterization Jacobian	Native sampling map	Map Jacobians and channel partitions are included in the returned value; parameterized samples report a unit unapplied Jacobian.
Monte Carlo weight	Integrator	The sample weight, seed, component, and correlation boundary.
Subtraction contributions	Correlated event group	Original and counterterm weights, signs, and the common multiplicative factor.
Overall physical normalization	Calculation definition	Any remaining coupling, projector, color, symmetry, phase-space, or conventional factor used for comparison.

Generated graph factors retain several combinatorial and fermionic contributions, but the source audit did not establish one universal statement that these plus a chosen projector form the complete physical symmetry and averaging factor for every process. Inspect the generated factor and write the full normalization used by the comparison calculation.

7.6 Scales and scheme names

Keep these settings distinct:

- `mu_r` is the renormalization scale and enters the parameter set as its square;
- `m_uv` is a UV reference mass;
- `renormalization_localization_scale` controls localization of local UV counterterms;
- MUV, PolePart, OS, IR, and Unsubtracted are accepted local-counterterm prescription names whose full physical definitions still require a method-author contract; OS and IR reach explicit unimplemented paths in at least one current counterterm evaluator; and
- Vakint's default `MSbar` choice describes its vacuum-integral normalization and must not be used as a synonym for GammaLoop's MUV prescription.

No factorization scale belongs to the current fixed-partonic external-kinematics path.

7.7 Terms that are easy to overload

- A **GammaLoop state** is the persisted calculation workspace, not a quantum state and not an integration checkpoint.
- An **integration workspace** owns resumable Monte Carlo iterations for selected `(process, integrand)` slots; its summary JSON is not the authoritative checkpoint.
- An **integration coordinate** is a parameterization coordinate unless `momentum_space` is explicitly selected, in which case each loop momentum is a flattened `(p_x, p_y, p_z)` triplet.
- A **target** is a comparison value used to report a delta. It is not the relative or absolute accuracy that stops integration.
- An **event group** contains correlated contributions from one Monte Carlo point. A **graph group** is a generation-time grouping of related graphs and multiplicity/numerator factors; the two are not interchangeable.

Conventions not yet established as universal contracts
Before publishing a result, obtain an explicit calculation-level statement for all 2π, i, sign, contour, and phase-space-measure factors; overall amplitude and cross-section normalization; color sums and averages; remaining symmetry factors; powered coupling constraints; the LO/NLO meaning of graph filters; finite-width treatment; and the selected renormalization prescription. The current source does not justify silently supplying any of these from convention alone.

The e+ e- partonic regression card is useful for tracing implemented factors, but it is not yet a normalization exemplar: its powered selector exponent is not enforced. For any audit, record the model, contribution filters, helicities, projectors, runtime settings, observable definition, and independently reviewed perturbative-order definition.

8 Tutorial

This tutorial builds the GammaLoop command-line interface and uses the included one-loop `g g -> h h h` run card to create a state that can be inspected and resumed. Compilation and process generation can take longer than a `--help` smoke test.

For the shortest installation and first-run path, begin with Using GammaLoop from the command line. Then return here to create, inspect, and resume the larger bundled example.

What this example establishes
The card selects one fixed-helicity, one-loop amplitude contribution and supplies an explicit `1/8` color projector. It demonstrates software state creation, inspection, and resumption; it is not an unpolarized, automatically color-averaged cross section. Read the method and capability boundary and normalization conventions before interpreting either integration block as a physical result.

8.1 Prerequisites

Work from a GammaLoop source checkout. The supported development environment is the repository Nix shell; without Nix you need Rust 1.85 or newer, `just`, a recent GNU toolchain, and the dependencies described in the root README. The bundled Standard Model used below does not need the UFO loader. A Symbolica license may be required by your build and use case.

```
nix develop
just build-cli
./gammaloop --help
```

The last command should print the one-shot CLI options and command tree. The `./gammaloop` wrapper selects the binary built under `target/dev-optim/`.

Verification scope and cost
The docs harness checks these shell blocks for syntax; it does not build or execute GammaLoop. Verify a clean checkout manually in `nix develop`. A cold CLI build and process generation are the high-resource path and can take tens of minutes, while reopening a valid state is normally much cheaper. The invariant for this tutorial is a resumable state with the files listed below, not a completed Monte Carlo integration.

8.2 Generate an example process

The run card declares a state folder, settings, and named command blocks. Run its `generate` block and persist the result on exit:

```
./gammaloop --clean-state \
  ./examples/cli/gg_hhh/1L/gg_hhh_1L.toml \
  run generate -c "quit -o"
```

> **`--clean-state` removes the resolved state first**
> Use it only for this first, reproducible run. Omit it when resuming work you want to keep. Its generated argument reference records the exact valueless-flag semantics. The example card resolves its state to `examples/cli/gg_hhh/1L/state` and requests ten worker cores; make a private copy of the card before changing either value.

The block imports `sm-default.json`, generates the selected one-loop pentagon amplitude contribution, applies the card's explicit helicity and color choices, builds its integrand, saves DOT data, and writes the state. A successful run exits without an error and leaves at least `run.toml`, `global_settings.toml`, `default_runtime_settings.toml`, and `processes/` in the state folder. `run.toml` records the commands and settings needed to replay the run; it is not merely a log file.

Use GammaLoop DOT input to inspect a diagram interactively or render the exported drawing bundle with `just draw`.

8.3 Resume the saved state

Load the saved state and ask the active session to display its processes:

```
./gammaloop -s ./examples/cli/gg_hhh/1L/state \
  run -c "display processes; quit -o"
```

Success means the display includes the generated `gg_hhh` process and the command exits while keeping the same state. You can now run the card's `integrate_euclidean` or `integrate_physical` block, but those are deliberately beyond the first-success path because they request a substantial Monte Carlo integration and require a separate normalization and validation plan.

8.4 Inspect before expensive work

Reopen the state read-only and inspect both the generated structure and the effective integrator settings before launching either integration block:

```
./gammaloop --read-only-state \
  -s ./examples/cli/gg_hhh/1L/state \
  run -c "display integrand -p gg_hhh -i 1L; display settings process -p gg_hhh -i 1L
integrator; quit"
```

`display integrand` reports the generation backend, compiled record size, graph and graph-group counts, and detailed orientation, loop-momentum-basis, cut, and threshold tables. The settings command resolves the values attached to this generated integrand, which may differ from the current defaults. Check these records together: an unexpected graph count points back to process generation, while an unexpected sample budget, target accuracy, or seed belongs to runtime settings.

> **Read-only inspection is not persistence**
> `--read-only-state` prevents commands from writing inside the active state directory and disables file logging there. It does not make the in-memory session immutable. This command intentionally exits without `-o`; change settings in a separate writable session or in the run card that reconstructs the state.

The exact fields and selectors are kept current in the generated integrand display and process-settings references.

8.4.1 Inspect sampling and threshold choices

For generated integrands, the dedicated metadata views expose the actual channel catalogue and persisted threshold declarations:

```
display integrands -p epem_a_tth -i NNLO --graph GL638 --show_sampling pretty
display integrands -p epem_a_tth -i NNLO --graph GL638 --show_threshold_subtraction pretty
```

Use the sampling channels and maps guide to choose channels, understand their discrete indices, and export graph-specific TOML. The threshold subtraction metadata guide explains solve subspaces, cross-cut grouping, multiplier functions, and paste-ready DOT exports. Both guides include examples and describe the implemented boundaries.

8.5 Troubleshooting and next steps

- If the wrapper cannot find a binary, rerun `just build-cli` and confirm that `target/dev-optim/gammaloop` exists.
- If compilation or process generation exhausts local resources, copy the card and reduce the values under `cli_settings.global.n_cores`; do not edit a state midway through generation.
- If startup reports a state fingerprint or settings mismatch, replay the card with a new state folder instead of transplanting only its `processes/` directory.
- Use `./gammaloop help generate` to inspect the flags supported by your installed version, then continue with the process-generation guide and the generate-command reference.

Example run card
See the complete gg_hhh run card before adapting the process, state location, or resource settings for your own calculation.

9 Process generation and state workflows

GammaLoop describes a calculation with a TOML run card and stores its reusable state in a directory. Start the command-line interface through the repository wrapper (`./gammaloop`) or the Cargo-built executable, then generate processes, integrands, and integration jobs within that state.

9.1 Model import and restrictions

JSON and UFO models use the same restriction semantics. With the default `--simplify-model=true`, applying a restriction freezes zero-valued parameters as constants. A mass fixed to exact zero is replaced by symbolic `ZERO` in particles and propagators. Diagram generation, unresolved-particle selection, and graph grouping then treat it as massless, just as if the model had declared `ZERO` from the start. Nonzero masses, however small, remain symbolic. Chemical potentials whose internal expressions become exact zero, including through other restriction-fixed parameters, likewise become symbolic `ZERO` and generate no Fermi sectors.

Importing the full model or using `--simplify-model=false` retains adjustable external mass parameters. Runtime changes to their numerical values preserve the symbolic mass assignment used for generation, including when the new value is zero.

The full bundled Standard Model includes masses and Higgs/Goldstone Yukawa interactions for all quark flavors. Its light-quark benchmark inputs are `MU = ymu = 0.0022`, `MD = ymd = 0.0047`, and `MS = yms = 0.095`, in GeV. As for the heavier flavors, the propagator masses and Yukawa input masses are independently adjustable; the dimensionless couplings satisfy `yq = sqrt(2) * ymq / vev`. These are model defaults, not running-mass evolution. The ordinary restriction cards fix all six light-quark inputs to zero. The exception, `thermal_s_mass`, retains nonzero `MS` and `yms` so both remain adjustable.

Default jet clustering selects colored particles with zero resolved mass. When using finite quark masses in the full model, set `clustered_pdgs` explicitly to include those quarks in jets.

9.2 Choose a generation mode

The interactive command tree separates cross sections, amplitudes, and operations on processes already stored in the active state:

```
generate xs INITIAL > FINAL ...
generate amp INITIAL > FINAL ...
generate existing ...
generate help xs
```

`xs` constructs forward-scattering graphs and filters compatible Cutkosky cuts. `amp` constructs ordinary amplitudes. Their final-state lists therefore have different meanings even when the printed particle syntax is identical. Use the GammaLoop DOT input guide when preparing or reviewing imported graph files. Use `generate help <mode>` inside the stateful CLI to see the flags supported by your installed version. Amplitudes can also be generated in an equilibrium medium; see thermal and dense media.

9.3 Process specification grammar

Process specifications accept `to` or `>` between space-separated initial and final states. Braces express alternatives in a cross-section final state, while `{}` denotes an empty state:

```
e+ e- > mu+ mu-
e+ e- > { Z Z, a a, H H }
{} > {}
```

The empty-initial-state form is generation grammar, not evidence that the default cross-section flux evaluator supports a zero-incoming-particle calculation. Its implemented flux branches require exactly one or two incoming particles.

A slash vetoes particles and a vertical bar selects an allow-list. The words `veto` and `only` are equivalent forms. Outside the bracketed perturbative block, coupling constraints use the active model's coupling-order name:

```
e+ e- > d d~ g / u c QED==2 QCD>=2 QCD<=4
e+ e- > mu+ mu- | g ghG QED==2 QCD>=2
```

> **Powered and unpowered constraints are not interchangeable**
> An unpowered spelling such as `QCD==2` builds an amplitude-side coupling-order filter. A powered spelling such as `QCD^2==2` builds a cross-section-side coupling-order filter, but the parsed exponent is currently discarded. Substituting one spelling for the other changes which filter container is used and still does not define a squared amplitude or a complete cross-section order. Production work therefore needs a scientifically reviewed selector set; do not infer one from the spelling alone.

The bracketed perturbative block is intentionally distinct from ordinary flags. For `amp`, `{n}` fixes the amplitude graph's loop count; for `xs`, it fixes the sum of loop counts on the two cut sides. `{{n}}` fixes the forward graph's loop count. On a cross-section process, bracketed `QCD=n` or the shorthand `QCD` resolves the model's unresolved-particle set and permits at most the summed requested count of additional cut particles from those sets; it is not an exact graph coupling power. No corresponding amplitude-side selection effect has yet been established for that bracketed named-order spelling:

```
e+ e- > Z [ {1} {{2}} QCD=2 QED=1 ]
e+ e- > Z [ QCD ]
```

These selectors are generation filters, not universal definitions of LO, NLO, or NNLO. Record the amplitude-side loops, forward loops, unresolved-cut allowance, and coupling filters explicitly for the chosen generation mode;

use the physics-scope guide to distinguish that calculation definition from the formal perturbative reach of Local Unitarity.

> **Resolve names through the active model**
> Particle names, antiparticles, coupling-order names, and allowed interactions come from the model loaded in the current state. A syntactically valid specification can still be rejected when that model does not define a requested name.

9.4 Filters, grouping, and multiplicity

Generation flags control topology filters, loop ranges, cut blobs and spectators, symmetrization, and numerator-aware grouping. These choices are physics-significant. In particular, grouping can combine graph multiplicities and numerator ratios; external-fermion symmetrization requires the caller to retain the associated ordering signs. Run `generate help <mode>` before choosing filters to see the available aliases, defaults, values, and argument counts.

The generated graph's overall factor keeps separate contributions for automorphisms, internal fermion loops, external-fermion ordering, numerator-independent symmetry grouping, and numerator-dependent grouping. It does not establish a universal incoming-color average. Persist the state and inspect that factor together with any explicit projector when auditing diagram normalization instead of replacing it with an assumed factorial; the normalization checklist assigns each factor to its owner.

9.5 A maintainable generation card

The following reduced card uses the repository's scalar model and the same one-loop bubble command exercised by the maintained scalar-topology example. Save it as `manual-bubble.toml` and run `./gammaloop --clean-state manual-bubble.toml run generate -c "quit -o"` from the repository root.

```toml
commands = []

[cli_settings.state]
folder = "./gammaloop_state/manual-bubble"
name = "manual_bubble"

[[command_blocks]]
name = "generate"
commands = [
  "import model scalars-default.json",
  "generate amp scalar_1 > scalar_1 [{1}] --allowed-vertex-interactions V_3_SCALAR_122 -p
bubble -i scalar_bubble",
  "generate",
  "save state -o",
]
```

The acceptance invariant is a persisted state in which `display processes` identifies process `bubble` and integrand `scalar_bubble`; replaying the card with a clean destination must produce the same named objects. The exact command and setting semantics are linked from the amplitude-generation reference, state-persistence reference, and state-folder setting. The full maintained source is the scalar bubble run card.

> **Interpret the first failing stage**
> An unknown particle or `V_3_SCALAR_122` error means the scalar model was not imported or no longer exposes that interaction. A process with no retained diagram points to the process specification or generation filters. A generated process that disappears after restart means `save state -o` did not complete or the resumed `-s` path differs from `cli_settings.state.folder`.

9.6 From generation to evaluation

A reproducible run keeps its stages explicit:

- import or select the model before resolving a process specification;
- generate the process and inspect the retained diagrams;
- generate the requested integrand representations;
- set kinematics, sampling, stability, and subtraction settings;
- evaluate samples or run an integration command block;
- exit with persistence enabled when the state should be resumed.

9.7 Choose three-dimensional representations

`global.generation.three_dimensional_representations` selects the representations built for an integrand. Its default is `["cff"]`; `"ltd"` and `["ltd", "cff"]` are also valid. The list must be nonempty, and duplicate entries are removed while preserving the first occurrence. The first entry supplies the default representation for stability levels that omit `three_dimensional_representation`.

LTD requires `global.generation.uv.local_uv_cts_from_expanded_4d_integrands = true` and automatically selects complete residue sums. Generation orientation filters and runtime selection or sampling of individual orientations are unavailable for these integrands: LTD's cancellation of H-surfaces requires summing its residues. LTD is supported only with `medium.mode = "vacuum"` and `vacuum_subtraction = false`; finite-temperature and finite-density modes require CFF alone, including when the requested list contains both representations. Both vacuum representations share the generated graph, physical cuts, threshold geometry, and four-dimensional UV counterterms.

Integrand generation validates these options and the initial runtime settings before generating diagrams or clearing existing processes. Requests with `--only-diagrams` skip runtime evaluator validation but retain the process and medium compatibility checks.

```
[global.generation]
three_dimensional_representations = ["ltd", "cff"]

[global.generation.uv]
local_uv_cts_from_expanded_4d_integrands = true
```

Each entry of `runtime.stability.levels` can set `three_dimensional_representation = "cff"` or `three_dimensional_representation = "ltd"`, provided that representation was generated. Repeated precisions are allowed: a ladder may try double-precision LTD, then double-precision CFF, then a higher precision. CFF avoids the H-surface cancellations present in LTD, so switching representation supplies a distinct stability check. The numerical result, cut weights, and threshold-counterterm weights agree after the complete sums. For a degenerate higher-order pole, this comparison includes all derivative-order pieces of the same physical cut or threshold residue. Individual pieces can differ between representations; contributions for different cuts or observables remain separate.

`display processes` and `display integrands` report the representations actually stored in each integrand, in generation order. Changing `global.generation.three_dimensional_representations` does not change that inventory; imported diagrams without an integrand are marked as not generated. The detailed orientation view distinguishes native residue-map keys from runtime execution slots. For example, an LTD triacontagon has 30 native keys and one complete-sum execution slot. Shared graph topology, cuts, and threshold geometry appear once.

The generation summary and `display integrand -p <process> -i <integrand> --category generation` divide accumulated graph work into an aggregate row, shared preparation, and ordered representation rows. CFF and LTD each have expression preparation, Spenso contraction, Symbolica evaluator construction, and compilation timings. Common graph preparation, four-dimensional UV work, and helper programs are counted once in the shared row. Percentages use the aggregate duration; graph jobs can overlap when generation runs in parallel, so the summed durations are not elapsed process time. Saved states retain the same inventory and timing breakdown.

The `3drep` diagnostic (also spelled `3Drep`) builds the selected graph's symbolic expression directly, without UV or threshold subtraction. Select LTD with `3drep build -g 0 --representation ltd --no-color`; `validate` checks its input topology. This diagnostic choice is independent of the integrand's generated representation list. It does not generate an auxiliary CFF expression.

The LTD summary displays each affine loop-energy key using internal on-shell energies `OSE[i]`, external energies `E[i]`, and any numerator sampling scale `M`. It lists E/H surfaces, exact prefactors, factor powers, and denominator trees. The numerator is shared across the map. Use `--show-details-for-residue 0` for the full loop/edge maps and terms of row 0; the existing `--show-details-for-orientation` spelling also works. A quoted `"<label>|N<map>|<variant>"` selector disambiguates maps with the same orientation label. These selectors inspect symbolic terms; numerical evaluation uses the ordinary integrand commands and sums all LTD residues.

9.8 Select integration slots and targets

An integration slot is one `(process, integrand)` pair. Repeat `-p/--process` and `-i/--integrand-name` in matching order to integrate several slots together. By default those slots train and sample a shared grid, so their sample shapes must be compatible; add `--uncorrelated` when each slot needs an independent grid.

A single `--target re im` (or `--target re,im`) applies the same known comparison value to every selected slot. Multi-slot runs can instead use one keyed value per slot:

```
integrate \
  -p bubble_no_integrated_UV -i scalar_bubble_below_thres \
  -p bubble -i scalar_bubble_below_thres \
  --target bubble_no_integrated_UV@scalar_bubble_below_thres=1.471664021721597e-2,0.0 \
           bubble@scalar_bubble_below_thres=2.7029875684552542e-3,0.0 \
  --workspace-path ./integration/bubble-below-threshold \
  --n-cores 1
```

Targets annotate result deltas; they do not replace `integrator.target_relative_accuracy`, `integrator.target_absolute_accuracy`, or the sample-budget settings that control convergence. The maintained scalar bubble run card contains the complete settings and both below- and above-threshold target sets. The generated integration reference is authoritative for selectors, renderers, batching controls, and allowed values.

9.9 Resume or replace an integration workspace

An integration workspace is a completed-iteration checkpoint, not a second GammaLoop state. Without `--workspace-path`, writable sessions use `STATE_FOLDER/integration_workspace`; read-only sessions use `./integration_workspace_STATE_NAME` (or `./integration_workspace`) so they do not write into the active state.

- Without `--restart`, GammaLoop resumes when the workspace already contains a compatible checkpoint. Slots, shared-versus-uncorrelated sampling, effective model parameters, and generated-integrand fingerprints must match. Saved targets and non-model runtime settings win over changed values and produce a warning.
- With `--restart`, GammaLoop removes that specific workspace and starts the integration from scratch. Use it when changing slots, sampling correlation, generated integrands, or settings that should take effect. It does not mean "resume".
- `--show-summary-only` reads the last completed result without evaluating more samples and cannot be combined with `--restart`.

The workspace root contains `manifest.json`, the latest user-facing `integration_result.json`, per-slot settings and results under `integrands/`, and the internal resume checkpoint under `state/integration_state.bin`. Observable resume snapshots live at `state/observables/<process@integrand>/latest.json`. Configured user-facing output is written per slot as `integrands/<process@integrand>/observables_final.json` or `integrands/<process@integrand>/observables_final.hwu`. `--write-results-for-each-iteration` additionally retains numbered result and observable history at the corresponding root or slot boundary.

Archive the right boundary
`integration_result.json` is a presentation snapshot, not the authoritative resume state. Keep the complete integration workspace when a run must be resumed, and keep the GammaLoop state/run card that produced the referenced integrands. A copied result JSON alone is suitable for analysis, not continuation.

Keep the complete state together
`run.toml` records boot settings, reusable command blocks, and top-level commands. Generated process and integrand artifacts live beside it. Resume with `-s STATE_FOLDER`; replay the run card to reconstruct the state from scratch. Copy or archive the entire state directory rather than moving a generated subdirectory on its own, because settings and fingerprints are checked together.

Contributor-facing ownership and data flow are documented in the GammaLoop architecture and the UV renormalization architecture.

10 GammaLoop DOT input

GammaLoop imports Feynman graphs from Graphviz `digraph` files. The generic DOT syntax and parser behavior are covered in Linnet's DOT input and graph indices this page records GammaLoop's physics contract.

10.1 Explore a DOT diagram

Edit an amplitude or cross-section diagram using the same rendering pipeline as `save dot` followed by `just draw`.

The notebook loads automatically when it comes into view. The first visit downloads browser Python and its dependencies; rendering then runs locally in your browser.

The online guide includes an interactive notebook. Open the physics rendering notebook source to run the same example locally.

Try changing an internal edge's `particle`: `a` draws a photon wave, `g` a gluon coil, `H` a dashed scalar, and `t` a fermion with its model label. The same generated particle map and Typst callbacks control these styles in exported GammaLoop drawings.

The initial settings match ordinary `just draw`: 1200 iterations, seed 42, and momentum arrows and labels disabled. The preview draws edited DOT without importing it into a GammaLoop calculation, so it does not validate interactions or numerators against the model.

The amplitude assigns half-edge ports `5:12` and `4:15` to put the outgoing leg at vertex `5` above the leg at vertex `4`. This external order allows the default layout to draw the internal cycle without crossings. The ports are global half-edge indices; the remaining indices are inferred. Reordering the DOT statements alone would not establish this order.

10.2 Graph shape and half-edges

```
digraph box {
  ext [style=invis];
  ext -> v0:0 [particle="e-"];
  v0 -> v1 [id=1, particle="a"];
  v1 -> ext [particle="e+"];
}
```

Use `digraph NAME { ... }`. DOT arrows define the underlying edge orientation. An invisible node represents an external dangling half-edge: invisible-node to vertex is incoming, and vertex to invisible-node is outgoing. An edge between two invisible nodes is invalid.

Use one shared `ext [style=invis]` node for all external legs. Each connection still creates a separate dangling half-edge. Keep the shared node otherwise attribute-free: attributes on a dangling node are merged into every external edge, so put `particle`, `num`, and other per-leg data on the edge.

Numeric ports (`vertex:0`) fix half-edge indices; an edge `id=1` fixes its edge index. These are separate index spaces. Assign only indices needed by momentum or numerator references; omitted indices are allocated automatically. Either endpoint of an internal edge can be indexed independently. Supplied indices must be unique and in range across the entire graph, including external legs. A numeric port is not a slot numbered locally within one vertex. Omitted indices follow parser order, which need not be DOT statement order; see DOT input and graph indices for the allocation rules.

Input	Drawing	GammaLoop calculation
Edge `id=n`	Names the momentum label q_n.	Identifies an edge in momentum expressions such as `Q(n, ...)`.
Numeric port `vertex:h`	Sets initial amplitude row order and identifies half-edge debug labels.	Orders amplitude external momentum and helicity entries; also supplies tensor-index identities.
Edge `is_cut=k`	Orders cross-section rows numerically and pairs legs at the same vertical position.	Marks an initial-state cut and orders its external momentum entries; equal tags sew split legs.
Edge `lmb_id=k`	Does not rename the edge's q label.	Selects this edge as the carrier of loop momentum `K(k, ...)`.

DOT arrow direction determines incoming versus outgoing, independently of these numbers and of `dir`, which controls the displayed or particle orientation. For an amplitude, the runtime external momentum and helicity lists follow increasing dangling half-edge index. Incoming momenta enter the conservation equation with a plus sign and outgoing momenta with a minus sign. Automatic amplitude placement uses this same half-edge order, separately for the incoming left column and outgoing right column. Gaps in the indices do not create empty rows. These are initial vertical positions that layout may adjust; explicit positions still take precedence. Moving a port index to another leg changes its kinematic-list position and its initial drawing order. See Kinematics, normalization, and weights for the four-vector and sign conventions.

The graph-level `threshold_counterterms` attribute controls subtraction solve spaces and weighted variants. Its schema, scoped functions and copyable exports are described in Threshold subtraction metadata. These generation-time directives are separate from runtime sampling channels and maps.

For example, the edge and half-edge indices deliberately differ here:

```
digraph amplitude_order {
  ext [style=invis];
  ext -> v:3 [id=0, particle="H"];
  v:2 -> ext [id=1, particle="H"];
  v:1 -> ext [id=2, particle="H"];
  ext -> v:0 [id=3, particle="H"];
}
```

The incoming half-edges are `0, 3`, so the left column starts with q_3 above q_0. The outgoing half-edges are `1, 2`, so the right column starts with q_2 above q_1. The runtime external list follows half-edges `0, 1, 2, 3`, belonging to edges `3, 2, 1, 0`. This ordering does not renumber either collection: edge IDs continue to determine the q labels.

10.3 Cross-section cuts and drawing order

A cross-section input may describe an initial-state cut as an internal edge carrying `is_cut`, or as two dangling legs with the same `is_cut` value. In the split form, one leg must be incoming and the other outgoing. They still

have distinct edge IDs and distinct half-edge IDs. For example, these two statements in a larger graph identify one pair:

```
ext -> left:0 [id=0, is_cut=0, particle="e-"];
right:7 -> ext [id=5, is_cut=0, particle="e-"];
```

Here `ext` must be declared invisible, and the enclosing graph must have enough edges and half-edges for the explicit indices. Sharing `id=0` between the two statements would be an error; sharing `is_cut=0` is what associates them. Use one tag per initial-state pair, with consistent particle data on its two legs. A cut-tagged dangling leg without its opposite-flow partner is invalid for a GammaLoop calculation.

On import, GammaLoop sews matching legs into one edge, then sorts the cut tags numerically and moves the resulting cut edges and their incoming half-edges to leading indices `0, 1, ...`. These cut entries determine the cross-section's external momentum order. Sewing and this normalization can change other edge and half-edge indices too. Exports conventionally use the incoming cut half-edge index as the tag. On import, however, tags are non-negative integer matching and ordering values: they need not be contiguous or name an existing half-edge. The index bounds described above apply to `id` and numeric ports, not to these tags.

The notebook and `just draw` render DOT directly, without this physics import or sewing. Cross-section placement follows the same numeric `is_cut` order as the calculation: incoming legs occupy rows from top to bottom, and outgoing legs find their row through the matching tag. For example, tag `2` precedes tag `10`; gaps do not create empty rows. Incoming legs go on the left and outgoing legs on the right. These cross-section rows are pinned vertically, while amplitude rows use the adjustable starting positions described above. All dangling depths are pinned to zero, and explicit horizontal and vertical placements retain precedence. An outgoing cut tag without an incoming counterpart can still be drawn, but receives no automatic row placement.

Generated momentum labels use the current drawing edge's `eid`, including on split cut legs: the example's labels are q_0 and q_5. With edge IDs fixed, changing `is_cut`, a half-edge port, or `lmb_id` does not rename these labels. After importing and saving a graph, the labels instead reflect the edge IDs in that newly exported DOT. Do not infer kinematic-list positions from the drawing's q subscripts.

10.4 Physics attributes

Location	Fields	Meaning
Graph	`num`	Global numerator factor, default `1`.
Graph	`overall_factor`, `projector`, `params`, `group_id`, `is_group_master`	Advanced imported-state and grouping metadata.
Node	`int_id`	UFO interaction identifier when incident particles do not uniquely select a rule.
Node	`num`, `dod`	Vertex numerator override and degree-of-divergence override.
Edge	`particle`, `pdg`	Model particle name or signed UFO PDG code.
Edge	`dir`	Explicit orientation; otherwise fermion orientation is derived from the signed particle.
Edge	`name`, `mass`	Optional stable name and Symbolica mass override.

Location	Fields	Meaning
Edge	`lmb_id`	Loop-momentum slot carried by this edge.
Edge	`num`, `is_cut`, `is_dummy`, `momtrop_edge_power`, `vakint_edge_power`	Numerator and evaluator controls.

For fermions, signed particles and edge orientation must give a consistent fermion flow around closed loops and along open fermion lines. External momentum labels are not a current GammaLoop physics attribute; older examples using `mom` should use edge `particle`/`pdg` and half-edge ports. The active model supplies propagator tensors; the legacy `propagator` field is not a current GammaLoop input field. `multiplicity_factor` is likewise a legacy field; current grouping uses `group_id`, `is_group_master`, and `overall_factor`.

10.5 Numerators and loop bases

A graph, vertex, or edge `num` is parsed as a Symbolica expression. Quote expressions containing punctuation or spaces. Keep vertex and edge numerators attached to their owning statement when editing an exported graph. In an edge numerator, `eid`, `source`, and `sink` refer to that edge's index and its existing endpoint indices; their function forms, such as `source(0)`, construct corresponding tensor-index identities. This local shorthand is resolved for edge numerators, not for an arbitrary graph or vertex expression.

By contrast, generated `hedge(h)` or `hedge(h, k)` expressions contain explicit tensor-index identities: `h` is not a local port number within the statement. Preserve the exported topology, indices, and numerator expressions together. Sewing can move graph records without renaming those abstract tensor identities, so changing only the printed ports or only numbers in `num` is not a safe way to renumber an exported calculation.

Edge momenta `Q(e, ...)`, loop momenta `K(k, ...)`, and external momenta `P(p, ...)` use different indices. Setting `lmb_id=k` chooses the internal edge carrying `K(k, ...)`; it does not set the edge ID or an external momentum slot. The remaining edge momenta are expressed through the chosen basis and external flows. Exports show these expressions in `lmb_rep`; they are generated routing information, not a replacement for the `lmb_id` input.

Load a DOT file after importing its model:

```
import model assets/models/json/sm/sm.json
import graphs ./my_graphs.dot
```

Save loaded graphs back to DOT with `save dot ./my_graphs_exported`. GammaLoop fills omitted names, indices, factors, and loop-momentum basis entries during import/export. The current spelling is `lmb_id`; older wiki examples may use `lmb_index`.

> **Keep external data on edges**
> A shared invisible node is deliberately compact. Put each external particle, numerator, and cut flag on its own connecting edge so those attributes do not get copied to every leg.

For PDF figures, run `just draw` from the directory written by `save dot`. See Clinnet DOT rendering for renderer configuration, or Rendering graphs from Python to build graphs with arbitrary Python data and custom drawing selectors.

11 Threshold subtraction metadata

Threshold metadata tells GammaLoop which loop variables to vary when constructing each threshold counterterm and how to combine alternative counterterms for one threshold. It is generation input attached to a DOT graph. Changing it requires regenerating the integrand; changing runtime sampling channels does not change the subtraction prescription. State format 20 changes the persisted projected-bound data; regenerate older states.

The interface applies to amplitudes and cross sections. GammaLoop discovers eligible thresholds, resolves the supplied directives, and checks their geometry. It does not automatically derive an IR-safe splitting or prove that a user multiplier preserves the integral. The examples below explain the implemented interface and the checks needed when designing such a prescription.

11.1 Start from the generated metadata

Generate the desired process and orientation selection, then inspect the effective metadata:

```
display integrands -p epem_a_tth -i NNLO --graph GL638 --show_threshold_subtraction pretty
display integrands -p epem_a_tth -i NNLO --graph GL638 --show_threshold_subtraction toml
```

The pretty report shows physical cuts, sides, threshold edge sets, named variants, generation status, selected subspaces, full parent bases, solve groups, multipliers and shared definitions. This is persisted generation information; changing the current beam energy does not retrospectively change the exported declarations.

TOML mode emits a complete `threshold_counterterms = "..."` DOT attribute for exactly one master graph. It expands eligible defaults and fills resolved fields on explicit variants, preserving skipped and disabled declarations, function-map scope, and the absence of automatic group IDs or identity multipliers. To capture it from a saved state:

```
./gammaloop --read-only-state -s ./saved_state \
  run -c "display integrands -p epem_a_tth -i NNLO --graph GL638 --
show_threshold_subtraction toml; quit" \
  > threshold-attribute.dot
```

Replace the graph's existing attribute with that fragment; it is not a complete graph file. The embedded TOML's double quotes are escaped as `\"` inside the DOT string. Linnet removes that DOT quoting before the TOML parser runs. Prefer this exporter or `save dot` to manual escaping. Numerical edge arrays are emitted on one line.

Threshold generation is controlled by `global.generation.threshold_subtraction.enable_thresholds`. If generation was disabled, the pretty report says so and TOML export fails clearly: a DOT threshold attribute cannot encode that global toggle. Enabled generation with no eligible thresholds exports a valid empty specification. Runtime `subtraction.disable_threshold_subtraction` is a separate diagnostic switch.

11.2 Schema and defaults

The attribute contains versioned TOML with the hierarchy `cuts → thresholds → counterterms`. A minimal partial GL297 declaration is:

```
threshold_counterterms = "
schema_version = 1

[[cuts]]
edges = [2, 11, 14]
[[cuts.thresholds]]
edges = [5, 7]
[[cuts.thresholds.counterterms]]
name = \"left_1l\"
subspace = [5]
parent_lmb = [3, 5, 11, 14]
";
```

This is one association, not the complete GL297 prescription; use the maintained DOT or its expanded export when reproducing the full calculation.

All IDs are graph edge IDs, not half-edge indices, E-surface IDs, cut ordinals or integration channel indices. The declared cut and threshold edge lists are sets: their order is canonicalized and duplicates are errors. `subspace` and

`parent_lmb` are ordered lists of defining edges; their order is retained. The left/right side is inferred from topology and must not be supplied as another field. For an amplitude use `cuts.edges = []`.

Field	Meaning
`schema_version`	Required; currently `1`. Unknown fields and versions are rejected.
`function_map`	Optional graph-wide map of scalar definitions used by multipliers.
`cuts`	Physical cuts; each has required `edges` and optional `thresholds`.
`thresholds`	Each has required nonempty `edges` and optional `counterterms`.
`name`	Variant name. A single unnamed variant becomes `default`; multiple variants require distinct nonblank names within that threshold.
`parent_lmb`	Required on every explicitly supplied variant, including disabled ones. It must specify a complete valid parent loop-momentum basis.
`subspace`	Optional nonempty list of active defining edges from that parent. Omission requests the maximal inferred cut-side subspace in the supplied parent.
`group_id`	Optional nonnegative refinement label; explicit IDs must start at zero and be contiguous in their graph/group namespace.
`disable`	Defaults to `false`; disables this variant when `true`.
`multiplier`	Optional scalar weight. Absence is identity and allocates no evaluator.

With no metadata, GammaLoop uses the maximal available loop subspace on each side of each cut. All thresholds on one side of that cut consequently share an automatic solve group. Missing cuts, missing thresholds and an empty or omitted `counterterms` list retain those defaults. An explicit nonempty variant list replaces the default for that association; it does not append to it. If every listed variant is disabled, no default is restored.

A topology-valid declaration filtered out by the selected orientation remains dormant and is retained in the export. This differs from a malformed edge set or invalid parent, which is an error. A selected-orientation run cannot establish coverage of every orientation.

11.3 What identifies a common solve space

A defining edge alone does not identify the variation: its fundamental cycle depends on the parent LMB. GammaLoop derives a canonical signature from every selected edge and the complete signed cycle generated by varying its momentum with the other parent momenta fixed. Each cycle is oriented positively along its defining edge and sorted by edge ID; the list of defining-edge/cycle pairs is also sorted.

For example, the pretty report's `e7 → +e7 +e8 +e14` means that an increment of the selected edge-7 momentum induces the same increment on edges 7, 8 and 14, with all omitted edges unchanged. Minus signs would mean the opposite increment. These are coefficients of a vector-momentum variation, not energies or an additional threshold equation.

Two different parents can therefore define the same solve space. They share a group when their selected defining edges and normalized signed cycles coincide. Equal parent names are unnecessary; merely spanning the same abstract vector space with different defining edges is insufficient. Parent order and changes of the fixed complement do not enter the group key. Each association still retains its own native parent and sampled complement.

An explicit `group_id` can only subdivide these automatic groups:

- Equal signatures with the same explicit ID share a group.
- Equal signatures with different IDs, including an absent ID, are separate groups.
- Different signatures never share a group. Reusing an explicit ID across them is an error, with the conflicting cuts, thresholds, variants, parents and signed cycles reported.

Use such subdivision only when the physics permits independent subtraction. Constituents of one degenerate higher-power residue must retain compatible variant names, group IDs, solve cycles, disabling and multiplier directives. GammaLoop rejects incompatible declarations instead of splitting that residue across independently treated groups.

11.4 Cross-cut kinematics and cancellation

Compatible thresholds from different Cutkosky cuts of one graph participate in the same group. **Every participating cut's kinematics, including its own LU rescaling root, must be prepared before constructing that group's SOCP.** The common problem uses those distinct cut-specific external data. Reusing one cut's rescaling for another would change the surfaces being solved.

Each group independently owns surface classification, maximal-overlap discovery, SOCP center construction, radial projections and multichanneling over its overlap structure. More than one maximal overlap can require more than one center within a group. A group's center is expressed in the common selected-edge coordinates and transported to each association's native frame while retaining that association's complement. It is not a common full-graph momentum point across different cuts. The radial measure uses the number of active loops of that variant. Changing the parent chart does not authorize dropping the existing projection or coordinate Jacobians.

This threshold multichanneling is distinct from the integration sampling channels in the sampling guide. A sampling-map change cannot repair an incorrect threshold-group assignment.

There are two competing requirements when choosing subspaces:

- Cuts approaching a common pinched IR configuration need compatible threshold counterterms in a common solve space so their leading soft terms cancel.
- Intersecting thresholds within one amplitude need common coordinates and centers for dual cancellation. They are not repaired by adding same-amplitude iterated threshold counterterms.

Split variants and weights allow one threshold to participate in different regions with different subspaces. GammaLoop also constructs the required left/right Cartesian-product terms for cross sections; users do not enumerate those pairs in DOT metadata. For such pairs each selected cycle must leave the other variant's defining edges fixed; incompatible pairs are rejected. This linear compatibility is necessary but does not prove that arbitrary nonlinear projections preserve both threshold equations. Coupled choices still require a physics check of their merged roots.

For amplitude graph groups, supplied member metadata is interpreted using the master graph's edge IDs and topology. The user must align those IDs meaningfully; GammaLoop does not infer graph correspondences. Native member masses and residue evaluators remain member-specific. Implicit amplitude defaults retain native full-space treatment. For cross-section graph groups, explicit threshold metadata on non-master graphs is currently rejected. This does not restrict sharing between cuts of the same master graph.

11.5 Multiplier expressions and reusable functions

Each multiplier contains `expression`, optional `function_map`, `symmetrize = false` and `opaque_derivatives = true`. Only the latter two values are implemented: `symmetrize = true` is not an automatic cure, and `opaque_derivatives = false` is rejected. Multipliers are applied after the raised-residue derivatives have been formed, as constants with respect to those derivatives. They must evaluate to a finite real scalar in the active precision. Tensor expressions must contract to a scalar without free indices.

Expression	Value
`E(edge)`, `E(effective,edge)`, `E(star,edge)`	Positive on-shell energy of a graph edge in the selected view.
`Q3(edge,cind(i))`, `Q3(star,edge,cind(i))`	Spatial momentum component, with `i = 1, 2, 3`; explicit `effective` also works. The Lorentz-indexed tensor has zero temporal component.
`eta(eset(a,b,...))`, `eta(star,eset(a,b,...))`	Cut-local E-surface residual; explicit `effective` also works. The symmetric `eset` wrapper is mandatory. Ambiguous external shifts are errors.
`P(position,cind(i))`	External four-momentum component in the existing external order.
`UFO::MT`	Example of a model parameter, using its registered model symbol.

`Q` and `K` are not multiplier primitives; use `Q3` for edge spatial momenta. A Minkowski contraction of two `Q3` tensors is minus the Euclidean spatial dot product. The default view is `effective`, not `star`. `eta` only addresses an unambiguous surface in the owning cut's catalogue; a foreign-cut residual may need an equivalent energy expression.

Graph-wide definitions and per-multiplier definitions are merged before constructing the Symbolica evaluator. A local entry overrides the identical shared key. Use the same formal signature for an override: multiple signatures for one function head are rejected. Bare scalar names and zero-argument functions are supported, as are functions with distinct scalar formal arguments and nested calls. Edge IDs and frame tags are static inputs to the kinematic primitives, not generic function formals. Reserved primitives cannot be redefined; recursive reachable functions and undefined scalar symbols are errors.

Here is an amplitude syntax example; edge IDs and the parent must match the actual graph:

```
schema_version = 1

[function_map]
"scale()" = "P(0,cind(0))+P(1,cind(0))"
"damping(x)" = "1/(1+(x/scale())^2)"

[[cuts]]
edges = []
[[cuts.thresholds]]
edges = [3, 4]
[[cuts.thresholds.counterterms]]
name = "weighted"
subspace = [3]
parent_lmb = [3]
[cuts.thresholds.counterterms.multiplier]
expression = "damping(eta(effective,eset(3,4)))"
opaque_derivatives = true
[cuts.thresholds.counterterms.multiplier.function_map]
"scale()" = "UFO::MT"
```

This illustrates binding and local scope, not a complete IR-safe partition: another variant or an analytic argument is needed before changing a physical subtraction weight.

Graph-declared scalar `params` can also appear in multipliers. For example, declare `params = "threshold_weight_bias";` in DOT and use that symbol in the expression. After generation its value is supplied in declaration order through the ordinary runtime field:

```
[general]
additional_param_values = [1.0]
```

The number of supplied values must match the declared parameters. Adding a parameter or changing an expression requires regeneration; varying an already bound parameter does not.

The built-in, overridable scalar helper `dE(ma,mb,Ea,Eb,ax,ay,az,bx,by,bz)` is the rationalized on-shell energy difference

```
((ma-mb)*(ma+mb)+(ax-bx)*(ax+bx)+(ay-by)*(ay+by)+(az-bz)*(az+bz))/(Ea+Eb)
```

For consistent on-shell inputs it equals `Ea-Eb`, while avoiding subtraction of nearly equal rounded square roots. Its denominator must still be nonzero. A compact edge-specific alias can capture the static geometry:

```
[function_map]
"de46()" = '''
dE(UFO::MT,UFO::MT,E(star,4),E(star,6),
```

```
   Q3(star,4,cind(1)),Q3(star,4,cind(2)),Q3(star,4,cind(3)),
   Q3(star,6,cind(1)),Q3(star,6,cind(2)),Q3(star,6,cind(3)))
'''
```

11.5.1 Which point does a multiplier see?

Let `base` be the cut-rescaled sample and let `left` and `right` denote the selected threshold projections. `L` is a local counterterm, `I` an integrated contribution, and `0` the unmodified side. Every variant evaluates its own projection; the two variants of one threshold need not have equal star points.

Component	effective	star
`L × 0`	base	left
`I × 0`	left	left
`0 × L`	base	right
`0 × I`	right	right
`L × L`	base	merged left/right
`I × L`	left	merged left/right
`L × I`	right	merged left/right
`I × I`	merged left/right	merged left/right

Both multipliers in a pair see the same complete component-specific context. A missing counterterm side leaves its spectator parent coordinates unchanged; cross-dependent momenta are nevertheless rebuilt from the complete context. The coefficient of a pair is the product of its two multiplier values. Exact zero can skip a completed component but does not remove its threshold from overlap discovery or change a group's normalization. All participating factors must be finite even if another factor is zero.

In particular, `eta(star,eset(...))` for the counterterm's own threshold vanishes at its root. A partition built from that quantity alone may select a variant identically or produce `0/0`, rather than distinguish the desired physical regions.

11.6 Worked GL638 splitting

The maintained GL638 DOT uses explicit variants on cut `(2,6,10)` with full parent `[3,6,7,10]`. Other cut sides retain maximal one-loop defaults. The selected one-loop space `[7]` supplies compatible partners across cuts; the two-loop space `[3,7]` retains the same-amplitude dual cancellation needed away from the relevant soft region.

In the center-of-mass frame, at each variant's own cut-preserving star, write `Q = P0^0 + P1^0`, and label these residuals:

```
H  = eta(2,4,12)       P  = eta(3,12)        Z = eta(3,10,13)
G0 = eta(2,6,12,13)    G4 = eta(2,4,10,13)
WH = H^2 / (H^2 + (P*Z/Q)^2)
WF = G0^2*G4^2 / (G0^2*G4^2 + P^2*Z^2)
```

This shorthand describes the host-shell physics; the actual definitions use `E`, `Q3` and `dE` because foreign surfaces need not belong to the local catalogue. Off the host shell, `wH`, `g0`, and `g4` are the corresponding foreign residual **minus** the host `eta(2,6,10)` residual, and `wP = 2*E(star,3)-wQ()`. Replacing these definitions with foreign `eta` calls would change their off-shell meaning.

Threshold edges on cut `(2,6,10)`	`[7]` weight	`[3,7]` weight
`(7,8)` and `(8,12,14)`	`WHc()`	`WH()`
`(8,10,13,14)`	`1-WF()`	`WF()`
`(3,7,14)`, `(3,12)`, `(3,10,13)`	absent	1

For instance the first threshold is declared in the embedded TOML as follows, using the shared definitions already present in that DOT:

```toml
[[cuts]]
edges = [2, 6, 10]
[[cuts.thresholds]]
edges = [7, 8]
[[cuts.thresholds.counterterms]]
name = "shared_1l"
subspace = [7]
parent_lmb = [3, 6, 7, 10]
[cuts.thresholds.counterterms.multiplier]
expression = "WHc()"
[[cuts.thresholds.counterterms]]
name = "native_2l"
subspace = [3, 7]
parent_lmb = [3, 6, 7, 10]
[cuts.thresholds.counterterms.multiplier]
expression = "WH()"
```

No explicit `group_id` is needed. In the DOT, `WH` and `WHc` use complementary lazy common-zero values zero and one. That assigns a value at their common zero; it is neither a denominator regulator nor a proof of continuity. Algebraic complementarity at one point also does not establish a pointwise partition between variants evaluated at different stars. The shared soft and intersecting-threshold limits must be checked together.

A possible continuous tuning of a complementary pair is `w/(w+c*(1-w))` and `c*(1-w)/(w+c*(1-w))`, with positive dimensionless `c`. This preserves the endpoints and their vanishing orders for `0 <= w <= 1`; apply it consistently to partners whose cancellation requires common weights. It does not remove a singular common-zero limit or establish an optimal variance. Changing a valid subtraction prescription may change the integral of the absolute value while preserving the signed integral. A sampling-only change should preserve both for the same physical integrand and orientation-summation convention.

The top and Higgs masses separate some otherwise apparently competing soft/threshold regimes. This motivates the Higgs-aware partition; it is not a topology-independent recipe. The maintained GL297 DOT provides the simpler example with explicit one-loop associations across multiple cuts.

11.7 Runtime localization and validation boundaries

The local threshold envelope uses the existing `subtraction.local_ct_settings.uv_localisation` controls, despite that historical name:

```toml
[subtraction.local_ct_settings.uv_localisation]
gaussian_width = 1.0
sliver_width = 10.0
dynamic_width = false
smooth_sliver = false
force_uv_dampers_to_one = false
```

For signed radial displacement `delta = r-r_star`, the envelope is a Gaussian times compact support `|delta| <= sliver_width*S`, with Gaussian width `gaussian_width*S`. Here `S = E_cm` unless `dynamic_width = true`, when `S = r_star`. These settings are dimensionless. `smooth_sliver = true` adds an even bump that is flat at the support boundary and remains one at the pole.

The even envelope and both radial mirror terms preserve the local counterterm's zero principal-value integral. An arbitrary asymmetric extra radial weight does not inherit that property. Nor does evenness alone guarantee cross-cut IR cancellation: hard support boundaries can separate nearby projected cut contributions. Inspect boundary approaches as well as the interior; a smooth sliver removes the abrupt boundary but is not a general variance optimization. Do not infer higher-power moving-boundary correctness from a simple-cut check.

The integrated counterterm's normalized radial profile is `h(r/r_star)/r_star`. Its `subtraction.integrated_ct_settings.range` and nested `h_function_settings` are distinct from both the local envelope and the LU Cutkosky h-function. The implemented integrated range is `type = "infinite"`; the compact variant is not implemented. Preserve normalization when changing profile parameters.

Validation of a new prescription should compare CTs off, default CTs and the proposed metadata at identical physical coordinates. Examine each cut and their sum, each split variant, relevant left/right products, soft limits, intersecting-threshold limits and localization boundaries. Include normal and higher-precision replays. A generic rotation can expose cancellations missed by a special axis permutation; a stable complex norm does not by itself bound the relative error in a tiny real component.

For `|f| ~ lambda^beta` in a soft sector with `D` independent spatial components, the radial measure is `lambda^(D-1) d lambda`; the directional convergence margin is `beta + D`. One independent soft three-momentum has `D = 3`; two at fixed ratio have `D = 6`. Count independent directions, not massless edge labels: three gluons at a vertex can span only two soft momenta. A soft-plus-threshold ray does not establish the additional hard-normal codimension. Keep its power as a directional diagnostic unless that geometry is independently established. Fixed-ratio rays also do not certify true hierarchical, angular or tangential limits.

Use the fully weighted total returned by `inspect` or `approach` for scaling fits; rounded cut/component reconstructions are diagnostics. A nonpositive radial margin or an unresolved fit needs review. If a profiler subtracts a constant before fitting, its power need not be the raw integrand power. Generate and evaluate the complete physical orientation sum; generation alone does not test its cancellations. Replay difficult points at identical coordinates with higher precision and generic rotations. Preserve failures separately from successful precision rescues, and check stability of the physical component rather than borrowing a larger component's scale.

A finite-energy collinear region can be narrower than an affine diagonal approach. When the splitting gap scales as `theta^2`, probe the hard normal on that scale, `eta / E_cm ~ theta^2`; a linear approach can miss the dangerous region. Test genuine hierarchies separately from fixed-ratio rays. Retest every independent generic soft class after changing a multiplier: improving one intersection can spoil another soft limit.

Two durable GL638 cautions remain relevant when interpreting such tests. Coincident radial roots can expose a removable singularity as separate undefined residues; increasing precision rescues nearby cancellation but does not define the exact common-root limit. Separately, a hard two-normal corner with local behavior `f ~ 1/R` has a finite first moment under `R dR`, but a smooth nonzero sampling density gives a logarithmic second moment if the leading coefficient persists on an angular/tangential neighborhood. Correct subtraction and effective sampling are therefore separate requirements. Surface-focused sampling can address that corner; it does not prove bounded weights everywhere or replace the threshold-prescription checks above.

11.8 Generation and center checks

Compare the materialized export before and after a refinement. Preserve every eligible association's full parent LMB, selected defining edges and signed solve cycles, including raised-residue constituents. Dormant or skipped declarations are not active validation targets; check generated associations rather than counting DOT entries. Verify each host shell and target threshold after that cut's own rescaling. Test the completed higher-power residue, its lower-order pole coefficients and merged-root limits; compatible variant lists alone do not establish that an after-derivative multiplier is valid.

An admissible re-expression of a varying cycle can place a strict interior witness exactly at zero, allowing the existing origin check to avoid an ill-conditioned SOCP solve without changing tolerances. Update every partner's defining edge and parent consistently: the grouping key still includes the selected defining edge. Record `subtraction.overlap_settings.try_origin`, `check_global_center` and the required interior mass gaps. An origin-based check does not cover a forced nonzero center or `try_origin = false` without further validation.

11.9 Scoped soft-improved UV treatment

For the local three-dimensional UV path, `prescription = "IR"` selects the soft-improved operator `H_UV = U + S - U S`. Scope this prescription to the required components rather than applying it indiscriminately. For example, an exact signed single-gluon boundary flow can be selected in a run card by:

```
[[cli_settings.global.generation.uv.renormalization_prescription.overrides]]
prescription = "IR"
ct_identifier = { external_pdg_set = [21] }
```

The boundary-flow set matches exactly: `[21]`, `[-21]` and `[-21,21]` select different components. An omitted internal-PDG set is a wildcard. Include the positive-degree containing components required by an IR child, so the reduced cograph has its corresponding parent `S-US` completion.

Check scheme preservation separately from local soft improvement: compare complete recursively assembled U and H_UV Laurent poles at the same masses and normalization, retaining finite and positive-epsilon child terms required by parents. Include analytically integrated UV terms in the numerical checks; neither a smoother local soft limit nor threshold metadata alone proves equality of renormalized results. A massive physical soft sector must not be discarded as scaleless. Vakint's `MSbar` normalization and GammaLoop's local prescription are distinct settings.

12 Sampling channels and maps

Sampling channels map unit-cube coordinates to the graph's unbounded spatial loop momenta. They can use ordinary loop-momentum bases (LMBs), concentrate near an energy surface, or combine a physical Cutkosky cut with thresholds in its remaining loop variables. They change the integration measure and its partition, not the integrand's physical cut sum or its threshold counterterms. Amplitudes and cross sections use the same channel catalogue and integration engine. Channel names and IDs are independent of threshold `group_id` values. The threshold metadata guide describes the common solve spaces and centers needed for cancellation; sampling is an additional change of variables.

The settings below are **runtime overlays**: apply them to a loaded integrand with `set process -p PROCESS -i INTEGRAND file sampling.toml`. In a run card, put the same settings under `[default_runtime_settings.sampling]`, with the corresponding prefix on its subtables, or apply the overlay in a command block. Changed channel definitions invalidate warm-up caches. Start a new integration workspace when changing channels or their weighting so an old grid is not confused with the new channel order.

12.1 Select channels

This baseline uses optimized ordinary LMB channels and samples one channel per point:

```
[sampling]
graphs = "monte_carlo"
orientations = "summed"
sampling_multichanneling = true
sampling_channels = "monte_carlo"
default_channel_selection = ["auto:optimized_lmb"]
sampling_channel_weight = "ose"
alpha = 3.0
coordinate_system = "spherical"
mapping = "linear"
b = 1.0
```

`graphs`, `orientations`, and `sampling_channels` are separate choices, each accepting `summed` or `monte_carlo`. With `sampling_channels = "summed"`, every selected channel maps the same outer cube point and their contributions are summed before statistics are accumulated. With `monte_carlo`, the channel is another adaptive discrete coordinate. Keep `sampling_multichanneling = true` for either mode: setting it to false disables the channel partition rather than merely disabling advanced maps. By default multichanneling is off and all three sum modes are `summed`.

Selector	Expansion
`auto:lmb`	All admissible generated LMB channels.

Selector	Expansion
`auto:optimized_lmb`	The generated optimized subset, augmented for elementary massless-edge coverage when no explicit basis restriction is supplied.
`auto:surfaces`	Currently the same optimized-LMB coverage. Production does not yet discover automatic surface candidates; add named surface channels explicitly.
`lmb(6,12,13,14)`	One generated basis with exactly these ordered edges. No named definition is required.
`cut1_joint_HZ`	A user-defined channel in this graph's `channel_definitions` table.

A graph-specific selection replaces the default list. Entries **within** a list are additive: automatic selectors, explicit generated LMBs and names can be combined. Generated entries are deduplicated in first-selection order; selecting an automatic preset twice does not add copies. Named definitions keep their identity, even if two happen to describe equal maps.

```
[sampling]
default_channel_selection = ["auto:optimized_lmb"]
channel_selection = { GL638 = ["auto:surfaces", "cut1_joint_HZ"] }
```

`GL638` is the actual master graph name; `cut1_joint_HZ` is any name chosen for a definition. TOML inline tables use `=`, not JSON's `:`. Bare keys such as `GL638` are valid; quote names containing spaces or other special characters. If neither a graph override nor a nonempty default is provided, catalogue resolution uses `auto:optimized_lmb`. An explicitly empty graph selection stays empty and is not a request for automatic fallback.

`lmb_basis_ids = { GL638 = [1, 2] }` restricts admissible generated bases by their displayed basis IDs, in the requested order. The restriction also applies to explicit `lmb(...)` selectors. Missing, excluded or ambiguous ordered matches are errors; edge order is never silently changed. Basis IDs, physical cut IDs and zero-based **sampling channel IDs** are different index spaces. Use edge selectors or named definitions for portable steering and inspect the resolved catalogue before using a channel ID.

To use only advanced maps, select only their names. They still must cover the integration domain: a compact joint map requires an explicitly selected full-support sibling, which may be a full-volume physical-cut channel rather than an LMB channel. Elementary massless-edge coverage is useful even when no regular E-surface exists; it does not by itself prove coverage of every simultaneous soft or collinear limit.

12.2 Define a channel

A named definition has one Symbolica expression in `around`. Its structural validation and graph routing determine the map; this is not a regular-expression mini-language.

Field	Meaning
`around`	Map expression. Its `surface` or `cut` edges identify energy equations, not the independent variables used to solve them.
`parent_lmb`	Complete ordered parent basis defining the routing of the independent variables.
`subspace_lmb`	Active parent edges for a simple surface map. For compositions, `block(lmb(...), ...)` assigns the individual active blocks.
`on_cut`	Optional list of physical cut IDs used to check an explicitly identified host. It does not select the cuts evaluated by the integrand.
`channel_weight`	Optional override of the global channel partition score.
`radial_profile`	Optional `lu_h` proposal for the unique physical-cut block.
`singularity_proxy`	Explicit Symbolica score expression, required when using `singularity_proxy` weighting.

Surface definitions require a complete valid parent and active edges inside it. The remaining coordinates form the complement. The full parent matters: an edge label alone does not identify the cycle generated by varying that

momentum. A requested parent ordering can be resolved from a generated basis without changing the generated catalogue's IDs.

Expression	Meaning
`surface(a,b,...)`	A routed positive-energy surface, including its external energy shift.
`phase_space(cut(a,b,...))`	A physical-cut radial map retaining the auxiliary LU scale.
`lmb(a,b,...)`	An ordinary complete LMB map when used as a named channel's expression.
`complement(a,b,...)`	Ordinary coordinates for these remaining parent edges.
`block(lmb(a,...), MAP)`	Assign these active coordinates to `MAP`. The descriptor itself consumes no extra coordinates.
`then(A,B,...)`	Ordered conditional blocks; later geometry may depend on earlier outputs.
`product(A,B,...)`	Independent blocks with a direct-sum dependency check.
`at_cut(cut(a,...), MAP)`	Evaluate the target in the kinematics of this physical host.
`left(MAP)`, `right(MAP)`	Resolve a target on the specified side of its host.
`intersect(surface(...),surface(...))`	One joint block for two supported, distinct energy equations. It does not allocate two independent copies of the same loop variables.

The parser also recognizes `soft(edge)` and `collinear(a,b)`, but numerical compilation of these dedicated primitives is not implemented. Use ordinary LMB coverage for soft sampling. General nested compositions, arbitrary multi-surface intersections and CT-projected star-target maps are likewise not implemented. A parsed expression is not a promise that every topology admits its geometry; unsupported or ambiguous requests fail during resolution or warm-up.

12.3 Amplitude example: a massive two-loop kite

The massive kite fixture has parent `[4,6]`. With unit internal masses and incoming energy 5 in its rest frame, the following is the tested surface-plus-LMB configuration:

```toml
[sampling]
graphs = "summed"
orientations = "summed"
sampling_multichanneling = true
sampling_channels = "summed"
sampling_channel_weight = "map_density"
power = 2.0
channel_selection = { massive_kite = ["C", "D", "ordinary"] }

[sampling.channel_definitions.massive_kite.C]
around = "surface(2,4,6)"
parent_lmb = [4,6]
subspace_lmb = [4,6]

[sampling.channel_definitions.massive_kite.D]
around = "surface(3,5,6)"
parent_lmb = [4,6]
subspace_lmb = [4,6]

[sampling.channel_definitions.massive_kite.ordinary]
around = "lmb(4,6)"
parent_lmb = [4,6]
```

These three-energy surfaces genuinely depend on both loop vectors. In contrast, a surface with only one independent varying energy direction must use a proper three-dimensional subspace; requesting it as a bounded six-dimensional surface is invalid. The simple `subspace_lmb` form samples its complement first, then the conditional surface block. There is no Cutkosky host, LU rescaling or LU h-function for an amplitude.

For an existing regular surface and fixed complement, the map chooses an interior center and solves the positive radial root in each direction. `power > 1` concentrates on both sides of that root. Locally its density scales as `q ~ |r-r_star|^(1/power-1)`; `power = 2` gives an inverse square-root enhancement. `b * e_cm` sets the radial scale. The proposal retains normalized tails. A density proportional to `1/|r-r_star|` across an entire smooth shell would not be normalizable and is not supplied by taking a finite value of `power`. A sampling chart's interior center need not be the subtraction group's center. This freedom does not extend to a hypothetical CT-star target: focusing the projected singularity would require the actual counterterm projection, which the current map language does not implement.

Some conditional surfaces exist only for part of the complement phase space. Their existence is decided from the already sampled complement. Certified absent or pinched fibers use a normalized ordinary conditional fallback; forward and inverse use the same decision. An ambiguous numerical solve is an error, not permission to discard a point or reinterpret a regular surface as absent. This keeps the channel list and discrete grid dimensions fixed.

12.4 Cross-section example: a cut and a joint threshold block

This GL638 overlay combines optimized LMB coverage with one cut channel and a composed Cut 1/HZ channel. The short labels H and Z are mnemonic names, not particle identities: here H denotes `surface(2,4,12)` and Z denotes `surface(3,10,13)`.

```
[sampling]
graphs = "monte_carlo"
orientations = "summed"
sampling_multichanneling = true
sampling_channels = "monte_carlo"
sampling_channel_weight = "map_density"
power = 2.0
b = 0.3
channel_selection = { GL638 = ["auto:optimized_lmb", "cut1", "cut1_joint_HZ"] }

[sampling.channel_definitions.GL638.cut1]
around = "phase_space(cut(2,6,10))"
parent_lmb = [3,4,7,10]
subspace_lmb = [3,4,7,10]
on_cut = [1]
radial_profile = "lu_h"

[sampling.channel_definitions.GL638.cut1_joint_HZ]
around =
"then(block(lmb(6,10),phase_space(cut(2,6,10))),complement(7),block(lmb(3),at_cut(cut(2,6,10),intersect(s
parent_lmb = [3,6,7,10]
on_cut = [1]
radial_profile = { kind = "lu_h", approximation = "log_logistic", broad_fraction = 0.02 }
```

The composed channel first prepares Cut 1 on variables `(6,10)`, samples complement `7`, then focuses both thresholds in variable `3`. The active displacement leaves the host cut fixed; the physical-to-raw affine transformation and its determinant are part of the complete map. Neither its name nor `on_cut = [1]` removes the other physical cuts from the evaluation. The full GL638 run card supplies the other cut channels, a right-side threshold channel, and the generation and physics settings needed for a complete calculation.

For example, Cut 3 and its right threshold use `then(block(lmb(4,12),phase_space(cut(2,4,12))),complement(7),block(lm` with parent `[4,5,7,12]`. Side qualifiers can disambiguate multiple eligible associations; they do not replace checking the actual energy equation and its shift. Compositions may prepare left and right targets after one host

when the routed dependency checks permit it. `product` is suitable only when the blocks are independent: distinct active edge lists alone do not establish independence.

12.4.1 Matching the Cutkosky h-function

`radial_profile = "lu_h"` is shorthand for the detailed table above. Optional positive `scale` and `shape` override the automatic fit. The default `broad_fraction = 0.02` retains a positive ordinary-radius component. The implementation fits a log-logistic proposal to the runtime `[h_function]`; it does **not** invert the exact physical h-function.

For a simple multiplicative-flow cut, let the physical radial root be R and the raw radius be r, so `t = R/r`. At fixed angular shape the physical radial measure is proportional to `h(t) dt`. Sampling t approximately according to h therefore reduces this auxiliary variance. The focused CDF is `t^a/(t^a+s^a)` for positive shape a and scale s. A normalized broad component is added, and its complete CDF is inverted with a safeguarded solve in `log(t)`. The Jacobian uses the derivative of this **actual proposal**, including its mixture, and inverse density is evaluated at the supplied point.

Changing this proposal does not alter the physical h-function, its raised-cut derivatives, or the symmetric localization multiplying local threshold counterterms. Matching h alone does not flatten angular structure, soft limits or threshold intersections. In particular, raised-cut derivatives may require stronger tail optimization than this fit provides.

12.4.2 What a joint map improves

The implemented joint primitive supports two energy sums sharing one routed on-shell energy in the same three-dimensional active block. It retains the original unsquared equations, their masses and shifts, and both branches of the tangential circle. A certified compact disk in the two normal coordinates gives density `q ~ 1/R`, where R is their normal-plane radius. Unsupported energy classes, rank loss and tangencies are not solved by this primitive.

A locally integrable corner `f ~ 1/R` in two normal dimensions has a logarithmically divergent second moment under a smooth nonzero proposal: its first moment contains `dR`, but its second contains `dR/R`. A regular joint `q ~ 1/R` removes that leading weight growth. A one-normal inverse square-root map can improve local variance while leaving generic-ray weights unbounded. This is why a direct H map and a joint H/Z map have different purposes.

The GL638 local scans found flat joint-map weights on the investigated regular H/Z approach directions. This is not a global bounded-weight or variance guarantee: other thresholds, thresholds approached only after a counterterm projection, soft endpoints, tangencies and shrinking chart support need separate analysis. Sampling a physical threshold does not automatically focus its displaced counterterm-star image.

12.5 Partition scores and support

For channel c, the integrand contribution contains its map determinant `J_c` times a partition `w_c = rho_c / sum_b rho_b`, evaluated in the **same raw master momentum frame**. The integrator separately supplies adaptive cube and discrete-selection probabilities. This is a partition of unity using static map scores, not a balance heuristic containing the foreign channels' adaptive grid densities.

Weight setting	Score
`map_density`	Actual unadapted inverse-map density, including branch and support information.
`inverse_jacobian`	Another spelling for the same exact-density strategy.
`ose`	On-shell-energy score for a complete ordinary LMB map.
`singularity_proxy`	The supplied positive Symbolica expression in raw components `x0`, `x1`, …; it is not inferred from the map.

For L loops and selected LMB edges B, the OSE score is `rho = e_cm^(-3L) product_(e in B) (e_cm/E_e)^alpha`. Energies include masses and full affine routing at the unrescaled point. `alpha` is finite and nonnegative, defaults to 3, and zero gives a constant score. The energy-dimension factor matters when mixing OSE and exact map densities. OSE changes the partition, not the map's Jacobian or its radial law.

For a mixed catalogue, keep the global `map_density` default and override only an ordinary soft-coverage channel:

```
[sampling.channel_definitions.GL638.soft_6_12]
around = "lmb(6,12,13,14)"
parent_lmb = [3,4,7,10]
channel_weight = "ose"
```

Add `soft_6_12` to that graph's selection to activate it. A global `ose` choice requires advanced channels to override it explicitly; OSE is not supported on a surface or composed map. A user proxy must be finite and positive wherever its channel has support, and should retain the singular features the map was designed to sample. Actual support still gates proxy scores: a proxy cannot assign weight to a point outside its map. A selected full-support channel keeps the denominator positive; numerical uncertainty is not treated as zero support. Stronger OSE or proxy singularities do not automatically improve variance, since they may assign an overlapping region to a channel that samples its other directions poorly.

12.6 Inspect and export the effective catalogue

```
display integrands -p epem_a_tth -i NNLO --graph GL638 --show_sampling pretty
display integrands -p epem_a_tth -i NNLO --graph GL297 GL638 --show_sampling toml
```

The pretty view shows ordered selector expansion, canonical channel IDs, generated basis and physical cut IDs, complete expressions, resolved blocks and complements, profiles and scores. It states whether channels are sampled, summed or inactive. These are static recipes; point-dependent roots, centers and existence decisions are not fabricated for display.

The TOML view serializes the actual settings types, replacing generated LMB expansions with explicit `lmb(...)` selectors and retaining named definitions. Its clean stdout can be redirected to a file and applied through `set process ... file`. Multiple graphs produce one valid document; separate exports can be applied successively without resetting unrelated graphs. Do not concatenate complete TOML documents. The graph-specific entries belong in the existing run-card sampling tables, with their `default_runtime_settings` prefix.

12.7 Validate a map on a known integral

Use the normal integration workflow with a Gaussian reference target before interpreting a variance comparison on an expensive physical integrand:

```
integrate -p epem_a_tth -i NNLO -c 4 -w reference_workspace --reference-gaussian
'{"width":300}' --show-phase both
```

This substitutes a normalized Gaussian in all D spatial raw-momentum components while retaining the real graph routing, selected maps, channel partition, adaptive grid and stability machinery. Re reports its normalization; Im reports the raw `|K|^2` moment divided by `|center|^2 + D*width^2`. **Both targets are one.** Im here is a second acceptance observable, not a physical imaginary amplitude. The optional `center` is a D-element list; omitting it means zero. `width` is positive and in the momentum units of the calculation.

Disable active physical selectors and observables for this substitution. All loaded graphs in one integrand slot must have the same nonzero loop count. Use a separate workspace and repeat the same reference descriptor when resuming; it cannot be silently resumed as a physics integration. Through Python, use the same command with `api.run(...)`.

Check normalization **and** the nonconstant moment, their reported errors, invalid-point counts and stability behavior. Repeat with enough statistics and suitable width; agreement inside a very large error bar is weak evidence. A normalization test alone does not certify individual branches, support or every singular limit: forward/inverse, independent Jacobian and physical-limit tests remain necessary.

For physical runs, the absolute monitor takes componentwise absolute values after summing physical cuts, counterterms, group members and any summed orientations at each mapped point. When channels are explicitly summed, their positive absolute contributions are added before the outer-sample statistics update; the code does not take the absolute value of the final signed sum over different mapped points. If orientations are sampled, the monitor concerns that sampled-orientation domain. Report these choices when comparing signed and absolute errors, sample counts or maximum-weight influence.

13 Inspect events and observables

GammaLoop can evaluate selected points without launching a full adaptive integration. This is the shortest path for inspecting the generated cut events, testing selectors, and checking that histograms receive the expected weights. It is an investigative workflow: a few chosen points cannot establish convergence or replace the persisted result of an integration.

13.1 Start from the differential regression example

The repository contains matching Python and Rust journeys for the differential Local Unitarity process `e+ e- > d d~ g`. Their run cards generate the real two-graph process and configure:

- event generation and additional event weights;
- jet transverse-momentum, jet-count, and down-quark-energy quantities;
- a leading-jet selector; and
- continuous and discrete histogram observables.

> **What this example verifies**
> This is an API and event-pipeline regression fixture, not a scientifically reviewed perturbative-order or normalization benchmark. Its run card uses a powered coupling selector, but the current filter construction discards that exponent. Keep it for inspecting events and observable plumbing; define and validate production contributions independently.

The run card's `display_named_settings_examples` block lets you inspect each named object before evaluation:

```
display quantities -p #0
display quantities -p #0 leading_jet_pt
display selectors -p #0 leading_jet_pt_cut
display observables -p #0 leading_jet_pt_hist
```

Use these displays as a preflight check. A missing quantity name belongs to configuration; an empty event list belongs to event generation or selection; an unexpected histogram belongs to the quantity, phase, binning, or weights. Keeping those stages separate is more informative than debugging the final number alone.

13.2 Run the Python journey

Build the native package, then run the maintained script from the repository root. It creates a fresh state beside the script, generates the configured process, evaluates one integration-space point, evaluates a two-point batch, and evaluates one momentum-space point:

```
nix develop
uv venv .venv
source .venv/bin/activate
just build-api
python examples/api/python/epem_a_ddxg_xs_LO/inspect_events.py
```

The exact workflow is kept in the Python event-inspection script and its differential run card. The core API sequence is:

```python
from pathlib import Path

import numpy as np
from gammaloop import GammaLoopAPI

example = Path("examples/api/python/epem_a_ddxg_xs_LO")
api = GammaLoopAPI(
    state_folder=example / "state",
    boot_commands_path=example / "run.toml",
    clean_state=True,
)
api.run("run display_named_settings_examples")

info = api.get_integrand_info()
assert info.kind == "cross section"
assert info.graph_count == 2
assert info.graph_group_count == len(info.graph_groups)
assert all(
    sum(graph.is_master for graph in group.graphs) == 1
    for group in info.graph_groups
)

point = [0.17, 0.31, 0.53, 0.23, 0.41, 0.67]
single = api.evaluate_sample(point, return_events=True)
assert single.parameterization_jacobian is not None
assert single.stability_results
assert single.event_groups

points = np.array([
    point,
    [0.11, 0.29, 0.47, 0.19, 0.37, 0.59],
], dtype=float)
batch = api.evaluate_samples(points, return_events=True)
assert len(batch.samples) == 2
assert all(sample.event_groups for sample in batch.samples)
accumulator = api.observable_accumulator()
for sample in batch.samples:
    accumulator.add_sample(sample, sample.integrator_weight)
histograms = accumulator.snapshot()
assert len(histograms["leading_jet_pt_hist"].bins) == 8
assert len(histograms["jet_count_hist"].bins) == 6
assert histograms["leading_jet_pt_hist"].sample_count == 2
assert histograms["jet_count_hist"].sample_count == 2

print(single.integrand_result, single.generated_event_count)
for group in single.event_groups:
    for event in group.events:
        print(event.cut_info.graph_id, event.weight, event.outgoing_momenta)
print(histograms["leading_jet_pt_hist"].sample_count)
```

`return_events=True` temporarily requests returned events for that call; it does not permanently rewrite the integrand setting. Every `EventGroup` contains correlated accepted events produced by one graph group. Each event carries incoming/outgoing momenta, its primary complex weight, cut and graph identifiers, and any configured additional weights.

The normalization and weight contract defines which factors are already present in an event weight and why all contributions from one Monte Carlo point must be committed as one statistical sample.

One independent sample per result
Both `evaluate_sample` and each entry of `evaluate_samples(...).samples` expose an `EvaluationResult`. Evaluating does not commit observable statistics. Its complete event-group list belongs to one sample; groups must not be accumulated separately. Configured observables retain that payload even with diagnostic event output disabled.

`ObservableAccumulator.add_sample(result, coefficient)` applies the caller's complete outer weight once. A zero coefficient records an attempted sample without fills. The payload remains reusable, for example with different stratum coefficients. Use the same integrand, selector, observable, and clustering definitions for evaluation and accumulation; changing definitions requires a fresh evaluation and accumulator. `merge_in_place` combines independent sample statistics. To add independent stratum integrals, use `ObservableAccumulator.sum_independent_estimates([stratum0, stratum1])`: this adds means and variances while retaining each stratum's count. Merge batches within each stratum first. Empty strata have unavailable means/errors; one attempt has no error estimate. Raw snapshots remain separate from these derived estimates.

For a fixed stratified proposal with total inverse-density weight W and exact selection probability p_k, add each draw only to its chosen stratum's accumulator, with coefficient $p_k W$ on a match and zero on a miss. The stratum mean uses its own attempted-draw count. Summing those means and error variances requires independent draws and the correct probabilities; GammaLoop does not establish these sampler guarantees.

The histogram values are immutable snapshots. Inspect `bins`, underflow/overflow, raw sums of weights and squared weights, entry counts, and the aggregate statistics before deriving a plot. Keep raw statistics when combining results; rounded rendered values are not a merge format.

13.3 Run the Rust journey

The Rust example loads the same kind of run card through `StateLoadOption`, executes the display block through a CLI session, then calls the typed evaluation functions. It is a `rust-script` program whose dependencies point to the local workspace crates:

```
EXTRA_MACOS_LIBS_FOR_GNU_GCC=T \
SYMBOLICA_LICENSE="$SYMBOLICA_LICENSE" \
rust-script --debug examples/api/rust/epem_a_ddxg_xs_LO/inspect_events.rs
```

The documentation gate compiles the request boundary below against the workspace API. It keeps the event-return override and every required field synchronized even though the licensed process evaluation remains outside the pull-request tier:

```rust
use gammaloop_api::commands::evaluate_samples::EvaluateSamples;
use ndarray::arr2;

let points = arr2(&[[0.17, 0.31, 0.53, 0.23, 0.41, 0.67]]);
let request = EvaluateSamples {
    process_id: None,
    integrand_name: None,
    use_arb_prec: false,
    minimal_output: false,
    return_generated_events: Some(true),
    momentum_space: false,
    points: points.view(),
    integrator_weights: None,
    discrete_dims: None,
    graph_names: None,
    orientations: None,
};
assert_eq!(request.return_generated_events, Some(true));
```

```
let loop_momenta = arr2(&[[
    0.11, -0.07, 0.19, // k1 = (px, py, pz)
    -0.13, 0.05, 0.29, // k2 = (px, py, pz)
]]);
let momentum_request = EvaluateSamples {
    process_id: None,
    integrand_name: None,
    use_arb_prec: true,
    minimal_output: true,
    return_generated_events: None,
    momentum_space: true,
    points: loop_momenta.view(),
    integrator_weights: None,
    discrete_dims: None,
    graph_names: None,
    orientations: None,
};
assert_eq!(momentum_request.points.ncols(), 2 * 3);
```

Read the Rust event-inspection script with its run card. The ordinary `EvaluateSamples` path returns the cross-language `f64` boundary. Rust callers that must retain the active numeric precision use `EvaluateSamplesPrecise`; arbitrary-precision internal evaluation does not make the ordinary result fields arbitrary-precision. `use_arb_prec=true` forces arbitrary-precision (Arb) internal evaluation, using the configured Arb stability level when available and a default Arb level otherwise. The sample evaluation contract defines this flattened momentum layout and the precision behavior once for CLI, Rust, and Python.

Verification and resource cost
The pull-request gate parses the commands, compiles the Python source, and type-checks the Rust request literal, but does not run process generation or native evaluation. The maintained scripts are the real acceptance path and require a built API, the repository's scientific dependencies, and an appropriate Symbolica license. They create or replace only their example-local `state` directory because they opt into `clean_state=True`; remove that option before pointing at work you need to keep.

13.4 From point inspection to integration output

Selected points answer structural questions: whether events are produced, how graph/cut metadata is grouped, which selector accepts them, and which histogram bins are filled. A production result still needs an integration workspace, target-accuracy settings, iteration diagnostics, and the final observable output. Continue with the state and integration-workspace guide for resume semantics and the distinction between `integration_result.json`, `observables_final.*`, and the authoritative checkpoint.

Contributors changing progress reporting, cancellation, or terminal ownership should also read the integration dashboard architecture.

The exact Python return types and fields are linked from the interface guide and generated Python API.

14 Thermal and dense media

Medium modes evaluate amplitudes in an equilibrium medium at finite temperature or density. The medium is at rest in the frame of the supplied momenta.

14.1 Scope and limitations

Medium modes generate fixed-order amplitudes only; cross sections are rejected. Connected vacuum graphs, which give the pressure, are the only amplitudes validated against literature values. Higher-point amplitudes are supported but remain experimental.

Medium modes require `global.generation.three_dimensional_representations = ["cff"]`. LTD supports vacuum integrands only; requests containing LTD, including mixed CFF/LTD generation, are rejected.

> **Infrared safety and thresholds**
> GammaLoop has no thermal infrared subtraction or resummation, so only infrared-safe fixed-order amplitudes can be evaluated. At finite temperature, soft bosonic modes, whose occupation grows like `T/E`, eventually require resummation that GammaLoop does not perform. Threshold subtraction is also unavailable, so choose kinematics without thresholds, including the thermal (Landau-damping) cuts that a medium adds to the vacuum ones.

The following are also unsupported:

- local UV counterterms from expanded 4D integrands (`local_uv_cts_from_expanded_4d_integrands`); medium modes use 3D local subtraction;
- external momenta or distinct mass parameters with values equal up to sign that make otherwise distinct propagator poles coincide, leaving unresolved `0/0` thermal factors. Generation uses the derivative treatment below only when propagators share one mass parameter and the same momentum routing, including external shifts;
- at zero temperature, a Fermi-surface term in which another fermion's occupation step depends on the localized loop momentum, so that the two Fermi surfaces intersect; generation reports it;
- standalone evaluator export of processes with Fermi-surface localization; keep the saved process state instead;
- evaluating medium expressions with the standalone evaluator of the diagnostic `3Drep` command.

14.2 Select the medium

Set `global.generation.medium.mode` before `generate`:

- `thermodynamic_equilibrium` evaluates the distributions at the inverse temperature `1/T` given by `runtime.general.inverse_temperature` (default `1`, in inverse model energy units);
- `zero_temperature_equilibrium` takes their `T -> 0` limit: the inverse temperature is unused, and the distributions become step functions at the chemical potentials.

The mode is fixed at generation; changing it requires regenerating the integrand. The inverse temperature and chemical potentials are runtime values that can change per integrand without regeneration. `enable_thresholds` defaults to `true` and is rejected in medium modes, so disable it explicitly:

```toml
[cli_settings.global.generation.medium]
mode = "thermodynamic_equilibrium"
vacuum_subtraction = true

[cli_settings.global.generation.threshold_subtraction]
enable_thresholds = false

[default_runtime_settings.general]
inverse_temperature = 10.0

[default_runtime_settings.model]
muB = [0.5, 0.0]
```

14.3 Chemical potentials

Chemical potentials are model parameters. Each particle may name one (`chemical_potential` in JSON and UFO models); a missing assignment or the literal `ZERO` means zero chemical potential. Restriction-fixed chemical

potentials are canonicalized to `ZERO`, including derived expressions. A runtime value of zero does not erase an adjustable assignment. UFO import keeps these assignments and therefore requires `ufo-model-loader>=1.0.0`. In the bundled `sm` model, antiparticles use the negated `minus_<name>` parameter, and every particle's value is derived from the external parameters `muB`, `muQ`, `muLe`, `muLmu`, and `muLtau` (LHA block `CHEMICALPOTENTIAL`) using its baryon number, electric charge, and lepton flavor. Assignments use explicit particle metadata, not the `mu` prefix: `muH` belongs to the Higgs potential. The other bundled models declare no chemical potentials.

For medium evaluation, a particle and its antiparticle must have equal and opposite chemical-potential values; a self-conjugate particle must have zero chemical potential. Warm-up checks these relations at the current model values, including after parameter updates or state reloads. Independent external parameters are allowed when their values satisfy the relations.

With the default `--simplify-model=true`, a restriction card turns every parameter it sets to zero into a constant. `sm-default` therefore fixes all five chemical potentials at zero. Import `sm-thermal` instead, which sets `muB = 3` and keeps it adjustable. To vary other chemical potentials, create a custom restriction card based on `thermal` and give the desired parameters nonzero initial values. Keep `MU = MD = MS = ymu = ymd = yms = 0.0` in that card when the light quarks should remain massless with vanishing Yukawa couplings. `sm-thermal_s_mass` matches `sm-thermal` but also keeps the strange-quark mass `MS` and Yukawa input `yms` adjustable, retaining the corresponding Higgs and Goldstone interactions. After import, set the desired runtime values, including zero, for example with `set model muB=0.5`.

Finite-temperature evaluation requires a finite, positive inverse temperature. Chemical potentials must be finite and real. Bosons require a finite, nonnegative real mass and `|mu| < m`, with the massless `m = mu = 0` case also supported. Massive saturation (`|mu| = m > 0`) and boson condensation are unsupported. Fermions may have `|mu| >= m`. Finite-temperature fermions require a finite real mass; at zero temperature the same check applies when a fermion has a chemical potential and therefore an occupation step. These checks use the current model values and any DOT mass overrides when the integrand is warmed up, including after model updates or state reloads.

Amplitude warm-up also checks mixed-sign denominators in the selected generated orientations and rejects those that vanish for every loop momentum at the current masses and external momenta. For coincident poles with the same routing, regenerate with a shared mass parameter so generation can use the derivative treatment. The check uses exact equality; nearly coincident poles remain a numerical issue.

14.4 Vacuum subtraction and the pressure

With `vacuum_subtraction = true`, only the medium-dependent part is generated: each distribution weight is replaced by its difference from the vacuum limit, and UV counterterms covering all loops are omitted, including when bridges remain in the graph. This option requires a medium mode.

GammaLoop keeps equilibrium vacuum amplitudes in its Minkowski convention. For the complete connected vacuum-graph sum A, including model factors and counterterms, convert to the pressure contribution by hand: $\delta p = -iA$. This holds at every loop order and also after vacuum subtraction. The phase-convention derivation follows from Wick rotating the single overall spacetime-volume factor; stripped integrals and arbitrary numerator replacements require their own conversion. Keep `integrator.integrated_phase = "imag"` and comparison targets in the Minkowski convention; the real pressure contribution is then the reported imaginary part of A, with its sign and uncertainty preserved. The maintained NLO cold quark matter run card integrates such a contribution.

14.5 Fermi surfaces at zero temperature

Several propagators sharing one mass parameter and the same momentum up to an overall sign, including external shifts, produce energy derivatives of a distribution, as in self-energy insertions. In `zero_temperature_equilibrium`, those derivatives of a fermion with a nonzero chemical potential are delta functions on its Fermi surface. Bosons and fermions at zero chemical potential have no Fermi surface, so their derivatives vanish. The pointwise occupation is undefined (NaN) exactly on the Fermi surface, `E = sigma*mu`; deterministic inspect points should lie off that discontinuity. Localized delta terms are evaluated separately and do not assign a pointwise value to `theta(0)`. GammaLoop localizes each delta function by rescaling the loop momentum and inserting the normalized positive-scale profile configured in `runtime.h_function`. The profile

needs a positive `sigma` and a supported `power`; `exponential_ct` is rejected. Integrated results do not depend on that profile, but pointwise values do, so fix it explicitly when comparing sampled values. Positive-order Fermi-surface terms at the degenerate onset `sigma*mu = |m| > 0` are unsupported unless their product already has empty support. This is checked when the selected term is evaluated, at that evaluation's precision; ordinary order-zero occupation steps are not rejected by this check. The one-loop Fermi-surface run card illustrates regular-shell localization.

15 CLI, Rust, and Python APIs

15.1 Rust packages

The Rust API spans two primary packages.

- `gammalooprs` contains the physics implementation, data model, integrands, integration, observables, and lower-level algorithms.
- `gammaloop-api` provides the supported state-loading API, session/command integration, CLI assembly, and the PyO3 extension used by the Python distribution.

Load a state with `StateLoadOption::load()`. Its options select a state directory, boot card, logging overrides, read-only behavior, and optional settings overrides. Once loaded, callers can create a CLI-style session or use dedicated structured operations. A raw command string is the compatibility fallback, not a replacement for a typed operation where one exists.

```rust
use std::path::PathBuf;
use gammaloop_api::{state::CommandHistory, StateLoadOption};

let mut loaded = StateLoadOption {
    state_folder: Some(PathBuf::from("./state")),
    ..StateLoadOption::default()
}.load()?;

let command = CommandHistory::from_raw_string("display settings global")?;
loaded.cli_session().execute_command(command)?;
```

Some Rust types are public so that GammaLoop's packages can work together, but are not intended as stable integration points. Prefer the state-loading and structured-operation APIs described here; use the Rust orientation to choose a crate, then use that revision's Rustdoc for exact signatures, trait implementations, and lower-level types.

15.1.1 Rust reference map

This authored map separates the supported workflow from the much larger compiled surface. Follow these exact Rustdoc paths instead of beginning in an arbitrary internal module:

- **Load and command a state:** begin with `StateLoadOption`, retain the returned `LoadedState`, and execute parsed `CommandHistory` values through `CliSession`.
- **Replay and inspect:** use `RunHistory` for run cards and `IntegrandInfo` for structured graph-group, orientation, loop-basis, cut, and threshold metadata.
- **Evaluate samples:** construct `EvaluateSamples` for the ordinary `f64` boundary. Use `EvaluateSamplesPrecise` only when the caller must retain the active `f64`, `f128`, or arbitrary-precision result type.
- **Work below the facade:** the `gammalooprs` Rustdoc includes the integrand contract, runtime settings, precision-specific result records, and the mergeable histogram snapshot boundary. Treat public items not named by a maintained workflow as implementation-facing unless their crate documents a stronger compatibility promise.

15.2 Python packaging

A standalone GammaLoop distribution
The Python distribution and import package are both named `gammaloop`. Its compiled backend is `gammaloop._gammaloop`, which applications normally access through the public package. This is separate from the `symbolica.community.*` modules used by Spenso, Idenso, and Vakint; installing GammaLoop does not install those community modules as independent packages.

The main Python entry point is `GammaLoopAPI`. Its constructor loads or creates one stateful session:

```
from gammaloop import GammaLoopAPI

gl = GammaLoopAPI(
    state_folder="./state",
    boot_commands_path="./run.toml",
)
gl.run("display settings global")
```

The Python package requires Python 3.11 or newer. Run `just build-api` when building the bindings from a source checkout.

15.2.1 Python reference map

The generated module reference covers every registered public export, but the objects form a few connected workflows rather than forty unrelated entry points:

- **Session lifecycle:** construct `GammaLoopAPI`, then use `run`, the history getters, and `SettingsValue` to automate the same state and commands as the CLI.
- **Point evaluation:** `evaluate_sample` returns one `EvaluationResult`. `evaluate_samples` returns `BatchEvaluationResult` with those same records in `samples` and optional numerical-stability diagnostics. Both retain each sample's observable contribution without accumulating statistics. Create an `ObservableAccumulator` with `observable_accumulator()` and add samples with explicit outer coefficients.
- **Generated-integrand structure:** start at `IntegrandInfo`, then follow its graph groups into graph, orientation, loop-momentum-basis, cut, and threshold records. These objects describe compiled structure; they do not mutate it. `generated_representations` keeps the stored generation order. Each graph's `native_residue_counts` records the native map size for those modes; a group's `complete_residue_sum` distinguishes a full physical sum from individual orientation execution. The `orientations` list describes runtime slots, which can contain one complete-sum slot even when the native LTD map has many keys.
- **Native residue maps:** `get_residue_map` returns the stored graph-level CFF or LTD catalogue, including exact affine energy bindings, immutable map keys, scalar variants, and surfaces. Its native entries are distinct from the execution slots in `IntegrandInfo`.
- **Events and observables:** evaluation records lead to `EventGroup` and `Event`. For caller-owned aggregation, `HistogramAccumulator` produces immutable `HistogramSnapshot` records with raw statistics that remain mergeable and reconstructible.

Full integrations still use the command interface
The current Python module does not expose a supported structured `integrate()` method. Run an integration through `GammaLoopAPI.run("integrate ...")` or the CLI and consume its persisted workspace/results. Several integration-result record classes are registered by the native module for ongoing API work, but without a public producer they are not part of the curated Python boundary yet.

Result ownership
Objects returned by evaluation and integration are snapshots. Mutating a Python list or dictionary

derived from them does not update the live GammaLoop session. The explicit mutable exception is `HistogramAccumulator`, whose methods update caller-owned aggregation state.

Caller-owned histogram correlation limit
Do not yet use `HistogramAccumulator.fill_continuous_sample` or `fill_discrete_sample` to replay raw correlated event entries when more than one entry can land in the same bin. The helper counts the call as one sample but currently accumulates the entries' squared weights separately, unlike the native observable path, which groups their weights before recording one bin sample. Keep production histograms in the configured native observable pipeline until this statistical contract is aligned.

15.2.2 Aggregate independent histogram samples

This safe standalone use keeps one entry per bin in each independent sample. Merge pending worker state before committing it, then retain raw sums and squared sums for later combinations:

```
from gammaloop import HistogramAccumulator

left = HistogramAccumulator.continuous("energy", 0.0, 4.0, 4)
right = HistogramAccumulator.continuous("energy", 0.0, 4.0, 4)
left.fill_continuous_sample([(0.5, 2.0)])
right.fill_continuous_sample([(2.5, 3.0)])
left.merge_in_place(right)
left.update_results()

snapshot = left.snapshot()
assert snapshot.sample_count == 2
assert snapshot.bins[0].sum_weights == 2.0
assert snapshot.bins[0].sum_weights_squared == 4.0
assert snapshot.bins[0].sum_weights / snapshot.sample_count == 1.0
assert snapshot.bins[2].sum_weights == 3.0
assert snapshot.bins[2].sum_weights_squared == 9.0
assert right.snapshot().sample_count == 0
assert len(left.rebin(2).snapshot().bins) == 2
```

`snapshot()` includes both committed and pending samples. `update_results()` moves pending values into the completed counters; it is not needed merely to inspect the current snapshot. A successful `merge_in_place` consumes only the donor's pending samples, so merge worker accumulators before committing them.

15.3 Inspect and evaluate an existing state

The following workflow assumes that `./state` contains a generated integrand. Evaluation points are integrand-specific: their length must match the selected integrand and any discrete dimensions. Use the generated reference for the exact single-sample and batch contracts.

```
from collections.abc import Sequence

from gammaloop import GammaLoopAPI

api = GammaLoopAPI(state_folder="./state", read_only_state=True)
api.run("display processes")

print(api.get_run_history())
runtime = api.get_default_runtime_settings()
print(runtime.get("integrator.n_start"))
```

```
def evaluate_one(point: Sequence[float]) -> complex:
    result = api.evaluate_sample(
        point,
        process_id=0,
        minimal_output=True,
    )
    return result.integrand_result
```

Verification tier: compile
The documentation checks compile this example as Python syntax. They do not import or execute the native module: a runtime check additionally needs a built GammaLoop package, a provisioned backend and license, an existing generated state, and a point with the correct dimension.

The `run` method uses the same command language as the CLI and can change the in-memory state, settings, and run history. `read_only_state=True` protects files inside the active state directory; it does not make the Python object immutable or automatically persist the session. Inspect the live session through `get_run_history`, `get_global_settings`, and `get_active_command_blocks`.

For structured inspection, `get_integrand_info` describes the selected backend and graph structure, while `get_integrand_settings` and `get_default_runtime_settings` return detached, read-only `SettingsValue` snapshots. Use `get(path)`, attribute access, indexing, or `to_dict()` to read them; modifying derived Python values does not update the live session.

15.3.1 Inspect native residue maps

`get_residue_map(graph_name, process_id=None, integrand_name=None, three_dimensional_representation=None)` returns a detached `ResidueMap` for one generated graph. Select `"cff"` or `"ltd"` explicitly, or omit the representation to use the first mode in the stored generation order. The requested representation must already have been generated; this getter does not regenerate the graph. Process and integrand selectors resolve the same session ambiguities as the other inspection methods.

```
from gammaloop import GammaLoopAPI

api = GammaLoopAPI(state_folder="./state", read_only_state=True)
residue_map = api.get_residue_map(
    "graph_name",
    process_id=0,
    integrand_name="integrand_name",
    three_dimensional_representation="ltd",
)
for key, residues in residue_map.entries.items():
    print(key.canonical_string)
    for residue in residues:
        print(residue.native_id, residue.label, len(residue.variants))
```

`entries` is a Python dictionary from immutable, hashable `ResidueMapKey` objects to lists of `Residue` snapshots. A key contains the complete ordered edge `directions`, `loop_energy_map`, and `edge_energy_map`. Equality and hashing use these native values; labels, expression-local IDs, and scalar variants do not enter the key. Equal keys retain every associated native entry in their value list. A hash is a Python lookup value, not a persistent residue identifier.

Each `LinearEnergyExpression` exposes ordered `internal_terms` and `external_terms` pairs of edge ID and exact `fractions.Fraction`, together with `uniform_scale_coeff` and `constant`. These describe on-shell energies, external energies, the uniform numerator-sampling scale M, and the affine constant, respectively. The map arrays retain their native loop-slot and edge-slot order. `canonical_string` provides the existing native identity spelling

for a key and a readable exact spelling for an affine expression. Snapshot classes have no public constructors; their returned containers do not mutate the stored graph or a key's hash.

Each residue retains `native_id`, `label`, `numerator_map_index`, and all scalar `variants`. Variants preserve the exact prefactor, origin, repeated half-edge factors, denominator-edge support, both denominator sign-provenance maps, uniform-scale power, numerator surfaces, and the denominator tree. `variant.thermal_weight` supplies typed `ThermalWeight`, `ThermalNumerator` and `ThermalDistributionFactor` records for CFF media, preserving medium mode, signed energy lists, contour offsets and derivative orders. Vacuum LTD weights contain no thermal factors. Tree nodes retain their IDs, surface references, parents, and children; the getter does not expand the tree or discard repeated factors. Surface references use `("esurface", id)`, `("hsurface", id)`, or `("linear", id)`; unit and infinite references use `("unit", None)` and `("infinite", None)`.

The shared `surfaces` dictionary supplies cached E/H/linear records, including physical E/H energy occurrences and external shifts, or exact linear expressions with their kind, origin, and numerator-only flag. `residual_denominators`, `energy_factor_ownership`, `energy_factor_components` and `source_frame` retain the generated scalar expression's remaining denominators and convention metadata.

This is the stored graph-level native catalogue. It is not a catalogue of all projected UV or threshold-counterterm expressions, nor an evaluated, fully normalized production integrand. Native map IDs and keys remain separate from runtime complete-sum slots. Use the evaluation methods for physical values.

15.4 Sample evaluation contract

All three supported interfaces use the same two input layouts:

- An **integration-space** row contains the unit-hypercube coordinates expected by the selected integrand and discrete dimensions. Its required length is integrand-specific.
- A **momentum-space** row is `[k1x, k1y, k1z, k2x, k2y, k2z, ...]`: exactly one spatial `(px, py, pz)` triplet per independent loop momentum. It contains neither loop-energy components nor external momenta; GammaLoop obtains the latter from the integrand's kinematics. Select momentum space explicitly with `--momentum-space`, `momentum_space=true`, or `momentum_space=True`.

Every momentum-space row must therefore have a coordinate count divisible by three, and its number of complete triplets must match the selected integrand, graph, or graph group. `approach` axes use the same layout and dimension as their midpoint. The CLI, structured Rust API, and Python API all reach the same input builder and reject incomplete triplets before numerical evaluation.

Precision selection is independent of the coordinate layout. With `use_arb_prec=false`, the configured stability ladder may evaluate and escalate through `f64`, `f128`, and arbitrary precision. Setting `use_arb_prec=true` forces arbitrary-precision (Arb) internal evaluation, using the configured Arb stability level when available and a default Arb level otherwise. The `-f` CLI shorthand has the same behavior. CLI output, Python numeric fields, and ordinary Rust `EvaluateSamples` results remain `f64`. Only Rust `EvaluateSamplesPrecise` retains the numeric type used by the selected stability level. Each stability level can also set `three_dimensional_representation` to a generated `cff` or `ltd` representation; omission selects the first entry of the generation-time `three_dimensional_representations` list. Stability diagnostics report both precision and representation. When forcing Arb without a configured Arb level, the fallback inherits the first stability level's representation choice.

`evaluate_sample` returns one sample result with its complete event-group payload. `evaluate_samples` accepts a two-dimensional NumPy array and returns one result per row without accumulating observable statistics. Per-sample weights, discrete coordinates, graph names, and orientations must have the same row count as the input batch when provided. Graph and orientation selection applies only to momentum-space evaluation.

Both the ordinary Rust and Python endpoints expose numeric results through an `f64` contract, even when `use_arb_prec=True` forces arbitrary-precision internal evaluation. Evaluation may warm the integrand and update in-memory caches, including in a read-only-state session. Observable statistics require explicit accumulation. Rust-only callers that must retain the active precision use `evaluate_sample_precise` and `evaluate_samples_precise`.

Point evaluation returns the native contribution including map Jacobians and channel partition factors, before the outer-grid weight. The kinematics, normalization, and weights guide defines the exact $I_{\text{returned}} J_{\text{parameterization}} w_{\text{MC}}$ relation, with the reported unapplied $J_{\text{parameterization}} = 1$ for parameterized samples, and the correlated event-weight boundary. Direct momentum inputs can omit the reported Jacobian.

For a complete, source-backed run card and scripts that expose event groups, cut metadata, selectors, and merged histogram snapshots, follow the events and observables guide.

15.5 Symbolic conversion helpers

The supported module-level helpers are `atom_to_canonical_string` for parsing and canonicalizing a Symbolica expression, `evaluate_graph_overall_factor` for evaluating a graph's symbolic prefactor, and `to_dots` for rewriting tensor contractions into Idenso dot-product notation. Their generated entries document accepted strings, return values, failure modes, and task-oriented examples.

15.6 CLI and settings reference

15.6.1 Shell completion

`--completions` emits a static script from the same Clap command tree as `--help`. Load it for the current shell or save it in the shell's normal completion directory:

```
# Bash for the current session
source <(./gammaloop --completions bash)

# Zsh for the current session
source <(./gammaloop --completions zsh)
```

Fish, Elvish, PowerShell, and Nushell are also supported values. For Fish, pipe the output to `source`; for Nushell, save the generated module and then source it. Bash and Fish output also registers the repository wrapper spelling `./gammaloop`.

Static and state-aware completion
The generated shell script covers executable subcommands, flags, enumerated values, and path hints. Completion inside the interactive GammaLoop prompt additionally knows the active state's processes, integrands, settings, model objects, graphs, cuts, and orientations. A static shell script cannot contain that changing session data.

Use `./gammaloop --help` and the generated CLI and settings reference for command names, aliases, flags, positional arguments, defaults, possible values, and setting paths. The tutorials explain how commands and settings combine into a persistent workflow. The logging and diagnostics guide covers startup precedence, selective tag filters, sink routing, release-build limitations, and copyable investigation patterns.

16 Logging and diagnostics

This guide explains the default tracing configuration used by the CLI and API at startup and gives copyable filters for narrowing a noisy calculation to the subsystem and work unit that matter.

Before you start
Prerequisites: a built GammaLoop CLI and a state or run card that reaches the behavior you want to inspect. Filter changes take effect immediately and add negligible setup time, but verbose `inspect` or `dump` events can produce large files and slow a run. The expected invariant is that a narrow directive changes diagnostic visibility, not numerical results. If a filter produces nothing, first use a broader target at `debug`, confirm that release compilation has not removed the callsite, and then add tag constraints. After isolating the event,

> record the exact directive with the run card and continue to the CLI/settings reference for persistence and state controls.

16.1 Default directives

Normal session defaults come from `GlobalSettings`:

- `display_directive = "info"`
- `logfile_directive = "off"`

These are the application defaults written into `global_settings.toml` when defaults are shown or persisted.

In practice, `info` is the current convention for normal screen-facing output. Selective internal diagnostics should generally stay on `debug` and be turned on via narrower target/tag filters rather than by raising the whole display logger.

16.2 Startup precedence

Startup applies logging in this order:

1. Base settings come from `GlobalSettings`.
2. Environment overrides replace the base spec:
   - `GL_ALL_LOG_FILTER` overrides both stderr and logfile filters.
   - `GL_DISPLAY_FILTER` overrides only the stderr/display filter.
   - `GL_LOGFILE_FILTER` overrides only the logfile filter.
3. CLI overrides are then applied:
   - `-l/--level` overrides the stderr/display filter for the session.
   - `-L/--logfile-level` overrides the logfile filter for the session.
4. Some CLI modes hard-disable logfile logging for the session:
   - `--read-only-state`
   - `--logfile-level off`

When logfile logging is hard-disabled at boot, later settings changes cannot re-enable it for that session.

16.3 CLI level mapping

`-l/--level` and `-L/--logfile-level` expand to explicit crate directives:

- `off` -> `gammaloop_api=off,gammalooprs=off`
- `error` -> `gammaloop_api=error,gammalooprs=error`
- `warn` -> `gammaloop_api=warn,gammalooprs=warn`
- `info` -> `gammaloop_api=info,gammalooprs=info`
- `debug` -> `gammaloop_api=debug,gammalooprs=debug`
- `trace` -> `gammaloop_api=trace,gammalooprs=trace`

16.4 Empty-spec fallback floors

The filter builders also have hardcoded fallback floors used when a spec is empty:

- display/stderr builder fallback: `off`
- logfile builder fallback: `warn`

This is separate from the normal application defaults above. In other words:

- if startup uses the normal settings path, the defaults are `info` for display and `off` for logfile
- if an empty filter string is explicitly parsed, the display builder falls back to `off` and the logfile builder falls back to `warn`

16.5 Runtime updates

Changing `global.display_directive` or `global.logfile_directive` after startup reloads the active tracing filters. The CLI stderr override from `-l/--level` is treated as a session override and is separate from the persisted global setting.

16.6 Tag-based debug filtering

For selective debug logging, GammaLoop uses its own logging DSL rather than raw `EnvFilter`.

This follows the general idea in Tom Mrazik's tag-based logging note.

The main reason for owning the DSL is that GammaLoop needs composable tag groups and stable semantics around presence, absence, and explicit boolean values.

- Use stable targets for broad subsystems such as `gammalooprs::uv::forest` or `gammalooprs::integrands::process::cross_section`.
- Add boolean event fields as composable tags.
- Filter by field presence with `target[{tag_a,tag_b,!tag_c}]=debug`, or by displayed boolean values with `target[{#tag_a,#!tag_c}]=debug`.

This is preferable to span-name filtering because span-based filters can admit child-library events emitted while the span is active. GammaLoop tag filters only look at the event target and the boolean tag fields on the event itself.

16.6.1 Supported directive syntax

The supported directive forms are:

- `level`
- `target=level`
- `target[{tag_a,tag_b,!tag_c}]=level`
- `target[{#tag_a,#!tag_c}]=level`
- `target`

Notes:

- Directives are comma-separated.
- `target` is matched as a module-style prefix, so `gammalooprs::uv=debug` matches `gammalooprs::uv` and `gammalooprs::uv::forest`.
- A directive without an explicit `=level` is treated as `=trace`.
- Tag groups are conjunctions: `[{generation,uv}]` means both tags must match.
- `!tag` means the field is absent.
- `#tag` means the field is present with boolean value `true`.
- `#!tag` means the field is present with boolean value `false`.
- `field=value` matches an explicit field value.

16.6.2 Tag matching model

Tags are represented by event fields.

- `#generation` at the callsite emits `generation = true`.
- In a directive, `generation` means the event must carry a field named `generation`.
- In a directive, `#generation` means the event must carry `generation = true`.
- In a directive, `!inspect` means the event must not carry a field named `inspect`.
- In a directive, `#!inspect` means the event must carry `inspect = false`.
- In a directive, `inspect=true`, `mode=summary`, or `label="soft region"` means the event must carry that value specifically.

This means the callsite controls both:

- whether a log is selectable by a presence/absence query
- whether a log can be selected by an explicit value query such as `inspect=false` or `mode=summary`

16.6.3 Static vs dynamic filtering

Presence/absence-only directives stay on the lazy metadata path.

- `generation`
- `!inspect`
- `gammalooprs::uv::forest[{generation,uv,!dump}]=debug`

These can be decided from the callsite target and declared field names alone, so the filter can answer `always` or `never` at callsite registration time.

Value-matching directives are dynamic.

- `inspect=false`
- `#!inspect`
- `#generation`
- `mode=summary`
- `label="soft region"`

Those depend on the event instance, so they are evaluated in the per-event pass.

16.6.4 Precedence

When multiple directives match the same event, GammaLoop prefers the most specific one:

- longer target prefix wins
- then the directive with more tag requirements wins
- then later directives win if the earlier specificity is identical

This lets broad directives such as `gammalooprs=info` coexist with narrow tag-specific directives such as `gammalooprs::uv::forest[{generation,uv,dump}]=debug`.

16.6.5 Copy-pasteable display tags

Display logs render boolean fields next to the source as a directive tag group:

```
@gammalooprs::uv::forest[{#generation, #uv, #!inspect}] DEBUG: message
```

Every boolean field is rendered this way, not only the standard tag vocabulary. `true` becomes `#field_name`; `false` becomes `#!field_name`. These boolean fields are removed from the normal display field table.

Use the `full` logging prefix when you want the rendered source to be a valid directive head:

```
gammaloop --logging-prefix full -l debug ...
```

Then the text after `@` and before the log level can be copied into a directive by adding `=debug`, for example:

```
display_directive = "gammalooprs::uv::forest[{#generation, #uv, #!inspect}]=debug"
```

This copy-paste form assumes the display source is the module target. Enabling `full_line_source` adds file and line information to the source display, which is useful for locating code but is not a valid directive target.

16.6.6 Sink-only field prefixes

This repo also has sink-routing prefixes for fields:

- `file.<name>`: only rendered into the logfile/json sink

- `display.<name>`: only rendered into the stderr/display sink

Examples:

- `file.integrands = %...` will appear only in the file logger output
- `display.progress = %...` will appear only in the display logger output

These prefixes are a formatting/routing feature, not a separate event kind. They decide where a field is rendered after the event has been emitted. This lets a callsite attach large payloads such as `file.integrands` without dumping them to stderr.

16.6.7 Pipeline-wide tag set

Prefer a small stable vocabulary that cuts across the whole pipeline.

Primary phase tags:

- `generation`: work that builds or prepares runtime objects before Monte Carlo integration starts
- `integration`: work performed while evaluating samples or managing the adaptive integration loop
- `profile`: UV/IR/profile-style diagnostic scans and their analysis
- `persistence`: reading or writing saved state, manifests, checkpoints, and exported results

Core domain tags:

- `uv`: ultraviolet counterterms, UV forests, UV profiles, or UV-specific generation/evaluation logic
- `ir`: infrared subtraction, IR profiles, or IR-specific generation/evaluation logic
- `subtraction`: threshold, UV, or IR subtraction logic when the main concern is subtraction rather than the specific regime
- `sampling`: channel choice, discrete axes, parameterizations, or sample-generation choices
- `stability`: precision escalation, retries, instability diagnosis, and numerical safety checks
- `observables`: histogramming, event-to-observable projection, and observable snapshot production
- `selectors`: event-selection logic and selector decisions
- `cache`: cache lookup, reuse, invalidation, or cache-debug instrumentation

Common work-unit tags:

- `graph`: the log is about one graph or graph-local data
- `group`: the log is about a graph group or another explicitly grouped aggregate
- `orientation`: the log is about orientation-dependent data or choosing/summing orientations
- `channel`: the log is about multi-channeling or a particular channel
- `cut`: the log is about a cut, raised cut, or cut-local computation
- `event`: the log is about generated/retained event objects or event-group processing
- `sample`: the log is about one evaluation sample, its coordinates, or per-sample intermediate values
- `iteration`: the log is about one adaptive integration iteration or iteration-level summaries
- `term`: the log is about one algebraic term, summand, or term-local contribution

Common purpose tags:

- `solver`: the log is about root-finding, linear solves, fitting, or similar numerical solver state
- `compile`: the log is about evaluator/code generation or compilation-oriented preparation
- `inspect`: the log exposes detailed intermediate state for debugging, rather than a high-level milestone
- `summary`: the log is a compact roll-up rather than a step-by-step trace
- `dump`: the log emits large or structured payloads such as expressions, tables, or serialized views

16.6.8 Tag boundaries

Use the most general tag that accurately captures the reason you want to turn the log on or off.

- Prefer `generation` over `compile` when the message is a broad generation milestone.
- Add `compile` only when the message is specifically about evaluator construction or compilation-like work.
- Prefer `uv` or `ir` when the regime matters to the user; use `subtraction` when the subtraction mechanism is the real concern.

- Prefer `inspect` for verbose intermediate values that are mainly useful while debugging internals.
- Add `dump` when the payload is large enough that users may want to suppress it separately from lighter debug logs.
- Do not use `graph`, `cut`, or `sample` as substitutes for `generation` or `integration`; they refine phase tags rather than replace them.

16.6.9 Naming guidance

- Use phase tags first. They answer "when in the pipeline did this happen?"
- Use domain tags second. They answer "what subsystem is this about?"
- Use work-unit tags third. They answer "what object is being worked on?"
- Use purpose tags last for optional refinement.
- Prefer tags that are meaningful across multiple modules.
- Avoid tags that merely restate a function name.
- Avoid tags tied to one internal representation unless that representation is a stable concept in user-facing debugging.

`parametric` is usually not a core pipeline tag. It is acceptable as a local refinement when needed, but should not be treated as part of the primary vocabulary unless it becomes a consistently useful cross-cutting concept.

16.6.10 Example queries

- all generation-time UV forest logs:
  - `gammalooprs::uv::forest[{generation,uv}]=debug`
- only the large UV forest dumps for orientation-dependent generation logs:
  - `gammalooprs::uv::forest[{generation,uv,orientation,dump}]=debug`
- UV forest term-by-term generation logs:
  - `gammalooprs::uv::forest[{generation,uv,term}]=debug`
- all integration-time subtraction debug in amplitude evaluation:
  - `gammalooprs::integrands::process::amplitude[{integration,subtraction}]=debug`
- per-sample integration inspection in cross-section evaluation:
  - `gammalooprs::integrands::process::cross_section[{integration,sample,inspect}]=debug`
- all integration-time cut solver debug in cross-section evaluation:
  - `gammalooprs::integrands::process::cross_section[{integration,cut,solver}]=debug`
- integration-time debug excluding inspect-tagged logs:
  - `gammalooprs::integrands::process::cross_section[{integration,!inspect}]=debug`
- only events that explicitly set `inspect=true`:
  - `gammalooprs::integrands::process::cross_section[{integration,inspect=true}]=debug`
- only events with a specific textual mode field:
  - `gammalooprs::integrands::process::cross_section[{integration,mode=summary}]=debug`

Example display directive:

```
[cli_settings.global]
display_directive =
"gammaloop_api=info,gammalooprs=info,symbolica=off,poly::gcd=off,gammalooprs::uv::forest[{generation,uv,o
```

16.7 Unsupported `EnvFilter` syntax

GammaLoop no longer treats the directive string as generic `EnvFilter` syntax.

In particular, do not rely on:

- span-name filters such as `target[span_name]=debug`
- generic field filters such as `[{field=value}]`
- `EnvFilter` regex semantics

If those are needed later, they must be added explicitly to the GammaLoop DSL.

16.8 Release-build note

`gammalooprs` is compiled with `tracing` feature `release_max_level_info`, so `debug!` and `trace!` callsites in that crate are compiled out in release builds.

16.9 Authoritative implementation

The startup precedence and sink wiring live in the API tracing setup. The shared directive parser, CLI level mapping, and filter behavior live in the runtime tracing utilities, while persisted defaults are owned by GlobalSettings.

17 Kurvst curve and path API

Kurvst is GammaLoop's Typst-facing WebAssembly layer for Bezier and Hobby paths, arc-length trimming, sampled path patterns, parallel curves, and CeTZ conversion. This page embeds the complete maintained Kurvst manual used by the drawing pipeline.

> **Geometry rather than topology**
> Kurvst transforms curve geometry. Linnet and Linnest own graph topology and layout; GammaLoop's drawing templates combine those results with Kurvst paths and styles.

`kurvst` is a Typst package backed by `kurvst.wasm`, a small Kurbo-based plugin. Its public API is path-based: construct a path dictionary, pass that path into transforms, and draw the returned path.

It exposes Bezier utilities that are awkward or unavailable in native Typst:

- constructing cubic and Hobby paths,
- trimming paths by arc length,
- generating sampled path patterns,
- fitting Kurbo offset/parallel paths,
- converting returned path geometry to CeTZ drawing commands.

17.1 Choose an import path

Kurvst is currently a bundled source package, not a Typst Universe package. A Clinnet run writes it below `build/templates/crates/kurvst/typst/`; a custom template in `build/templates/` can therefore import it with:

```
#import "crates/kurvst/typst/src/lib.typ" as kurvst
```

Repository examples live one directory beside `src/` and instead use `#import "../src/lib.typ" as kurvst`. Keep `kurvst.wasm`, `typst.toml`, and the `src/` tree together when copying the package to another Typst project.

Path geometry points are two-item tuples:

```
#let p = (1.2, -0.4)
```

Cubic segments use `start`, `control-start`, `control-end`, and `end`:

```
#let segment = (
  start: (0, 0),
  control-start: (1, 0.5),
  control-end: (2, -0.5),
  end: (3, 0),
)
```

Use `from-cubic(segment)` once to turn that cubic dictionary into a path dictionary. Returned paths contain a curve-command wire path in `path`. Rust converts that wire path to Kurbo's `BezPath` internally, and every path-level Kurvst function accepts either a returned dictionary or the raw wire path.

```
#let path = kurvst.from-cubic(segment)
#let trimmed = kurvst.trim(path, start-outset: 0.2, end-outset: 0.1)
#let shifted = kurvst.parallel(trimmed, distance: 0.15)
```

17.2 Path Wire Format

A Kurvst wire path is a dictionary with one `elements` array. The elements mirror Typst's native `curve` commands, but points are plain numeric tuples:

```
#let path = (
  elements: (
    (kind: "move", start: (0, 0)),
    (kind: "line", end: (0.6, 0.3)),
    (kind: "quad", control: (1.0, 1.0), end: (1.4, 0.3)),
    (
      kind: "cubic",
      control-start: (1.8, -0.4),
      control-end: (2.4, 1.0),
      end: (3.0, 0),
    ),
    (kind: "close", mode: "straight"),
  ),
)
```

The supported element kinds are:

- `move`: starts a subpath at `start`.
- `line`: adds a straight segment ending at `end`.
- `quad`: adds a quadratic segment using `control` and `end`.
- `cubic`: adds a cubic segment using `control-start`, `control-end`, and `end`.
- `close`: closes the current subpath. `mode` is optional and defaults to `"straight"` when emitted by Kurvst.

Prefer the path fragment helpers for new code. `line`, `quad`, and `cubic` include their start points, so fragments can be built independently:

```
#let custom = kurvst.path(
  kurvst.line((0, 0), (0.6, 0.3)),
  kurvst.quad((0.6, 0.3), (1.0, 1.0), (1.4, 0.3)),
  kurvst.cubic((1.4, 0.3), (1.8, -0.4), (2.4, 1.0), (3.0, 0)),
)
```

`arc(center, radius, start, stop)` builds a circular arc from cubic pieces of at most 90°. Angles are measured counterclockwise from the positive x axis in y-up coordinates, as in CeTZ; `stop < start` runs clockwise:

```
#let stadium = kurvst.path(
  kurvst.arc((1, 0.5), 1, 0deg, 180deg),
  kurvst.line((0, 0.5), (0, -0.5)),
  kurvst.arc((1, -0.5), 1, 180deg, 360deg),
  kurvst.close(),
)
```

`path` and `append` flatten fragments. If an appended fragment starts where the current path ends, its leading `move` is skipped; if it starts elsewhere, the `move` begins a new subpath. The edited path can go straight back into Kurvst transforms:

```
#let base = kurvst.from-cubic(segment)
#let extended = kurvst.append(base, kurvst.line(segment.end, (3.4, 0.2)))

#let trimmed = kurvst.trim(extended, start-outset: 0.15)
#let shifted = kurvst.parallel(trimmed, distance: 0.1)

#kurvst.to-native(shifted, unit: 36pt, stroke: rgb("#1b7f4c") + 0.7pt)
```

Use `elements` when you need the raw command stream, `points` for the visited endpoints, `segments` for cubic segment dictionaries, `to-native` for native Typst drawing, and `to-cetz-data` or `to-cetz` for CeTZ.

A typical chain keeps the returned dictionaries intact until the final drawing step:

```
#let base = kurvst.hobby-through(demo-start, demo-through, demo-end)
#let trimmed = kurvst.trim(base, start-outset: 0.2, end-outset: 0.1)
#let shifted = kurvst.parallel(trimmed, distance: 0.15)

#cetz.canvas({
  kurvst.to-cetz(base, stroke: rgb("#bbbbbb") + 0.4pt)
  kurvst.to-cetz(trimmed, stroke: rgb("#d72638") + 0.6pt)
  kurvst.to-cetz(shifted, stroke: rgb("#1b7f4c") + 0.6pt)
})
```

17.3 Paths And Trimming

`cubic` constructs a path from one cubic Bezier. `trim` trims by curve distance from the start and/or end and returns another path dictionary.

```
#let path = kurvst.from-cubic(segment)
#let trimmed = kurvst.trim(path, start-outset: 0.15, end-outset: 0.1)
```

`intersections(a, b)` returns transverse crossings sorted by arc distance along `a`. Each record includes `point`, `distance-a`, `distance-b`, segment indices, and local segment parameters. Path-endpoint and tangential contacts are omitted, so the distances can be passed directly to path-splitting logic.

`hobby-through(start, through, end)` builds a smooth open curve through three points; `segments` returns the two cubic halves split at `through`. `hobby-spline(points)` does the same for any open point sequence with at least two points. Both return path dictionaries and can be passed directly to path-level helpers.

```
#let spline = kurvst.hobby-spline((
  (0.0, 0.0),
  (0.9, 0.8),
  (1.8, -0.3),
  (2.8, 0.4),
))
#let shifted = kurvst.parallel(spline, distance: 0.14)
#let wiggle = kurvst.pattern(
  spline,
  pattern: kurvst.wave(samples-per-period: 24),
  amplitude: 0.1,
  wavelength: 0.55,
)
#cetz.canvas({
  kurvst.to-cetz(spline, stroke: rgb("#bbbbbb") + 0.45pt)
```

```
  kurvst.to-cetz(shifted, stroke: rgb("#1b7f4c") + 0.6pt)
  kurvst.to-cetz(wiggle, stroke: rgb("#355c9a") + 0.55pt)
})
```

`split-through` combines Hobby spline construction with endpoint trimming and returns one path part between each consecutive point. Consumers such as Linnest can wrap it for graph-edge geometry.

17.4 Path Patterns

`pattern` generates a one-dimensional pattern along any path dictionary. Built-ins are regular Typst dictionaries:

```
#let wave = kurvst.wave()
#let zigzag = kurvst.zigzag()
#let coil = kurvst.coil(longitudinal-scale: 1.6)
```

String names `"wave"`, `"zigzag"`, and `"coil"` are accepted for convenience, but they are resolved in Typst before calling wasm.

`split-at` takes arc distances along the input path and returns the one patterned path cut there as `parts`, so pieces can be styled independently while following a single pattern:

```
#let base = kurvst.from-cubic(segment)
#let split = kurvst.pattern(base, pattern: "coil", amplitude: 0.12,
  wavelength: 0.4, split-at: (kurvst.length(base) / 2,))
#cetz.canvas({
  kurvst.to-cetz(split.parts.at(0), stroke: blue + 0.6pt)
  kurvst.to-cetz(split.parts.at(1), stroke: orange + 0.6pt)
})
```

Custom patterns use the same object shape:

```
#let hook = (
  kind: "points",
  name: "hook",
  interpolation: "linear",
  points: (
    (at: 0, x: 0, y: 0),
    (at: 0.25, x: 0.15, y: 1),
    (at: 0.5, x: 0, y: 0),
    (at: 0.75, x: -0.15, y: -1),
    (at: 1, x: 0, y: 0),
  ),
)
```

`at` is the phase position inside one wavelength, from `0` to `1`. The `x` coordinate offsets along the path tangent and `y` offsets along the path normal; both are scaled by `amplitude`. If `at` is omitted, points are spaced evenly. Use `interpolation: "linear"` for corners and `"smooth"` for a spline through sampled points.

`kurvst.coil` defaults to `samples-per-period: 16`, `longitudinal-scale: 1.25`, `fit-length: none`, `amplitude: 0.1`, and `wavelength: 1.0`. With `fit-length: none`, the periodic coil is unchanged; `amplitude` and `wavelength` are used only for fitting.

Set `fit-length: L` to return an ordinary normalized point-pattern dictionary spanning `P = max(1, round(L / wavelength)) - 0.5` coil periods, using the requested wavelength. It retains full amplitude with inward endpoint phases, exact zero offsets at both ends, and `endpoint-ramp: false`: no taper, straight stubs, or connectors. Longitudinal fitting depends on `amplitude`, so apply the dictionary once over a carrier of length `L` with the same amplitude, a wavelength of `L`, all its samples, and zero phase:

```
#let base = kurvst.from-cubic(segment)
#let L = kurvst.length(base)
#let A = 0.12
#let coil = kurvst.coil(fit-length: L, amplitude: A, wavelength: 0.55)
#let fitted = kurvst.pattern(
  base,
  pattern: coil,
  amplitude: A,
  wavelength: L,
  samples-per-period: coil.points.len() - 1,
  phase: 0,
)
```

Fitting requires positive, finite `fit-length` and `wavelength`, finite `amplitude`, and finite, nonnegative `longitudinal-scale`. Fitting happens in Typst; `kurvst.pattern` has no `natural-endpoints` argument. As for other point patterns, curved carriers use local tangent/normal offsets, not evaluation at a corrected arc distance. `endpoint-slope` has no effect with `endpoint-ramp: false`.

Patterns with `endpoint-ramp: true`, including periodic coils, taper amplitude over 75% of a wavelength at each anchored endpoint, capped at half the path length for short paths. This is useful for coils, whose longitudinal offset would otherwise put the first and last visible points inside the turn near nodes. The longitudinal offset uses the square of the taper envelope, letting the coil open sideways before it starts doubling back.

On `kurvst.pattern`, `endpoint-slope: 0` keeps the taper tangential to the base path. Values from `0` to `3` control the envelope's initial slope; try `1` for an angled finish with coil `phase: calc.pi / 2`. This keeps the endpoint attached and still flattens the envelope into the full-sized coil. It is not an angle: the direction also depends on amplitude, wavelength, and the lateral offset at the endpoint phase. Unanchored endpoints and patterns without `endpoint-ramp` are unaffected.

```
#let base = kurvst.from-cubic(segment)
#let path = kurvst.pattern(
  base,
  pattern: hook,
  amplitude: 0.15,
  wavelength: 0.7,
)
#native-scene({
  native-cubics(kurvst.segments(base), stroke: rgb("#c8c8c8") + 0.45pt)
  native-polyline(kurvst.points(path), stroke: rgb("#1b7f4c") + 0.8pt)
})
```

17.5 Parallel Paths

`parallel` uses Kurbo's offset curve fitter to produce a path at a fixed normal distance from the source path. Positive distances follow the left normal of the path direction; negative distances follow the right normal. `start-outset` and `end-outset` trim the fitted path by arc length after the offset is computed.

```
#let base = kurvst.from-cubic(segment)
#let left = kurvst.parallel(base, distance: 0.18, start-outset: 0.35, end-outset: 0.35)
#let right = kurvst.parallel(base, distance: -0.18)
#native-scene({
  native-cubics(kurvst.segments(base), stroke: rgb("#c8c8c8") + 0.45pt)
  native-cubics(kurvst.segments(left), stroke: rgb("#1b7f4c") + 0.8pt)
  native-cubics(kurvst.segments(right), stroke: rgb("#355c9a") + 0.8pt)
})
```

17.6 Stroke Outlines

`outline` turns a stroked path into a closed region, so a line drawing becomes a filled solid with the same visible shape. It wraps Kurbo's stroker: `join` is `"miter"`, `"round"`, or `"bevel"`, and `cap` (or `start-cap` and `end-cap` separately) is `"butt"`, `"square"`, or `"round"`. Open subpaths become one contour; closed subpaths become an outer and an inner contour, so fill with the default non-zero rule.

```
#let base = kurvst.path(
  kurvst.line((0, 1), (0, 0)),
  kurvst.cubic((0, 0), (1, 0), (2, 1), (3, 0)),
)
#let solid = kurvst.outline(base, width: 0.2, cap: "round")
#cetz.canvas(kurvst.to-cetz(solid, fill: black, stroke: none))
```

CeTZ `merge-path` bridges separate subpaths with straight lines. That leaves fills unchanged, but a stroked outline with several contours shows the bridge; use `to-native` to stroke the contours themselves. See `examples/outline-logo.typ` for a full logo converted to solids.

17.7 Path Layers

`layer` is a convenience wrapper for drawing derived visible paths. It combines side-aware offsetting, endpoint outsets, and shortening into one path-in/path-out operation. Offsetting happens first: `length` is a fixed visible arc length, `ratio` is a fraction of the full offset path length before trimming, and `resolve-length` decides how to combine them. The default `"min"` keeps whichever limit is shorter. `start-outset`, `end-outset`, and `shift` are arc distances on the offset path. Positive `shift` moves the shortened interval toward the path end; it is clamped to preserve the endpoint outsets.

```
#let base = kurvst.hobby-spline((
  (0.0, 0.0),
  (0.9, 0.8),
  (1.8, -0.3),
  (2.8, 0.4),
))
#let layer = kurvst.layer(
  base,
  offset: 0.16,
  length: 1.6,
  ratio: 0.5,
  resolve-length: "min",
  shift: 0.35,
)
#cetz.canvas({
  kurvst.to-cetz(base, stroke: rgb("#bbbbbb") + 0.45pt)
  kurvst.to-cetz(layer, stroke: rgb("#1b7f4c") + 0.8pt)
})
```

Use `side-point` to choose the sign of the offset from a point on the desired side of the original path, before offsetting or trimming. Drawing packages can use this to place derived layers on the same side as an edge label without knowing anything about the physics or graph style that requested the layer.

17.8 Native Drawing Primitives

Kurvst returns dictionaries and arrays. The core geometry can be drawn without CeTZ by emitting native `curve` content:

```
#kurvst.to-native(kurvst.from-cubic(segment),
unit: 36pt, stroke: black + 0.7pt)
```




The generated reference below keeps drawing code inline. It only uses the small common helpers above for coordinate scaling, native `curve` construction, point markers, and fixed-size preview blocks.

17.9 CeTZ Interoperability

The CeTZ helpers are thin adapters over the same returned geometry. Use them when the surrounding document already lives in a CeTZ canvas, or when you want CeTZ path merging and styling:

```
#cetz.canvas({
  let base = kurvst.from-cubic(segment)
  kurvst.to-cetz(base, stroke: rgb("#d72638")
+ 0.6pt)

  let path = kurvst.pattern(
    base,
    pattern: kurvst.coil(longitudinal-scale:
1.6),
    amplitude: 0.12,
    wavelength: 0.55,
  )
  kurvst.to-cetz(path, stroke: rgb("#355c9a")
+ 0.55pt)
})
```



17.10 Generated Reference

17.11 kurvst

- append()
- arc()
- center-outset()
- close()
- coil()
- cubic()
- cubic-point()
- cubic-tangent()
- cubic-to()
- elements()
- from-cubic()
- from-elements()
- hobby-spline()
- hobby-through()
- intersections()
- layer()
- length()
- line()
- line-segment()
- line-to()
- move-to()
- outline()

- outset-point()
- parallel()
- path()
- pattern()
- point()
- points()
- quad()
- quad-to()
- resolve-length()
- segments()
- split-through()
- to-cetz()
- to-cetz-data()
- to-native()
- trim()
- wave()
- zigzag()

Variables

- layer-defaults

17.11.1 append

Return a path with additional fragments or elements appended.

17.11.1.1 Parameters

```
append(
  path: dictionary,
  ..parts: any
) -> dictionary
```

17.11.1.1.1 path `dictionary`

Base Kurvst path dictionary.

17.11.1.1.2 ..parts `any`

Path fragments, path elements, or element arrays to append.

17.11.2 arc

Build a circular arc path fragment from cubic segments.

17.11.2.1 Parameters

```
arc(
  center: array,
  radius: int float,
  start: angle,
  stop: angle
) -> dictionary
```

17.11.2.1.1 center `array`

Arc center.

17.11.2.1.2 radius `int` or `float`

Positive arc radius.

17.11.2.1.3 start `angle`

Start angle, measured counterclockwise from the positive x axis.

17.11.2.1.4 stop `angle`

Stop angle; `stop < start` runs clockwise.

17.11.3 center-outset

Compute the symmetric trim needed to center a shorter path layer.

17.11.3.1 Parameters

```
center-outset(
  base-length: int float,
  length: none int float,
  ratio: none int float,
  resolve-length: string function,
  start-outset: int float,
  end-outset: int float
) -> int float
```

17.11.3.1.1 base-length `int` or `float`

Full base path arc length.

17.11.3.1.2 length `none` or `int` or `float`

Fixed target visible length.

Default: none

17.11.3.1.3 ratio `none` or `int` or `float`

Relative target visible length as a fraction of `base-length`.

Default: `none`

17.11.3.1.4 resolve-length `string` or `function`

Resolution strategy for fixed and relative targets.

Default: `"min"`

17.11.3.1.5 start-outset `int` or `float`

Already-applied trim at the start of the path.

Default: `0`

17.11.3.1.6 end-outset `int` or `float`

Already-applied trim at the end of the path.

Default: `0`

17.11.4 close

Build a `close` path element.

17.11.4.1 Parameters

`close(mode: string) -> dictionary`

17.11.4.1.1 mode `string`

Native Typst curve close mode.

Default: `"straight"`

17.11.5 coil

A smooth coil path pattern.

17.11.5.1 Parameters

```
coil(
  samples-per-period: int,
  longitudinal-scale: int float,
  fit-length: none int float,
  amplitude: int float,
  wavelength: int float
) -> dictionary
```

17.11.5.1.1 samples-per-period `int`

Number of samples used to approximate one coil period.

Default: `16`

17.11.5.1.2 longitudinal-scale `int` or `float`

Horizontal scale of the coil before it is mapped onto a path.

Default: `1.25`

17.11.5.1.3 fit-length `none` or `int` or `float`

Fit a complete coil between inward-facing natural endpoints, without tapering. A positive path length fits half-integer periods using wavelength as nominal spacing. Apply once with pattern wavelength equal to fit-length, phase zero, and samples-per-period equal to the returned points.len() - 1.

Default: `none`

17.11.5.1.4 amplitude `int` or `float`

Amplitude used for longitudinal fitting; pass the same amplitude to pattern.

Default: `0.1`

17.11.5.1.5 wavelength `int` or `float`

Requested coil spacing when fit-length is set.

Default: `1.0`

17.11.6 cubic

Build a cubic path fragment.

17.11.6.1 Parameters

```
cubic(
  start: array,
  control-start: array,
  control-end: array,
  end: array
) -> dictionary
```

17.11.6.1.1 start `array`

Start point.

17.11.6.1.2 control-start `array`

Cubic control point near `start`.

17.11.6.1.3 control-end `array`

Cubic control point near `end`.

17.11.6.1.4 end `array`

Endpoint.

17.11.7 cubic-point

Evaluate a cubic segment at parameter `t`.

17.11.7.1 Parameters

```
cubic-point(
  segment: dictionary,
  t: int float
) -> array
```

17.11.7.1.1 segment `dictionary`

Segment with `start`, `control-start`, `control-end`, and `end`.

17.11.7.1.2 t `int` or `float`

Segment parameter in the range `[0, 1]`.

17.11.8 cubic-tangent

Evaluate the tangent of a cubic segment at parameter `t`.

17.11.8.1 Parameters

```
cubic-tangent(
  segment: dictionary,
  t: int float
) -> array
```

17.11.8.1.1 segment `dictionary`

Segment with `start`, `control-start`, `control-end`, and `end`.

17.11.8.1.2 t `int` or `float`

Segment parameter in the range `[0, 1]`.

17.11.9 cubic-to

Build a `cubic` path element.

17.11.9.1 Parameters

```
cubic-to(
  control-start: array,
  control-end: array,
  end: array
) -> dictionary
```

17.11.9.1.1 control-start `array`

Cubic control point near the start point.

17.11.9.1.2 control-end `array`

Cubic control point near the endpoint.

17.11.9.1.3 end `array`

Cubic endpoint.

17.11.10 elements

Return the command elements that make up a Kurvst path.

17.11.10.1 Parameters

```
elements(path: dictionary) -> array
```

17.11.10.1.1 path `dictionary`

Kurvst path dictionary to inspect.

17.11.11 from-cubic

Build a path fragment from a cubic segment dictionary.

17.11.11.1 Parameters

```
from-cubic(segment: dictionary) -> dictionary
```

17.11.11.1.1 segment `dictionary`

Segment with `start`, `control-start`, `control-end`, and `end`.

17.11.12 from-elements

Build a path dictionary from an existing element array.

17.11.12.1 Parameters

```
from-elements(elements: array) -> dictionary
```

17.11.12.1.1 elements `array`

Array of Kurvst path elements.

17.11.13 hobby-spline

Construct a Hobby spline through an arbitrary point sequence.

17.11.13.1 Parameters

```
hobby-spline(
  points: array,
  omega: float,
  accuracy: float
) -> dictionary
```

17.11.13.1.1 points `array`

Two or more points for the open spline to pass through.

17.11.13.1.2 omega `float`

Hobby curl/tension parameter.

Default: `1.0`

17.11.13.1.3 accuracy `float`

Geometry approximation accuracy passed to the Rust geometry engine.

Default: `0.001`

17.11.14 hobby-through

Construct a cubic Hobby path through three points.

17.11.14.1 Parameters

```
hobby-through(
  start: array,
  through: array,
  end: array,
  omega: float,
  accuracy: float
) -> dictionary
```

17.11.14.1.1 start `array`

Start point.

17.11.14.1.2 through `array`

Intermediate point that the curve passes through.

17.11.14.1.3 end `array`

Endpoint.

17.11.14.1.4 omega `float`

Hobby curl/tension parameter.

Default: `1.0`

17.11.14.1.5 accuracy `float`

Geometry approximation accuracy passed to the Rust geometry engine.

Default: `0.001`

17.11.15 intersections

Find transverse crossings between two paths, sorted by arc distance along the first path.

17.11.15.1 Parameters

```
intersections(
  a: dictionary,
  b: dictionary,
  accuracy: float
) -> array
```

17.11.15.1.1 a `dictionary`

First Kurvst path dictionary.

17.11.15.1.2 b `dictionary`

Second Kurvst path dictionary.

17.11.15.1.3 accuracy `float`

Absolute geometry and arc-length tolerance.

Default: `0.001`

17.11.16 layer

Build a derived visible path layer.

17.11.16.1 Parameters

```
layer(
  path: dictionary,
  offset: int float,
  length: none int float,
  ratio: none int float,
  resolve-length: string function,
  shift: int float,
  start-outset: int float,
  end-outset: int float,
  side-point: none array,
  accuracy: float,
  optimize: bool
) -> dictionary
```

17.11.16.1.1 path `dictionary`

Base Kurvst path dictionary.

17.11.16.1.2 offset `int` or `float`

Signed normal offset distance.

Default: `0`

17.11.16.1.3 length `none` or `int` or `float`

Fixed target visible length.

Default: `none`

17.11.16.1.4 ratio `none` or `int` or `float`

Relative target visible length as a fraction of the full offset path length.

Default: `none`

17.11.16.1.5 resolve-length `string` or `function`

Resolution strategy for fixed and relative targets.

Default: `"min"`

17.11.16.1.6 shift `int` or `float`

Arc-length displacement on the offset path; positive moves toward its end.

Default: `0`

17.11.16.1.7 start-outset `int` or `float`

Arc length removed from the start.

Default: `0`

17.11.16.1.8 end-outset `int` or `float`

Arc length removed from the end.

Default: `0`

17.11.16.1.9 side-point `none` or `array`

Optional point used to choose the sign of `offset`.

Default: `none`

17.11.16.1.10 accuracy `float`

Geometry approximation accuracy passed to the Rust geometry engine.

Default: `0.001`

17.11.16.1.11 optimize `bool`

Let Kurbo simplify/optimize fitted parallel paths.

Default: `true`

17.11.17 length

Compute the arc length of a path dictionary.

17.11.17.1 Parameters

```
length(
  path: dictionary,
  accuracy: float
) -> int float
```

17.11.17.1.1 path `dictionary`

Kurvst path dictionary to measure.

17.11.17.1.2 accuracy `float`

Arc-length approximation accuracy passed to the Rust geometry engine.

Default: `0.001`

17.11.18 line

Build a straight-line path fragment.

17.11.18.1 Parameters

```
line(
  start: array,
  end: array
) -> dictionary
```

17.11.18.1.1 start `array`

Start point.

17.11.18.1.2 end `array`

Endpoint.

17.11.19 line-segment

Build a cubic segment dictionary for a straight line.

17.11.19.1 Parameters

```
line-segment(
  start: array,
  end: array
) -> dictionary
```

17.11.19.1.1 start `array`

Start point.

17.11.19.1.2 end `array`

Endpoint.

17.11.20 line-to

Build a `line` path element.

17.11.20.1 Parameters

```
line-to(end: array) -> dictionary
```

17.11.20.1.1 end `array`

Line endpoint.

17.11.21 move-to

Build a `move` path element.

17.11.21.1 Parameters

```
move-to(start: array) -> dictionary
```

17.11.21.1.1 start `array`

New current point and subpath start.

17.11.22 outline

Expand a stroked path into a closed outline that can be filled.

17.11.22.1 Parameters

```
outline(
  path: dictionary,
  width: int float,
  join: string,
  miter-limit: int float,
  cap: string,
  start-cap: auto string,
  end-cap: auto string,
  accuracy: float
) -> dictionary
```

17.11.22.1.1 path `dictionary`

Kurvst path dictionary to stroke.

17.11.22.1.2 width `int` or `float`

Stroke width in path units.

Default: `0.1`

17.11.22.1.3 join `string`

Corner join: `"miter"`, `"round"`, or `"bevel"`.

Default: `"miter"`

17.11.22.1.4 miter-limit `int` or `float`

Miter length limit as a multiple of the width; longer miters are beveled.

Default: `4`

17.11.22.1.5 cap `string`

End cap for both ends: `"butt"`, `"square"`, or `"round"`.

Default: `"butt"`

17.11.22.1.6 start-cap `auto` or `string`

Cap at each subpath start; `auto` uses `cap`.

Default: `auto`

17.11.22.1.7 end-cap `auto` or `string`

Cap at each subpath end; `auto` uses `cap`.

Default: `auto`

17.11.22.1.8 accuracy `float`

Curve fitting tolerance passed to the Rust geometry engine.

Default: `0.001`

17.11.23 outset-point

Return `from` moved toward `toward` by `distance`.

17.11.23.1 Parameters

```
outset-point(
  from: array,
  toward: array,
  distance: int float
) -> array
```

17.11.23.1.1 from `array`

Point to move.

17.11.23.1.2 toward `array`

Target point that defines the direction.

17.11.23.1.3 distance `int` or `float`

Distance to move from `from` toward `toward`.

Default: `0`

17.11.24 parallel

Generate a parallel path for a path.

17.11.24.1 Parameters

```
parallel(
  path: dictionary,
  distance: int float,
  start-outset: int float,
  end-outset: int float,
  accuracy: float,
  optimize: bool
) -> dictionary
```

17.11.24.1.1 path `dictionary`

Base Kurvst path dictionary.

17.11.24.1.2 distance `int` or `float`

Signed normal offset distance.

Default: `0`

17.11.24.1.3 start-outset `int` or `float`

Arc length removed from the start of the offset path.

Default: `0`

17.11.24.1.4 end-outset `int` or `float`

Arc length removed from the end of the offset path.

Default: `0`

17.11.24.1.5 accuracy `float`

Geometry approximation accuracy passed to the Rust geometry engine.

Default: `0.001`

17.11.24.1.6 optimize `bool`

Let Kurbo simplify/optimize the fitted path.

Default: `true`

17.11.25 path

Build a path dictionary from path fragments or elements.

17.11.25.1 Parameters

```
path(..parts: any) -> dictionary
```

17.11.25.1.1 ..parts `any`

Path fragments, path elements, or element arrays to concatenate.

17.11.26 pattern

Apply a repeated path pattern to a base path.

17.11.26.1 Parameters

```
pattern(
  path: dictionary,
  pattern: string dictionary,
  amplitude: int float,
  wavelength: int float,
  phase: int float,
  samples-per-period: int,
  coil-longitudinal-scale: int float,
  anchor-start: bool,
  anchor-end: bool,
  endpoint-slope: int float,
  accuracy: float,
  split-at: array
) -> dictionary
```

17.11.26.1.1 path `dictionary`

Base Kurvst path dictionary.

17.11.26.1.2 pattern `string` or `dictionary`

Pattern dictionary or built-in pattern name.

Default: `"wave"`

17.11.26.1.3 amplitude `int` or `float`

Normal amplitude of the pattern in path units.

Default: `0.1`

17.11.26.1.4 wavelength `int` or `float`

Arc length of one pattern period.

Default: `1.0`

17.11.26.1.5 phase `int` or `float`

Initial phase offset in radians.

Default: `0`

17.11.26.1.6 samples-per-period `int`

Samples per period for string-resolved patterns and smooth point-pattern mapping.

Default: `16`

17.11.26.1.7 coil-longitudinal-scale `int` or `float`

Longitudinal scale used when resolving the built-in coil pattern.

Default: `1.25`

17.11.26.1.8 anchor-start `bool`

Force the generated path to start on the base path.

Default: `true`

17.11.26.1.9 anchor-end `bool`

Force the generated path to end on the base path.

Default: `true`

17.11.26.1.10 endpoint-slope `int` or `float`

Initial slope of an anchored taper envelope, from 0 to 3. Zero keeps tangential ends; positive values allow angled ends when the pattern's lateral offset is nonzero at its endpoint phase. This is not an angle. Ignored for unanchored ends and patterns without endpoint ramping, including fitted coils.

Default: `0`

17.11.26.1.11 accuracy `float`

Geometry approximation accuracy passed to the Rust geometry engine.

Default: `0.001`

17.11.26.1.12 split-at `array`

Arc distances along `path` at which to cut the result into `parts`, one patterned path split into independently stylable pieces.

Default: `()`

17.11.27 point

Build a numeric point tuple.

17.11.27.1 Parameters

```
point(
  x: int float,
  y: int float
) -> array
```

17.11.27.1.1 x `int` or `float`

X coordinate.

17.11.27.1.2 y `int` or `float`

Y coordinate.

17.11.28 points

Return the points visited by a Kurvst path's command stream.

17.11.28.1 Parameters

```
points(path: dictionary) -> array
```

17.11.28.1.1 path `dictionary`

Kurvst path dictionary to inspect.

17.11.29 quad

Build a quadratic path fragment.

17.11.29.1 Parameters

```
quad(
  start: array,
  control: array,
  end: array
) -> dictionary
```

17.11.29.1.1 start `array`

Start point.

17.11.29.1.2 control `array`

Quadratic control point.

17.11.29.1.3 end `array`

Endpoint.

17.11.30 quad-to

Build a `quad` path element.

17.11.30.1 Parameters

```
quad-to(
  control: array,
  end: array
) -> dictionary
```

17.11.30.1.1 control `array`

Quadratic control point.

17.11.30.1.2 end `array`

Quadratic endpoint.

17.11.31 resolve-length

Resolve a fixed and relative visible path length.

17.11.31.1 Parameters

```
resolve-length(
  base-length: int float,
  length: none int float,
  ratio: none int float,
  method: string function
) -> none int float
```

17.11.31.1.1 base-length `int` or `float`

Full base path arc length.

17.11.31.1.2 length `none` or `int` or `float`

Fixed target arc length.

Default: `none`

17.11.31.1.3 ratio `none` or `int` or `float`

Relative target length as a fraction of `base-length`.

Default: `none`

17.11.31.1.4 method `string` or `function`

Resolution strategy for fixed and relative targets.

Default: `"min"`

17.11.32 segments

Return drawable cubic segments for any Kurvst path dictionary.

17.11.32.1 Parameters

```
segments(path: dictionary) -> array
```

17.11.32.1.1 path `dictionary`

Kurvst path dictionary to convert.

17.11.33 split-through

Split a path through a point sequence into per-span paths.

17.11.33.1 Parameters

```
split-through(
  points: array,
  omega: float,
  start-outset: int float,
  end-outset: int float,
  accuracy: float
) -> dictionary
```

17.11.33.1.1 points `array`

Two or more points for the curve to pass through.

17.11.33.1.2 omega `float`

Hobby curl/tension parameter.

Default: `1.0`

17.11.33.1.3 start-outset `int` or `float`

Arc length removed from the first span start.

Default: `0`

17.11.33.1.4 end-outset `int` or `float`

Arc length removed from the last span end.

Default: `0`

17.11.33.1.5 accuracy `float`

Geometry approximation accuracy passed to the Rust geometry engine.

Default: `0.001`

17.11.34 to-cetz

Draw a path dictionary through CeTZ.

17.11.34.1 Parameters

```
to-cetz(
  path: dictionary,
  unit: int float length ratio,
  ..style: any
) -> content
```

17.11.34.1.1 path `dictionary`

Kurvst path dictionary to draw.

17.11.34.1.2 unit `int` or `float` or `length` or `ratio`

Coordinate multiplier for emitted CeTZ points.

Default: `1`

17.11.34.1.3 ..style `any`

CeTZ draw style arguments forwarded to `merge-path`.

17.11.35 to-cetz-data

Emit a Kurvst path as CeTZ path data.

17.11.35.1 Parameters

```
to-cetz-data(
  path: dictionary,
  unit: int float length ratio
) -> array
```

17.11.35.1.1 path `dictionary`

Kurvst path dictionary to convert.

17.11.35.1.2 unit `int` or `float` or `length` or `ratio`

Coordinate multiplier for emitted CeTZ points.

Default: 1

17.11.36 to-native

Emit a Kurvst path as native Typst `curve` content.

17.11.36.1 Parameters

```
to-native(
  path: dictionary,
  unit: int float length ratio,
  ..style: any
) -> content
```

17.11.36.1.1 path `dictionary`

Kurvst path dictionary to emit.

17.11.36.1.2 unit `int` or `float` or `length` or `ratio`

Coordinate multiplier for emitted Typst curve points.

Default: 1

17.11.36.1.3 ..style `any`

Native `curve` style arguments.

17.11.37 trim

Trim a path by arc length from each end.

17.11.37.1 Parameters

```
trim(
  path: dictionary,
  start-outset: int float,
  end-outset: int float,
  accuracy: float
) -> dictionary
```

17.11.37.1.1 path `dictionary`

Kurvst path dictionary to trim.

17.11.37.1.2 start-outset `int` or `float`

Arc length removed from the start.

Default: `0`

17.11.37.1.3 end-outset `int` or `float`

Arc length removed from the end.

Default: `0`

17.11.37.1.4 accuracy `float`

Arc-length approximation accuracy passed to the Rust geometry engine.

Default: `0.001`

17.11.38 wave

A smooth sinusoidal path pattern.

17.11.38.1 Parameters

```
wave(samples-per-period: int) -> dictionary
```

17.11.38.1.1 samples-per-period `int`

Number of samples used to approximate one wave period.

Default: `16`

17.11.39 zigzag

A straight-segment triangular path pattern.

17.11.39.1 Parameters

```
zigzag() -> dictionary
```

`dictionary`

17.11.40 layer-defaults

Default geometry options for derived path layers.

18 Version history

> **History coverage**
> GammaLoop does not yet have a consolidated changelog. Repository tags and their linked pull requests are the available release record. This page makes that gap explicit instead of presenting development documentation as a complete release history.

18.1 Components and version sources

- Repository revision: GammaLoop tags and releases.
- Python distribution: pyproject.toml.
- Core Rust library: gammalooprs package metadata.
- Rust/Python application API: gammaloop-api package metadata.

These components can evolve independently. Record all of them when reporting a result or asking for support.

18.2 Choosing the matching documentation

The `latest` channel follows current development. Documentation under `snapshots/<tag>` stays with a tagged release. Use the snapshot matching your checkout whenever command options, state files, or API signatures differ from `latest`.

18.3 Upgrade checklist

Release notes currently live with repository tags and their linked pull requests rather than in one consolidated changelog. Review them before upgrading, especially when you depend on persisted states, CLI scripts, Python bindings, or numerical results. Keep a copy of valuable state directories and re-run validation samples after changing versions.

18.4 Reproducibility record

Include the repository tag or commit, the Python distribution version, the `gammalooprs` version, the run card, and any relevant settings overrides. This makes a calculation easier to reproduce and distinguishes a software change from a configuration change.

Python API reference

The supported Python packages available in this version are listed below. The HTML manual provides a separate page for every public class, function, and constant; this printable edition keeps a compact inventory. Rust APIs use canonical Rustdoc in the HTML manual.

`gammaloop-python`

`Exports registered by gammaloop.`

`AdditionalWeight`

`Named auxiliary complex weight attached to a generated event.`

`Named auxiliary complex weight attached to a generated event.`

```
class AdditionalWeight:
```

Requires features: `python, abi3, python-stubs`

`key`

Kind: `Getter`

```
def key(self) -> str:
```

`Stable weight name, optionally followed by colon-separated identifiers.`

`value`

Kind: `Getter`

```
def value(self) -> Any:
```

`Complex auxiliary event weight associated with ``key``.`

Exhaustive reference · Source

`BatchEvaluationResult`

`One evaluation record per input sample, plus optional batch stability diagnostics.`

`One evaluation record per input sample, plus optional batch stability diagnostics.`

```
class BatchEvaluationResult:
```

Requires features: `python, abi3, python-stubs`

`samples`

Kind: `Getter`

```
def samples(self) -> list[EvaluationResult]:
```

`Evaluation records in the same order as the requested samples.`

`numerical_stability`

Kind: `Getter`

```
def numerical_stability(self) -> Optional[dict]:
```

`__str__`

Kind: `Method`

```
def __str__(self) -> str:
```

`Return a human-readable per-sample batch summary.`

`__repr__`

Kind: `Method`

```
def __repr__(self) -> str:
```

Return the human-readable per-sample batch summary.

Exhaustive reference · Source

CutInfo

Process, graph, orientation, and loop-basis identifiers for one cut event.

Process, graph, orientation, and loop-basis identifiers for one cut event.

```
class CutInfo:
```

Requires features: `python, abi3, python-stubs`

incoming_pdgs

Kind: Getter

```
def incoming_pdgs(self) -> list[int]:
```

PDG identifiers aligned with ``Event.incoming_momenta``.

outgoing_pdgs

Kind: Getter

```
def outgoing_pdgs(self) -> list[int]:
```

PDG identifiers aligned with ``Event.outgoing_momenta``.

cut_id

Kind: Getter

```
def cut_id(self) -> int:
```

Zero-based cut identifier within the selected graph.

graph_id

Kind: Getter

```
def graph_id(self) -> int:
```

Zero-based graph identifier within the integrand.

graph_group_id

Kind: Getter

```
def graph_group_id(self) -> Optional[int]:
```

Graph-group identifier, when group metadata is available.

orientation_id

Kind: Getter

```
def orientation_id(self) -> Optional[int]:
```

Causal-flow orientation identifier, when sampled explicitly.

sampling_channel_id

Kind: Getter

```
def sampling_channel_id(self) -> Optional[int]:
```

Canonical sampling channel identifier, when sampled explicitly.

sampling_channel_edge_ids

Kind: Getter

```
def sampling_channel_edge_ids(self) -> Optional[list[int]]:
```

Edge identifiers defining the selected sampling channel basis, when available.

Exhaustive reference · Source

DotExportSettings

Controls which graph details and algebraic transformations are included in DOT exports.

Controls which graph details and algebraic transformations are included in DOT exports.

```
class DotExportSettings:
```

Requires features: `python, abi3, python-stubs`

combine_diagrams

Kind: Getter

```
def combine_diagrams(self) -> bool:
```

Write all diagrams of an integrand to one file during filesystem export.

combine_diagrams

Kind: Setter

```
def combine_diagrams(self, value: bool) -> None:
```

Write all diagrams of an integrand to one file during filesystem export.

value

Kind: Parameter

```
bool
```

with_uv

Kind: Getter

```
def with_uv(self) -> bool:
```

Request UV counterterm graph output; currently retained for compatibility.

with_uv

Kind: Setter

```
def with_uv(self, value: bool) -> None:
```

Request UV counterterm graph output; currently retained for compatibility.

value

Kind: Parameter

```
bool
```

output_full_numerator

Kind: Getter

```
def output_full_numerator(self) -> bool:
```

Add the complete symbolic numerator as the graph-level `full_num` field.

output_full_numerator

Kind: Setter

```
def output_full_numerator(self, value: bool) -> None:
```

Add the complete symbolic numerator as the graph-level `full_num` field.

value

Kind: Parameter

```
bool
```

split_xs_by_initial_states

Kind: Getter

```
def split_xs_by_initial_states(self) -> bool:
```

Split cross-section graphs by distinct initial-state assignments.

split_xs_by_initial_states

Kind: Setter

```
def split_xs_by_initial_states(self, value: bool) -> None:
```

Split cross-section graphs by distinct initial-state assignments.

value

Kind: Parameter

```
bool
```

do_gamma_algebra

Kind: Getter

```
def do_gamma_algebra(self) -> bool:
```

Simplify gamma-matrix algebra in the full numerator before formatting it.

do_gamma_algebra

Kind: Setter

```
def do_gamma_algebra(self, value: bool) -> None:
```

Simplify gamma-matrix algebra in the full numerator before formatting it.

value

Kind: Parameter

```
bool
```

do_color_algebra

Kind: Getter

```
def do_color_algebra(self) -> bool:
```

Simplify color algebra in the full numerator before formatting it.

do_color_algebra

Kind: Setter

```
def do_color_algebra(self, value: bool) -> None:
```

Simplify color algebra in the full numerator before formatting it.

value

Kind: Parameter

bool

include_autogenerated_fields

Kind: Getter

def include_autogenerated_fields(self) -> bool:

Include vertex and edge fields whose values GammaLoop generated automatically.

include_autogenerated_fields

Kind: Setter

def include_autogenerated_fields(self, value: bool) -> None:

Include vertex and edge fields whose values GammaLoop generated automatically.

value

Kind: Parameter

bool

__new__

Kind: AssociatedFunction

def __new__(cls) -> DotExportSettings:

Construct DOT export settings with GammaLoop's defaults.

Exhaustive reference · Source

EvaluationResult

Numerical value, metadata, stability records, and generated events for one sample.

Numerical value, metadata, stability records, and generated events for one sample.

class EvaluationResult:

Requires features: python, abi3, python-stubs

integrand_result

Kind: Getter

def integrand_result(self) -> complex:

Complex physical contribution including map Jacobians and channel partitions, before the outer-grid weight.

absolute_integrand_result

Kind: Getter

def absolute_integrand_result(self) -> Optional[complex]:

Componentwise absolute physical contributions summed over channel points, before the outer-grid weight.

integrator_weight

Kind: Getter

def integrator_weight(self) -> float:

Monte Carlo weight supplied by the integrator, excluding the parameterization
Jacobian.

generated_event_count

Kind: Getter

def generated_event_count(self) -> Optional[int]:

Number of candidate events generated, or ``None`` when metadata was omitted.

accepted_event_count

Kind: Getter

def accepted_event_count(self) -> Optional[int]:

Number of generated events accepted by selectors, or ``None`` without metadata.

event_processing_time_seconds

Kind: Getter

def event_processing_time_seconds(self) -> Optional[float]:

Time spent building and selecting events, in seconds, or ``None`` without metadata.

parameterization_jacobian

Kind: Getter

def parameterization_jacobian(self) -> Optional[float]:

Sample parameterization Jacobian, or ``None`` when no Jacobian was supplied.

is_nan

Kind: Getter

def is_nan(self) -> Optional[bool]:

Whether evaluation metadata flagged a non-finite result, or ``None`` without
metadata.

stability_results

Kind: Getter

def stability_results(self) -> Optional[list[StabilityResult]]:

Ordered stability-level attempts, or ``None`` when metadata was omitted.
Each attempt records its precision and representation; precision may repeat.

event_groups

Kind: Getter

def event_groups(self) -> list[EventGroup]:

All correlated event groups for this sample, before the outer sampler weight.

__str__

Kind: Method

def __str__(self) -> str:

Return a human-readable evaluation summary.

__repr__

Kind: Method

```
def __repr__(self) -> str:
```

Return the human-readable evaluation summary.

Exhaustive reference · Source

Event

Accepted cut event with momenta, its primary weight, and auxiliary weights.

Accepted cut event with momenta, its primary weight, and auxiliary weights.

```
class Event:
```

Requires features: `python, abi3, python-stubs`

incoming_momenta

Kind: Getter

```
def incoming_momenta(self) -> list[FourMomentum]:
```

Incoming four-momenta, aligned with ``cut_info.incoming_pdgs``.

outgoing_momenta

Kind: Getter

```
def outgoing_momenta(self) -> list[FourMomentum]:
```

Outgoing four-momenta, aligned with ``cut_info.outgoing_pdgs``.

cut_info

Kind: Getter

```
def cut_info(self) -> CutInfo:
```

Cut, graph, orientation, and loop-basis identifiers for this event.

weight

Kind: Getter

```
def weight(self) -> Any:
```

Primary complex event weight.

additional_weights

Kind: Getter

```
def additional_weights(self) -> list[AdditionalWeight]:
```

Named auxiliary complex weights such as threshold-counterterm contributions.

threshold_counterterms

Kind: Getter

```
def threshold_counterterms(self) -> Optional[ThresholdCountertermEventInfo]:
```

Addable threshold decomposition with physical occurrence metadata, when retained.

__str__

Kind: Method

```
def __str__(self) -> str:
```

Return a human-readable event summary.

__repr__
Kind: `Method`

```
def __repr__(self) -> str:
```

Return the human-readable event summary.

Exhaustive reference · Source

EventGroup
Correlated accepted events produced by one graph group for one sample.

Correlated accepted events produced by one graph group for one sample.

```
class EventGroup:
```

Requires features: `python, abi3, python-stubs`

events
Kind: `Getter`

```
def events(self) -> list[Event]:
```

Correlated accepted events in this group.

__str__
Kind: `Method`

```
def __str__(self) -> str:
```

Return a human-readable summary of the grouped events.

__repr__
Kind: `Method`

```
def __repr__(self) -> str:
```

Return the human-readable grouped-event summary.

Exhaustive reference · Source

FourMomentum
One energy-momentum four-vector returned with a generated event.

One energy-momentum four-vector returned with a generated event.

```
class FourMomentum:
```

Requires features: `python, abi3, python-stubs`

e
Kind: `Getter`

```
def e(self) -> float:
```

Energy component.

px
Kind: `Getter`

```
def px(self) -> float:
```

Momentum along the x axis.

py
Kind: `Getter`

```
def py(self) -> float:
```

```
Momentum along the y axis.
```

pz

Kind: `Getter`

```
def pz(self) -> float:
```

```
Momentum along the z axis.
```

Exhaustive reference · Source

GammaLoopAPI

```
Load, inspect, and evaluate one mutable GammaLoop session.
```

```
Load, inspect, and evaluate one mutable GammaLoop session.

One instance owns a GammaLoop state, run history, CLI settings, default runtime
settings, and session state. Calls to ``run`` and the evaluation methods all act
on that same in-memory session.

Notes
-----
``read_only_state=True`` prevents writes inside the active state directory; it
does not make this Python object immutable. Commands may still change in-memory
settings, processes, or run history. Create separate instances when independent
sessions are required.
```

```
class GammaLoopAPI:
```

Requires features: `python, abi3, python-stubs`

read_only_state

Kind: `Getter`

```
def read_only_state(self) -> bool:
```

active_state_folder

Kind: `Getter`

```
def active_state_folder(self) -> str:
```

__new__

Kind: `AssociatedFunction`

```
def __new__(cls, state_folder: Optional[str | os.PathLike | pathlib.Path] = None,
boot_commands_path: Optional[str | os.PathLike | pathlib.Path] = None, model_file:
Optional[str | os.PathLike | pathlib.Path] = None, trace_logs_filename: Optional[str]
= None, level: Optional[LogLevel] = None, logfile_level: Optional[LogLevel] = None,
logging_prefix: object | None = None, read_only_state: bool = False,
settings_global_path: Optional[str | os.PathLike | pathlib.Path] = None,
settings_runtime_defaults_path: Optional[str | os.PathLike | pathlib.Path] = None,
clean_state: bool = False, processes: Optional[Sequence[str]] = None, integrands:
Optional[Sequence[str]] = None) -> GammaLoopAPI:
```

```
Load or create a GammaLoop state and initialize its CLI session.

Parameters
----------
state_folder : path-like, optional
```

```
    State directory to load or create. The default is ``./gammaloop_state``.
boot_commands_path : path-like, optional
    TOML run card whose commands are applied during startup.
model_file : path-like, optional
    Model file override used while loading or initializing the state.
trace_logs_filename : str, optional
    File receiving native trace records for this session.
level : LogLevel, optional
    Terminal log-level override for this session.
logfile_level : LogLevel, optional
    File log-level override for this session.
logging_prefix : object, optional
    Native logging-prefix configuration.
read_only_state : bool, default=False
    Prevent writes whose target lies inside the active state directory and
    disable file logging there. In-memory session changes remain possible.
settings_global_path : path-like, optional
    TOML file overriding the global settings loaded at startup.
settings_runtime_defaults_path : path-like, optional
    TOML file overriding the default runtime settings loaded at startup.
clean_state : bool, default=False
    Remove the resolved state path before startup. This is destructive and
    cannot be combined with ``read_only_state=True``.

Returns
-------
GammaLoopAPI
    A stateful API instance sharing one state, history, and settings session.

Raises
------
Exception
    If startup options conflict, the state or settings cannot be loaded, a
    boot command fails, or a boot card requests process exit.

Examples
--------
Open an existing generated state without permitting writes to it:

```python
api = GammaLoopAPI(state_folder="./state", read_only_state=True)
```
```

state_folder

Kind: Parameter

```
Optional[str | os.PathLike | pathlib.Path]
```

Default: None

```
State directory to load or create. The default is ``./gammaloop_state``.
```

boot_commands_path

Kind: Parameter

```
Optional[str | os.PathLike | pathlib.Path]
```

Default: None

TOML run card whose commands are applied during startup.

model_file
Kind: Parameter

Optional[str | os.PathLike | pathlib.Path]

Default: None

Model file override used while loading or initializing the state.

trace_logs_filename
Kind: Parameter

Optional[str]

Default: None

File receiving native trace records for this session.

level
Kind: Parameter

Optional[LogLevel]

Default: None

Terminal log-level override for this session.

logfile_level
Kind: Parameter

Optional[LogLevel]

Default: None

File log-level override for this session.

logging_prefix
Kind: Parameter

object | None

Default: None

Native logging-prefix configuration.

read_only_state
Kind: Parameter

bool

Default: False

Prevent writes whose target lies inside the active state directory and disable file logging there. In-memory session changes remain possible.

settings_global_path
Kind: Parameter

Optional[str | os.PathLike | pathlib.Path]

Default: None

TOML file overriding the global settings loaded at startup.

settings_runtime_defaults_path

Kind: Parameter

Optional[str | os.PathLike | pathlib.Path]

Default: None

TOML file overriding the default runtime settings loaded at startup.

clean_state

Kind: Parameter

bool

Default: False

Remove the resolved state path before startup. This is destructive and cannot be combined with ``read_only_state=True``.

processes

Kind: Parameter

Optional[Sequence[str]]

Default: None

integrands

Kind: Parameter

Optional[Sequence[str]]

Default: None

is_read_only_state

Kind: Method

def is_read_only_state(self) -> bool:

state_access_mode

Kind: Method

def state_access_mode(self) -> str:

observable_accumulator

Kind: Method

def observable_accumulator(self, process_id: Optional[int] = None, integrand_name: Optional[str] = None) -> ObservableAccumulator:

Create empty observable statistics for the selected integrand.
Evaluation itself never commits observable moments. See ``ObservableAccumulator``.

process_id

Kind: Parameter

Optional[int]

Default: None

integrand_name

Kind: Parameter

Optional[str]

Default: None

evaluate_sample

Kind: Method

```
def evaluate_sample(self, point: Sequence[float], process_id: Optional[int] = None,
integrand_name: Optional[str] = None, use_arb_prec: bool = False, minimal_output:
bool = False, return_events: Optional[bool] = None, momentum_space: bool = False,
integrator_weight: Optional[float] = None, discrete_dim: Optional[Sequence[int]] =
None, graph_name: Optional[str] = None, orientation: Optional[int] = None) ->
EvaluationResult:
```

```
Evaluate one integration or momentum-space sample.

Parameters
----------
point : Sequence[float]
    Coordinates for one sample. In integration space, the length must match
    the selected integrand and ``discrete_dim``. In momentum space, values
    are grouped as ``(px, py, pz)`` with one triplet per independent loop
    momentum. Energy components and external momenta are not accepted.
process_id : int, optional
    Process containing the integrand. Supply this when selection is ambiguous.
integrand_name : str, optional
    Integrand to evaluate. Supply this when selection is ambiguous.
use_arb_prec : bool, default=False
    Force arbitrary-precision (Arb) internal evaluation instead of following
    the configured stability ladder.
    Returned numeric fields remain ``float64``.
minimal_output : bool, default=False
    Omit the optional evaluation metadata from the returned sample.
return_events : bool, optional
    Temporarily override event generation for this call. The integrand setting
    is restored afterward.
momentum_space : bool, default=False
    Interpret ``point`` as consecutive spatial loop-momentum ``(px, py, pz)``
    triplets instead of integration-space coordinates.
integrator_weight : float, optional
    Weight associated with this sample. The default is 1.0.
discrete_dim : Sequence[int], optional
    Discrete integration coordinates used to determine the expected dimension.
graph_name : str, optional
    Graph selected for momentum-space evaluation.
orientation : int, optional
    Orientation index for ``graph_name`` in momentum-space evaluation.

Returns
-------
EvaluationResult
    One independent sample, with an unweighted contribution for configured
observables.

Raises
```

```
------
Exception
    If integrand selection is ambiguous or invalid, dimensions do not match,
    graph or orientation selection is invalid, or warm-up/evaluation fails.

Notes
-----
With ``use_arb_prec=False``, evaluation follows the configured ``f64``,
``f128``, and arbitrary-precision stability ladder. ``use_arb_prec=True``
forces arbitrary-precision (Arb) internal evaluation. Python-visible numeric
fields use the package's ``float64`` output contract. Evaluation may
warm the integrand and update in-memory caches even in a read-only-state
session. Observable statistics change only through explicit accumulation.

See Also
--------
GammaLoop's sample-evaluation contract in the interface guide and the
maintained events-and-observables example.

Examples
--------
Evaluate one point from the repository's differential API regression fixture:

```python
from pathlib import Path

from gammaloop import GammaLoopAPI

example = Path("examples/api/python/epem_a_ddxg_xs_LO")
api = GammaLoopAPI(
    state_folder=example / "state",
    boot_commands_path=example / "run.toml",
    clean_state=True,
)
point = [0.17, 0.31, 0.53, 0.23, 0.41, 0.67]
result = api.evaluate_sample(point, return_events=True)
assert result.parameterization_jacobian is not None
assert result.stability_results
assert result.event_groups
```

This card verifies API and event plumbing. Its powered coupling selector is not an
independently reviewed perturbative-order definition or normalization benchmark.
```

point

Kind: Parameter

Sequence[float]

Coordinates for one sample. In integration space, the length must match the selected integrand and ``discrete_dim``. In momentum space, values are grouped as ``(px, py, pz)`` with one triplet per independent loop momentum. Energy components and external momenta are not accepted.

process_id

Kind: Parameter

Optional[int]

Default: None

Process containing the integrand. Supply this when selection is ambiguous.

integrand_name

Kind: Parameter

Optional[str]

Default: None

Integrand to evaluate. Supply this when selection is ambiguous.

use_arb_prec

Kind: Parameter

bool

Default: False

Force arbitrary-precision (Arb) internal evaluation instead of following the configured stability ladder. Returned numeric fields remain ``float64``.

minimal_output

Kind: Parameter

bool

Default: False

Omit the optional evaluation metadata from the returned sample.

return_events

Kind: Parameter

Optional[bool]

Default: None

Temporarily override event generation for this call. The integrand setting is restored afterward.

momentum_space

Kind: Parameter

bool

Default: False

Interpret ``point`` as consecutive spatial loop-momentum ``(px, py, pz)`` triplets instead of integration-space coordinates.

integrator_weight

Kind: Parameter

Optional[float]

Default: None

Weight associated with this sample. The default is 1.0.

discrete_dim

Kind: Parameter

Optional[Sequence[int]]

Default: None

Discrete integration coordinates used to determine the expected dimension.

graph_name

Kind: Parameter

Optional[str]

Default: None

Graph selected for momentum-space evaluation.

orientation

Kind: Parameter

Optional[int]

Default: None

Orientation index for ``graph_name`` in momentum-space evaluation.

evaluate_samples

Kind: Method

```
def evaluate_samples(self, points: numpy.NDArray[numpy.float64], process_id:
Optional[int] = None, integrand_name: Optional[str] = None, use_arb_prec: bool =
False, minimal_output: bool = False, return_events: Optional[bool] = None,
momentum_space: bool = False, integrator_weights:
Optional[numpy.NDArray[numpy.float64]] = None, discrete_dims:
numpy.NDArray[numpy.unsignedinteger] | None = None, graph_names:
Optional[Sequence[Optional[str]]] = None, orientations:
Optional[Sequence[Optional[int]]] = None) -> BatchEvaluationResult:
```

Evaluate a batch of integration or momentum-space samples.

```
Parameters
----------
points : numpy.ndarray[numpy.float64]
    Two-dimensional array with one sample per row. Integration-space columns
    must match the selected integrand; momentum-space columns are flattened
    ``(px, py, pz)`` groups with one triplet per independent loop momentum.
    Energy components and external momenta are not accepted.
process_id : int, optional
    Process containing the integrand. Supply this when selection is ambiguous.
integrand_name : str, optional
    Integrand to evaluate. Supply this when selection is ambiguous.
use_arb_prec : bool, default=False
    Force arbitrary-precision (Arb) internal evaluation instead of following
    the configured stability ladder.
    Returned numeric fields remain ``float64``.
minimal_output : bool, default=False
    Omit the optional evaluation metadata from every returned sample.
return_events : bool, optional
    Temporarily override event generation for this call. The integrand setting
    is restored afterward.
momentum_space : bool, default=False
    Interpret each row as consecutive spatial loop-momentum ``(px, py, pz)``
```

```
    triplets instead of integration-space coordinates.
integrator_weights : numpy.ndarray[numpy.float64], optional
    One weight per row. Defaults to 1.0 for every sample.
discrete_dims : numpy.ndarray[numpy.unsignedinteger], optional
    Two-dimensional array with one row of discrete coordinates per sample.
graph_names : Sequence[str | None], optional
    Momentum-space graph selection for each sample.
orientations : Sequence[int | None], optional
    Momentum-space orientation selection for each sample.

Returns
-------
BatchEvaluationResult
    One evaluation per input sample and optional numerical-stability diagnostics.

Raises
------
Exception
    If integrand selection is ambiguous or invalid, array or option lengths do
    not match, dimensions are invalid, or warm-up/evaluation fails.

Notes
-----
With ``use_arb_prec=False``, evaluation follows the configured ``f64``,
``f128``, and arbitrary-precision stability ladder. ``use_arb_prec=True``
forces arbitrary-precision (Arb) internal evaluation. Python-visible numeric
fields use the package's ``float64`` output contract. Evaluation may
update numerical caches; observable statistics change only through explicit
accumulation.

See Also
--------
GammaLoop's sample-evaluation contract in the interface guide and the
maintained events-and-observables example.

Examples
--------
Evaluate two rows and explicitly accumulate their correlated observable
contributions:

```python
from pathlib import Path

import numpy as np
from gammaloop import GammaLoopAPI

example = Path("examples/api/python/epem_a_ddxg_xs_LO")
api = GammaLoopAPI(
    state_folder=example / "state",
    boot_commands_path=example / "run.toml",
    clean_state=True,
)
points = np.array([
    [0.17, 0.31, 0.53, 0.23, 0.41, 0.67],
    [0.11, 0.29, 0.47, 0.19, 0.37, 0.59],
], dtype=float)
```
```

```
result = api.evaluate_samples(points, return_events=True)
assert len(result.samples) == 2
assert all(sample.event_groups for sample in result.samples)
accumulator = api.observable_accumulator()
for sample in result.samples:
    accumulator.add_sample(sample, sample.integrator_weight)
histograms = accumulator.snapshot()
assert histograms["leading_jet_pt_hist"].sample_count == 2
assert len(histograms["leading_jet_pt_hist"].bins) == 8
```

The fixture exercises the API surface; its powered coupling selector is not a validated
perturbative-order or normalization benchmark.

points

Kind: Parameter

numpy.NDArray[numpy.float64]

Two-dimensional array with one sample per row. Integration-space columns must match the selected integrand; momentum-space columns are flattened ``(px, py, pz)`` groups with one triplet per independent loop momentum. Energy components and external momenta are not accepted.

process_id

Kind: Parameter

Optional[int]

Default: None

Process containing the integrand. Supply this when selection is ambiguous.

integrand_name

Kind: Parameter

Optional[str]

Default: None

Integrand to evaluate. Supply this when selection is ambiguous.

use_arb_prec

Kind: Parameter

bool

Default: False

Force arbitrary-precision (Arb) internal evaluation instead of following the configured stability ladder. Returned numeric fields remain ``float64``.

minimal_output

Kind: Parameter

bool

Default: False

Omit the optional evaluation metadata from every returned sample.

return_events

Kind: Parameter

Optional[bool]

Default: None

Temporarily override event generation for this call. The integrand setting is restored afterward.

momentum_space

Kind: Parameter

bool

Default: False

Interpret each row as consecutive spatial loop-momentum ``(px, py, pz)`` triplets instead of integration-space coordinates.

integrator_weights

Kind: Parameter

Optional[numpy.NDArray[numpy.float64]]

Default: None

One weight per row. Defaults to 1.0 for every sample.

discrete_dims

Kind: Parameter

numpy.NDArray[numpy.unsignedinteger] | None

Default: None

Two-dimensional array with one row of discrete coordinates per sample.

graph_names

Kind: Parameter

Optional[Sequence[Optional[str]]]

Default: None

Momentum-space graph selection for each sample.

orientations

Kind: Parameter

Optional[Sequence[Optional[int]]]

Default: None

Momentum-space orientation selection for each sample.

import_graphs

Kind: Method

def import_graphs(self, graphs: str, process_name: Optional[str] = None, process_id: Optional[int] = None, integrand_name: Optional[str] = None, format: str = 'dot', overwrite: bool = False, append: bool = False) -> None:

```
Import DOT graphs into a new or existing process/integrand collection.

Parameters
----------
graphs : str
    DOT file path when ``format="dot"`` or inline DOT text when
    ``format="string"``.
process_name, process_id : str or int, optional
    Process to create or update. Inline text requires one of these selectors.
integrand_name : str, optional
    Integrand within the selected process.
format : {"dot", "string"}, default="dot"
    Select file-backed or inline input.
overwrite, append : bool, default=False
    Replace an existing collection or append to it; these modes conflict.

Raises
------
Exception
    If selectors conflict, the source is missing or malformed, or importing fails.
```

graphs

Kind: Parameter

`str`

DOT file path when ``format="dot"`` or inline DOT text when ``format="string"``.

process_name

Kind: Parameter

`Optional[str]`

Default: `None`

Process to create or update. Inline text requires one of these selectors.

process_id

Kind: Parameter

`Optional[int]`

Default: `None`

Process to create or update. Inline text requires one of these selectors.

integrand_name

Kind: Parameter

`Optional[str]`

Default: `None`

Integrand within the selected process.

format

Kind: Parameter

`str`

Default: `'dot'`

Select file-backed or inline input.

overwrite

Kind: Parameter

bool

Default: False

Replace an existing collection or append to it; these modes conflict.

append

Kind: Parameter

bool

Default: False

Replace an existing collection or append to it; these modes conflict.

get_lmbs

Kind: Method

```
def get_lmbs(self, graphs: str, format: str = 'dot') -> list[list[tuple[list[int],
list[int], dict[int, tuple[list[int], list[int]]]]]]:
```

Generate loop-momentum bases for each supplied graph.

```
Parameters
----------
graphs : str
    DOT file path or inline DOT text, as selected by ``format``.
format : {"dot", "string"}, default="dot"
    Select file-backed or inline input.

Returns
-------
list
    Per graph, a list of ``(loop_edges, external_edges, edge_signatures)``
    tuples. Each signature contains its loop and external coefficients.
```

graphs

Kind: Parameter

str

DOT file path or inline DOT text, as selected by ``format``.

format

Kind: Parameter

str

Default: 'dot'

Select file-backed or inline input.

get_residue_map

Kind: Method

```
def get_residue_map(self, graph_name: str, process_id: Optional[int] = None,
integrand_name: Optional[str] = None, three_dimensional_representation: Optional[str]
= None) -> ResidueMap:
```

Return a detached snapshot of one graph's persisted native residue map.

Keys retain the complete direction vector and exact ordered affine loop and
edge energy maps. Values retain every native residue ID and all scalar
variants, with exact Fraction coefficients and unexpanded denominator trees.
This is graph-level generation data, not the evaluated UV/threshold catalogue.

Parameters
---
graph_name : str
    Name of the graph within the selected integrand.
process_id : int, optional
    Numeric process identifier; omit when process selection is unambiguous.
integrand_name : str, optional
    Integrand containing the graph; omit when selection is unambiguous.
three_dimensional_representation : str, optional
    ``cff`` or ``ltd``; defaults to the first representation generated for
    this integrand, independently of current mutable generation settings.

Returns

ResidueMap
    Detached native entries, shared surfaces and persisted normalization metadata.

Raises

ValueError
    If the graph or representation is unavailable or the integrand is ungenerated.

graph_name

Kind: Parameter

str

Name of the graph within the selected integrand.

process_id

Kind: Parameter

Optional[int]

Default: None

Numeric process identifier; omit when process selection is unambiguous.

integrand_name

Kind: Parameter

Optional[str]

Default: None

Integrand containing the graph; omit when selection is unambiguous.

three_dimensional_representation

Kind: Parameter

Optional[str]

Default: None

``cff`` or ``ltd``; defaults to the first representation generated for this integrand, independently of current mutable generation settings.

get_model

Kind: Method

```
def get_model(self) -> str:
```

Serialize the active physics model as JSON.

```
Returns
-------
str
    JSON representation of the model currently owned by this session.
```

evaluate

Kind: Method

```
def evaluate(self, process_id: Optional[int] = None, graphs_group_name: Optional[str]
= None, result_path: Optional[str | os.PathLike | pathlib.Path] = None, numerical:
bool = True, number_of_terms_in_epsilon_expansion: Optional[int] = None) -> str:
```

Evaluate one generated graph group as a symbolic or numerical expression.

```
Parameters
----------
process_id : int, optional
    Process containing the requested graph group.
graphs_group_name : str, optional
    Group to evaluate when the current state is ambiguous.
result_path : path-like, optional
    Optional destination for the evaluated expression.
numerical : bool, default=True
    Evaluate numerically instead of retaining a symbolic result.
number_of_terms_in_epsilon_expansion : int, optional
    Truncate the dimensional-regulator expansion to this many terms.

Returns
-------
str
    Canonical Symbolica representation of the result.
```

process_id

Kind: Parameter

Optional[int]

Default: None

Process containing the requested graph group.

graphs_group_name

Kind: Parameter

Optional[str]

Default: None

Group to evaluate when the current state is ambiguous.

result_path

Kind: Parameter

Optional[str | os.PathLike | pathlib.Path]

Default: None

Optional destination for the evaluated expression.

numerical

Kind: Parameter

bool

Default: True

Evaluate numerically instead of retaining a symbolic result.

number_of_terms_in_epsilon_expansion

Kind: Parameter

Optional[int]

Default: None

Truncate the dimensional-regulator expansion to this many terms.

import_model

Kind: Method

```
def import_model(self, model_specifier: str | os.PathLike | pathlib.Path,
simplify_model: bool = True) -> None:
```

Replace the active model from a GammaLoop model file or supported model source.

``simplify_model`` applies the standard symbolic simplification pass while importing. Existing process data may no longer be compatible with a replaced model, so import the model before generating processes.

```
Parameters
----------
model_specifier : path-like
    Path or model specifier accepted by GammaLoop's model importer.
simplify_model : bool, default=True
    Apply the standard symbolic simplification pass while importing.
```

model_specifier

Kind: Parameter

str | os.PathLike | pathlib.Path

Path or model specifier accepted by GammaLoop's model importer.

simplify_model

Kind: Parameter

bool

Default: True

Apply the standard symbolic simplification pass while importing.

list_outputs

Kind: Method

```
def list_outputs(self) -> tuple[dict[str, int], dict[str, int]]:
```

List generated amplitude and cross-section names with their process ids.

```
Returns
-------
tuple[dict[str, int], dict[str, int]]
    Amplitude mapping followed by the cross-section mapping.
```

get_integrand_info

Kind: Method

```
def get_integrand_info(self, process_id: Optional[int] = None, integrand_name:
Optional[str] = None) -> IntegrandInfo:
```

Describe the selected generated integrand and its graph structure.

```
Parameters
----------
process_id : int, optional
    Process containing the integrand. Supply this when selection is ambiguous.
integrand_name : str, optional
    Integrand to inspect. Supply this when selection is ambiguous.

Returns
-------
IntegrandInfo
    Structured process, backend, graph, orientation, cut, and size metadata.

Raises
------
Exception
    If no unique generated integrand matches the selection.

Examples
--------
Inspect the generated graph groups in the repository's differential API fixture:

```python
from pathlib import Path

from gammaloop import GammaLoopAPI

example = Path("examples/api/python/epem_a_ddxg_xs_LO")
api = GammaLoopAPI(
    state_folder=example / "state",
    boot_commands_path=example / "run.toml",
    clean_state=True,
)
info = api.get_integrand_info()
assert info.kind == "cross section"
assert info.graph_count == 2
assert info.graph_group_count == len(info.graph_groups)
assert all(
    sum(graph.is_master for graph in group.graphs) == 1
```
```

```
    for group in info.graph_groups
)
```

This fixture's powered coupling selector is a regression input, not a reviewed
physical
perturbative-order definition.

process_id

Kind: Parameter

Optional[int]

Default: None

Process containing the integrand. Supply this when selection is ambiguous.

integrand_name

Kind: Parameter

Optional[str]

Default: None

Integrand to inspect. Supply this when selection is ambiguous.

get_integrand_settings

Kind: Method

def get_integrand_settings(self, process_id: Optional[int] = None, integrand_name:
Optional[str] = None) -> SettingsValue:

Return a detached, read-only snapshot of one integrand's settings.

Parameters
----
process_id : int, optional
    Process containing the integrand. Supply this when selection is ambiguous.
integrand_name : str, optional
    Integrand whose settings are required.

Returns

SettingsValue
    Serialized settings snapshot supporting ``get(path)``, attribute access,
    indexing, and ``to_dict()``. Mutating it does not update the live session.

Raises

Exception
    If selection fails, the integrand has not been generated, or its settings
    cannot be serialized.

Examples

Read a nested setting without changing the live integrand:

```python
settings = api.get_integrand_settings(process_id=0)
```

```
print(settings.get("general.generate_events"))
```

process_id

Kind: Parameter

Optional[int]

Default: None

Process containing the integrand. Supply this when selection is ambiguous.

integrand_name

Kind: Parameter

Optional[str]

Default: None

Integrand whose settings are required.

get_run_history

Kind: Method

```
def get_run_history(self) -> str:
```

Render the current in-memory run history as TOML.

```
Returns
-------
str
    TOML representation of the history owned by this API instance.

Raises
------
Exception
    If the current history cannot be serialized.

Notes
-----
This reports the live session, including commands run through ``run``; it does
not imply that the history has been persisted to the state directory.

Examples
--------
Capture a reproducible run card from the current session:

```python
run_card_toml = api.get_run_history()
```
```

get_global_settings

Kind: Method

```
def get_global_settings(self) -> str:
```

Render the current effective CLI and global settings as TOML.

```
Returns
-------
```

```
str
    TOML representation of the settings used by this API session.

Raises
------
Exception
    If the settings cannot be rendered.

Examples
--------
Record the effective settings after applying startup overrides:

```python
settings_toml = api.get_global_settings()
```
```

get_active_command_blocks

Kind: Method

```
def get_active_command_blocks(self) -> dict[str, list[str]]:

Return the named command blocks in the current run history.

Returns
-------
dict[str, list[str]]
    Mapping from block name to its rendered CLI commands.

Examples
--------
Inspect the commands currently grouped under each block:

```python
for name, commands in api.get_active_command_blocks().items():
    print(name, commands)
```
```

get_default_runtime_settings

Kind: Method

```
def get_default_runtime_settings(self) -> SettingsValue:

Return a detached, read-only snapshot of the default runtime settings.

Returns
-------
SettingsValue
    Serialized settings including defaults. Use ``get(path)`` or ``to_dict()``
    to inspect it; changes to derived Python values do not affect the session.

Raises
------
Exception
    If the settings cannot be serialized.

Examples
--------
Inspect a runtime default by its documented settings path:
```

```python
runtime = api.get_default_runtime_settings()
print(runtime.get("integrator.n_start"))
```

get_dot_files

Kind: Method

```
def get_dot_files(self, process: Optional[int | str] = None, integrand_name:
Optional[str] = None, settings: DotExportSettings = ...) -> str:
```

```
Render a selected amplitude or cross section as Graphviz DOT text.

Parameters
----------
process : int or str, optional
    Process id or name; omit only when selection is unambiguous.
integrand_name : str, optional
    Integrand to render.
settings : DotExportSettings, optional
    Controls diagram combination, UV terms, algebra, and generated fields.

Returns
-------
str
    DOT source suitable for Graphviz or GammaLoop's drawing pipeline.
```

process

Kind: Parameter

```
Optional[int | str]
```

Default: None

```
Process id or name; omit only when selection is unambiguous.
```

integrand_name

Kind: Parameter

```
Optional[str]
```

Default: None

```
Integrand to render.
```

settings

Kind: Parameter

```
DotExportSettings
```

Default: ...

```
Controls diagram combination, UV terms, algebra, and generated fields.
```

run

Kind: Method

```
def run(self, command: str) -> None:
```

```
Parse and execute a CLI command in this API instance's session.
```

```
Parameters
----------
command : str
    GammaLoop CLI command text.

Returns
-------
None
    The command's normal output is emitted through the configured CLI/logging
    sinks; inspect structured state through the corresponding getter methods.

Raises
------
Exception
    If the command cannot be parsed or execution fails.

Notes
-----
Commands share and may mutate the instance's in-memory state, settings, and run
history. ``read_only_state=True`` only blocks writes inside the active state
directory. The API does not automatically persist the session after this call;
persistence depends on the executed command's explicit output behavior.

Examples
--------
Display the processes loaded in the current state:

```python
api.run("display processes")
```
```

command

Kind: Parameter

str

GammaLoop CLI command text.

Exhaustive reference · Source

HistogramAccumulator

Mutable continuous or discrete histogram accumulator with sample-level statistics.

Mutable continuous or discrete histogram accumulator with sample-level statistics.

```
Notes
-----
Each fill call represents one independent sample. Repeated entries in a bin
are summed before their squared contribution is recorded, matching the native
observable pipeline. Empty fills still increment the sample count.

Examples
--------
Merge two pending, statistically independent samples before committing them:

```python
from gammaloop import HistogramAccumulator
```
```

```
left = HistogramAccumulator.continuous("energy", 0.0, 4.0, 4)
right = HistogramAccumulator.continuous("energy", 0.0, 4.0, 4)
left.fill_continuous_sample([(0.5, 2.0)])
right.fill_continuous_sample([(2.5, 3.0)])
left.merge_in_place(right)
left.update_results()

snapshot = left.snapshot()
assert snapshot.sample_count == 2
assert snapshot.bins[0].sum_weights == 2.0
assert snapshot.bins[0].sum_weights_squared == 4.0
assert snapshot.bins[0].sum_weights / snapshot.sample_count == 1.0
assert snapshot.bins[2].sum_weights == 3.0
assert snapshot.bins[2].sum_weights_squared == 9.0
assert right.snapshot().sample_count == 0
assert len(left.rebin(2).snapshot().bins) == 2
```

```
class HistogramAccumulator:
```

Requires features: `python, abi3, python-stubs`

`continuous`

Kind: `AssociatedFunction`

```
def continuous(title: str, x_min: float, x_max: float, n_bins: int, type_description:
str = 'AL', phase: str = 'real', value_transform: str = 'identity', log_x_axis: bool
= False, log_y_axis: bool = True) -> HistogramAccumulator:
```

```
Create an evenly binned continuous histogram accumulator.

Parameters
----------
title : str
    Human-readable title used by snapshots and exported output.
x_min : float
    Lower edge of the histogram range.
x_max : float
    Upper edge of the histogram range.
n_bins : int
    Number of equal-width in-range bins.
type_description : str, default="AL"
    HwU ``TYPE@`` metadata.
phase : {"real", "imag"}, default="real"
    Component of each complex event weight to accumulate.
value_transform : {"identity", "log10"}, default="identity"
    Transformation applied to coordinates before binning.
log_x_axis : bool, default=False
    Request logarithmic horizontal-axis rendering.
log_y_axis : bool, default=True
    Request logarithmic vertical-axis rendering.
```

`title`

Kind: `Parameter`

```
str
```

```
Human-readable title used by snapshots and exported output.
```

x_min
Kind: Parameter

float

Lower edge of the histogram range.

x_max
Kind: Parameter

float

Upper edge of the histogram range.

n_bins
Kind: Parameter

int

Number of equal-width in-range bins.

type_description
Kind: Parameter

str

Default: 'AL'

HwU ``TYPE@`` metadata.

phase
Kind: Parameter

str

Default: 'real'

Component of each complex event weight to accumulate.

value_transform
Kind: Parameter

str

Default: 'identity'

Transformation applied to coordinates before binning.

log_x_axis
Kind: Parameter

bool

Default: False

Request logarithmic horizontal-axis rendering.

log_y_axis
Kind: Parameter

bool

Default: True

Request logarithmic vertical-axis rendering.

discrete

Kind: AssociatedFunction

```
def discrete(title: str, min_bin_id: int, max_bin_id: int, ordering: str =
'ascending_bin_id', labels: Optional[Sequence[str]] = None, type_description: str =
'AL', phase: str = 'real', log_y_axis: bool = True) -> HistogramAccumulator:
```

Create a discrete histogram accumulator over an inclusive integer range.

```
Parameters
----------
title : str
    Human-readable title used by snapshots and exported output.
min_bin_id : int
    Smallest accepted bin identifier.
max_bin_id : int
    Largest accepted bin identifier, inclusive.
ordering : {"ascending_bin_id", "value_descending", "abs_value_descending"},
default="ascending_bin_id"
    Ordering used when bins are returned or exported.
labels : Sequence[str], optional
    One label per bin, ordered by ascending bin identifier.
type_description : str, default="AL"
    HwU ``TYPE@`` metadata.
phase : {"real", "imag"}, default="real"
    Component of each complex event weight to accumulate.
log_y_axis : bool, default=True
    Request logarithmic vertical-axis rendering.

Raises
------
ValueError
    If the range, label count, ordering, or phase is invalid.
```

title

Kind: Parameter

```
str
```

Human-readable title used by snapshots and exported output.

min_bin_id

Kind: Parameter

```
int
```

Smallest accepted bin identifier.

max_bin_id

Kind: Parameter

```
int
```

Largest accepted bin identifier, inclusive.

ordering

Kind: Parameter

```
str
```

Default: `'ascending_bin_id'`

Ordering used when bins are returned or exported.

`labels`
Kind: Parameter

`Optional[Sequence[str]]`

Default: `None`

One label per bin, ordered by ascending bin identifier.

`type_description`
Kind: Parameter

`str`

Default: `'AL'`

HwU ``TYPE@`` metadata.

`phase`
Kind: Parameter

`str`

Default: `'real'`

Component of each complex event weight to accumulate.

`log_y_axis`
Kind: Parameter

`bool`

Default: `True`

Request logarithmic vertical-axis rendering.

`snapshot`
Kind: Method

```
def snapshot(self) -> HistogramSnapshot:
```

Return an immutable snapshot including committed and pending samples.

`merge_in_place`
Kind: Method

```
def merge_in_place(self, other: HistogramAccumulator) -> None:
```

Move pending samples from another compatible accumulator into this one.

```
Parameters
----------
other : HistogramAccumulator
    Compatible accumulator whose pending samples are consumed.

Raises
------
ValueError
    If histogram definitions differ.
```

other

Kind: Parameter

HistogramAccumulator

Compatible accumulator whose pending samples are consumed.

rebin

Kind: Method

```
def rebin(self, contiguous_bins: int) -> HistogramAccumulator:
```

Return a copy with each run of adjacent continuous bins combined.

Discrete histograms are copied unchanged.

```
Parameters
----------
contiguous_bins : int
    Positive number of old bins per new bin; it must divide the bin count.
```

contiguous_bins

Kind: Parameter

int

Positive number of old bins per new bin; it must divide the bin count.

rescale

Kind: Method

```
def rescale(self, factor: float) -> None:
```

Multiply all accumulated weights by a constant in place.

```
Parameters
----------
factor : float
    Scale applied to weight sums; squared-weight sums use its square.
```

factor

Kind: Parameter

float

Scale applied to weight sums; squared-weight sums use its square.

change_bin_ordering

Kind: Method

```
def change_bin_ordering(self, ordering: str) -> None:
```

Change the display ordering of a discrete histogram.

```
Parameters
----------
ordering : {"ascending_bin_id", "value_descending", "abs_value_descending"}
    New ordering for snapshots and exported output.

Raises
------
```

```
ValueError
    If this is a continuous histogram or the name is invalid.
```

ordering

Kind: Parameter

```
str
```

New ordering for snapshots and exported output.

update_results

Kind: Method

```
def update_results(self) -> None:
```

Commit pending samples to the accumulator's completed-result counters.

fill_continuous_sample

Kind: Method

```
def fill_continuous_sample(self, entries: Sequence[tuple[float, float]]) -> None:
```

Add one independent continuous sample containing coordinate-weight pairs.

```
Parameters
----------
entries : Sequence[tuple[float, float]]
    ``(coordinate, projected_weight)`` entries for this sample.

Raises
------
ValueError
    If this is not a continuous histogram.
```

entries

Kind: Parameter

```
Sequence[tuple[float, float]]
```

``(coordinate, projected_weight)`` entries for this sample.

fill_discrete_sample

Kind: Method

```
def fill_discrete_sample(self, entries: Sequence[tuple[int, float]]) -> None:
```

Add one independent discrete sample containing bin-weight pairs.

```
Parameters
----------
entries : Sequence[tuple[int, float]]
    ``(bin_id, projected_weight)`` entries for this sample.

Raises
------
ValueError
    If this is not a discrete histogram.
```

entries

Kind: Parameter

Sequence[tuple[int, float]]

``(bin_id, projected_weight)`` entries for this sample.

Exhaustive reference · Source

HistogramBin

Raw statistics and optional coordinate metadata for one histogram bin.

Raw statistics and optional coordinate metadata for one histogram bin.

class HistogramBin:

Requires features: python, abi3, python-stubs

x_min

Kind: Getter

def x_min(self) -> Optional[float]:

Lower coordinate edge, or ``None`` for a discrete or overflow bin.

x_max

Kind: Getter

def x_max(self) -> Optional[float]:

Upper coordinate edge, or ``None`` for a discrete or underflow bin.

bin_id

Kind: Getter

def bin_id(self) -> Optional[int]:

Discrete bin identifier, or ``None`` for a continuous bin.

label

Kind: Getter

def label(self) -> Optional[str]:

Optional label of a discrete bin.

entry_count

Kind: Getter

def entry_count(self) -> int:

Number of event entries accumulated in this bin.

sum_weights

Kind: Getter

def sum_weights(self) -> float:

Sum of per-sample projected weights for this bin.

sum_weights_squared

Kind: Getter

def sum_weights_squared(self) -> float:

Sum of squared per-sample projected weights for this bin.

mitigated_fill_count

Kind: Getter

```
def mitigated_fill_count(self) -> int:
```

Number of fills produced by paired boundary-misbinning mitigation.

average

Kind: Method

```
def average(self, sample_count: int) -> float:
```

Compute this bin's Monte Carlo mean from its raw weight sum.

```
Parameters
----------
sample_count : int
    Number of statistically independent samples represented by the histogram.

Returns
-------
float
    ``sum_weights / sample_count``, or zero when ``sample_count`` is zero.
```

sample_count

Kind: Parameter

```
int
```

Number of statistically independent samples represented by the histogram.

error

Kind: Method

```
def error(self, sample_count: int) -> float:
```

Compute the standard error of this bin's Monte Carlo mean.

```
Parameters
----------
sample_count : int
    Number of statistically independent samples represented by the histogram.

Returns
-------
float
    Sample-mean standard error, or zero when it cannot be estimated reliably.
```

sample_count

Kind: Parameter

```
int
```

Number of statistically independent samples represented by the histogram.

Exhaustive reference · Source

HistogramSnapshot

Immutable, mergeable histogram snapshot containing raw per-bin statistics.

Immutable, mergeable histogram snapshot containing raw per-bin statistics.

class HistogramSnapshot:

Requires features: python, abi3, python-stubs

kind

Kind: Getter

def kind(self) -> str:

``"continuous"`` or ``"discrete"``.

title

Kind: Getter

def title(self) -> str:

Human-readable histogram title.

type_description

Kind: Getter

def type_description(self) -> str:

HwU ``TYPE@`` description retained with the histogram.

phase

Kind: Getter

def phase(self) -> str:

Complex-weight component accumulated: ``"real"`` or ``"imag"``.

value_transform

Kind: Getter

def value_transform(self) -> str:

Coordinate transform: ``"identity"`` or ``"log10"``.

supports_misbinning_mitigation

Kind: Getter

def supports_misbinning_mitigation(self) -> bool:

Whether paired fills can mitigate bin-boundary instability.

x_min

Kind: Getter

def x_min(self) -> Optional[float]:

Lower bound of a continuous histogram, otherwise ``None``.

x_max

Kind: Getter

def x_max(self) -> Optional[float]:

Upper bound of a continuous histogram, otherwise ``None``.

sample_count

Kind: Getter

def sample_count(self) -> int:

Number of statistically independent Monte Carlo samples represented.

log_x_axis
Kind: Getter

def log_x_axis(self) -> bool:

Whether compatible renderers should use a logarithmic horizontal axis.

log_y_axis
Kind: Getter

def log_y_axis(self) -> bool:

Whether compatible renderers should use a logarithmic vertical axis.

discrete_min_bin_id
Kind: Getter

def discrete_min_bin_id(self) -> Optional[int]:

Smallest discrete bin identifier, otherwise ``None``.

discrete_ordering
Kind: Getter

def discrete_ordering(self) -> Optional[str]:

Discrete display ordering, otherwise ``None``.

bins
Kind: Getter

def bins(self) -> list[HistogramBin]:

Raw statistics for every in-range bin, in display order.

underflow_bin
Kind: Getter

def underflow_bin(self) -> HistogramBin:

Raw statistics for entries below a continuous histogram's range.

overflow_bin
Kind: Getter

def overflow_bin(self) -> HistogramBin:

Raw statistics for entries above a continuous histogram's range.

statistics
Kind: Getter

def statistics(self) -> HistogramStats:

Histogram-wide entry and mitigation counters.

Exhaustive reference · Source

HistogramStats
Aggregate entry, NaN, and misbinning-mitigation counts for a histogram.

Aggregate entry, NaN, and misbinning-mitigation counts for a histogram.

class HistogramStats:

Requires features: python, abi3, python-stubs

in_range_entry_count
Kind: Getter

def in_range_entry_count(self) -> int:

Number of event entries assigned to in-range bins.

nan_value_count
Kind: Getter

def nan_value_count(self) -> int:

Number of entries skipped because their coordinate was non-finite.

mitigated_pair_count
Kind: Getter

def mitigated_pair_count(self) -> int:

Number of entry pairs processed by boundary-misbinning mitigation.

Exhaustive reference · Source

IntegrandActiveThresholdCut
Viable cut associated with a threshold E-surface.

Viable cut associated with a threshold E-surface.

class IntegrandActiveThresholdCut:

Requires features: python, abi3, python-stubs

cut_id
Kind: Getter

def cut_id(self) -> int:

Zero-based identifier of a cut on which the E-surface remains viable.

can_become_pinched
Kind: Getter

def can_become_pinched(self) -> bool:

Whether this cut can make the E-surface pinched for some kinematics.

Exhaustive reference · Source

IntegrandCut
Cut edges, raising power, and threshold associations for one cross-section cut.

Cut edges, raising power, and threshold associations for one cross-section cut.

class IntegrandCut:

Requires features: python, abi3, python-stubs

cut_id
Kind: Getter

def cut_id(self) -> int:

Zero-based cut identifier within the representative graph.

edge_ids
Kind: Getter

def edge_ids(self) -> list[int]:

Edge identifiers crossed by the cut.

raising_power
Kind: Getter

def raising_power(self) -> int:

Maximum multiplicity of the cut's related threshold group.

left_thresholds
Kind: Getter

def left_thresholds(self) -> list[IntegrandCutThreshold]:

Threshold associations on the left side of the cut.

right_thresholds
Kind: Getter

def right_thresholds(self) -> list[IntegrandCutThreshold]:

Threshold associations on the right side of the cut.

Exhaustive reference · Source

IntegrandCutThreshold
Classification and boundary edges of one threshold associated with a cut.

Classification and boundary edges of one threshold associated with a cut.

class IntegrandCutThreshold:

Requires features: python, abi3, python-stubs

esurface_id
Kind: Getter

def esurface_id(self) -> int:

Threshold E-surface identifier within the graph group.

status
Kind: Getter

def status(self) -> str:

Viability classification for this threshold-cut association.

cut_boundary_edge_ids
Kind: Getter

def cut_boundary_edge_ids(self) -> list[int]:

Cut edges that bound the associated threshold region.

threshold_boundary_edge_ids
Kind: Getter

```
def threshold_boundary_edge_ids(self) -> list[int]:
```

Threshold edges that bound the associated threshold region.

invariant_bound_is_applicable
Kind: Getter

```
def invariant_bound_is_applicable(self) -> bool:
```

Whether the invariant-bound criterion applies to this association.

Exhaustive reference · Source

IntegrandGraph
Identity and master-graph status of one graph in an integrand.

Identity and master-graph status of one graph in an integrand.

```
class IntegrandGraph:
```

Requires features: `python, abi3, python-stubs`

graph_id
Kind: Getter

```
def graph_id(self) -> int:
```

Zero-based graph identifier within the integrand.

name
Kind: Getter

```
def name(self) -> str:
```

Persistent graph name.

is_master
Kind: Getter

```
def is_master(self) -> bool:
```

Whether this graph is the representative graph of its group.

native_residue_counts
Kind: Getter

```
def native_residue_counts(self) -> list[tuple[str, int]]:
```

Native residue-map counts as (representation, count), in generation order.

threshold_counterterm_directives
Kind: Getter

```
def threshold_counterterm_directives(self) -> list[ThresholdCountertermDirective]:
```

Threshold directives requested for this graph, including implicit defaults.

threshold_counterterms
Kind: Getter

```
def threshold_counterterms(self) -> Optional[ThresholdCountertermMetadataRegistry]:
```

Resolved graph-local threshold registry, when generated metadata is available.

Exhaustive reference · Source

IntegrandGraphGroup

Graphs and shared orientation, loop-basis, threshold, and cut data in one group.

Graphs and shared orientation, loop-basis, threshold, and cut data in one group.

```
class IntegrandGraphGroup:
```

Requires features: `python, abi3, python-stubs`

group_id

Kind: Getter

```
def group_id(self) -> int:
```

Zero-based graph-group identifier within the integrand.

graphs

Kind: Getter

```
def graphs(self) -> list[IntegrandGraph]:
```

Graphs in this group, with the representative graph marked as master.

complete_residue_sum

Kind: Getter

```
def complete_residue_sum(self) -> bool:
```

Whether every native residue is evaluated through the complete-sum layout.

orientation_edge_ids

Kind: Getter

```
def orientation_edge_ids(self) -> list[int]:
```

Edge identifiers that establish the ordering of every orientation signature.

orientations

Kind: Getter

```
def orientations(self) -> list[IntegrandOrientation]:
```

Runtime execution orientations; a complete-sum slot is not a native residue key.

loop_momentum_bases

Kind: Getter

```
def loop_momentum_bases(self) -> list[IntegrandLoopMomentumBasis]:
```

Available loop-momentum bases for the representative graph.

threshold_esurface_ids

Kind: Getter

```
def threshold_esurface_ids(self) -> list[int]:
```

Ordered identifiers of threshold E-surfaces retained for the group.

threshold_esurfaces

Kind: Getter

```
def threshold_esurfaces(self) -> list[IntegrandThresholdEsurface]:
```

Structured metadata for the retained threshold E-surfaces.

cuts

Kind: Getter

```
def cuts(self) -> list[IntegrandCut]:
```

Cross-section cuts; empty for amplitude graph groups.

Exhaustive reference · Source

IntegrandInfo

Structured description of a generated integrand and its evaluation backend.

Structured description of a generated integrand and its evaluation backend.

```
class IntegrandInfo:
```

Requires features: `python, abi3, python-stubs`

process_id

Kind: Getter

```
def process_id(self) -> int:
```

Numeric identifier of the process that owns the integrand.

process_name

Kind: Getter

```
def process_name(self) -> str:
```

Persistent folder name of the owning process.

integrand_name

Kind: Getter

```
def integrand_name(self) -> str:
```

Canonical name of the resolved integrand.

kind

Kind: Getter

```
def kind(self) -> str:
```

``"amplitude"`` or ``"cross section"``.

generated_representations

Kind: Getter

```
def generated_representations(self) -> list[str]:
```

Generated representations, in persisted generation order.

generation_backend

Kind: Getter

```
def generation_backend(self) -> str:
```

Compilation backend frozen into the generated integrand.

generation_compile_options

Kind: Getter

```
def generation_compile_options(self) -> Optional[str]:
```

Backend-specific compilation options, when configured.

active_f64_backend

Kind: Getter

```
def active_f64_backend(self) -> str:
```

Floating-point evaluator backend currently active for f64 evaluation.

graph_count

Kind: Getter

```
def graph_count(self) -> int:
```

Number of amplitude graphs or cross-section supergraphs.

graph_group_count

Kind: Getter

```
def graph_group_count(self) -> int:
```

Number of graph groups in the generated integrand.

record_size_bytes

Kind: Getter

```
def record_size_bytes(self) -> int:
```

Serialized integrand-record size in bytes, excluding its compiled evaluator.

graph_groups

Kind: Getter

```
def graph_groups(self) -> list[IntegrandGraphGroup]:
```

Per-group graph, orientation, basis, threshold, and cut metadata.

Exhaustive reference · Source

IntegrandLoopMomentumBasis

Loop-momentum basis and optional multichannel identifier for a graph group.

Loop-momentum basis and optional multichannel identifier for a graph group.

```
class IntegrandLoopMomentumBasis:
```

Requires features: `python, abi3, python-stubs`

basis_id

Kind: Getter

```
def basis_id(self) -> int:
```

Zero-based loop-momentum-basis identifier on the representative graph.

channel_id

Kind: Getter

```
def channel_id(self) -> Optional[int]:
```

Effective multichannel identifier, or ``None`` when this basis is not sampled.

edge_ids

Kind: Getter

```
def edge_ids(self) -> list[int]:
```

Edge identifiers whose momenta form the basis.

matches_generation_basis
Kind: Getter

```
def matches_generation_basis(self) -> bool:
```

Whether this is the loop-momentum basis used during integrand generation.

Exhaustive reference · Source

IntegrandOrientation
Edge-direction signature for one causal-flow orientation.

Edge-direction signature for one causal-flow orientation.

```
class IntegrandOrientation:
```

Requires features: `python, abi3, python-stubs`

orientation_id
Kind: Getter

```
def orientation_id(self) -> int:
```

Zero-based orientation identifier within the graph group.

signature
Kind: Getter

```
def signature(self) -> list[int]:
```

Direction per ``IntegrandGraphGroup.orientation_edge_ids``: ``1``, ``-1``, or ``0``.

Exhaustive reference · Source

IntegrandThresholdEsurface
Threshold E-surface metadata and the cuts on which it remains active.

Threshold E-surface metadata and the cuts on which it remains active.

```
class IntegrandThresholdEsurface:
```

Requires features: `python, abi3, python-stubs`

esurface_id
Kind: Getter

```
def esurface_id(self) -> int:
```

E-surface identifier within the graph group.

representative_graph_id
Kind: Getter

```
def representative_graph_id(self) -> int:
```

Graph whose local E-surface supplies ``edge_ids``.

edge_ids
Kind: Getter

```
def edge_ids(self) -> list[int]:
```

Edge identifiers contributing energies to this E-surface.

classification
Kind: Getter

```
def classification(self) -> Optional[str]:
```

```
Kinematic existence class, or ``None`` when no static classification was computed.
```

active_cuts

Kind: Getter

```
def active_cuts(self) -> list[IntegrandActiveThresholdCut]:
```

```
Cuts on which this E-surface remains viable.
```

Exhaustive reference · Source

ObservableAccumulator

```
Independent observable statistics compiled from one integrand's definitions.
```

```
Independent observable statistics compiled from one integrand's definitions.

Construct with ``api.observable_accumulator()`` and add exactly one evaluation
record per independent draw. The coefficient is the complete outer weight;
zero keeps the attempted sample count without fills. Event groups stay unmodified.

Examples
--------
```python
accumulator = api.observable_accumulator()
batch = api.evaluate_samples(points)
for sample in batch.samples:
    accumulator.add_sample(sample, sample.integrator_weight)
histograms = accumulator.snapshot()
```
```

```
class ObservableAccumulator:
```

Requires features: `python, abi3, python-stubs`

add_sample

Kind: Method

```
def add_sample(self, sample: EvaluationResult, coefficient: float) -> None:
```

```
Commit one sample with an explicit outer weight, including zero-weight misses.
```

sample

Kind: Parameter

```
EvaluationResult
```

coefficient

Kind: Parameter

```
float
```

merge_in_place

Kind: Method

```
def merge_in_place(self, other: ObservableAccumulator) -> None:
```

```
Merge independent sample statistics without changing the source accumulator.
```

other

Kind: Parameter

ObservableAccumulator

sum_independent_estimates

Kind: AssociatedFunction

def sum_independent_estimates(accumulators: Sequence[ObservableAccumulator]) -> Any:

Sum means and variances of independent populations, preserving their separate counts. Merge batches within a stratum before passing its accumulator here.

accumulators

Kind: Parameter

Sequence[ObservableAccumulator]

snapshot

Kind: Method

def snapshot(self) -> dict:

Return mergeable raw histogram statistics, without clearing or committing them.

Exhaustive reference · Source

SettingsValue

Read-only, detached view over serialized GammaLoop settings.

Read-only, detached view over serialized GammaLoop settings.

class SettingsValue:

Requires features: python, abi3, python-stubs

path

Kind: Getter

def path(self) -> str:

Dot-separated location of this value within the settings tree.

kind

Kind: Getter

def kind(self) -> str:

JSON value kind: ``object``, ``array``, ``string``, ``number``, ``boolean``, or ``null``.

is_object

Kind: Method

def is_object(self) -> bool:

Return whether this value is an object with named children.

is_array

Kind: Method

def is_array(self) -> bool:

Return whether this value is an array with indexed children.

is_scalar

Kind: Method

```
def is_scalar(self) -> bool:
```

Return whether this value is a scalar JSON value, including ``null``.

keys

Kind: Method

```
def keys(self) -> list[str]:
```

Return this object's child keys in lexical order.

```
Raises
------
TypeError
    If this value is not an object.
```

get

Kind: Method

```
def get(self, path: str) -> Any:
```

Resolve a dot-separated descendant path.

```
An empty path returns this value. Objects become ``SettingsValue`` views,
while scalar values become their ordinary Python equivalents.

Parameters
----------
path : str
    Relative path such as ``"sampling.parameterization"``.

Raises
------
KeyError
    If the path does not exist below this value.
```

path

Kind: Parameter

```
str
```

Relative path such as ``"sampling.parameterization"``.

to_dict

Kind: Method

```
def to_dict(self) -> Any:
```

Convert the complete detached value tree to ordinary Python containers and scalars.

__getattr__

Kind: Method

```
def __getattr__(self, name: str) -> Any:
```

Resolve an object child by attribute name.

```
Parameters
----------
name : str
    Immediate child key to resolve.
```

name

Kind: Parameter

str

Immediate child key to resolve.

__dir__

Kind: Method

def __dir__(self) -> list[str]:

Return object-child names in lexical order, or an empty list for other kinds.

__len__

Kind: Method

def __len__(self) -> int:

Return the number of object or array children.

__str__

Kind: Method

def __str__(self) -> str:

Return the detached settings value as pretty-printed JSON.

__repr__

Kind: Method

def __repr__(self) -> str:

Return a compact representation containing this value's path and kind.

__getitem__

Kind: Method

def __getitem__(self, key: Any, /) -> Any:

Resolve a relative string path or array index.

Parameters
----
key : str or int
    Descendant path for an object, or zero-based index for an array.

key

Kind: Parameter

Any

Descendant path for an object, or zero-based index for an array.

Exhaustive reference · Source

StabilityResult

Outcome and cost of one stability attempt, including precision and representation.

Outcome and cost of one stability attempt, including precision and representation.

class StabilityResult:

Requires features: python, abi3, python-stubs

precision

Kind: Getter

```
def precision(self) -> str:
```

Numerical precision used for this stability level.

three_dimensional_representation

Kind: Getter

```
def three_dimensional_representation(self) -> str:
```

Generated three-dimensional representation evaluated at this level.

estimated_relative_accuracy

Kind: Getter

```
def estimated_relative_accuracy(self) -> Optional[float]:
```

Estimated relative accuracy, or ``None`` when it could not be estimated.

estimated_decimal_digits

Kind: Getter

```
def estimated_decimal_digits(self) -> Optional[float]:
```

status

Kind: Getter

```
def status(self) -> str:
```

Human-readable stability outcome and number of rotated samples.

sample_count

Kind: Getter

```
def sample_count(self) -> int:
```

Number of rotated samples evaluated at this precision level.

total_time_seconds

Kind: Getter

```
def total_time_seconds(self) -> float:
```

Total wall-clock time spent at this precision level, in seconds.

Exhaustive reference · Source

atom_to_canonical_string

Parse a Symbolica expression and return its canonical string form.

Parse a Symbolica expression and return its canonical string form.

```
Parameters
----------
atom_str : str
    Symbolica expression to parse and normalize.

Returns
-------
str
    The parsed expression in canonical string form.
```

```
Raises
------
Exception
    If ``atom_str`` is not a valid Symbolica expression.

Examples
--------
Normalize a symbolic expression before comparing or storing it:

```python
atom_to_canonical_string("x + x")
```
```

```
def atom_to_canonical_string(atom_str: str) -> str:
```

Requires features: `python, abi3, python-stubs`

Exhaustive reference · Source

`evaluate_graph_overall_factor`

```
Evaluate a graph's symbolic overall factor and return its canonical form.
```


```
Evaluate a graph's symbolic overall factor and return its canonical form.
```


```
Parameters
----------
overall_factor : str
    Symbolica expression used as the graph's overall factor.

Returns
-------
str
    The evaluated factor in canonical Symbolica form.

Raises
------
Exception
    If the expression cannot be parsed or evaluated.

Examples
--------
Evaluate the symmetry and fermion-loop factors attached to a graph:

```python
evaluate_graph_overall_factor(
    "AutG(2)^-1*InternalFermionLoopSign(-1)"
)
```
```

```
def evaluate_graph_overall_factor(overall_factor: str) -> str:
```

Requires features: `python, abi3, python-stubs`

Exhaustive reference · Source

`to_dots`

```
Rewrite a Symbolica tensor expression into Idenso dot-product notation.
```

```
Rewrite a Symbolica tensor expression into Idenso dot-product notation.

Parameters
----------
atom_str : str
    Symbolica tensor expression whose repeated indices encode contractions.

Returns
-------
str
    The equivalent expression using Idenso dot-product notation.

Raises
------
Exception
    If ``atom_str`` cannot be parsed or converted.

Examples
--------
Rewrite a contraction before passing it to an Idenso workflow:

```python
to_dots("p(mu) * q(mu)")
```
```

```
def to_dots(atom_str: str) -> str:
```

Requires features: `python, abi3, python-stubs`

Exhaustive reference · Source

CLI commands and settings

Commands and settings available in this version are listed below.

Command tree

Command	Description
`gammaLoop`	An implementation of the Local Unitarity method for computing differential collider cross-sections.
`gammaLoop display`	Inspect models, processes, integrands, settings, and named session data
`gammaLoop display model`	Show model particles, parameters, couplings, and vertices for the selected context
`gammaLoop display processes`	List processes currently stored in the active state
`gammaLoop display integrand`	Show stored representations, graph groups, generation timings, and selected detail tables
`gammaLoop display quantities`	List configured named quantities, or inspect one quantity in a selected process
`gammaLoop display observables`	List configured observables, or inspect one observable in a selected process
`gammaLoop display selectors`	List configured event selectors, or inspect one selector in a selected process
`gammaLoop display command_block`	Show one stored command block, or list every block when no name is supplied
`gammaLoop display settings`	Show effective global, default-runtime, or process-specific settings
`gammaLoop display settings global`	Show effective global generation, logging, and parallelization settings
`gammaLoop display settings default-runtime`	Show the default runtime settings inherited by newly generated integrands
`gammaLoop display settings process`	Show effective settings for one generated process or integrand
`gammaLoop duplicate`	Copy generated data to a new process or integrand name
`gammaLoop duplicate integrand`	Copy one generated integrand and its process context under new names
`gammaLoop set`	Change global, runtime, model, or process settings
`gammaLoop set base-dir`	Set the base directory for gammaloop state and logs
`gammaLoop set global`	Change global generation, logging, and parallelism settings
`gammaLoop set global file`	Merge a TOML file into the current global or default-runtime settings
`gammaLoop set global string`	Load settings from TOML content passed as a CLI string
`gammaLoop set global kv`	Merge one or more dotted `KEY=VALUE` assignments into the current settings

Command	Description
gammaLoop set global defaults	Sync process runtime settings from the current default runtime settings
gammaLoop set global stored	Reload the corresponding settings from the active state's stored file
gammaLoop set default-runtime	Change the runtime settings inherited by newly generated integrands
gammaLoop set default-runtime file	Merge a TOML file into the current global or default-runtime settings
gammaLoop set default-runtime string	Load settings from TOML content passed as a CLI string
gammaLoop set default-runtime kv	Merge one or more dotted `KEY=VALUE` assignments into the current settings
gammaLoop set default-runtime defaults	Sync process runtime settings from the current default runtime settings
gammaLoop set default-runtime stored	Reload the corresponding settings from the active state's stored file
gammaLoop set model	Assign model parameters in the selected context or reset them to defaults
gammaLoop set process	Change runtime settings or named analysis objects for one process or integrand
gammaLoop set process file	Merge a TOML file into the selected process or integrand settings
gammaLoop set process string	Load settings from TOML content passed as a CLI string
gammaLoop set process kv	Merge one or more dotted `KEY=VALUE` assignments into the selected settings
gammaLoop set process defaults	Sync process runtime settings from the current default runtime settings
gammaLoop set process stored	Reload the selected process or integrand settings from its stored file
gammaLoop set process add	Add a named quantity/observable/selector
gammaLoop set process add quantity	Add a named derived quantity to the selected process settings
gammaLoop set process add observable	Add a named observable to the selected process settings
gammaLoop set process add selector	Add a named event selector to the selected process settings
gammaLoop set process update	Update a named quantity/observable/selector
gammaLoop set process update quantity	Update fields of an existing named quantity
gammaLoop set process update observable	Update fields of an existing named observable
gammaLoop set process update selector	Update fields of an existing named selector
gammaLoop set process remove	Remove a named quantity/observable/selector

Command	Description
gammaLoop set process remove quantity	Remove a named quantity from the selected process settings
gammaLoop set process remove observable	Remove a named observable from the selected process settings
gammaLoop set process remove selector	Remove a named selector from the selected process settings
gammaLoop import	Import models or previously generated graphs into the active state
gammaLoop import model	Load a UFO model and make it the active model for subsequent generation
gammaLoop import graphs	Load serialized graph data into a new or existing process
gammaLoop save	Export graph data, standalone evaluators, schemas, or the current state
gammaLoop save dot	Export generated graphs as DOT files and drawing templates
gammaLoop save uv-forest	Export the ultraviolet forest for selected generated graphs
gammaLoop save standalone	Export an integrand as a standalone evaluator or serialized data file
gammaLoop save state	Persist the active state, settings, and replayable run history
gammaLoop save schema	Regenerate the JSON schema files for CLI and runtime configuration
gammaLoop run	Execute a stored command block or an inline command list
gammaLoop start_commands_block	Begin recording subsequent commands under a reusable block name
gammaLoop finish_commands_block	Stop recording commands and store the active command block
gammaLoop remove	Remove generated processes from the active state
gammaLoop remove processes	Remove one integrand, one process, or all processes selected by the supplied target
gammaLoop integrate	Integrate one or more generated process integrands
gammaLoop generate	Generate cross-section or amplitude integrands from a process specification
gammaLoop generate xs	Generate a cross-section integrand through the forward-scattering construction
gammaLoop generate amp	Generate an amplitude integrand for the supplied process specification
gammaLoop generate existing	Create another integrand from an existing process without regenerating its graphs
gammaLoop select	Select graph groups and write the selection to a new process or integrand

Command	Description
gammaLoop quit	End the interactive GammaLoop session without executing further commands
gammaLoop inspect	Inspect integrand contributions at one phase-space point or momentum configuration
gammaLoop approach	Sample an integrand while approaching a phase-space point along selected scaling axes
gammaLoop evaluate	Evaluate a vacuum amplitude analytically or numerically with Vakint
gammaLoop renormalize	Compute and export ultraviolet renormalization contributions for an amplitude
gammaLoop bench	Measure evaluation throughput at a fixed point over a target duration
gammaLoop profile	Profile ultraviolet or infrared scaling limits of a generated integrand
gammaLoop profile ultra-violet	Sample ultraviolet scaling rays and report the fitted large-momentum behavior
gammaLoop profile bulk	Probe multiple infrared scaling limits and report their fitted behavior in one run
gammaLoop 3Drep	Validate a graph or build its diagnostic three-dimensional energy representation
gammaLoop 3Drep validate	Check the selected graph for supported energy-representation kinematics
gammaLoop 3Drep build	Construct and export the selected graph's three-dimensional expression
gammaLoop batch	Evaluate a process-definition file against an HPC batch input and write named results
gammaLoop !	Run an operating-system shell command from the interactive GammaLoop session

Settings

Path	Type	Default
cli.global.display_directive	string	"info"
cli.global.generation.compile.compilation_mode	CompilationMode	"symjit"
cli.global.generation.compile.compiler	string	"g++"
cli.global.generation.compile.custom	array<string>	[]
cli.global.generation.compile.fast_math	boolean	true
cli.global.generation.compile.jit_direct_translation	boolean	true
cli.global.generation.compile.optimization_level	OptimizationLevel	"O3"
cli.global.generation.compile.unsafe_math	boolean	true
cli.global.generation.evaluator.active_level	integer	0
cli.global.generation.evaluator.compile	boolean	false
cli.global.generation.evaluator.coupling_powers	integer | null	no serialized default
cli.global.generation.evaluator.direct_translation	boolean	true
cli.global.generation.evaluator.do_bench	boolean	false

Path	Type	Default
cli.global.generation.evaluator.dodecagon_replacement	boolean	false
cli.global.generation.evaluator.homology_iterations	integer	1
cli.global.generation.evaluator.inbound_enumerator_functions	boolean	true
cli.global.generation.evaluator.iterative_orientation_optimization	boolean	true
cli.global.generation.evaluator.max_common_pair_cache_entries	integer	1000000
cli.global.generation.evaluator.max_common_pair_distance	integer	1000
cli.global.generation.evaluator.max_integer_scheme_variables	integer	500
cli.global.generation.evaluator.n_cores	integer	1
cli.global.generation.evaluator.symbolic_execution_mode	array<ExecutionMode, ContractionMode>	["Sequential","MinResultRank"]
cli.global.generation.evaluator.store_atom	boolean	false
cli.global.generation.evaluator.symmetrize	boolean	false
cli.global.generation.evaluator.symmetrize_function_map	boolean	false
cli.global.generation.evaluator.tensor_network_contraction_mode	TensorNetworkContractionMode	"action_and_size_cost"
cli.global.generation.evaluator.verbose	boolean	false
cli.global.generation.explicit_orientation_sum_only	boolean	false
cli.global.generation.feyngen.gamma_simplification_closure	boolean	false
cli.global.generation.force_cuts	array<array<string>>	[]
cli.global.generation.medium.mode	MediumMode	"vacuum"
cli.global.generation.medium.vacuum_only_interaction	boolean	false
cli.global.generation.orientation_pattern	string	no serialized default
cli.global.generation.override_lmb_heuristics	boolean	false
cli.global.generation.three_dimensional_representation_mode	RepresentationMode | array<RepresentationMode>	["cff"]
cli.global.generation.threshold_subtraction.assume_positive_external_energies	boolean	true
cli.global.generation.threshold_subtraction.check_esurface_at_generation	boolean	false
cli.global.generation.threshold_subtraction.disable_integrated_ct	boolean	false
cli.global.generation.threshold_subtraction.enable_thresholds	boolean	true
cli.global.generation.threshold_subtraction.esurface_existence_threshold	number	1e-7
cli.global.generation.threshold_subtraction.skip_thresholds_that_are_cuts	boolean	true
cli.global.generation.tropical_subgraph_table.disable_tropical_generation	boolean	false
cli.global.generation.tropical_subgraph_table.panic_on_fail	boolean	false
cli.global.generation.tropical_subgraph_table.target_omega	number	1.0
cli.global.generation.uniform_numerator_sampling_scale	UniformNumeratorSamplingScale	"ThreeD"
cli.global.generation.uv.add_markers	boolean	false
cli.global.generation.uv.final_integrand_dimension	FinalIntegrandDimension	"ThreeD"
cli.global.generation.uv.generate_integrated	boolean	true
cli.global.generation.uv.inner_products	boolean	true
cli.global.generation.uv.keep_markers	boolean	true
cli.global.generation.uv.local_uv_cts_from_expanded_4d_integrands	boolean	false

Path	Type	Default
cli.global.generation.uv.orchestrator	UVOrchestrator	"hedge_poset"
cli.global.generation.uv.project_integrated_uv_cts_on_tensor_integrals	boolean	true
cli.global.generation.uv.renormalization_type.MLU	ApproximationType	"MLU_divergent"
cli.global.generation.uv.renormalization_type.MLU_massive_power_divergent	ApproximationType	"MLU"
cli.global.generation.uv.renormalization_type.MLU_massless_power_divergent	ApproximationType	"MLU"
cli.global.generation.uv.renormalization_type.Unsubtracted	ApproximationType	"Unsubtracted"
cli.global.generation.uv.renormalization_type.custom.overall_factor	integer	1
cli.global.generation.uv.renormalization_type.custom.overall_factor_evaluated	integer	1
cli.global.generation.uv.renormalization_type.custom.overall_factor_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.subtraction_currents	array<CTRenormalizationRules>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_currents	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_currents_evaluated	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_currents_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_defaults	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_defaults_evaluated	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_defaults_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_identifier.external_pdg_set	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_identifier.internal_pdg_set	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_identifier_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_suffix	string	""
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_vectors	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_vectors_evaluated	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_integrated_ct_vectors_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.subtraction_overall_factor	integer	1
cli.global.generation.uv.renormalization_type.custom.subtraction_overall_factor_evaluated	integer	1
cli.global.generation.uv.renormalization_type.custom.subtraction_overall_factor_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.subtraction_vectors	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_vectors_evaluated	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.subtraction_vectors_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.uv_dod_to_lambda_power_offset	integer	0
cli.global.generation.uv.renormalization_type.custom.uv_dod_to_log_power_offset	integer	0
cli.global.generation.uv.renormalization_type.custom.uv_propagator_power_to_subtract	integer	0
cli.global.generation.uv.renormalization_type.custom.uv_propagator_powers_to_subtract	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.uv_propagator_vectors_to_subtract	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.uv_vertex_power_to_subtract	integer	0
cli.global.generation.uv.renormalization_type.custom.uv_vertex_vectors_to_subtract	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.vakint_expression	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_numerator_rank	integer	0
cli.global.generation.uv.renormalization_type.custom.vakint_numerator_rank_evaluated	integer	0
cli.global.generation.uv.renormalization_type.custom.vakint_numerator_rank_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_topology_name	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_topology_name_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_topology_powers	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.vakint_topology_powers_evaluated	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.vakint_topology_powers_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_topology_propagators	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.vakint_topology_propagators_evaluated	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.vakint_topology_propagators_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_topology_vectors	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.vakint_topology_vectors_evaluated	array<integer>	[]
cli.global.generation.uv.renormalization_type.custom.vakint_topology_vectors_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_dot_product_notation	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_pysecdec_integrator_for_numerical_evaluation	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_pysecdec_integrator_for_symbolic_evaluation	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_q_shift_for_numerical_evaluation	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_q_shift_for_symbolic_evaluation	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_numerical_evaluation	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_evaluation	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_evaluation_of_integrated_ct	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_evaluation_of_integrated_ct_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_evaluation_of_integrated_ct_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_evaluation_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrated_ct_evaluation	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrated_ct_evaluation_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrated_ct_evaluation_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrated_ct_integration	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrated_ct_integration_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrated_ct_integration_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrated_ct_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integration	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integration_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integration_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol	null	null
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol_evaluated	boolean	false
cli.global.generation.uv.renormalization_type.custom.vakint_use_vakint_integrator_for_symbolic_integrator_symbol

Path	Type	Default
cli.global.n_cores.integrate	integer	1
cli.override_state	boolean	false
cli.state.folder	string	"./gammaloop_state"
cli.state.name	string | null	""
cli.try_strings	boolean	true
runtime.general.additional_param_values	array<number>	[]
runtime.general.debug_cache	boolean	false
runtime.general.disable_flux_factor	boolean	false
runtime.general.enable_cache	boolean	false
runtime.general.evaluator_method	EvaluatorMethod	"SingleParametric"
runtime.general.generate_events	boolean	false
runtime.general.integral_unit	IntegralUnit	"auto"
runtime.general.inverse_temperature	number	1.0
runtime.general.load_compiled_cff	boolean	false
runtime.general.m_uv	number	1000.0
runtime.general.mu_r	number	1000.0
runtime.general.numerator_sampling_scale	number	1.0
runtime.general.orientation_pat.pat	null | string	no serialized default
runtime.general.renormalization_local_ca	number	1000.0
runtime.general.store_additional_weights_in	boolean	false
runtime.h_function.enabled_dampening	boolean	true
runtime.h_function.function	HFunction	"poly_exponential"
runtime.h_function.power	integer | null	no serialized default
runtime.h_function.sigma	number	1.0
runtime.integrator.bin_number_evolution	array | null	no serialized default
runtime.integrator.continuous_dim_learning	number	1.0
runtime.integrator.discrete_dim_learning	number	1.0
runtime.integrator.integrated_phase	IntegratedPhase	"real"
runtime.integrator.max_prob_ratio	number	30.0
runtime.integrator.min_samples_for_update	integer	1000
runtime.integrator.n_bins	integer	64
runtime.integrator.n_increase	integer	10000
runtime.integrator.n_max	integer	10000000000
runtime.integrator.n_start	integer	100000
runtime.integrator.observables_output_format	array<ObservableFileFormat>	["Json"]
runtime.integrator.seed	integer	69
runtime.integrator.show_max_wgt_info	boolean	true
runtime.integrator.target_absolute_accuracy	number | null	no serialized default
runtime.integrator.target_relative_accuracy	number | null	no serialized default
runtime.integrator.train_on_avg	boolean	false

Path	Type	Default
runtime.kinematics.e_cm	number	64.0
runtime.kinematics.externals.data.parameters	array<integer | string>	[]
runtime.kinematics.externals.data.improvement_settings	improvement_settings	log_large_deformation_check
runtime.kinematics.externals.data.improvement_settings.mode	ImprovementMode	"none"
runtime.kinematics.externals.data.improvement_settings.only_warn_on_large_deformation	boolean	false
runtime.kinematics.externals.data.momenta	array<Dep | array<number>>	[]
runtime.kinematics.externals.type	string	"constant"
runtime.model	object	{}
runtime.observables	object	{}
runtime.quantities	object	{}
runtime.sampling.alpha	number	3.0
runtime.sampling.b	number	1.0
runtime.sampling.channel_definitions	object	no serialized default
runtime.sampling.channel_selection	object	no serialized default
runtime.sampling.coordinate_system	CoordinateSystem	"spherical"
runtime.sampling.default_channel_selection	array<string>	no serialized default
runtime.sampling.graph_names	array<string>	[]
runtime.sampling.graphs	SumMode	"summed"
runtime.sampling.lmb_basis_ids	object	no serialized default
runtime.sampling.mapping	ParameterizationMapping	"linear"
runtime.sampling.orientations	SumMode	"summed"
runtime.sampling.power	number	1.0
runtime.sampling.sampling_channel_weight	SamplingChannelWeight	"gmap_density"
runtime.sampling.sampling_channels	SumMode	"summed"
runtime.sampling.sampling_multichanneling	boolean	false
runtime.selectors	object	{}
runtime.stability.check_on_norm	boolean	true
runtime.stability.escalate_if_exact_zero	boolean	false
runtime.stability.integrated_energy_dimension	integer | null	no serialized default
runtime.stability.levels	array<StabilityLevelSetting>	[{"ecm_relative_tolerance_for_im":0.0,"ecm_rela {"ecm_relative_tolerance_for_im":0.0,"ecm_relat {"ecm_relative_tolerance_for_im":0.0,"ecm_relat
runtime.stability.levels[].ecm_relative_tolerance_for_im	number | null	no serialized default
runtime.stability.levels[].ecm_relative_tolerance_for_re	number | null	no serialized default
runtime.stability.levels[].escalate_for_large_weight_threshold	number | null	no serialized default
runtime.stability.levels[].precision	Precision	no serialized default
runtime.stability.levels[].required_precision_for_im	number | null	no serialized default
runtime.stability.levels[].required_precision_for_re	number | null	no serialized default
runtime.stability.levels[].three_d_representation	RepresentationMode | null	no serialized default

Path	Type	Default
runtime.stability.loop_momenta_norm_escala	number	1.0
runtime.stability.min_abs_wgt_for_escalation	number	0.0
runtime.stability.recording.recorded_stability_levels	array<integer>	no serialized default
runtime.stability.recording.recorded_loop_momenta_escalation	boolean	no serialized default
runtime.stability.recording.recorded_rotated_results	boolean	no serialized default
runtime.stability.rotation_axis	array<object>	[{"alpha":0.1,"beta":0.2,"gamma":0.3,"type":"eu
runtime.stability.rotation_axis[].alpha	number	no serialized default
runtime.stability.rotation_axis[].beta	number	no serialized default
runtime.stability.rotation_axis[].gamma	number	no serialized default
runtime.stability.rotation_axis[].type	string	no serialized default
runtime.subtraction.disable_threshold_subtraction	boolean	false
runtime.subtraction.esurface_existence_threshold	number	1e-7
runtime.subtraction.integrated_ct_settings	settings.range.h_function_settings	function_settings.enabled_dampening
runtime.subtraction.integrated_ct_settings.h_function_settings	string	"poly_exponential"
runtime.subtraction.integrated_ct_settings.range	integer	1
runtime.subtraction.integrated_ct_settings.range.h_function_settings	number	function_settings.sigma
runtime.subtraction.integrated_ct_settings.range.type	string	"infinite"
runtime.subtraction.local_ct_settings.dynamic_width	boolean	false
runtime.subtraction.local_ct_settings.force_uv_dampers_to_one	boolean	false
runtime.subtraction.local_ct_settings.gaussian_width	number	1.0
runtime.subtraction.local_ct_settings.sliver_width	number	10.0
runtime.subtraction.local_ct_settings.smooth_sliver	boolean	false
runtime.subtraction.overlap_settings.check_global_center	boolean	true
runtime.subtraction.overlap_settings.force_global_center	array<number>	no serialized default
runtime.subtraction.overlap_settings.try_origin	boolean	true
runtime.subtraction.overlap_settings.try_origin_all_lmbs	boolean	false
runtime.subtraction.radial_root_residual_tolerance	number	64.0

Version information

Save these identifiers with published results and include them in issue reports so that collaborators can reproduce the same software environment.

- **Documentation channel:** `latest`
- **Documentation route:** `/products/gammaloop/latest/`
- **Source revision:** `227e3534a5fb39f64710b6754cc63f34ed4c95a7`

Package versions and enabled features

- `gammaloop/gammalooprs` — `0.3.4` (`no optional features`)
- `gammaloop/gammaloop-api` — `0.1.0` (`features: cli`)
- `gammaloop/gammaloop` — `0.3.4` (`features: python, abi3, python-stubs`)
- `linnet/linnet` — `0.17.0` (`features: native, serde, bincode, drawing, symbolica`)
- `linnet/linnet-py` — `0.1.0` (`features: extension-module, abi3`)
- `spenso/spenso` — `0.6.0` (`features: native, symbolica`)
- `spenso/spenso-macros` — `0.3.2` (`no optional features`)
- `spenso/spenso-hep-lib` — `0.1.7` (`features: native`)
- `spenso/spynso3` — `0.1.2` (`features: python-stubs`)
- `idenso/idenso` — `0.3.0` (`features: native, reference-cases`)
- `idenso/idenso` — `0.3.0` (`features: python, python-stubs`)
- `vakint/vakint` — `0.1.2` (`no optional features`)
- `vakint/vakint` — `0.1.2` (`features: python, python-stubs`)