Introduction: Primary aldosteronism (PA) is more common than previously thought. Up to 15% of all hypertension is due to PA. PA can be caused by bilateral or unilateral hyperplasia, an adenoma, or by mutations in genes coding for enzymes involved in aldosterone (AS) synthesis. Adrenal venous sampling (AVS) is a procedure used to diagnose the source of the excess aldosterone (i.e. whether it is uni- or bilateral). Why is this important? Because unilateral PA is treated surgically, whereas bilateral PA is managed medically. AVS is, by far, the most reliable way of establishing the source of excess AS.

The procedure: With AVS, the difference between left and

right adrenal AS excretion is measured by sampling blood from each adrenal vein (AV). This is more complicated than it sounds, mostly for anatomical reasons. The right adrenal vein is very short and originates directly from the inferior vena cava (IVC), making it very difficult to cannulate. The left AV originates from a common trunk with the inferior phrenic vein (IPV), which, in turn, originates from the left renal vein. The common trunk is easier to cannulate than the left AV itself, but dilution from the IPV must then be compensated for when interpreting the AS level (in the common trunk, left AV blood is mixed with IPV blood, which obviously has a lower AS concentration).