Enterprise ERP

ADMINISTRATOR HANDBOOK · VERSION 1.0

Admin hierarchy & access dena

Sab se upar wala admin apne neeche admins kaise banata hai, aur har level apne neeche walon ko access kaise deta hai — har click ke screenshot ke sath.

- Platform Owner → Company + Company Owner
- Company Owner → Company Administrator ("chhota admin")
- Admin → branch-restricted HR, Accountant, Department Manager
- Custom roles, kis role ko kya dikhta hai, access wapas lena, audit log

Version 1.0 **Date** 16 October 2026 **Audience** Owners & administrators

Table of contents

Kisi bhi heading par click karein — seedha us page par pahunch jayenge.

1 **Admin hierarchy — kaun kis ko access deta hai** 4
- 1.1 Is guide ka maqsad 4
- 1.2 Levels (seedhi) 4
- 1.3 Kaun kis ko bana sakta hai 5
- 1.4 Teen bunyadi qawaid 6

2 **Level 0 — Platform Owner (super admin)** 7
- 2.1 Platform Owner banana (server par, aik dafa) 7
- 2.2 Pehla login aur 2FA 8

3 **Platform Owner → Company + Company Owner** 9
- 3.1 Nayi company aur us ka owner banana 9
- 3.2 Owner ko email — aur development mein link kahan milta hai 12
- 3.3 Owner apna password set karta hai 12
- 3.4 Platform Admin banana (sirf Platform Owner) 15

4 **Company Owner → Company Administrator** 18
- 4.1 Company Administrator kyun? 18
- 4.2 Invite karna — step by step 18
- 4.3 Admin ko kya nazar aata hai 21

5 **Admin → department heads (branch restriction ke sath)** 23
- 5.1 Misaal ka plan 23
- 5.2 Branch-restricted user invite karna 23
- 5.3 Branch restriction ka asar 25

6 **Custom role banana aur assign karna** 27
- 6.1 Custom role kab? 27
- 6.2 Role banana — step by step 27
- 6.3 Custom role assign karna 30
- 6.4 System roles edit karna aur Owner role lock 33

7 **Kis role ko kya dikhta hai** 36
- 7.1 Sidebar hi pehli nishani hai 36
- 7.2 Gallery 36
- 7.3 Permission matrix (module × role) 38

8 Access badalna, rokna aur hatana 41

8.1 Chaar tareeqe — kab kaunsa 41
8.2 Role badalna 41
8.3 Membership deactivate karna 43
8.4 Company se remove karna aur platform-level deactivate 45
8.5 Jab koi bina ijazat page khole 49
8.6 Audit log mein sab tabdeeliyan 50

9 Maker–checker: banane wala approve nahi karta 54

9.1 Maker–checker kya hai? 54
9.2 Misaal: manager ki apni requisition 54
9.3 Roles bante waqt separation ka khayal 56

10 Best-practice checklist 57

10.1 Shuru mein (aik dafa) 57
10.2 Naya shakhs aaye to 57
10.3 Har mahine review 57
10.4 Koi chhor kar jaye to (usi din) 57
10.5 Bahar ke auditor ke liye 58

CHAPTER 1

Admin hierarchy — kaun kis ko access deta hai

Poore system ki "seedhi": sab se upar Platform Owner, neeche company ke log.


1.1 Is guide ka maqsad

Is guide mein hum aik **asli misaal** step-by-step chalayenge: sab se upar wala admin (Platform Owner) aik nayi company aur us ka owner banata hai; Company Owner apne liye aik "chhota admin" (Company Administrator) banata hai; woh admin branch-wise managers banata hai aur zaroorat par custom role. Aakhir mein dekhenge ke access wapas kaise liya jata hai aur sab kuch audit log mein kaise nazar aata hai.

Har screenshot mein jis button ya field par click karna hai, us ke gird **laal (red) box** hai, aur jahan kai steps hain wahan 1 2 3 jaise numbers — wohi order follow karein.

> **NOTE**
> Screenshots development database ke hain. Is guide ke liye **fictional** demo log aur company banayi gayi: `Guide Demo Co (Demo)`, `sub.admin@northwind.test`, `branch.hr@northwind.test` waghera. Asli company mein aap apne logon ke naam aur emails use karenge.

1.2 Levels (seedhi)



1.3 Kaun kis ko bana sakta hai

Table 1.1 — Access dene ka ikhtiyar

Kaun	Kya bana / de sakta hai	Kahan se
Server ka IT person	Sirf pehla Platform Owner (aik dafa)	`php artisan erp:create-admin`
Platform Owner	Nayi company + us ka Company Owner; Platform Admin banana/hatana; kisi bhi account ko poore platform par deactivate	**Platform → Companies**, **Platform → Platform users**
Platform Admin	Companies aur accounts manage; platform roles **nahi** de sakta	Platform panel
Company Owner	Company mein koi bhi user, koi bhi role (Company Owner samet); roles edit; custom roles	**Users & roles → Users** / **Roles & permissions**
Company Administrator	Users invite/edit/remove, roles edit, custom roles — kyun ke us ke paas "Invite, update, deactivate users" aur "Manage roles & permissions" hai	Wohi pages
Baqi roles	Kisi ko access nahi de sakte (users.manage / roles.manage nahi)	—

SECURITY

Access dene ka ikhtiyar bhi aik permission hai: "Invite, update, deactivate users" (users.manage) aur "Manage roles & permissions" (roles.manage). Jis role ko yeh do permissions dein, woh admin ban jata hai — is liye yeh sirf bharosemand logon ko dein.

1.4 Teen bunyadi qawaid

- **Access roles se aati hai** — user ki permissions us ke tamam roles ka majmooa (union) hain, aur yeh **har company mein alag** hain.
- **Branch restriction** — user ko sirf kuch branches tak rakha ja sakta hai; phir woh dusri branches ka branch-wise data nahi dekhta.
- **Server faisla karta hai** — menu chhupana sirf suhulat hai; koi URL khud type kare tab bhi server permission check karta hai.

TIP

Aam usool: **Owner kam, Admin chand, baqi sab apne kaam ke role mein.** Har shakhs ka apna login ho — shared accounts nahi.

CHAPTER 2

Level 0 — Platform Owner (super admin)

Sab se upar wala account kaise banta hai aur pehla login.

2.1 Platform Owner banana (server par, aik dafa)

ERP mein koi default "admin/admin" account nahi. Pehla super admin server par command chala kar banaya jata hai. Backend folder mein:

```
Development

PS C:\…\ERP\backend> php artisan erp:create-admin

 Full name:
 > Adnan Ahmed

 Email:
 > adnan@yourcompany.com

 Password (min 10 chars, letters + numbers):
 >

 INFO  Platform owner created: adnan@yourcompany.com
 WARN  Enable two-factor authentication for this account after first login.
```

1. Naam, apna asli email, aur mazboot password dein (kam az kam 10 characters, letters + numbers; leaked passwords reject hote hain).
2. "Platform owner created" message ka matlab kaam ho gaya; yeh event audit log mein bhi jata hai.

Production server par

```
Production

# 1) backend/.env:   ERP_ALLOW_ADMIN_BOOTSTRAP=true    (config:cache use karte hain to dobara cache
karein)
# 2) command (password prompt par dein, command line par nahi):
php artisan erp:create-admin --force
# 3) foran wapas:     ERP_ALLOW_ADMIN_BOOTSTRAP=false
```

> ⚠ **DHYAN DEIN**
>
> Production mein flag ya `--force` ke baghair command inkaar karti hai, `--password` option refuse hota hai (shell history ki wajah se), aur agar Platform Owner pehle se ho to dusra isi tareeqe se nahi banta — "Manage further admins from the platform panel."

2.2 Pehla login aur 2FA

1. Browser mein ERP kholein, apne email/password se **Sign in** karein.
2. Platform Owner ka sidebar sirf **Platform** section dikhata hai: **Companies**, **Platform users**, **System**. Woh kisi company ka business data nahi dekhta.
3. Upar right Account menu → **Security** kholein aur **Set up two-factor** (1) dabayein.
4. Password dobara confirm karein, phone ki authenticator app se QR scan karein, 6-digit code daal kar Verify & enable, aur recovery codes mehfooz rakhein.




Figure 2.1 — Platform Owner → Security: Two-factor authentication "Off" — Set up two-factor (1).

> **SECURITY**
> Platform Owner poori installation ki chaabi hai. Is account par 2FA **lazmi** on karein aur password kisi ke sath share na karein.

> **TIP**
> Platform Owner jab Dashboard kholta hai to "Dashboard unavailable" aata hai — yeh normal hai, kyun ke platform staff company data nahi dekhte.

CHAPTER 3

Platform Owner → Company + Company Owner

Nayi company banana, owner ko invitation, owner ka password set karna aur Platform Admin.

3.1 Nayi company aur us ka owner banana

Platform Owner ka sab se aham kaam: nayi company "provision" karna. Is ke sath hi company ka pehla shakhs — **Company Owner** — invite hota hai.

1 Sidebar mein **Companies** 1 kholein, upar right **New company** 2 dabayein.




Figure 3.1 — Platform → Companies — (1) Companies menu, (2) New company button.

1 "Provision a company" drawer mein **Name** 1 likhein (yahan "Guide Demo Co (Demo)"), phir **Legal name**, **Email**, **Country** (ISO code, maslan PK), **Base currency** (PKR) aur **Time zone** (Asia/Karachi).

2 **Demo company** 2 — sirf training/testing company ke liye on karein. Asli company ke liye **off** rakhein.




Figure 3.2 — Company section — (1) Name, (2) Demo company switch (sirf is fictional company ke liye on).

1. Neeche **Owner** section: **Owner name** (3) aur **Owner email** (4). Hint: "Existing users are added as owner; new users receive an email to set their password."
2. **Create company** (5) dabayein.




Figure 3.3 — Owner section — (3) Owner name, (4) Owner email, (5) Create company.

System khud: company, aik **head office** branch, **10 standard roles**, **chart of accounts** aur defaults banata hai, owner ko **Company Owner** role deta hai, aur email bhejta hai.




Figure 3.4 — Nayi company list mein — "Guide Demo Co (Demo)" Demo badge ke sath.

3.2 Owner ko email — aur development mein link kahan milta hai

Naye owner ko do emails jati hain: (1) "You've been added to Guide Demo Co (Demo)" — "An account was created for you… Check your inbox for a link to set your password, then sign in." aur (2) **Reset Password** email jis mein password set karne ka link hota hai. Kisi email mein password nahi hota.

Development mein `MAIL_MAILER=log` hota hai — email bheji nahi jati, balke `backend\storage\logs\laravel.log` file ke aakhir mein likhi jati hai. File Notepad/VS Code mein kholein aur neeche se `reset-password` search karein:

```
backend\storage\logs\laravel.log (token yahan chhupaya gaya hai)

[2026-10-15 20:06:46] local.DEBUG: From: Enterprise ERP <hello@example.com>
To: guide.owner@guidedemo.test
Subject: Reset your password
You are receiving this email because we received a password reset request for your account.
Reset Password: http://localhost:3000/reset-password?token=
<redacted>&email=guide.owner%40guidedemo.test
This password reset link will expire in 60 minutes.
If you did not request a password reset, no further action is required.
```

> ⚠ **DHYAN DEIN**
>
> Yeh link aik **secret** hai — jis ke paas link ho woh password set kar sakta hai. Link sirf us shakhs ko dein jis ke liye hai, aur production mein asli mail server (MAIL_*) configure karein taake link seedha owner ke inbox mein jaye. Link kuch der baad expire ho jata hai; phir login page ka "Forgot password?" use karein.

3.3 Owner apna password set karta hai

1. Owner email ka link kholta hai — "Choose a new password" page, upar us ka email likha hota hai.
2. **New password** (1) aur **Confirm password** (2) — kam az kam 10 characters, letters + numbers, aur koi leaked password nahi.
3. **Update password** (3) dabata hai. "Other active sessions will be signed out."




Figure 3.5 — Reset password page — (1) New password, (2) Confirm password, (3) Update password.




Figure 3.6 — Update password dabane ke baad — password save ho raha hai; is ke baad owner login page se sign in karta hai.

1. Owner login karta hai — us ki nayi company ka khaali dashboard (currency PKR) aur poora sidebar nazar aata hai.
2. Sab se pehle: Account menu → Security → two-factor on (chapter 2.2 jaisa).
3. **Users & roles → Roles & permissions** mein 10 tayyar roles maujood hain.




Figure 3.7 — Guide Owner ka pehla login — nayi company "Guide Demo Co (Demo)", sab KPIs zero, poora menu.




Figure 3.8 — Nayi company ke 10 standard roles — Company Owner "Locked", baqi "System".

3.4 Platform Admin banana (sirf Platform Owner)

Agar Platform Owner ko madadgar chahiye jo companies aur accounts manage kare, to woh kisi account ko **Platform Admin** bana sakta hai:

1. **Platform users** kholein — har account ki platform role, companies ki tadaad, 2FA aur last sign-in nazar aata hai.
2. Us user ki row ke aakhir mein ⋯ (Row actions) dabayein.
3. **Make ... a platform admin** (1) chunein — confirm dialog aata hai.
4. Confirm karein. (Is guide mein demo ke liye dialog **cancel** kiya gaya — kisi ko platform role nahi diya gaya.)




Figure 3.9 — Platform users — tamam accounts, platform role, 2FA status.




Figure 3.10 — Row actions menu — (1) platform admin banane ka option; "Deactivate account" bhi yahin hai.




Figure 3.11 — Confirm dialog — Platform admins poore platform par companies aur users manage kar sakte hain.

NOTE

Sirf **Platform Owner** platform roles de ya hata sakta hai ("Only a platform owner can change platform roles"), aur koi apni platform role khud nahi badal sakta.

SECURITY

Platform staff (Owner/Admin) kisi company ka business data — employees, salaries, invoices — **nahi** dekh sakte jab tak woh us company ke member na hon. Platform panel sirf companies aur accounts ka intezam hai.

TIP

Agar Owner email ghalat likh di gayi ho to company ke Users page se sahi shakhs ko Company Owner role ke sath invite karein, phir ghalat account remove karein.

CHAPTER 4

Company Owner → Company Administrator

Roz ke admin kaam ke liye "chhota admin" banana.

4.1 Company Administrator kyun?

Company Owner ke paas har cheez ka ikhtiyar hai aur us ka role **locked** hai. Roz-marrah ka kaam — users add karna, roles theek karna, settings — aik **Company Administrator** ko dein, taake Owner ka login kam se kam istemal ho.

Table 4.1 — config/erp.php: "Manages users, settings and all modules except payroll processing." — 88 permissions

Company Administrator	
Kar sakta hai	Users invite/edit/deactivate/remove, roles aur permissions manage, company settings & branding, branches, departments, aur tamam modules (HR, finance, sales, inventory, projects…), audit log, reports export.
Nahi kar sakta	"Run & approve payroll" (payroll.process) — default role mein shamil nahi. Company Owner role edit nahi kar sakta (locked). Apni membership edit/deactivate/remove nahi kar sakta.

4.2 Invite karna — step by step

1. Company Owner (yahan `owner@northwind.test`) sidebar mein **Users & roles → Users** (1) kholta hai.
2. Upar right **Invite user** (2) dabata hai.




Figure 4.1 — Users page — (1) Users menu, (2) Invite user.

1. "Invite a user" drawer: **Full name** (1) aur **Work email** (2).
2. **Roles** mein **Company Administrator** (3) tick karein.
3. **Access to all branches** (4) on rehne dein — admin ko poori company chahiye.
4. **Send invitation** (5).




Figure 4.2 — Invite drawer — (1) naam, (2) email, (3) Company Administrator role, (4) Access to all branches, (5) Send invitation.




Figure 4.3 — Naya admin list mein (neeche laal box) — role "Company Administrator", Branches "All", Last sign-in ki jagah "Invite pending"; "User created" toast. Pehle login tak row menu mein "Resend invitation" bhi hota hai.

Naye shakhs ko company ka invitation email aur password-set link milta hai (chapter 3.2 jaisa). Woh password set karke login karta hai.

> **NOTE**
> Is guide mein development ki suhulat ke liye invited demo users ka password server par seedha set kiya gaya (`php artisan tinker`). Asli users hamesha emailed link se khud password chunte hain — admin ko kabhi kisi ka password maloom nahi hona chahiye.

4.3 Admin ko kya nazar aata hai




Figure 4.4 — sub.admin@northwind.test ka dashboard — Owner jaisa poora menu (Users & roles samet).

> **DHYAN DEIN**
> **Ahem — admin ko taqreeban Owner jitna bharosemand samjhein.** Company Administrator ke paas "Manage roles & permissions" aur "Invite users" hai. Is version mein system usay yeh karne se nahi rokta: (a) kisi naye user ko **Company Owner** role dena, ya (b) **Company Administrator** system role mein khud "Run & approve payroll" permission add kar dena. Yani "payroll processing ke siwa" wali hadd tooti ja sakti hai. Is liye admin sirf bharosemand shakhs ko banayein, aur Audit log (Roles & permissions, Users) par nazar rakhein.

> **TIP**
>
> Kam log hon to bhi Owner aur Admin alag accounts rakhein — Owner ka password aur 2FA mehfooz jagah, roz ka kaam Admin se.

CHAPTER 5

Admin → department heads (branch restriction ke sath)

HR Manager, Accountant aur Department Manager — har aik sirf apni branch tak.

5.1 Misaal ka plan

Ab Company Administrator (`sub.admin@northwind.test`) teen department heads banata hai. Har aik ko sirf **aik branch** ka access milega:

Table 5.1 — Is chapter mein banaye gaye users

Shakhs (fictional)	Login	Role	Branch
Branch HR (Guide Demo)	`branch.hr@northwind.test`	HR Manager	Boston Office (BOS)
Branch Accountant (Guide Demo)	`branch.accountant@northwind.test`	Accountant	Chicago Office (CHI)
Branch Manager (Guide Demo)	`branch.manager@northwind.test`	Department Manager	Austin Office (AUS)

5.2 Branch-restricted user invite karna

1. Admin **Users & roles → Users** → **Invite user** dabata hai.
2. **Full name** aur **Work email** bharta hai.
3. **Roles** mein munasib role tick karta hai — yahan **HR Manager**.
4. **Access to all branches** 2 ko **off** karta hai — neeche **Allowed branches** list khul jati hai.
5. Sirf us branch ko tick karta hai — yahan **Boston Office (BOS)** 3.
6. **Send invitation** 4.
7. Yahi amal Accountant (Chicago) aur Department Manager (Austin) ke liye dohrayein.




Figure 5.1 — HR Manager role tick; (2) Access to all branches OFF, (3) sirf Boston Office, (4) Send invitation.




Figure 5.2 — Teen naye users — Branches column mein "All" ke bajaye "1 selected" (branch-restricted); Last sign-in "Never".

> **TIP**
> Kis branch ka access hai, yeh dekhne ke liye row ke ⋯ menu → **Edit access** kholein — wahan ticked branches nazar aati hain.

5.3 Branch restriction ka asar

Branch-restricted user ke topbar se **All branches** filter ghaib ho jata hai, aur is version mein yeh modules us ki allowed branches tak mehdood hain: **customer invoices, supplier bills, payments/receipts, journal entries, payroll runs aur payslips, warehouses, projects, dashboard aur reports/exports**.

> **⚠ DHYAN DEIN — KNOWN LIMITATION**
> **Is version ki hadd (known limitation):** kuch lists abhi branch restriction lagu **nahi** kartin — maslan **HR → Employees**. Neeche screenshot mein Boston tak mehdood Branch HR ko Head Office aur Chicago ke employees bhi nazar aa rahe hain. Isi tarah sales orders, purchase orders, attendance, leave aur stock lists bhi abhi branch se filter nahi hotin. Jab tak yeh theek na ho, branch restriction ko in modules ke liye hifazati deewar na samjhein — role ki permissions hi asal hadd hain.




Figure 5.3 — branch.hr@northwind.test (sirf Boston) ki Employees list — abhi doosri branches (Head Office, Chicago) ke employees bhi dikh rahe hain; yeh known limitation hai.

- Restriction role ki permissions ke **upar** lagti hai: pehle role decide karta hai kaunsa module, phir branch decide karti hai kaunse records.
- Jin records par branch set nahi (company-wide), woh role ke mutabiq nazar aate hain.

- Aik user ko kai branches di ja sakti hain — maslan regional manager ko do offices.

> **NOTE**
> HR Manager role mein "Run & approve payroll" bhi hai. Branch HR ko sirf apni branch ka payroll chalana ho to payroll run banate waqt scope mein branch chunein; agar payroll bilkul nahi dena to custom role banayein (chapter 6).

CHAPTER 6

Custom role banana aur assign karna

"Branch Sales Supervisor (Demo)" — sirf zaroori permissions ke sath.

6.1 Custom role kab?

Jab 10 default roles mein se koi bhi bilkul fit na ho — maslan aap chahte hain ke branch ka sales supervisor customers dekhe, quotations banaye, sales orders dekhe aur reports dekhe, lekin invoices, leads ya stock nahi. Is misaal mein role ki permissions:

- `dashboard.view` — View executive dashboard
- `customers.view` — View customers
- `quotations.view` + `quotations.manage` — View / Manage quotations
- `sales_orders.view` — View sales orders
- `reports.view` — View reports

6.2 Role banana — step by step

1 **Users & roles → Roles & permissions** kholein, upar right **New role** 1.




Figure 6.1 — Roles & permissions — (1) New role.

1. **Name** (1) (yahan "Branch Sales Supervisor (Demo)") aur **Description** likhein.




Figure 6.2 — New role drawer — (1) role ka naam aur description.

1. **Filter permissions** (2) box mein likh kar permission dhoondein — maslan "quotation".
2. Matching checkboxes tick karein (3): **View quotations**, **Manage quotations**. Har checkbox ke neeche technical code (`quotations.view`) bhi likha hai.
3. Filter saaf karke baqi permissions bhi isi tarah tick karein. Upar "6 permissions selected" ginti nazar aati hai.




Figure 6.3 — Filter permissions — (2) "quotation" search, (3) dono quotation permissions tick. Upar: "6 permissions selected".

1 Poori list dobara dekh lein, phir **Create role** 4 dabayein.




Figure 6.4 — Saari selected permissions — (4) Create role.




Figure 6.5 — Naya role card — "Custom" badge, 0 users, 6 permissions; custom role ka Edit aur Delete dono.

6.3 Custom role assign karna

1. **Users & roles → Users** → **Invite user** (naya shakhs) — ya maujooda user ke ⋯ → **Edit access**.
2. **Roles** list mein custom role bhi nazar aata hai — **Branch Sales Supervisor (Demo)** 1 tick karein.
3. Branch restriction: **Access to all branches** off, **Boston Office (BOS)** tick.
4. **Send invitation** / **Save access**.




Figure 6.6 — Invite drawer mein custom role (1) — sirf Boston Office ke liye.

Supervisor login karta hai to us ka sidebar bohat mukhtasar hota hai — sirf dashboard, Sales & CRM (customers, quotations, sales orders, sales reports) aur Reports:




Figure 6.7 — branch.sales@northwind.test (custom role) ka dashboard aur sidebar.




Figure 6.8 — Supervisor Quotations page par — "Manage quotations" ki wajah se naya quotation bana sakta hai.

6.4 System roles edit karna aur Owner role lock

System roles (jaise Accountant) ka **naam aur description fixed** hain, lekin permissions badli ja sakti hain: "System role: the name is fixed, but you can adjust its permissions." Tabdeeli us role ke **tamam** users par foran lagu hoti hai.




Figure 6.9 — Accountant (system role) editor — naam/description disabled, permissions checkboxes editable.




Figure 6.10 — Company Owner role — "The Company Owner role always has every permission and cannot be edited." Sirf View.

> ⚠ **DHYAN DEIN**
>
> System role ki permission badalne se pehle sochein: maslan Accountant role se kuch hataya to company ke **har** accountant par asar hoga. Aksar behtar hai ke system role ko chhor kar naya custom role banayein.

> ℹ **NOTE**
>
> Custom role tabhi delete hota hai jab us ke paas koi user na ho — pehle users se role hatayein. System roles delete nahi hote.

> 💡 **TIP**
>
> Har role tabdeeli audit log mein "Roles & permissions" category mein record hoti hai (chapter 8.5).

CHAPTER 7

Kis role ko kya dikhta hai

Das default roles ke dashboards/sidebars aur poora permission matrix.

7.1 Sidebar hi pehli nishani hai

Har user ko sirf woh menus nazar aate hain jin ki us ke role mein permission ho. Neeche Northwind demo company ke 10 demo logins (`<role>@northwind.test`) ke screenshots hain — login ke foran baad ka dashboard aur poora sidebar.

> **NOTE**
>
> Kuch roles (jaise Employee) ke dashboard par finance widgets "No data for this period" dikhate hain — un ke paas woh data dekhne ki permission nahi; yeh khaali hona normal hai.

7.2 Gallery




Figure 7.1 — **Company Owner** — Poora menu — Organisation, People, Finance, Operations, Insights (Audit log samet).




Figure 7.2 — **Company Administrator** — Owner jaisa menu; payroll mein runs dekh/structures manage kar sakta hai, process nahi.




Figure 7.3 — HR Manager — Company (view), HR, Payroll, Documents, Approvals, Reports.




Figure 7.4 — Accountant — Accounting, Receivables, Payables, financial reports; customers/suppliers sirf view.




Figure 7.5 — Sales Manager — Sales & CRM, invoices (bana sakta hai, approve nahi), products/stock view.




Figure 7.6 — Inventory Manager — Inventory poora, goods receipts, POs/sales orders view.




Figure 7.7 — Procurement Officer — Procurement (suppliers, requisitions, POs, goods receipts), bills banana.




Figure 7.8 — Department Manager — Approvals (leave, requisitions, expenses), Projects, team HR view.




Figure 7.9 — Employee — Sirf self-service: leave, attendance, payslips, expense claims, tasks, documents.




Figure 7.10 — Read-Only Auditor — Har module dekh sakta hai + Audit log; koi "New"/"Edit" button nahi.

7.3 Permission matrix (module × role)

Yeh table database mein assign ki gayi asli permissions se banayi gayi hai (source: `backend/config/erp.php` role_templates).

✓ = poora access 👁 = sirf dekhna ◐ = kuch actions — = koi access nahi

Module / area	Owner	Admin	HR Mgr	Accountant	Sales Mgr	Inventory Mgr	Procurement	Dept Mgr	Employee	Auditor
Dashboard	✓	✓	✓	✓	✓	✓	✓	✓	✓	✓
Company profile & settings	✓	✓	👁	👁	👁	👁	👁	👁	👁	👁
Branches & departments	✓	✓	◐	👁	👁	👁	👁	👁	—	👁
Users & roles	✓	✓	—	—	—	—	—	—	—	👁
Employees (HR records)	✓	✓	✓	—	—	—	—	👁	—	👁
Attendance & shifts	✓	✓	✓	—	—	—	—	👁	—	👁
Leave	✓	✓	✓	—	—	—	—	◐	◐	👁
Performance reviews	✓	✓	✓	—	—	—	—	—	—	👁
Payroll (runs & setup)	✓	◐	✓	👁	—	—	—	—	—	👁
Own payslips	✓	✓	✓	—	—	—	—	✓	✓	—
Chart of accounts & journals	✓	✓	—	✓	—	—	—	—	—	👁
Customer invoices	✓	✓	—	✓	◐	—	—	—	—	👁
Supplier bills	✓	✓	—	✓	—	—	◐	—	—	👁
Payments & receipts	✓	✓	—	✓	👁	—	—	—	—	👁
Expense claims	✓	✓	—	◐	—	—	—	✓	◐	👁
Bank, tax & periods	✓	✓	—	✓	—	—	—	—	—	—
Financial reports	✓	✓	—	✓	—	—	—	—	—	✓
Customers & leads (CRM)	✓	✓	—	👁	✓	—	—	—	—	👁
Quotations & sales orders	✓	✓	—	—	✓	👁	—	—	—	👁
Suppliers & requisitions	✓	✓	—	👁	—	👁	✓	◐	—	👁
Purchase orders & goods receipts	✓	✓	—	—	—	◐	◐	—	—	👁
Products & warehouses	✓	✓	—	—	👁	✓	👁	—	—	👁
Stock operations	✓	✓	—	—	👁	✓	👁	—	—	👁
Projects, tasks & time	✓	✓	—	—	—	—	—	✓	◐	👁
Documents	✓	✓	✓	👁	👁	👁	👁	👁	👁	👁
Approvals inbox	✓	✓	✓	✓	✓	✓	✓	✓	—	✓
Reports & exports	✓	✓	✓	✓	✓	✓	👁	👁	—	✓
Audit log	✓	✓	—	—	—	—	—	—	—	✓

◐ ki tafseel

Area	Role	Yeh actions milte hain
Branches & departments	HR Manager	View branches; View departments; Manage departments
Leave	Department Manager	View leave requests; Submit own leave requests; Approve/reject leave
Leave	Employee	Submit own leave requests
Payroll (runs & setup)	Company Administrator	View payroll; Manage salary structures
Customer invoices	Sales Manager	View invoices; Create invoices; Update draft invoices
Supplier bills	Procurement Officer	View supplier bills; Create supplier bills
Expense claims	Accountant	View expense claims; Approve expense claims
Expense claims	Employee	Submit expense claims
Suppliers & requisitions	Department Manager	View purchase requisitions; Create purchase requisitions; Approve purchase requisitions
Purchase orders & goods receipts	Inventory Manager	View purchase orders; Record goods received
Purchase orders & goods receipts	Procurement Officer	View purchase orders; Manage purchase orders; Record goods received
Projects, tasks & time	Employee	View projects; View tasks; Manage tasks; Log time

Roles ka khulasa

Role	Description (system)	Permissions
Company Owner	Full access to everything in the company.	89
Company Administrator	Manages users, settings and all modules except payroll processing.	88
HR Manager	Employees, attendance, leave, performance and payroll.	28
Accountant	Finance, accounting, invoices, bills, payments and financial reports.	31
Sales Manager	Customers, leads, quotations, sales orders and invoices.	22
Inventory Manager	Products, warehouses and all stock operations.	20
Procurement Officer	Suppliers, requisitions, purchase orders and goods receipts.	18
Department Manager	Approves leave, requisitions and expenses for their team; manages projects.	24
Employee	Self-service: own leave, expenses, tasks, time and payslips.	10
Read-Only Auditor	Reads every module including audit logs; cannot change anything.	36

CHAPTER 8

Access badalna, rokna aur hatana

Role change, membership deactivate, company se remove, platform-level deactivate — aur audit log.

8.1 Chaar tareeqe — kab kaunsa

Table 8.1 — Access control ke tareeqe

Tareeqa	Kahan	Asar	Kab use karein
Role badalna	Users & roles → Users → ⋯ → Edit access	Agli request se nayi permissions	Promotion, department change
Membership inactive	Edit access → Active in this company off	"Inactive members cannot sign in to this company." Record aur roles baqi	Lambi chhutti, suspension, investigation
Remove from company	⋯ → Remove from company	"They lose access to this company immediately." Doosri companies par asar nahi	Shakhs company chhor gaya
Account deactivate (platform)	Platform → Platform users → ⋯ → Deactivate account	"They are signed out everywhere and cannot sign in to any company."	Poore platform se bahar (sirf platform staff)

8.2 Role badalna

1. Users list mein us user ki row ke aakhir mein ⋯ (Row actions) 1 dabayein.
2. Edit access 2 chunein.




Figure 8.1 — Row actions — (1) ··· button, (2) Edit access. Neeche "Remove from company" bhi.

1. "Access for ..." drawer mein roles tick/untick karein — yahan Branch Manager ko **Employee** role 3 bhi diya gaya (dono roles ki permissions mil jati hain).
2. Branches bhi yahin badli ja sakti hain. **Save access** 4.




Figure 8.2 — Edit access drawer — (3) naya role, (4) Save access.

8.3 Membership deactivate karna

1. **Edit access** kholein, neeche **Active in this company** (1) switch off karein.
2. **Save access** (2). List mein status "Inactive" ho jata hai.




Figure 8.3 — Active in this company (1) off — Save access (2).




Figure 8.4 — User ab "Inactive" — roles aur branches record mein baqi hain.

Inactive member agar sign in kare to woh is company mein dakhil nahi ho sakta — us ka koi menu nahi hota aur Dashboard "unavailable" dikhata hai. Agar woh pehle se logged-in ho to agli request par hi bahar ho jata hai.




Figure 8.5 — Inactive member ka login — koi company/menu nahi, "Dashboard unavailable".

> **NOTE**
> Wapas access dene ke liye wohi switch on karke Save access. (Is guide mein demo user ko screenshot ke baad dobara active kar diya gaya.)

8.4 Company se remove karna aur platform-level deactivate

1. ⋯ → **Remove from company** 1 (laal, destructive option).
2. Confirm dialog: "They lose access to this company immediately. Their account and history in other companies are not affected." → **Remove**.




Figure 8.6 — Row actions — (1) Remove from company.




Figure 8.7 — Remove confirm dialog.

Poore platform se band karna (Platform Owner/Admin)

1. **Platform → Platform users** → user ki row ⋯ → **Deactivate account** (1).
2. Confirm: "They are signed out everywhere and cannot sign in to any company."
3. Baad mein wapas: ⋯ → **Reactivate account**.




Figure 8.8 — Platform users — (1) Deactivate account.




Figure 8.9 — Deactivate confirm — har jagah se sign out.




Figure 8.10 — Account "Inactive" — (demo ke baad dobara Reactivate kiya gaya).

> ⚠ **DHYAN DEIN**
>
> Aap apne aap ko remove/deactivate nahi kar sakte, aur apna aakhri woh role nahi hata sakte jis se users manage hote hain — taake company baghair admin ke na reh jaye.

8.5 Jab koi bina ijazat page khole

Branch HR ke paas finance ki permission nahi — sidebar mein Receivables menu hi nahi. Agar woh URL khud type kare (`/finance/invoices`), server inkaar karta hai aur koi data nahi bhejta:




Figure 8.11 — branch.hr@northwind.test ne /finance/invoices khola — "You don't have permission to perform this action." (auth.forbidden).




Figure 8.12 — Wohi user /access/users kholta hai — users list bhi forbidden.

> **TIP**
> Aisi har koshish audit log mein "auth.permission_denied" ke naam se likhi jati hai — baar baar ho to us user se baat karein.

8.6 Audit log mein sab tabdeeliyan

Insights → Audit log mein category filter se **Users** aur **Roles & permissions** chunein. Har invite, membership update, removal aur role permission change — kis ne, kab, kis IP se — nazar aata hai; row par click karne se drawer mein poori detail (purani/nayi values).




Figure 8.13 — Audit log → Users category — invitations aur membership updates.




Figure 8.14 — Aik users entry ki detail drawer.




Figure 8.15 — Audit log → Roles & permissions — role banana / permissions badalna.




Figure 8.16 — Role change entry ki detail — kaunsi permissions add/remove hui.

- Audit log **append-only** hai — entries edit ya delete nahi hotin.

- Har mahine Users aur Roles categories review karein (chapter 10).

CHAPTER 9

Maker–checker: banane wala approve nahi karta

Approval separation ke qawaid aur system unhein kaise lagu karta hai.

9.1 Maker–checker kya hai?

"Maker" woh hai jo koi request/document banata hai; "checker" woh jo usay approve karta hai. Dono alag log hon to ghalti ya dhoka pakarna aasaan hota hai. ERP yeh usool kai jagah khud lagu karta hai — chahe user ke paas approve ki permission ho.

Table 9.1 — System ke lagu kiye hue separation rules

Kaam	Rule	System kya karta hai
Payroll run	Run banane wala usay approve nahi kar sakta	Server: "You cannot approve a payroll run you created." (`payroll.self_approval`); run page par note: "another user with the Run & approve payroll permission must approve it."
Purchase requisition	Requester apni requisition approve nahi kar sakta	Approvals inbox mein apni requisition nahi aati; approve sirf doosra approver
Approvals inbox (sab types)	Apni requests kabhi nahi dikhtin	"Requests waiting for your decision. Your own requests never appear here."
Users	Koi apni membership edit/deactivate/remove nahi kar sakta	"You cannot deactivate your own membership." / apna aakhri users-manage role nahi hata sakta
Platform	Koi apni platform role nahi badal sakta	"You cannot change your own platform role."

9.2 Misaal: manager ki apni requisition

Demo mein **Manager User** ne requisition `PR-2026-000005` banayi hai. Us ke paas "Approve purchase requisitions" permission hai, phir bhi:




Figure 9.1 — manager@northwind.test ka Approvals inbox — "Your own requests never appear here." PR-2026-000005 is list mein nahi.




Figure 9.2 — Manager apni hi requisition kholta hai — Approve / Reject buttons nahi hain.




Figure 9.3 — Wohi requisition Company Owner ke login se — Approve button maujood (doosra shakhs = checker).

9.3 Roles bante waqt separation ka khayal

- Jo invoices/bills **banata** hai (maslan Sales Manager, Procurement Officer) us ke paas **approve** na ho — default roles mein yahi hai: Sales Manager invoices bana sakta hai, approve Accountant/Owner karte hain; Procurement Officer PO bana sakta hai, approve Owner/Admin.
- Payroll ke liye kam az kam **do** log jin ke paas "Run & approve payroll" ho — aik banaye, doosra approve kare. Warna run atak jayega.
- Custom role banate waqt aik hi role mein "create" aur "approve" dono dene se pehle sochein.
- Approvals ki history `Insights → Audit log` mein milti hai (kis ne kab approve kiya).

> **NOTE**
> Leave aur expense claims mein bhi approver alag hota hai: employee ki apni request us ke Approvals inbox mein nahi aati, manager/HR/accountant approve karta hai.

> **TIP**
> Chhoti company mein jahan log kam hon, Owner aksar checker hota hai — lekin Owner bhi apna banaya hua payroll run approve nahi kar sakta, is liye payroll `New run` HR banaye aur Owner approve kare.

CHAPTER 10

Best-practice checklist

Har mahine aur har naye shakhs ke waqt in points ko tick karein.

10.1 Shuru mein (aik dafa)

- [ ] Platform Owner `erp:create-admin` se bana, 2FA on, `ERP_ALLOW_ADMIN_BOOTSTRAP=false` wapas.
- [ ] Platform Admin sirf zaroorat ho to — 1 ya 2 bharosemand IT log.
- [ ] Har company ka sirf aik (zyada se zyada do) Company Owner.
- [ ] Roz ke admin kaam ke liye Company Administrator — Owner ka login roz istemal na ho.
- [ ] Owners, Admins, Accountants aur HR — sab ka 2FA on.
- [ ] Production par koi demo company ya demo user nahi.

10.2 Naya shakhs aaye to

- [ ] Apna personal account banayein — kabhi shared login nahi.
- [ ] **Least privilege:** sirf woh role jo us ke kaam ke liye zaroori ho; zyada access baad mein dena aasaan hai, wapas lena mushkil.
- [ ] Branch ka kaam ho to "Access to all branches" off karke sirf us ki branch.
- [ ] Employee ho to HR us ka employee record bana kar "Linked user" mein login jore.
- [ ] Create aur approve aik hi shakhs ko na milein (maker–checker).

10.3 Har mahine review

- [ ] **Users & roles → Users** mein "Last sign-in" dekhein — 60+ din se istemal na hone wale accounts inactive karein.
- [ ] Har role ki users list dekhein — kahin ghair-zaroori Owner/Admin to nahi?
- [ ] **Platform users** mein 2FA "Off" walon ko follow up.
- [ ] **Insights → Audit log** mein "Users" aur "Roles & permissions" categories — koi anjaan tabdeeli?
- [ ] `auth.permission_denied` entries — koi baar baar ijazat ke baghair pages to nahi khol raha?
- [ ] Custom roles ab bhi zaroori hain? Ghair-istemal roles delete karein (pehle users hatayein).

10.4 Koi chhor kar jaye to (usi din)

- [ ] Company membership "Active in this company" off ya "Remove from company".

- [ ] Agar woh kisi company mein nahi rahega to Platform users mein "Deactivate account".
- [ ] Us ke banaye hue pending kaam (drafts, approvals) kisi aur ko assign karein.
- [ ] HR mein employee record "Terminate" — record delete na karein (history ke liye).
- [ ] Shared passwords (agar kabhi diye hon) badal dein.

10.5 Bahar ke auditor ke liye

Table 10.1 — External auditor

Qadam	Kya karein
1	Usay Invite user se "Read-Only Auditor" role dein — sab modules aur audit log dekh sakta hai, reports export kar sakta hai, kuch badal nahi sakta.
2	Zaroorat ho to sirf mutalliqa branches tak mehdood karein.
3	Audit khatam hote hi "Remove from company".

> ⚠ **DHYAN DEIN**
> Kabhi kisi auditor, consultant ya vendor ko Owner/Admin login share na karein. Har bahar wale ke liye alag account aur mehdood role.

> 💡 **TIP**
> Yaad rakhein: jis ke paas "Manage roles & permissions" hai woh roles ki permissions badal sakta hai — is liye Company Administrator ko taqreeban Owner jitna bharosemand samjhein (chapter 4.3).