# **Computer Graphics I**


### Lecture 19: Computer animation 3

Xiaopei LIU

School of Information Science and Technology ShanghaiTech University

## What is a soft body?

- Unlike in simulation of rigid body
  - Shape of soft bodies can change
  - The relative distance of two points on the object is not fixed




## Soft body dynamics

#### A field of computer graphics

- Focus on visually realistic physical simulations of the motion and properties of deformable objects
- The scope of soft body dynamics is quite broad
  - Simulation of soft organic materials: muscle, fat, hair and vegetation
  - Other deformable materials: cloth, fabric, etc.
- Type of simulation methods
  - Mass-spring model
  - Finite-element simulation
  - Energy minimization methods
  - Position-based dynamics, etc.

- Mass-spring system
  - The spring has a non-negligible mass m
- Hook's law

$$ec{F}=-kec{x}$$






- Harmonic oscillator
  - Without damping

$$F=ma=mrac{\mathrm{d}^2x}{\mathrm{d}t^2}=m\ddot{x}=-kx$$

Analytical solution

$$x(t) = A\cos(\omega t + \phi)$$



#### • Harmonic oscillator


- With damping

$$rac{\mathrm{d}^2 x}{\mathrm{d}t^2} + 2\zeta\omega_0rac{\mathrm{d}x}{\mathrm{d}t} + \omega_0^{\,2}x = 0,$$

where


$$\omega_0 = \sqrt{rac{k}{m}}$$
 is called the 'undamped angular frequency of the oscillator' and

$$\zeta = rac{c}{2\sqrt{mk}}$$
 is called the 'damping ratio'.



#### Mass-spring system

- Physically-based technique for modeling deformable objects
- An object is modeled as point masses connected by springs



#### Mass-spring system

- The spring can be linear (Hook's law)
- Non-linear spring can also be used (model tissues such as human skin)
- Governing dynamic equation
  - Using linear spring model

$$m_i \ddot{\mathbf{x}}_i = -\gamma_i \dot{\mathbf{x}}_i + \sum_j \mathbf{g}_{ij} + \mathbf{f}_i$$

**g**<sub>ij</sub>: forces exerted on mass i by spring between masses i and j

#### Mass-spring system

Writing the equation for entire system

$$M\ddot{x} + C\dot{x} + Kx = f$$

M: mass matrix, diagonal

C: damping matrix, diagonal

K: stiffness matrix, encodes spring forces from nearby connected springs

Re-expression in first-order system

$$\dot{\mathbf{v}} = \mathbf{M}^{-1} \left( -\mathbf{C}\mathbf{v} - \mathbf{K}\mathbf{x} + \mathbf{f} \right)$$
 $\dot{\mathbf{x}} = \mathbf{v}$ 
velocity of mass point

- Mass-spring system
  - Numerical solution: explicit Euler

$$\frac{d}{dt} \begin{pmatrix} \mathbf{x} \\ \dot{\mathbf{x}} \end{pmatrix} = \frac{d}{dt} \begin{pmatrix} \mathbf{x} \\ \mathbf{v} \end{pmatrix} = \begin{pmatrix} \mathbf{v} \\ \mathbf{M}^{-1} \mathbf{f}(\mathbf{x}, \mathbf{v}) \end{pmatrix}$$

$$\mathbf{x}_0 = \mathbf{x}(t_0) \text{ and } \mathbf{v}_0 = \mathbf{v}(t_0)$$
 
$$\Delta \mathbf{x} = \mathbf{x}(t_0 + h) - \mathbf{x}(t_0) \text{ and } \Delta \mathbf{v} = \mathbf{v}(t_0 + h) - \mathbf{v}(t_0)$$
 
$$\begin{pmatrix} \Delta \mathbf{x} \\ \Delta \mathbf{v} \end{pmatrix} = h \begin{pmatrix} \mathbf{v}_0 \\ \mathbf{M}^{-1} \mathbf{f}_0 \end{pmatrix}$$

#### Mass-spring system

Numerical solution: implicit Euler

$$\frac{d}{dt}\begin{pmatrix} \mathbf{x} \\ \dot{\mathbf{x}} \end{pmatrix} = \frac{d}{dt}\begin{pmatrix} \mathbf{x} \\ \mathbf{v} \end{pmatrix} = \begin{pmatrix} \mathbf{v} \\ \mathbf{M}^{-1}\mathbf{f}(\mathbf{x}, \mathbf{v}) \end{pmatrix}$$

$$\begin{pmatrix} \Delta \mathbf{x} \\ \Delta \mathbf{v} \end{pmatrix} = h\begin{pmatrix} \mathbf{v}_0 + \Delta \mathbf{v} \\ \mathbf{M}^{-1}\mathbf{f}(\mathbf{x}_0 + \Delta \mathbf{x}, \mathbf{v}_0 + \Delta \mathbf{v}) \end{pmatrix}$$

$$\mathbf{f}(\mathbf{x}_0 + \Delta \mathbf{x}, \mathbf{v}_0 + \Delta \mathbf{v}) = \mathbf{f}_0 + \frac{\partial \mathbf{f}}{\partial \mathbf{x}} \Delta \mathbf{x} + \frac{\partial \mathbf{f}}{\partial \mathbf{v}} \Delta \mathbf{v}$$

$$\begin{pmatrix} \Delta \mathbf{x} \\ \Delta \mathbf{v} \end{pmatrix} = h\begin{pmatrix} \mathbf{v}_0 + \Delta \mathbf{v} \\ \mathbf{M}^{-1}(\mathbf{f}_0 + \frac{\partial \mathbf{f}}{\partial \mathbf{x}} \Delta \mathbf{x} + \frac{\partial \mathbf{f}}{\partial \mathbf{v}} \Delta \mathbf{v}) \end{pmatrix}$$

$$\Delta \mathbf{v} = h\mathbf{M}^{-1}\begin{pmatrix} \mathbf{f}_0 + \frac{\partial \mathbf{f}}{\partial \mathbf{x}} h(\mathbf{v}_0 + \Delta \mathbf{v}) + \frac{\partial \mathbf{f}}{\partial \mathbf{v}} \Delta \mathbf{v} \end{pmatrix}$$

12

### Mass-spring system

- Numerical solution: implicit Euler
  - Regrouping


$$\Delta \mathbf{v} = h\mathbf{M}^{-1} \left( \mathbf{f_0} + \frac{\partial \mathbf{f}}{\partial \mathbf{x}} h(\mathbf{v_0} + \Delta \mathbf{v}) + \frac{\partial \mathbf{f}}{\partial \mathbf{v}} \Delta \mathbf{v} \right)$$



$$\left(\mathbf{I} - h\mathbf{M}^{-1} \frac{\partial \mathbf{f}}{\partial \mathbf{v}} - h^2 \mathbf{M}^{-1} \frac{\partial \mathbf{f}}{\partial \mathbf{x}}\right) \Delta \mathbf{v} = h\mathbf{M}^{-1} \left(\mathbf{f_0} + h \frac{\partial \mathbf{f}}{\partial \mathbf{x}} \mathbf{v_0}\right)$$

- We then solve for  $\Delta v$  (sparse linear system, conjugate gradient)
- Given  $\Delta \mathbf{v}$ , we then compute  $\Delta \mathbf{x} = h(\mathbf{v_0} + \Delta \mathbf{v})$

- Simulate the motion of a cloth
  - Modeling internal forces within cloth



#### Forces

- Cloth's material behavior
  - Customarily described in terms of a scalar potential energy function E(x)
- Force f arising from this energy

$$\mathbf{f} = -\partial E/\partial \mathbf{x}$$

- Impractical as a single monolithic function
- Internal behavior by a vector condition C(x)
  - We want C(x) to be zero
  - Associated energy with stiffness constant k

$$E_{\mathbf{C}}(\mathbf{x}) = \frac{k}{2}\mathbf{C}(\mathbf{x})^T\mathbf{C}(\mathbf{x})$$


- Forces and force derivatives
  - Force evaluation
    - Each element **f**<sub>i</sub> is a vector in **R**<sup>3</sup>


$$\mathbf{f}_i = -\frac{\partial E_{\mathbf{C}}}{\partial \mathbf{x}_i} = -k \frac{\partial \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_i} \mathbf{C}(\mathbf{x})$$


- Force derivative
  - Derivative matrix

$$\mathbf{K}_{ij} = \frac{\partial \mathbf{f}_i}{\partial \mathbf{x}_j} = -k \left( \frac{\partial \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_i} \frac{\partial \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_j}^T + \frac{\partial^2 \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_i \partial \mathbf{x}_j} \mathbf{C}(\mathbf{x}) \right)$$

### Rest vs. deformed shapes







Deformed shape: external force applied

#### Stretch force

- Like texture mapping, a single continuous function w(u,v)
   mapping plane coordinates to world space
- Stretch can be measure by

$$\mathbf{w}_u = \partial \mathbf{w}/\partial u$$
 and  $\mathbf{w}_v = \partial \mathbf{w}/\partial v$ 

Stretch energy

$$(\mathbf{w}_u^T \mathbf{w}_u - 1)^2$$

Nearby vertices (triangle meshes, vertices i, j, k)

$$\Delta \mathbf{x}_1 = \mathbf{x}_j - \mathbf{x}_i$$
 and  $\Delta \mathbf{x}_2 = \mathbf{x}_k - \mathbf{x}_i$   $\Delta u_1 = u_j - u_i$   $\Delta u_2 = u_k - u_i$ 

$$\Delta \mathbf{x}_1 = \mathbf{w}_u \Delta u_1 + \mathbf{w}_v \Delta v_1 \text{ and } \Delta \mathbf{x}_2 = \mathbf{w}_u \Delta u_2 + \mathbf{w}_v \Delta v_2$$

#### Stretch force

Nearby vertices (triangle meshes, vertices i,j,k)

$$\Delta \mathbf{x}_{1} = \mathbf{w}_{u} \Delta u_{1} + \mathbf{w}_{v} \Delta v_{1} \text{ and } \Delta \mathbf{x}_{2} = \mathbf{w}_{u} \Delta u_{2} + \mathbf{w}_{v} \Delta v_{2}$$

$$(\mathbf{w}_{u} \quad \mathbf{w}_{v}) = (\Delta \mathbf{x}_{1} \quad \Delta \mathbf{x}_{2}) \begin{pmatrix} \Delta u_{1} & \Delta u_{2} \\ \Delta v_{1} & \Delta v_{2} \end{pmatrix}^{-1}$$

Condition for stretch energy

$$\mathbf{C}(\mathbf{x}) = a \begin{pmatrix} \|\mathbf{w}_u(\mathbf{x})\| - b_u \\ \|\mathbf{w}_v(\mathbf{x})\| - b_v \end{pmatrix} \qquad b_u = b_v = 1$$

a is the triangle's area in uv coordinates

#### Shear and bend forces

- Sheared in a triangle by considering the inner product

$$\mathbf{w}_u^T \mathbf{w}_v$$

Shear energy

$$C(\mathbf{x}) = a\mathbf{w}_u(\mathbf{x})^T \mathbf{w}_v(\mathbf{x})$$

- Bending energy
  - Adjacent triangles with normals **n**<sub>1</sub> and **n**<sub>2</sub>

$$\sin \theta = (\mathbf{n}_1 \times \mathbf{n}_2) \cdot \mathbf{e} \quad \cos \theta = \mathbf{n}_1 \cdot \mathbf{n}_2$$

$$C(\mathbf{x}) = \theta$$

#### Damping

- Robust dynamic cloth simulation critically dependent on well-chosen damping forces
  - A function of both position and velocity
- Should depend on the component of the system's velocity in the direction

$$\partial \mathbf{C}(\mathbf{x})/\partial \mathbf{x}$$

Damping force formulation

$$\mathbf{d} = -k_d \frac{\partial \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}} \dot{\mathbf{C}}(\mathbf{x})$$

#### Damping force derivative

$$\Delta \mathbf{v} = h\mathbf{M}^{-1} \left( \mathbf{f_0} + \frac{\partial \mathbf{f}}{\partial \mathbf{x}} h(\mathbf{v_0} + \Delta \mathbf{v}) + \frac{\partial \mathbf{f}}{\partial \mathbf{v}} \Delta \mathbf{v} \right)$$

Spatial derivative

$$\frac{\partial \mathbf{d}_i}{\partial \mathbf{x}_j} = -k_d \left( \frac{\partial \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_i} \frac{\partial \dot{\mathbf{C}}(\mathbf{x})}{\partial \mathbf{x}_j}^T + \frac{\partial^2 \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_i \partial \mathbf{x}_j} \dot{\mathbf{C}}(\mathbf{x}) \right)$$

Velocity derivative

$$\frac{\partial \mathbf{d}_i}{\partial \mathbf{v}_j} = -k_d \frac{\partial \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_i} \frac{\partial \dot{\mathbf{C}}(\mathbf{x})}{\partial \mathbf{v}_j}^T = -k_d \frac{\partial \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_i} \frac{\partial \mathbf{C}(\mathbf{x})}{\partial \mathbf{x}_j}^T$$

### Cloth simulation results

#### Constraints

Interaction with solids (collision detection)




## 3. Simulation of solid deformable object

## Solid deformable objects

#### A wide variety of behaviors

- Stretch and compress
- Twist, curl and knot
- Rip under large deformations
- Form complex wrinkles and buckle under pressure







#### **Continuum mechanics**


#### A branch of mechanics

- Modeled as a continuous mass rather than as discrete particles
- The matter in the body is continuously distributed
- A continuum is a body that can be continually sub-divided into infinitesimal elements
  - Derivatives are available to compute
- Deal with deformable bodies
  - As opposed to ideal rigid bodies
  - Analyzing internal force of rigid bodies should consider deformation (very small)

### Stress of a material


### A physical quantity of material

- Internal forces that neighboring particles exert on each other
- Defined as the force across a "small" boundary per unit area of that boundary



### Stress of a material

- Stress may be regarded as the sum of two components
  - Normal stress
    - The stress component perpendicular to the surface (compression or tension)
  - Shear stress
    - The stress component parallel to the surface



29

## Cauchy stress tensor

#### General stress

- Mechanical bodies experience more than one type of stress at the same time (combined stress)
- Combined stresses cannot be described by a single vector

### Cauchy's observation

 The stress vector across a surface will always be a linear function of the surface's normal

$$T = \boldsymbol{\sigma}(n)$$
  $\boldsymbol{\sigma}(\alpha u + \beta v) = \alpha \boldsymbol{\sigma}(u) + \beta \boldsymbol{\sigma}(v)$ 

## Cauchy stress tensor


#### Definition

A 3x3 matrix

$$egin{bmatrix} \sigma_{11} & \sigma_{12} & \sigma_{13} \ \sigma_{21} & \sigma_{22} & \sigma_{23} \ \sigma_{31} & \sigma_{32} & \sigma_{33} \end{bmatrix}$$
 or  $egin{bmatrix} \sigma_{xx} & \sigma_{xy} & \sigma_{xz} \ \sigma_{yx} & \sigma_{yy} & \sigma_{yz} \ \sigma_{zx} & \sigma_{zy} & \sigma_{zz} \end{bmatrix}$ 

$$T = n \cdot \boldsymbol{\sigma}$$

$$egin{bmatrix} T_1 \ T_2 \ T_3 \end{bmatrix} = egin{bmatrix} \sigma_{11} & \sigma_{21} & \sigma_{31} \ \sigma_{12} & \sigma_{22} & \sigma_{32} \ \sigma_{13} & \sigma_{23} & \sigma_{33} \end{bmatrix} egin{bmatrix} n_1 \ n_2 \ n_3 \end{bmatrix}$$



## Cauchy stress tensor

#### Symmetric stress tensor

Conservation of angular momentum implies that the stress tensor is symmetric

$$egin{bmatrix} \sigma_x & au_{xy} & au_{xz} \ au_{xy} & \sigma_y & au_{yz} \ au_{xz} & au_{yz} & \sigma_z \end{bmatrix}$$

Normal stresses

$$\sigma_x,\sigma_y,\sigma_z$$

• Shear stresses

$$au_{xy}, au_{xz}, au_{yz}$$

### **Deformation of material**

### Physical view of deformation

- Transformation of a body from a reference configuration to the current configuration
- A configuration is a set containing the positions of all particles of the body

#### Causes of deformation

- External loads (usually on the exterior surfaces)
- Body forces (volumetric force within the whole body, e.g., gravity force)

## Types of deformation

#### Elastic deformations

Deformations are recovered after the stress field has been removed

#### Irreversible deformation

- Deformations remain even after stresses have been removed
- Plastic deformation
  - Occurs in material bodies after stresses have attained a certain threshold value (elastic limit or yield stress)

### Strain of material

#### What is a strain

- A description of deformation in terms of relative displacement of particles
- The relation between stresses and induced strains is expressed by constitutive equations
  - E.g., Hooke's law for linear elastic materials

#### Formulation

A general deformation of a body can be expressed in the form

$$\mathbf{x} = \mathbf{F}(\mathbf{X})$$

 X is the reference position of material points in the body

### Strain of material

#### Formulation

- Such a measure does not distinguish between rigid body motions and changes in shape of the body
- Mathematical definition

$$oldsymbol{arepsilon} \dot{oldsymbol{arepsilon}} \dot{oldsymbol{arepsilon}} \left( \mathbf{x} - \mathbf{X} 
ight) = oldsymbol{F}' - oldsymbol{I}$$

 Strains measure how much a given deformation differs locally from a rigid-body deformation

# Strain of material


#### Strain tensor

$$arepsilon_{xx} = rac{\partial u_x}{\partial x} \hspace{0.5cm} arepsilon_{yy} = rac{\partial u_y}{\partial y} \hspace{0.5cm} arepsilon_{zz} = rac{\partial u_z}{\partial z}$$

$$egin{aligned} \gamma_{xy} &= \ \gamma_{yx} &= rac{\partial u_y}{\partial x} + rac{\partial u_x}{\partial y} \ \gamma_{yz} &= \gamma_{zy} &= rac{\partial u_y}{\partial z} + rac{\partial u_z}{\partial y} \ \gamma_{zx} &= \gamma_{xz} &= rac{\partial u_z}{\partial x} + rac{\partial u_x}{\partial z} \end{aligned} \qquad oldsymbol{arepsilon} oldsymbol{arepsilon} = egin{bmatrix} arepsilon_{xx} & arepsilon_{xy} & arepsilon_{xz} \ arepsilon_{yx} & arepsilon_{yy} & arepsilon_{yz} \ arepsilon_{zx} & arepsilon_{zy} & arepsilon_{zz} \end{bmatrix} = egin{bmatrix} arepsilon_{xx} & rac{1}{2}\gamma_{xy} & rac{1}{2}\gamma_{yz} \ rac{1}{2}\gamma_{zy} & arepsilon_{zz} \end{bmatrix} \ \gamma_{zx} &= \gamma_{xz} & rac{\partial u_z}{\partial x} + rac{\partial u_x}{\partial z} \end{aligned}$$

# Deformation of a continuum body

Motion and deformation of a continuum body



# Continuous model

Define material coordinates

$$\mathbf{u} = [u, v, w]^{\mathsf{T}}$$

Deformation of the material

$$\boldsymbol{x}(\boldsymbol{u}) = [x, y, z]^{\mathsf{T}}$$

- In areas where material exists, **x**(**u**) is continuous
- Except across a finite number of surfaces within the volume that correspond to fractures

# Continuous model

- Green's strain tensor
  - Measure the local deformation of the material

$$\epsilon_{ij} = \left(\frac{\partial \boldsymbol{x}}{\partial u_i} \cdot \frac{\partial \boldsymbol{x}}{\partial u_j}\right) - \delta_{ij}$$

Kronecker delta

$$\delta_{ij} = \begin{cases} 1 & : & i = j \\ 0 & : & i \neq j \end{cases}$$

- This strain metric only measures deformation
- Invariant with respect to rigid body transformations

## Continuous model

#### Strain rate tensor

- Measure the rate at which the strain is changing
- Take the time derivative of strain

$$\nu_{ij} = \left(\frac{\partial \boldsymbol{x}}{\partial u_i} \cdot \frac{\partial \boldsymbol{\dot{x}}}{\partial u_j}\right) + \left(\frac{\partial \boldsymbol{\dot{x}}}{\partial u_i} \cdot \frac{\partial \boldsymbol{x}}{\partial u_j}\right)$$

- Strain and strain rate tensors provide the raw information to compute internal elastic and damping forces
- Do not take into account the properties of the material

# **Notation**

#### Partial differentiation

$$\mathbf{x}_{,i} \equiv \partial \mathbf{x}/\partial \theta_i, \, \mathbf{u}_{,ik} \equiv \frac{\partial^2 \mathbf{u}}{\partial \theta_i \, \partial \theta_k}$$

### Operators

- Vector dot product:  $dot(\cdot)$
- Vector cross product: cross(x)
- Tensor double contraction: colon (:)

# Commonly used in computer graphics

- Relatively simple formulation
- Resulting efficient simulations

## Three essential parts

- Geometry: study of deformation a body can undergo
- Internal and external forces: how they affect an object's equilibrium or dynamics
- Constitutive relation: how deforming geometry relates to internal forces


### Geometry

- Restrict to Lagrangian description
  - Undeformed positions

$$\bar{\mathbf{x}}(\boldsymbol{\theta}) \qquad \boldsymbol{\theta} = (\theta_1, \theta_2, \theta_3)^T$$

• Undergo a deformation

$$\mathbf{x}(\boldsymbol{\theta}) = \bar{\mathbf{x}}(\boldsymbol{\theta}) + \mathbf{u}(\boldsymbol{\theta})$$



### Geometry

- Cauchy strain
  - Assuming only small displacements

$$\epsilon_{ij} = \frac{1}{2} \left( \mathbf{u}_{,i} \cdot \bar{\mathbf{x}}_{,j} + \bar{\mathbf{x}}_{,i} \cdot \mathbf{u}_{,j} \right)$$

- The main diagonal of the tensor
  - The amount of stretch in the three (normal) spatial directions
- Off-diagonal values
  - Amount of shear in the according planes
- Linearization of the more general (non-linear) strain

# Forces, equilibrium and dynamics

- Cauchy stress
  - Introduce a virtual cut plane with normal **n**
  - Force distribution at a point can compactly be described by the product of the Cauchy stress tensor with the plane normal

$$\sigma \cdot \mathbf{n} = \mathbf{f_n}$$

- Main diagonal
  - Normal stress
- Off-diagonal
  - Shear stress

- Forces, equilibrium and dynamics
  - Total force
    - Summing up all traction forces on the side of the corresponding infinitesimal cube
    - Using the divergence (Gauss) theorem

$$egin{aligned} \sigma \cdot \mathbf{n} &= \mathbf{f_n} \ & lacksquare & lac$$

- Forces, equilibrium and dynamics
  - Energy
    - Internal forces in an elastic body are conservative
    - Related to an underlying scalar energy potential characterizing the amount of work for deformation

$$W_{int}(\mathbf{u}) = \int_{\Omega} \boldsymbol{\epsilon}(\mathbf{u}) : \sigma(\mathbf{u}) d\Omega$$
Strain (length) Stress (force)

Conservative forces

$$\mathbf{f}_{int} = -\frac{\partial W_{int}(\mathbf{u})}{\partial \mathbf{u}}$$

- Forces, equilibrium and dynamics
  - Static equilibrium
    - All internal and external forces need to cancel each other

$$\nabla \cdot \boldsymbol{\sigma} = \mathbf{f}_{ext}$$

Making use of the elastic potential

$$-\frac{\partial W_{int}(\mathbf{u})}{\partial \mathbf{u}} = \mathbf{f}_{ext}$$

Better suited for setting up the corresponding discrete problems

# Forces, equilibrium and dynamics

- Equations of motion
  - If an object is not in static equilibrium: difference between internal and external forces results in net forces
  - Acceleration of the material according to Newton's second law

$$\rho \ddot{\mathbf{u}} + \mathbf{f}_d(\dot{\mathbf{u}}) + \nabla \cdot \boldsymbol{\sigma} = \mathbf{f}_{ext}$$

- $\mathbf{f}_d(\dot{\mathbf{u}})$ : a damping force
- Making use of the elastic energy potential

$$\rho \, \ddot{\mathbf{u}} + \mathbf{f}_d(\dot{\mathbf{u}}) - \frac{\partial W_{int}(\mathbf{u})}{\partial \mathbf{u}} = \mathbf{f}_{ext}$$

#### Constitutive relation

- Establish the relation between internal deformation and force
- The simplest is the linear relation
  - a Hookean material

$$\sigma = \mathbf{C} : \boldsymbol{\epsilon}$$

- Young modulus: material's stiffness
- Poisson's ratio: how much (linearized) change in volume (compression) is penalized during deformation

## Thin geometries


- Specialized variants of the theory
- More efficient and numerically better suited

#### Resultant-based models

- Material has only small extent in certain spatial directions
- Simplified by making certain assumption on how the material can deform in these directions
- Thin shell theory: reduction along one direction
- Rod theory: reduction along two directions

#### • Shells

- Consider a volumetric surface-like solid
- Extent along tangent directions is much greater than along normal direction



#### Shells

- Strain about middle surface
  - Middle surface parameterized by the material-domain surface

$$\boldsymbol{\theta}_0 = (\theta_1, \theta_2, 0)$$

Assuming the shell to be sufficiently thin in normal direction

$$\bar{\mathbf{x}}(\boldsymbol{\theta}) \approx \bar{\mathbf{x}}(\boldsymbol{\theta}_0) + \theta_3 \bar{\mathbf{x}}_{,3}(\boldsymbol{\theta}_0)$$

$$\mathbf{u}(\boldsymbol{\theta}) \approx \mathbf{u}(\boldsymbol{\theta}_0) + \theta_3 \mathbf{u}_{,3}(\boldsymbol{\theta}_0)$$

#### Shells

- In the view of the linear elasticity theory
  - Substitute into the linear Cauchy strain

$$\boldsymbol{\epsilon}_{ij} = \frac{1}{2} (\mathbf{u}_{,i} \cdot \bar{\mathbf{x}}_{,j} + \bar{\mathbf{x}}_{,i} \cdot \mathbf{u}_{,j}) \qquad \frac{\bar{\mathbf{x}}(\boldsymbol{\theta})}{\mathbf{u}(\boldsymbol{\theta})} \approx \bar{\mathbf{x}}(\boldsymbol{\theta}_{0}) + \theta_{3} \bar{\mathbf{x}}_{,3}(\boldsymbol{\theta}_{0}) \\ \mathbf{u}(\boldsymbol{\theta}) \approx \mathbf{u}(\boldsymbol{\theta}_{0}) + \theta_{3} \mathbf{u}_{,3}(\boldsymbol{\theta}_{0})$$

$$\boldsymbol{\epsilon}(\boldsymbol{\theta}) \approx \boldsymbol{\alpha}(\boldsymbol{\theta}_{0}) + \theta_{3} \boldsymbol{\beta}^{3}(\boldsymbol{\theta}_{0})$$

– Membrane strain 
$$\boldsymbol{\alpha}_{ij} = \frac{1}{2} \left( \mathbf{u}_{,i} \cdot \bar{\mathbf{x}}_{,j} + \bar{\mathbf{x}}_{,i} \cdot \mathbf{u}_{,j} \right)$$

– Bending strain 
$$\boldsymbol{\beta}_{ij}^k = \frac{1}{2} \left( \mathbf{u}_{,ik} \cdot \bar{\mathbf{x}}_{,j} + \bar{\mathbf{x}}_{,i} \cdot \mathbf{u}_{,jk} + \mathbf{u}_{,i} \cdot \bar{\mathbf{x}}_{,jk} + \bar{\mathbf{x}}_{,ik} \cdot \mathbf{u}_{,j} \right)_{57}$$

#### Shells

- Energy integration
  - Elastic energy of the volumetric shell model

$$W_{tot}(\mathbf{u}) = \frac{1}{2} \int_{\Omega} (\boldsymbol{\epsilon}(\mathbf{u}) : \mathbf{C} : \boldsymbol{\epsilon}(\mathbf{u}) - \mathbf{f}_{ext} \cdot \mathbf{u}) d\Omega \qquad \boldsymbol{\epsilon}(\boldsymbol{\theta}) \approx \boldsymbol{\alpha}(\boldsymbol{\theta}_0) + \theta_3 \boldsymbol{\beta}^3(\boldsymbol{\theta}_0)$$


$$W = \frac{1}{2} \int_{\Omega} (\boldsymbol{\alpha}(\boldsymbol{\theta}_0) + \theta_3 \boldsymbol{\beta}^3(\boldsymbol{\theta}_0)) : \mathbf{C} : (\boldsymbol{\alpha}(\boldsymbol{\theta}_0) + \theta_3 \boldsymbol{\beta}^3(\boldsymbol{\theta}_0)) d\Omega$$

Integration in normal direction can be performed analytically

$$W = \frac{h_3}{2} \int_{\mathcal{S}} \boldsymbol{\alpha} : \mathbf{C} : \boldsymbol{\alpha} + \frac{h_3^2}{12} \boldsymbol{\beta}^3 : \mathbf{C} : \boldsymbol{\beta}^3 \, \mathrm{d} \mathcal{S}$$

#### Rods

- A volumetric curve-like solid
- Extent along tangent direction is much greater than along normal directions



#### Rods

- Strain about centerline
  - Let the centerline curve  $\Gamma$  be parameterized by

$$\boldsymbol{\theta}_0 = (\theta_1, 0, 0)$$

For small extents along both normals

$$\bar{\mathbf{x}}(\boldsymbol{\theta}) \approx \bar{\mathbf{x}}(\boldsymbol{\theta}_0) + \theta_2 \bar{\mathbf{x}}_{,2}(\boldsymbol{\theta}_0) + \theta_3 \bar{\mathbf{x}}_{,3}(\boldsymbol{\theta}_0) 
\mathbf{u}(\boldsymbol{\theta}) \approx \mathbf{u}(\boldsymbol{\theta}_0) + \theta_2 \mathbf{u}_{,2}(\boldsymbol{\theta}_0) + \theta_3 \mathbf{u}_{,3}(\boldsymbol{\theta}_0)$$

• The same steps for the derivation of the small strain

$$\epsilon(\boldsymbol{\theta}) \approx \alpha(\boldsymbol{\theta}_0) + \theta_2 \boldsymbol{\beta}^2(\boldsymbol{\theta}_0) + \theta_3 \boldsymbol{\beta}^3(\boldsymbol{\theta}_0)$$


#### Rods


- Energy integration
  - Analytic integration in the normal directions yields the one-dimensional integral of axial energy density over the rod's centerline

$$W = \frac{h_2 h_3}{2} \int_{\Gamma} \alpha : \mathbf{C} : \alpha + \frac{h_2^2}{12} \beta^2 : \mathbf{C} : \beta^2 + \frac{h_3^2}{12} \beta^3 : \mathbf{C} : \beta^3 d\Gamma$$

# Discrete formulation

Finite-element method (FEM)





# Discrete formulation

#### Discrete formulation

- Representation of the finite dimensional space
  - Using a basis of shape functions

$$\mathbf{u}_N(\bar{\mathbf{x}}) = \sum_{i=1}^{N} \mathbf{u}_i N_i(\bar{\mathbf{x}}) \in V_N$$

- Basis functions must also fulfill the completeness property
  - Constant reproduction: In order to represent arbitrary translations of the body
    - » Partition of unity  $\sum_i N_i(\bar{\mathbf{x}}) = 1$
  - Linear reproduction: necessary for a basis to represent constant strain fields as well as arbitrary rigid body motions

# Space discretization for linear formulations

- Energy-based approach
  - Taking gradient to yield equation to solve
    - Static case

$$\mathbf{K}\mathbf{u} = \mathbf{f}_{ext}$$

• Dynamic case

$$M\ddot{\mathbf{u}} + K\mathbf{u} = \mathbf{f}_{ext}$$


$$\mathbf{M}_{ij} = \mathbf{I} \cdot \int_{\Omega} \rho N_i N_j d\Omega$$

# 4. Unifying resultant-based models

# Unifying resultant-based models


#### Resultant-based models

- Only valid for single types of geometry (thin shell or rod)
- Handle all three types in an unified manner?




## Basic building blocks

 For assembling the elastic energy of any deformable object, independent of its form



## Consider a volumetric point-like solid

- Extent along all three directions is small
- Strain in the vicinity of this point will measure
  - Linear deformations: stretch and shear at the center
  - Quadratic deformations: bending and twist along all three "normal" directions



## Linearizing strain

Employ curvilinear coordinates describe an elaston centered at

$$\boldsymbol{\theta}_0 = (0,0,0)$$

- First-order Taylor approximation of positions and displacements
  - In all three normal directions

$$\bar{\mathbf{x}}(\boldsymbol{\theta}) \approx \bar{\mathbf{x}}(\boldsymbol{\theta}_0) + \sum_{k=1}^{3} \theta_k \bar{\mathbf{x}}_{,k}(\boldsymbol{\theta}_0)$$

$$\mathbf{u}(\boldsymbol{\theta}) \approx \mathbf{u}(\boldsymbol{\theta}_0) + \sum_{k=1}^{3} \theta_k \mathbf{u}_{,k}(\boldsymbol{\theta}_0)$$

# Linearizing strain

Strain centered about the elaston

$$\boldsymbol{\epsilon}_{ij} = \frac{1}{2} \left( \mathbf{u}_{,i} \cdot \bar{\mathbf{x}}_{,j} + \bar{\mathbf{x}}_{,i} \cdot \mathbf{u}_{,j} \right) + \mathbf{v}_{,i} \cdot \mathbf{u}_{,j} + \mathbf{v}_{,i} \cdot \mathbf{u}_{,j} \right) + \mathbf{v}_{,i} \cdot \mathbf{v}_{,i} \cdot \mathbf{v}_{,j} + \mathbf{v}_{,i} \cdot \mathbf{v}_{,j} + \mathbf{v}_{,i} \cdot \mathbf{u}_{,j} + \mathbf{v}_{,i} \cdot \mathbf{u}_{,i} + \mathbf{v}_{,i} + \mathbf{v}_{,i} \cdot \mathbf{u}_{,i} + \mathbf{v}_{,i} \cdot \mathbf{u}_{,i} + \mathbf{v}_{,i} \cdot \mathbf{u}_{,i} + \mathbf{v}_{,i} + \mathbf{v}_$$

- Naturally generalizes its shell and rod analogues
- Capture stretching, shearing, bending, and twisting along all three axes

## Energy integration

Integral over the elaston's volume

$$\boldsymbol{\epsilon}(\boldsymbol{\theta}) \approx \boldsymbol{\alpha}(\boldsymbol{\theta}_0) + \sum_{k=1}^{3} \theta_k \boldsymbol{\beta}^k(\boldsymbol{\theta}_0) \qquad \boldsymbol{\sigma} = \mathbf{C} : \boldsymbol{\epsilon} \qquad W_{int}(\mathbf{u}) = \int_{\Omega} \boldsymbol{\epsilon}(\mathbf{u}) : \boldsymbol{\sigma}(\mathbf{u}) d\Omega$$

$$\mathbf{W} = \frac{1}{2} \int_{\Omega_e} \left( \boldsymbol{\alpha}(\boldsymbol{\theta}_0) + \sum_{k=1}^{3} \theta_k \boldsymbol{\beta}^k(\boldsymbol{\theta}_0) \right) : \mathbf{C} : \left( \boldsymbol{\alpha}(\boldsymbol{\theta}_0) + \sum_{k=1}^{3} \theta_k \boldsymbol{\beta}^k(\boldsymbol{\theta}_0) \right) d\Omega$$

- All three directions have thin extent
  - Analytically integrate


$$W = \frac{V}{2} \left( \boldsymbol{\alpha}(\boldsymbol{\theta}_0) : \mathbf{C} : \boldsymbol{\alpha}(\boldsymbol{\theta}_0) + \sum_{k=1}^{3} \frac{h_k^2}{12} \boldsymbol{\beta}^k(\boldsymbol{\theta}_0) : \mathbf{C} : \boldsymbol{\beta}^k(\boldsymbol{\theta}_0) \right)$$
$$V = h_1 h_2 h_3$$

- Summing up: a new integration rule
  - The classical goal of resultant-based model
    - Reduce the dimensionality of the model
    - Simplify its numerical treatment
    - Energy integration can be performed analytically
  - Elastons offer the most general integration rule
    - Approximate the stored elastic energy of rods, shells, or solids, respectively

$$W_{int}(\mathbf{u}) = \int_{\Omega} \boldsymbol{\epsilon}(\mathbf{u}) : \boldsymbol{\sigma}(\mathbf{u}) d\Omega$$

$$\mathbf{W} = \sum_{e \in \mathcal{E}} \frac{V^e}{2} \left( \boldsymbol{\alpha}^e : \mathbf{C} : \boldsymbol{\alpha}^e + \sum_{k=1}^3 \frac{(h_k^e)^2}{12} \boldsymbol{\beta}^{ke} : \mathbf{C} : \boldsymbol{\beta}^{ke} \right)$$

# Results




# 5. Example-based elastic materials

# Art-directable elastic potentials

#### Control the deformation

- Classical deformation mainly driven by the chosen material model and its parameter values
- Often, an artist starts with a vision on how an object should deform
- Setting up a specialized elastic model to follow the preferred example poses











# **Example Manifold**

- Example manifold by example interpolation
  - Interpolate between these examples by interpolating their descriptors



# Results



# Next lecture: computer animation 4