



RFX Unfold

Reimagine Fx | 0.2.3 | Maya 2026 / Windows

Install once. Open from the shelf.

Extract the whole ZIP before you start. It contains RFX Unfold, the Reimagine Fx Installer 1.3.3 and this guide; you don't need a separate installer download.

Use the included installer

1. Open Maya 2026. Drag **RFX_Installer/install.py** from the extracted folder into a Maya viewport.
2. Select **RFX Unfold** and the **Maya 2026** target. Keep **Shelf buttons** on, then click **Install**.
3. Open the **ReimagineFx_Tools** shelf and click **RFX Unfold**. The panel appears beside the Attribute Editor and Channel Box.

Tool missing from the list? Click **Add folder** and select the extracted RFX_ExplodedView folder. Keep RFX_Installer beside it when unpacking.

Manual install

Copy **RFX_ExplodedView** into your Maya 2026 user scripts folder, normally **Documents/maya/2026/scripts** on Windows. Keep its folder name unchanged.

Then drag **RFX_ExplodedView/Install_RFX_ExplodedView.py** into a viewport. This creates the shelf launcher; it doesn't copy the plugin files.

No pip setup needed. Maya supplies Python, PySide6 and Shiboken6; Unfold includes its own DPI helper. If Maya was already running during a manual file update, restart it before opening the new copy.

Installer's separate Gumroad listing

<https://reimagine-fx.gumroad.com/l/rfxtoolsinstaller>



Your first exploded view

Save your scene. Keep Maya Undo enabled.

1. Select your model group or its polygon objects, then click **Create exploded view**. Amount **0** is assembled; **1** is exploded.
2. For separate parts inside one combined mesh, enable **Split disconnected shells** before capture. A welded mesh stays one piece.
3. Adjust **Spread** and the **X/Y/Z gains**. Choose a layout and click **Update layout**. In Pieces, **Pin** holds selected parts in place.

Copies capture the current frame. Materials stay shared with the originals; their animation and deformation aren't copied as live inputs. Hide sources is on by default.

Animate it

Set **Start frame** and **Travel frames**. Stagger delays each piece after the first. Hold starts when the last piece arrives; Return frames sets the trip back (0 leaves the model exploded). Click **Create animation**, then scrub Maya's timeline.

For manual poses, type Amount and click **Key amount**. Once keyed, the slider follows the curve. A typed draft isn't saved until you key it; changing frames drops that draft. Enable **Replace existing Amount keys** before regenerating a sequence.

Panel and source recovery

Float opens its own window. Closing that window with **X** returns the panel to the right-side dock. The shelf button reopens a hidden panel, and your saved rig works with the panel closed.

Restore sources brings the recorded originals back. Use **Remove setup** to restore their visibility and delete generated nodes; Maya Undo brings the rig back. Don't delete the root directly in the Outliner.

Polygon models only; make instances unique. The 1,000-piece cap is a guard, not a playback promise. Unfold doesn't fracture geometry or solve collisions. Read the included README for connection protection and referenced-source limits.