

1) Crear el archivo linux.cfg con host y servicios (en el servidor Nagios)

Abre una terminal en el servidor Nagios y crea el archivo:

```
sudo mkdir -p /usr/local/nagios/etc/objects
```

```
sudo nano /usr/local/nagios/etc/objects/linux.cfg
```

Pega este contenido (reemplaza IP_CLIENTE por la IP del cliente):

```
## Definicion de servidores linux
```

```
define host{
```

```
    use          linux-server
```

```
    host_name     cliente_linux
```

```
    alias         Linux Ubuntu Client
```

```
    address       IP_CLIENTE
```

```
    check_interval 1
```

```
}
```

```
## Definicion de Services
```

```
define service{
```

```
    use          generic-service
```

```
    host_name     cliente_linux
```

```
    service_description  Hard Disk
```

```
    check_interval 1
```

```
    check_command  check_nrpe!check_hda1
```

```
}
```

```
define service{
```

```
    use          generic-service
```

```
    host_name     cliente_linux
```

```
    service_description  Uptime
```

```
    check_interval 1
```

```
    check_command  check_nrpe!check_uptime
```

```
}
```

```
define service{
```

```
    use          generic-service
```

```
    host_name     cliente_linux
```

```
    service_description  Carga del servidor
```

```
    check_interval 1
```

```
    check_command   check_nrpe!check_load
```

```
}
```

```
define service{
```

```
    use          generic-service
```

```
    host_name     cliente_linux
```

```
    service_description  Swap
```

```
    check_interval 1
```

```
    check_command   check_nrpe!check_swap
```

```
}
```

```
define service{
```

```
    use          generic-service
```

```
    host_name     cliente_linux
```

```
    service_description  Ping
```

```
    check_interval 1
```

```
    check_command   check_ping!500.0,20%!800.0,60%
```

```
}
```

```
define service{
```

```
    use          generic-service
```

```
    host_name     cliente_linux
```

```
    service_description  Usuarios activos
```

```
    check_interval 1
```

```
    check_command   check_nrpe!check_users
```

}

Guarda y cierra (Ctrl+O, Enter, Ctrl+X en nano).

2) Decirle a Nagios que cargue ese archivo (nagios.cfg)

Editar nagios.cfg:

```
sudo nano /usr/local/nagios/etc/nagios.cfg
```

Busca la sección donde están los `cfg_file=` y añade **UNA SOLA** línea (si ya existe otra igual no la dupliques):

```
cfg_file=/usr/local/nagios/etc/objects/linux.cfg
```

Guarda y cierra.

3) Verificar la configuración de Nagios (comprobación sintáctica)

Ejecuta la verificación:

```
sudo /usr/local/nagios/bin/nagios -v /usr/local/nagios/etc/nagios.cfg
```

- Si te sale "**Total Warnings:**" o "**Total Errors: 0**", perfecto.
- Si aparecen errores, el comando te indicará el fichero y la línea. Apunta esos errores.