CSE 4512 [Computer Networks Lab] Lab # 07

1. Objectives:

- Describe the concept of dynamic routing
- Explain disadvantages of RIPv1 and improvement in RIPv2
- Configure Routing Information Protocol (RIP) in a network topology following given specifications
- Describe the concept of OSPF and related terminologies
- Explain the advantages of OSPF over RIP
- Configure OSPF in a network topology following the given specifications

2. Theory:

As with other labs, this lab will also build up on the concepts and techniques of previous labs. So, make sure you've properly understood the previous lab contents.

Dynamic Routing:

In the previous lab you learnt the concept of static routing and how to configure static routing in a network. You also saw that static routing has some serious disadvantages when it comes to configure large-scale networks. Network administrator needs to know about the whole topology and the network changes have to be reflected manually in the configuration. In this lab, you'll learn about dynamic routing which overcomes all these issues but at the cost of bandwidth overhead. Still, its better to use extra bandwidth than to configure everything manually.

Basically, dynamic routing lets routers to select routes based on the real-time network condition. Always there will be packets travelling around the networks to keep the routers up-to-date about the present network condition. Then the routers will select an optimal route to a given destination based on some set of metrics. The dynamic routing protocols perform this basic function. As you know by now, there are different types of dynamic routing protocols following different algorithms. Two most common ones are **Routing Information Protocol** (RIP) following distance-vector algorithm and **Open Shortest Path First** (OSPF) protocol following link state routing algorithm. We'll not look at how these algorithms work. This is covered in your theory class. In this lab, we'll look at RIP only. OSPF will be covered in next task.

Routing Information Protocol (RIP)

Before starting, know that RIP is somewhat an obsolete protocol due to its limitations and the advent of more modern and sophisticated protocols like OSPF, EIGRP etc. Still, as this was one of the pioneering dynamic routing protocols and dominated the networking world for quite some time, you need to understand this. This will help you in turn to understand the improvements made in newer protocols.

There are two versions of RIP namely RIPv1 and RIPv2. **RIPv2** is the dominant one and is used almost in all cases where RIP is used. So, we'll focus on RIPv2 only for our lab. Major problem of RIPv1 was that it used to broadcast routing table updates every 30 seconds. You can imagine the flood of packets every 30 seconds that would take place where millions of networks are now interconnected, even if they are configured to send updates at random times. RIPv2 was designed to overcome this issue along with other improvements. You can learn more on these two versions here.

RIP uses hop count as the metric for routes. Paths with lower metric are selected always for a given destination. The max hop count is 15 for both versions of RIP to prevent loops. Any route further than 15 hops away are considered unreachable. To configure RIP, three steps are followed:

I. Enable RIP by using the *router rip* global configuration command.

II. Tell router to use the RIPv2 by the *version 2* command.

III. Tell RIP which networks to advertise by using one or more *network* commands.

In the 3rd step, you don't need to specify any subnet mask when using the network command. The network command takes a classful address as the parameter. As any address beginning with 10 belongs to class A, RIP will be enabled on *all the interfaces* that has IP address that begins with 10.

Open Shortest Path First (OSPF) Routing Protocol:

As you know already, OSPF uses Link State Routing (LSR) algorithm. In OSPF, each router sends its link information to the directly connected routers, known as neighbors, which in turn sends the info to other neighbors. After that each router runs the Shortest Path Algorithm on the received information to determine the optimal route to different networks. The running of the algorithm is one of the reason why OSPF is a CPU-intensive protocol as whenever there's a change the algorithm is run. Still OSPF is better than RIP due to its fast convergence and better load-balancing. Remember that, RIP sends the whole routing table to its neighbors whereas OSPF only sends the link information with various optimizations in place. You can learn more about OSPF and RIP here.

There's a plethora of terminologies and concepts related to OSPF that one needs to know for full understanding of the protocol. Some most common ones are listed <u>here</u>. But for our purpose, we'll just cover the ones necessary for our lab.

• Area: OSPF networks are divided into areas which are a logical collection of routers, links having the *same area identification*. A router within an area must maintain a topological database *for the area to which it belongs*. The router does not have detailed information about network topology outside of its area, which thereby reduces the size of its database. There's a special area called the **backbone area** (*area* 0) to which all other areas must be connected. Different areas can communicate with each other through area 0.

- Area Border Router (ABR): A router with interfaces in two areas is called an ABR. This router is the boundary between two areas.
- Autonomous System (AS): OSPF operates within a single Autonomous System which is a collection of areas. AS is basically a group of networks running under single administrative control. It controls how far the routing information should be propagated and facilitates the filtering of information for sharing with other AS.
- **Designated Router (DR):** A router is elected as the Designated Router (DR) and another as Backup Designated Router (BDR) on a multi-access network (like LAN) in OSPF. DR and BDR serve as the *central point* for exchanging OSPF routing information. Each non-DR or non-BDR router will exchange routing information *only* with the DR and BDR, instead of exchanging updates with every router on the network segment. DR will then distribute topology information to every other router inside the same area, which greatly reduces OSPF traffic. For more, you can read here.
- Router ID: Each router running the OSPF protocol is assigned a router ID to uniquely identify that router within an AS. This is a 32-bit number and can be set manually by using the router-id command. If the router ID is not set manually then the highest IP address of the router's loopback address will be the router ID. If there's no loopback address then the highest active IP address on any of the router's interfaces will be the router ID. Remember to restart the router to reflect the new router-id assignment. The reload command will restart the router. Also, the clear ip ospf process command will work for the new router-id assignment.
- Cost: The cost in OSPF is calculated as Reference Bandwidth / Interface Bandwidth. The default value of reference bandwidth is 100 Mbps but it can be set manually. The command to manually set the reference bandwidth is auto-cost reference-bandwidth <value>. Note that, value here is in units of Mbps. So, value=100 would mean 100 Mbps. You can change the interface bandwidth with the bandwidth <value> command. But, here the value is in units of kbps.
- Wildcard Mask: The command to configure which networks to advertise is network <ip_address> <wildcard_mask> area <area_id>. Unlike RIP, the network command in OSPF supports classless routing and that support is achieved by the wildcard_mask. This mask is like an inverted subnet_mask but with different interpretation. The 0 bits in the mask indicate the corresponding bit positions that must match the same bit positions in the IP address. The 1 bits indicate the corresponding bit positions don't need to match the same bit positions in the IP address. Its best understood by an example. Suppose, there's a 10.0.1.0 directly connected subnet to our router that we want to advertise in the OSPF routing process. The command to include that subnet in the advertisement would be:

network 10.0.1.0 0.0.0.255 area 0


According to the wildcard_mask used in the above command, first 24 bits of the addresses must match and rest 8 bits don't need to match. So, any interface having IP address in the format 10.0.1.x will match in this case. A more detailed explanation of wildcard_mask with more examples can be found here.

• **Process ID**: When enabling OSPF in a router, you need to mention a process ID. All OSPF functions will then be performed under that process. OSPF configuration mode is entered using the command router ospf process_id>. You can have more than one OSPF processes in a single router. The process IDs will be different for different processes. Each OSPF process has its separate database, topology table etc. More on process ID can be read from here.

Now lets mention some key concepts in OSPF. OSPF enabled routers to send *hello* packets to each other in certain intervals known as the *hello interval*. This is required to establish a neighbor relationships and to let other router know the availability of the router. For example, if the *hello interval* is 5 seconds, then each router will send *hello* packets to the neighboring router in every 5 seconds. There's another interval known as the *dead interval* which is usually 4 times of the hello interval. If a router doesn't receive *hello* packets from its neighbors then after this *dead interval* amount of time that neighbor will be declared *non-operational* and the routing table will be updated accordingly.

In OSPF, some interfaces are configured as passive-interfaces. Passive interfaces don't send hello packets. This is usually done for the local-LAN facing interfaces. Note that, the network connected with the passive interface will still be advertised as OSPF has been enabled in that interface. Check out this to learn more about passive interfaces.

3. Configure RIP:



I. Configure R1 Interfaces

```
R1(config) # int g0/0
R1(config-if) # ip address 10.0.1.1 255.255.255.0
R1(config-if) # no shutdown
R1(config-if) # exit

R1(config) # int g0/1
R1(config-if) # ip address 172.16.0.1 255.255.0.0
R1(config-if) # no shutdown
R1(config-if) # exit

R1# copy running-config startup-config
```

II. Configure R2 Interfaces

```
R2(config) # int g0/1
R2(config-if) # ip address 192.168.0.1 255.255.255.0
R2(config-if) # no shutdown
R2(config-if) # exit

R2(config) # int g0/0
R2(config-if) # ip address 172.16.0.2 255.255.0.0
R2(config-if) # no shutdown
R2(config-if) # exit

R2# copy running-config startup-config
```

III. Configure PC0

IP: 10.0.1.10

Mask: 255.255.255.0 Gateway: 10.0.1.1

IV. Configure PC1

IP: 192.168.0.10 Mask: 255.255.255.0 Gateway: 192.168.0.1

V. Configure RIP in R1

R1(config) #router rip R1(config-router) #version 2 R1(config-router) #network 10.0.0.0 R1(config-router) #network 172.16.0.0

VI. Configure RIP in R2

R2 (config) #router rip
R2 (config-router) #version 2
R2 (config-router) #network 192.168.0.0
R2 (config-router) #network 172.16.0.0

VII. Verify

R1# show ip route rip
Ping PC1 from PC0

4. Configure OSPF:



I. Configure R1 Interfaces

R1(config)# int g0/0
R1(config-if)# ip address 10.0.1.1 255.255.255.0
R1(config-if)# no shutdown
R1(config-if)# exit
R1(config)# int g0/1

```
R1(config-if)# ip address 172.16.0.1 255.255.0.0
R1(config-if)# no shutdown
R1(config-if)# exit
R1# copy running-config startup-config
```

II. Configure R2 Interfaces

```
R2(config) # int g0/1
R2(config-if) # ip address 192.168.0.1 255.255.255.0
R2(config-if) # no shutdown
R2(config-if) # exit

R2(config) # int g0/0
R2(config-if) # ip address 172.16.0.2 255.255.0.0
R2(config-if) # no shutdown
R2(config-if) # exit
```

R2# copy running-config startup-config

III. Configure PC0

IP: 10.0.1.10

Mask: 255.255.255.0 Gateway: 10.0.1.1

IV. Configure PC1

IP: 192.168.0.10
Mask: 255.255.255.0
Gateway: 192.168.0.1

V. Configure OSPF in R1

```
R1(config) # router ospf 1
R1(config-router) # network 10.0.1.0 0.0.255 area 0
R1(config-router) # network 172.16.0.0 0.0.255.255 area 0
```

VI. Configure OSPF in R2

```
R2(config) # router ospf 1
R2(config-router) # network 192.168.0.0 0.0.255 area 0
R2(config-router) # network 172.16.0.0 0.0.255.255 area 0
```

VII. Verify

```
R1# show ip ospf neighbor
R2# show ip ospf neighbor
Ping PC1 from PC0
```

5. Tasks:

I. Task 1

You will implement RIP following the address configurations. You need to create the topology on your own. Use PCs to check connection and configuration of RIP.

Device	Host Name	Interface	IP Address	Subnet Mask
R1	R1	Serial 0/0/0 (DCE)	172.X.0.1	255.255.255.224
		Fast Ethernet 0/0	172.X+5.0.1	255.255.255.128
		Fast Ethernet 0/1	172.X+5.0.150	255.255.255.128
R2	R2	Serial 0/0/0 (DTE)	172.X.0.2	255.255.255.224
		Fast Ethernet 0/0	172.X+10.0.1	255.255.255.0

X=Last 2 digits of your student ID

II. Task 2

Implement the given network topology with the provided address specifications as described in the pdf Task-2_OSPF. Answer the questions accordingly. You're not provided a .pka file for this task. Make sure you've properly read on the theory section of this handout to understand the concepts mentioned in Task-2_OSPF. Otherwise, you'll face difficulties and might not get everything that's introduced there.

III. Task 3

You will answer the given questions in this task and implement very small portion of OSPF. The task description for this task is provided in the pdf Task-3_verify-single-area-ospfv2. You're provided a .pka file for this task. As with task 2, make sure you've read the theory section properly. Our suggestion would be to attempt task 3 after you've completed task 2 as many of the concepts of OSPF are explained and shown in task 2.