Hibernate Tip: Map generated values

Question:

The database administrator set up a trigger to generate the value of a database column. How can map this column with Hibernate so that I can use the generated value within my application?

Solution:

You can annotate an entity attribute with @Generated(GenerationTime value), to tell Hibernate that the database will generate the value of the attribute. The GenerationTime Enum tells Hibernate when the database will generate the value. It can either do this NEVER, only on INSERT or ALWAYS (on insert and update). Hibernate will then execute an additional query to retrieve the generated value from the database.

The following code snippet shows an example for such an entity mapping.

```
@Entity
public class Author {

    @Column
    @Generated(GenerationTime.ALWAYS)
    private LocalDateTime lastUpdate;

...
}
```

Hibernate Tip: Map generated values

As you can see in the following log output, Hibernate now performs an additional query for each insert and update statement to retrieve the generated value.

```
10:33:49,612 DEBUG [org.hibernate.SQL] – insert into Author (firstName, lastName, version, id) values (?, ?, ?, ?)

10:33:49,620 DEBUG [org.hibernate.SQL] – select author_.lastUpdate as lastUpda4_0_ from Author author_ where author_.id=?

10:33:49,644 DEBUG [org.hibernate.SQL] – update Author set firstName=?, lastName=?, version=? where id=? and version=?

10:33:49,646 DEBUG [org.hibernate.SQL] – select author_.lastUpdate as lastUpda4_0_ from Author author where author .id=?
```