



Layer 2 Switching and Spanning Tree Protocol

Understanding the fundamentals of Layer 2 switching and how Spanning Tree Protocol prevents network loops

© DAC STRATEGIC ELECTRONICS GROUP

What is Layer 2 Switching?

01

Collision Domain Separation

Operates at the Data Link Layer of the OSI model using MAC addresses. Unlike hubs, switches create dedicated collision domains for each port, dramatically boosting network performance.

02

Intelligent MAC Address Learning

Maintains dynamic MAC address tables mapping device locations to specific ports. Frames are inspected and forwarded only to the appropriate destination, eliminating unnecessary traffic.

03

Full-Duplex Communication

Enables simultaneous, bidirectional sending and receiving on each active port. This results in maximum bandwidth utilization and significantly improved network scalability.



Understanding Spanning Tree Protocol (STP)

Spanning Tree Protocol is a network protocol that prevents loops in Ethernet networks by creating a loop-free logical topology. Originally defined in IEEE 802.1D, STP ensures that there is only one active path between any two network devices, even when multiple physical paths exist.

01

Root Bridge Election

All switches participate in electing a Root Bridge based on the lowest Bridge ID (priority + MAC address).

02

Path Cost Calculation

Each switch calculates the cost to reach the Root Bridge through different paths.

03

Port State Assignment

Ports are designated as Root, Designated, or Blocked based on their role in the spanning tree.

C-DAC STRATEGIC ELECTRONICS GROUP

Why STP is Essential: The Problem of Network Loops

WITHOUT STP: NETWORK CHAOS

01

Broadcast Storms

Frames circulate endlessly, consuming all available bandwidth.

02

MAC Address Instability

Switches constantly update their MAC tables as frames arrive from different ports.

03


Duplicate Frame Delivery

End devices receive multiple copies of the same frame.

04

Network Congestion

Exponential traffic growth leads to complete network failure.



CRITICAL IMPACT: Network loops can cause complete network failure within seconds due to exponential traffic multiplication.

How STP Creates a Loop-Free Network

STP transforms a potentially looped physical topology into a logical tree structure by strategically blocking redundant paths while maintaining network connectivity and fault tolerance.

1

Bridge Protocol Data Units (BPDUs)

Switches exchange BPDUs every 2 seconds to share topology information and coordinate the spanning tree calculation.

2


Root Bridge Selection

The switch with the lowest Bridge ID becomes the Root Bridge, serving as the reference point for all path calculations.


3

Port Blocking

Redundant ports are placed in blocking state, preventing loops while remaining ready for failover scenarios.



STP Port States and Transitions



Each state transition includes built-in timers (Forward Delay = 15 seconds) to ensure network stability during topology changes. This conservative approach prevents temporary loops during convergence.

Network Topology: Before and After STP

Physical Topology



Multiple physical connections exist between switches, creating potential loops and redundant paths for fault tolerance.

Logical STP Topology



STP creates a logical tree structure by blocking redundant ports while maintaining connectivity and redundancy.

"STP transforms complex meshed networks into elegant tree structures, ensuring both connectivity and stability."



STP Variants and Evolution

50s

Original STP Convergence

IEEE 802.1D convergence time can take up to 50 seconds during topology changes.

6s

RSTP Improvement

Rapid Spanning Tree Protocol (802.1w) reduces convergence to under 6 seconds.

1s

Modern Convergence

Per-VLAN STP variants can achieve sub-second convergence times.

The evolution of STP has focused on reducing convergence times while maintaining loop prevention. Rapid Spanning Tree Protocol (RSTP) introduced new port roles and states, while Per-VLAN Spanning Tree (PVST+) allows different spanning trees for each VLAN, optimizing load distribution across redundant links.

Types of Spanning Tree Protocol

STP (IEEE 802.1D)

The original Spanning Tree Protocol standard, providing basic loop prevention with slower convergence times of 30-50 seconds. Uses a single spanning tree instance for all VLANs, which can lead to suboptimal path utilization in multi-VLAN environments.

PVST+ (Cisco Proprietary)

Per-VLAN Spanning Tree Plus allows separate spanning tree instances for each VLAN, enabling load balancing across different VLANs. Provides better bandwidth utilization but requires more processing power and memory.

RSTP (IEEE 802.1w)

Rapid Spanning Tree Protocol significantly improves convergence times to 1-6 seconds through enhanced port states and faster topology change detection. Backward compatible with original STP while providing much faster recovery.

MSTP (IEEE 802.1s)

Multiple Spanning Tree Protocol combines the benefits of PVST+ and RSTP by grouping VLANs into instances, reducing CPU overhead while maintaining load balancing capabilities and fast convergence.

STP Protocol Comparison

STP

IEEE 802.1D

Convergence Time

30-50 seconds

VLAN Support

Single instance

Low Scalability

PVST+

Cisco Proprietary

Convergence Time

30-50 seconds

VLAN Support

Per-VLAN instance

Medium Scalability

RSTP

IEEE 802.1w

Convergence Time

1-6 seconds

VLAN Support

Single instance

Medium Scalability

MSTP

IEEE 802.1s

Convergence Time

1-6 seconds

VLAN Support

Multiple instances

High Scalability

C-DAC STRATEGIC ELECTRONICS GROUP

The evolution of spanning tree protocols has focused on reducing convergence times and improving VLAN support. MSTP represents the current best practice, combining fast convergence with efficient resource utilization in large-scale networks.

Bridge ID and Priority Fundamentals

Bridge ID Components

An 8-byte unique identifier used by STP to elect the network's root bridge.

Priority (2 bytes)

Configurable value that determines root bridge election priority.

MAC Address (6 bytes)

Unique hardware identifier serving as the ultimate tiebreaker.

FORMULA

Bridge ID = Priority + MAC

Election & Defaults

Default Priority Value

32768

Standard default for all switches. Without custom configuration, the lowest MAC address wins.

Root Election Process

1. Lowest Bridge ID wins.
2. Priority is evaluated first.
3. MAC address breaks ties.



Configuring STP Priority

01

Understanding Priority

Priority must be configured in multiples of 4096 (0 to 61440). Lower values have higher priority for root bridge election. Standard default is 32768.

02

Global Configuration

Enter global configuration mode on the Cisco switch to modify spanning tree parameters. This requires privileged administrative access.

03

Set Priority Value

Use the **spanning-tree vlan** command to set priority for specific VLANs or spanning-tree priority for all VLANs.

04

Verify Configuration

Use show spanning-tree commands to verify the priority changes and confirm root bridge election results across the active network topology.

```
Switch(config)# spanning-tree vlan 10 priority 4096
Switch(config)# spanning-tree vlan 20 priority 8192
Switch# show spanning-tree vlan 10
```

Key Design Principle

Setting a lower priority value (like 4096) makes a switch more likely to become the root bridge. This is crucial for network design, as the root bridge should typically be a high-performance, centrally located switch.

Root Bridge Election Process



1 Compare Bridge IDs

All switches exchange Bridge Protocol Data Units (BPDUs) containing their Bridge ID. The switch with the lowest Bridge ID is elected as root.

2 Calculate Root Path Cost

Each non-root switch calculates the cost to reach the root bridge through different paths, considering link speeds and hop counts.

3 Determine Port Roles

Ports are assigned roles: Root Port (best path to root), Designated Port (forwarding), or Blocked Port (preventing loops).

Port States in STP

Blocking: Receives BPDUs only

Listening: Processes BPDUs, no data forwarding

Learning: Builds MAC address table


Forwarding: Full operation, forwards data

Convergence Timeline

Traditional STP requires 50 seconds for full convergence: 20 seconds in Listening state, 15 seconds in Learning state, plus additional time for topology changes.

When to Disable Spanning Tree

Protocol



Valid Scenarios for Disabling STP

Point-to-Point Links: Direct connections between two devices with no possibility of loops

Access Ports: Ports connecting end devices (PCs, servers) that cannot create loops

Performance Critical Applications: Where STP convergence time is unacceptable

Controlled Environments: Networks with guaranteed loop-free physical topology

Alternative Solutions

Instead of completely disabling STP, consider using PortFast for access ports, or RSTP/MSTP for faster convergence while maintaining loop protection.

⊗ **Critical Warning:** Disabling STP removes loop protection and can cause network outages if physical loops exist.

Risks of Disabling STP

Broadcast Storms

Without STP, broadcast frames can circulate indefinitely in loops, consuming all available bandwidth and causing network congestion. This can bring down entire network segments within seconds of a loop formation.

MAC Address Table Instability

Looped traffic causes switches to constantly update their MAC address tables as they see the same MAC addresses on different ports, leading to forwarding errors and packet loss.

Network Outages

The combination of broadcast storms and MAC table instability can cause complete network failure, requiring physical disconnection of cables to restore service.

These risks make it essential to have absolute certainty that no physical loops exist before disabling STP. Even temporary loops created during maintenance or accidental cable connections can cause immediate network failure.

STP Configuration Commands

Disabling STP Commands

```
! Disable STP for specific VLAN
Switch(config)# no spanning-tree vlan 10
! Disable STP globally (dangerous)
Switch(config)# no spanning-tree vlan 1-4094
! Enable PortFast (safer alternative)
Switch(config-if)# spanning-tree portfast
! Verify STP status
Switch# show spanning-tree vlan 10
```

Best Practice Commands

```
! Configure root bridge priority
Switch(config)# spanning-tree vlan 10 root primary
! Set backup root bridge
Switch(config)# spanning-tree vlan 10 root secondary
! Enable RSTP mode
Switch(config)# spanning-tree mode rapid-pvst
! Configure port as edge port
Switch(config-if)# spanning-tree portfast edge
```

Monitoring Commands

`show spanning-tree summary` — Overview of STP status
`show spanning-tree interface` — Port-specific details
`debug spanning-tree events` — Real-time STP changes

Troubleshooting Tips

Always verify topology before changes, use `show cdp neighbors` to map connections, and implement changes during maintenance windows to minimize impact.

Key Takeaway: STP is essential for network stability. When modification is necessary, use safer alternatives like PortFast or RSTP rather than complete disabling.

Key Takeaways: STP Best Practices



Loop Prevention is Critical

STP ensures loop-free networks by blocking redundant paths while maintaining fault tolerance and network connectivity.



Root Bridge Selection Matters

Manually configure Bridge Priority values to control Root Bridge placement for optimal network performance and predictable behavior.



Choose the Right STP Variant

Use RSTP or PVST+ for faster convergence times and better scalability in modern network environments.



Never Disable STP Carelessly

Disabling STP without proper network design can lead to catastrophic broadcast storms and complete network failure.

Remember: STP is not just a protocol—it's the foundation of stable, scalable Ethernet networks. Proper understanding and configuration of STP variants is essential for network reliability.