Data Link Layer

Lecture 7 Framing and introduction to CRC

in the data link layer, we try to "make sense" of the incoming buts

which bits together mean

something in the stream of data.

- The resulting unit is called a frame.

In a frame, we first need to demarcate where the section begins/ends.

High-Level Data Link Control (HDLC) is used as Layer-2 technology in Wide Aea Networks.

(WANS)

The (HDLC) frame has a begin sequence, & bits header, 16 bits body, variable CRC, and 16 bits end sequence. 8 hits

The begin /end sequence are the same: 01111110 If there is nothing to send, we continuously send this It also helps in clock synchronization.

Bit Stuffing

Frame

What if this sequence appears elsewhere?

We do bit stuffing. Say 01111110 is somewhere in the middle. Lawe insert bits.

What HDLC does is:

→ If you see 5 consecutive Is, insert a O.

011/11/00/01/11/11/00/01/11/11/0

OITH TO 000 ITH TO 100 OITH TO 110

At the receiver,

we somehow have to remove these stuffed bits.

Wherever you see 5 consecutive Is, remove the subsequent stuffed 0.

The end sequence still has 6 consecutive Is.

But what if there is some bit error?

[1] | O → Remove (bit stuffing)

| 10 → Assume end sequence
| 11 — Assume error has occurred and discard the frame

(We discard everything until we see the sequence again)

This is very barebones though, we need something better for errors.

Cyclic Redundancy Check (CRC)

CRC We just append the k-bit CRC to the n-bit dataword to get a "codeword".

The space of datawords is the set of all 2^n bit words. We keep it such that only 2^n of the 2^{n+k} (n+k)-bit strings are valid. An issue only arises when the error is such that the error evaluation is a codeword as well.

⇒ We need to ensure that codewords are "for apart".

Given $v, w \in \{0,1\}^n$, the Hamming distance between v and w is $d(v, w) = \{i \in [n] : v_i \neq w_i\}$.

Hamming distance (number of positions they are distinct) For a "code" $C \subseteq \{0,1\}^n$: the Hamming distance of C is min $\{d(v,\omega): v,\omega\in C, v\neq\omega\}$.

We want this distance to be large.

GF(2) = IF(2) is a finite field with elements {0,1}.

Addition (+) has identity 0. (Note that a+b=a-b)

Multiplication (x) has identity (.

CRC is based on a cyclic code


If v is a codeword, cyclic shifts of value result in codewords.

To generate a CRC, we use long division (in \mathbb{F}_2)

The divisor/generator is of length k+1 bits.

For example, say k=3 and the generator or "divisor" is 11D1 and n=6 with data word 11D110

Generator Divisor



The codeword is then 110110111.

At the sender,

Long division for a given generator can be implemented using shift regristers. For generator 1101,

Dataword | 000 | Stores | bit and shifts to the right by I each clock cycle | (The (7) xDRs) |

(xOR with 000 if leading bit 0) | (xOR with 101 if leading bit 1) | (1) | (1) | (1) | (1) | (2) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1) | (1)

After Dataword 000 is emptied, the CRC is Left in the shift registers.

At the receiver, either

- 1. pass the dataword with k Os through the CRC circuit and verify that the CRCs match or
- 2. pass the entire received word through the CRC circuit and verify that you get all Ds.

Lecture 8 CRC Polynomial Arithmetic

So say we transmit some codeword with equivalent polynomial P(x). Let the error bitstring be E(x).

The received word is then P(x) + E(x).

We divide the received polynomial by C(x) and if the resultant is D, we say there is no bit error by corresponding to generator.

We want

$$\frac{P(x)+E(x)}{C(x)} \neq 0 \quad \text{if } E(x) \neq 0.$$

→ Single bit errors.

$$E(x) = x^{i}$$
 for some i.

$$\frac{P(x) + E(x)}{C(x)} = \frac{P(x)}{C(x)} + \frac{E(x)}{C(x)} = \frac{E(x)}{C(x)}.$$

If
$$C(x) = x^k + \cdots + 1$$
, single bit errors can be detected.
Os or 1s

$$E(x) = C(x) \cdot D(x)$$
will have at least two non-zero powers of x.

(So for example, 1101 can detect single but errors)

→ 2-bit errors.

 $E(x) = x^{j} + x^{\bar{i}} = x^{\bar{i}} (x^{j-\bar{i}} + i)$ (suppose $j > \bar{i}$) Write each polynomial as a product of irreducible polynomials.

$$\frac{E(x)}{C(x)} = \underbrace{g_1(x) \cdots g_t(x)}_{f_1(x)} \cdots f_m(x)$$

If C is of the form $x^k + \cdots + 1$, no $f_r(x)$ is of the form x^B . \Rightarrow no f_r will divide the x^i (if i > 0).

However, we could have

 $(x^k + \cdots + 1)(\cdots) = x^k + 1$ for some "large" Y. So if j-i is large (the errors are far apart), the bit errors might not be detected

The smallest Y such that C(x) divides x +1 is called its order.

It is known how to find C(x) of the form $x^k + \cdots + 1$ such that it has order $2^k - 1$.

So while this limits the length of the codeword that can be transmitted, it gets the job done quite well.

So if we have a 16 bit CRC, we can transmit data with at most 2^{16} -16 bits while detecting 2-bit errors.

$$E(x) = x^{i_1} + x^{i_2} + \cdots + x^{i_{2r+1}}$$
.

If $C(x)$ has $(1+x)$ as a factor, it cannot divide x of this form. Indeed,

$$D(x) \rightarrow 0001111000$$

$$XD(x) \rightarrow 0011110000$$

$$60100001000$$

$$\text{two Is in (1+x)D(x)}$$

 $+ x^{8} + x^{7} + x^{5} + x^{4} + x^{2} + x + 1$

If C(x) has an even number of terms, it can detect any error E(x) with an odd number of terms

HDLC uses
$$CRC-16-1BM$$

 $C(x) = x^{16} + x^{15} + x^2 + 1$
 $CRC-32$ has
 $C(x) = x^{32} + x^{26} + x^{23} + x^{22} + x^{16} + x^{12} + x^{11} + x^{10}$

Lecture 9 ARQ

How do we detect a burst of errors?

That is, a bunch of contiguous brits become erroneous.

The error is of the form $E(x) = x^{i+l-1} + x^{i+l-2} + \cdots + x^{i+l} + x^{i}$

Let the CRC be of the form
$$C(x) = x^{K} + \cdots + 1$$
 anything

To be undetected, C(x) divides E(x).

$$\frac{E(x)}{c(x)} = \frac{x^{i} \left(x^{i-1} + x^{i-2} + \dots + 1\right)}{x^{k} + \dots + 1}$$
 this is the part that matters no x^{i} factor

If l-1 < k, then C(x) cannot divide $x^{l-1} + x^{l-2} + \cdots + 1$. So bursts of length at most k can be detected.

Another thing we shall study is ARQ-Automatic Repeat request Sometimes, if the link between two nodes is unreliable, some of the handling of reliability is done by the DLL. (TCP is quite slow) WiFi uses ARQ.

(the wireless link is prone to errors)

Suppose the sender sends out a frame that the receiver receives St later. How do we know if the frame has got there reliebly?

Speed of light delay

The receiver sends out an acknowledgement that is received after St. (ACK)

The ACK frame is quite small, it just acknowledges the specific frame. How long should the sender wait for the ACK?

This is quite non-trivial in TCP because there are factors such as where you are located.

Here, however, we are just concerned about a single link.

We need to figure out what the RTT is.

first bit of sent frame from sender to last bit of ACK frame to sender

The distance between the (WiFi) occess point and the device is usually a few 10s of meters.

It will take a couple of nanoseconds (not insignificant).

Wait 2-3 times the RTT and if ACK not received, retransmit.

Note that the time also depends on the size of the frame and ACK.

What if the ACK frame is in error/did not reach the sender? A


Timeout timeout is said to occur. The sender assumes the worst case and resends the frame after the timeout (although the receiver has already received the frame).

It is also possible to run into problems if we set the timer to be too small. We receive the ACK for a previous version of the (same) frame while we are waiting for the current frame.


If the timer is too large, then we waste a lot of time if there is an issue with the frame (or ACK).

We must set the timer appropriately to cut down on resources and redundancy.

We often represent protocols using state diagrams or flowcharts. For example,



Each action is represented by a flowchart.



Wireless systems usually use ARQ.

Lecture 10 Medium Access

Recall the issue of medium access that we had (briefly) looked at. The wire there is the "medium" If everyone tries to use the medium at the same time, the messages will collide/interfere. It is more problematic in the wireless case since the signal decays very fact with distance.

For now, we shall look at Ethernet LAN, which uses CSMA - Carrier Sense Multiple Access.

There is a central bus (wire) and we want to prevent multiple people from simultaneously transmitting.

One idea is to have some central authority whose permission you need (this is used in wireless cellular networks).

Further, there is the issue of how this authority knows when someone wants to transmit. If we know how many nodes there are, we could do TDMA (Time Division Multiple Access) - give regular time slots during which (only) they can transmit. Obviously, this leads to massive inefficiency. What if a new person joins? What if the authority goes down?

If a node has data to send, it creates a frame and sends it. Broadcast signals are sent to everyone on the network.

Broadcast Unicast Multicast

The most common are unicast signals - there is a single destination node. There are also multicast signals.

This part of the pertinent information should be mentioned as well. In this scheme, what if there is a collision? Neither receiver receives the information if the information is sent by both users again, there could be another collision.

We also need a mechanism for collision detection.

If a collision is detected, we shouldn't have both senders try again immediately.

CSMA is a roundom access protocol— the schedule for transmission is not decided in advance.

At each sender node, we back off for some random amount of time before retransmitting.

The "Carrier Sense" means that if someone else is transmitting, we wait before sending our own message. This resolves the issue that occurs when one person retransmits slightly before the other-

This could still be problematic if many people are trying to communicate simultaneously, so we need to refine this idea.

|EEE 802.3 uses CSMA - CP La Collision Detection

To do carrier sense, we can just check if there is some reasonable amound of energy on the wire.

(sufficiently larger than the noise energy)

How do we perform collision detection?

In wireless, just check if ACK is received.

In wired, when the signals add up, we could do something with Fourier analysis. More simply however, we see that the energy of the signal increases after two signals add up.


Keep another threshold. If the energy is greater, then declare that a collision has occurred.

So we have two thresholds - one for carrier sense and one for collision detection


Amother issue is: what if one side detects the collision much earlier and stops transmitting so the other side does not detect a collision?

So after the first side realizes there is a callision, it sends out a (short) jamming signal so the other side detects a collision (it is guaranteed that detection will happen by the time the jamming signal ends)

It is worth noting that there may be multiple "other side"s.



Frame details in 802.3:




Why minimum frame size?

We assume that the WAN is at most 2500 m wide.

RTT
$$\simeq 5000$$
 = 25 µs 2×10^8 ?

Less to speed of light but not exactly

If the frame transmission time is (much) larger than the RTT, it is possible that we do not detect a collision before the frame finishes transmitting.



Along the way, we also have repeaters that reproduce the signal. This may add some more time, so let us conservatively take 50 µs (instead of 25 µs).

64 bytes at 10 Mbps \rightarrow 51.2 μ s.

If we have larger distances or higher rates, the minimum frame size would be made larger.

Why maximum frame size?

- i. If we have a larger frame, the probability of getting an erroneous bit is high.

 If p is the probability of a particular bit going wrong (assume iid), the probability of getting an error is 1-(1-p) ? Jength
- 2. Other people do not get an opportunity to transmit for a long time.
- 3. Memory requirements at the NIC card go up live need to store it for checking the CRC).


Finally, what distribution do we pick the random backoff from? If Δ is the minimum wait time, we pick uniformly from $\{\Delta u : u \in \{0,1,\cdots,2^k\}\}$. We want k to be larger if more people have callided. How?

What we do is that we initially pick some (small) k. If a collision occurs, we increase k (and recurse). This system is known as exponential back off.

If we use linear instead, we might end up waiting for a long time before no collision occurs

A more complete flowchart of the above information is given on the next page.

Backoff



Wireless LANs have ideas similar to wired systems, but slightly modified.

Say we have two laptops connected to the same access point that want to communicate.

What if we use CSMA-CD? The problem here is that the signal decays very fast, so it might be interpreted as noise by other systems performing carrier sense (it decays as other some 2<a<x). For the same reason, collision detection is not very effective either.

So what do we do? Assigning frequencies might work, but who would assign frequencies?

Note that carrier sense could work if the senders are close by, so lets leave it in.

Can we try cancelling out our own signal? The received might not be very close to the transmitted signal due to noise (in case of a collision).

Why not use acknowledgements? First do carrier sense for some time. If free, start transmitting. Then just hope that the receiver has received it correctly and wait for an acknowledgement.

If there is no acknowledgement, assume a collision has occurred.

There is another issue called the tridden terminal problem.

Hidden Terminal B

B can hear both A and C but A and C cannot hear each other. If $A \rightarrow B$ and $C \rightarrow B$, there is a collision at B. Neither receives an acknowledgment but a lot of time is wasted.


Virtual Carrier Sensing. Maybe before A transmits to B, it sensing sends a short request to send frame to tell B that it intends to send. B then tells its neighbours about the same then send A a short clear to send frame. Then when C hears the CTS, it knows that it should not transmit.

We can also include in the CTS how long the channel will be busy.

(time for A's frame + ACK to A)

This is known as the Network Allocation Vector. This tells B's reighbours how long to stay silent.

To do this, the RTS itself includes a NAV.



The rule is that anyone hearing a RTS or CTS remains silent for the corresponding NAV. We want silence around both the sender and receiver.

IF A doesn't hear CTS, it doesn't transmit.

If there isn't much contention in the network, we might not use RTS/CTS to save time.

RTS/CTS are usually sent using lower modulation (like BPSK) so the duration might be large—we want it to be heard by a lot of people.

Lecture 12 Collisions in WiFi

The overall WiFi algorithm is called CSMA-CA

Collision Avoidance

Another problem is the exposed terminal problem. Say we have

Exposed Terminal

D A B C

Each can hear neighbours.

In theory A-D and B-C could be transmitted simultaneously
But Corrier Sense Prevents this because A and B are exposed to each other.

(within hearing range)

Each will have a contention window (cw).

Contention Window $A \rightarrow B$ $A \rightarrow B$ $A \rightarrow B$ $C \rightarrow B \rightarrow B$ C

Say A is transmitting to B, A has more data to transmit after the corrent frame, and C has date to transmit as well. After the frame is done, each waits for a fixed time Distributed Inter-Frame Spacing (DIFS). This gives some notion of priority (if you wait less, you can transmit). The time gap between the RTS/CTS or CTS/Data or Data/ACK is called the Short Inter-Frame Spacing (SIFS).

Obviously, the DIFS should be greater than the SIFS.

Why do we need SIFS?

- -> Wait for processing (decoding and stuff PHY/MAC(DLL) processing)
- -> B hears RTS, then NIC switches from receive to transmit


(which takes some time)

-> A sends RTS, change from transmit to receive.

After the DIFS, each waits for a random amount of time.

Divide time into slots (9 µs in WiFi). If someone starts transmitting in a slot, someone who is weiting for the next slot to transmit should be able to carrier sense the first person and not transmit.

A starts



So the slot length should take propagation delay, offset in slots, and time to carrier sense into account.

C must hear and corrier sense A within the slot if it starts transmitting. Further, if A does not transmit, it needs time to switch from receive to transmit mode.

After the DIFS, we wait for some random number of slots. This is where contention window enters the picture.

Initialize $W = Unif(0, CW_{max})$ Remaining waiting time

For every idle slot, decrement W by 1.

The waiting time is not reset!

Freeze W if channel gets busy. $A \rightarrow B \qquad DIFS \qquad$

Note that the waiting time is not decremented during the SIFS. We detect a collision if -> sent RTS, no CTS -> sent data, no ACK.

In this case, we do

CW max = CW max × 2

CW max = min (CW max, Maximum allowed value) and then choose the (random) waiting time again.

The name of this protocol is IEEE 802:11. (b,g,n,ac,ax)

The frame has

Preamble | Signal | Modulation used, MAC addresses, data etc. Frame Check Sum (CRC) coding rate MAC part We "code" the data before passing it to the channel to protect against bit errors.

The rate is the degree of redundancy no number of bits Wifi has $\sim \frac{3}{4}$ or $\frac{5}{6}$.

information bits

	rate	bit rate	channel width
		(during frame)	
802.11 g - 64-QAM	(3/4)	54 Mleps	20 MHz
802.11 n - 64-QAM	(<i>5</i> %)	150 MAPS	40 MH2
802. Il ec - 256-QAM	(3/4) or (5/6)	866 Mbps	upto 160 MHz
802.11 ax - 1024-QAM	(3/4) or $(5/6)$	1.2 Glops	upto 160 MHz
		(ozlz)	•

Codes help us detect and possibly correct codewords In MIMO (Multiple Input Multiple Output), the sender/receiver have multiple antennas. The channel width is the wiath of the frequency bandwidth. Changing nothing else, bit rate & channel width.

Using MIMO instead of SISO could drastically increase the bit rate.

PIFS

Ly Point Coordination Function — intermediate priority more centralized

DIFS uses the Distributed Coordination Function.

Now, what about the QoS? Is it possible to give higher priority depending on the application?

IEEE 802.11 e was created for this. It does not give a hard guarantee.

Application Voice Video Other

CWmax(initial) 3 7 15 (Rarely used)

CWmax(max) 7 15 1023

To know which packet is there, there is some cross-application interaction between the application layer and DLL.

WiFi is, in general, terrible for Qos.

SIFS = 10 \mus for 11g, 11n = 16 \mus for 11ac etc.

Just like in ethernet, there is a maximum number of retries for collisions after which we give up.

Wifi protocols are usually backward compatible.

If we use the Distributed Coordination Function, Wifi is not too hard to set up and get working.

Lecture 12

We have discussed CSMA-CD and CA The government allots particular frequency bands and it is a free-for-all within those bands—anyone can try using them.

How would we ensure that say, our WiFi signals and our neighbours WiFi signals do not interfere?

Since there is no centralized coordinator, we just use CSMA, a very decentralized protocol.

This is for unlicensed bonds, what about licensed bands? The govt auctions frequency bands for exclusive usage by some company.

CSMA isn't the best here because we do have some centralized coordinator


let us book at cellular networks. The company can use a bandposs filter

to ensure that other companies signals do not interfere.

The geographical area is divided into "cells", each of which how a base station. Let us look at a single cell for now. We must decide how to divvy up the resources among the mobile users so that they don't interfere.

One idea: Give different time slots to different users. This is TDMA-Time Division Multiple Access.

TDMA




Some slots in the frame give the schedule—known as the downlink map

Uplink and uplink map.

To prevent interference, there is a guard band separating different companies' Band frequency bands


Can we similarly split frequency into slots?



FDMA OFDMA

This is FDMA-Fraquency Division Multiple Access.

4G-LTE uses OFDMA-Orthogonal FDMA. It is a combination of TDMA and FDMA.



-> Demarcate frame start

Tiles

-> Estimate attenuation and phase changes

We can't afford to have guard bands here because that would waste a lot.

OFDMA essentially allows us to transmit without guard bands

(we shall not study it)

It turns out that the attenuation in different tiles is different. Some slots at the end of the frame allow the users to tell the BS which tiles are good for them. This may not stay the same, a few frames later, the DL/UL map may change to benefit everyone.

We also only allocate slots to people who want to upload/download. This is where contention slots enter the picture, during which anyone can transmit. A user says they want to transmit. To do so, they use some sort of CSMA scheme

The DL/UL map could be used as a sort of acknowledgement or alternatively, the BS could just acknowledge during the DL window. If a collision occurs during contention slots, they do a random backoff.

Orthogonal Frequency Division Multiplexing

In OFDM, in each narrow band, it is like we have a completely different center frequency fc'. Distinct narrow bands can even use different modulations.

We can transmit along separate narrow bands at the same time. Essentially multiple modulations on narrow bands.

OFDM is used in WiFi.

LTE uses both OFDM and OFDMA.

Finally, let us look at CDMA-Code Division Multiple Access, which was used CDMA in 3G.

It allows multiple users to use the same time slot.

It uses a spreading code.

Say $U_1 \cdot C_1(t) \times A \cos(2\pi f_c t)$ $D < t < \frac{N}{f_c}$ $\begin{pmatrix} c_1 \text{ and } c_2 \text{ are} \\ \text{Spreading codes} \end{pmatrix}$

Spreading These codes are chosen such that a and a are orthogonal.

$$\int_{\Omega} c_1(t) c_2(t) dt = 0.$$

(How do we generate? If we randomly generate bits (-1,1), then for a sufficiently long string, the codes are orthogonal with high prob.)
All the codes are mutually orthogonal. How do we decode?

$$r(t) = \sum_{j=1}^{n} S_{i}(t) dt$$

Note that

$$S_1(t) \times c_1(t) \cos(2\pi f_c t) = A \cos^2(2\pi f_c t) \qquad (c_1^2(t) = 1)$$

$$= \frac{A}{2} \left(1 + \cos(4\pi f_c t)\right)$$
removed by a low pass filter

$$S_2(t) \times G(t) \cos (2\pi f_c t) = -A G(t) C_2(t) \cos^2(2\pi f_c t)$$

$$= -\frac{A}{2} c_1(t) C_2(t) \left(1 + \cos(4\pi f_c t)\right)$$
removed by a law park hilber


So we are left with something like
$$\frac{A}{2} + \left(\frac{-A}{2} c_i(t) c_2(t)\right)$$
 integrating from 0 to T removes this and just gives $\left(\frac{A}{2}\right)$. T

⇒ Not too hard to get the original desta back if you know the codes.

CDMA and OFDM are robust to multipath.

Lecture 14 Ethernet Switching

Layer 2 switches are in the ethernet and use the MAC address to switch. Layer 3 switches (novters) use the IP address.



A switch selectively forwards intelligently.

A-C would transmit but not A-B.

So if it hears a message for B at port D, it does not forward. How does it get to know the forwarding table? Automatic dynamic updation would be ideal.

Any device has a unique 6-byte MAC address hardcoded in the card. Each port of the switch has a MAC address as well.

Initially, the forwarding table is empty. We now connect it. Say it hears $A \rightarrow B$.

It now knows that A is at port O but since it doesn't know where B is, it decides to forward to port 1

We update the forwarding table based on the sender.


What if we unplug a device from one side and plug it on the other? Each entry in the table has an expiring time. If it has been a while since we have heard from someone, we delete their endry.

The process is similar if we have more than two ports.

- → We send to all ports if the receiver is not in the table.
- We update the sender's port in the table.

(further, there is an expiry time)

What about the following situation?



We use the spanning tree protocol (created by Radia Perlman):

- 1. Elect a root bridge
- 2 Each bridge finds which port is closest to the root and assigns this port as the "root port".

(what is the tiebreaking rule?)

- 3. Among all bridges connected to a LAN, elect one to forward frames on that LAN. ("designated port")
- 4. Any port which is neither a root port nor a designated port is disabled.

→ Each bridge has a bridge ID. The root is the bridge with the lowest bridge ID.

Configurable part MAC address

2 bytes smallest MAC
default: 32768

can be any multiple of 40Ab from 0-61440.

If we want a custom root bridge, we assign a lower value to it.

(the lower the value, the higher the priority)

Each bridge tells its neighbours

Smallest ID distance to Y my ID heard till now

d

if
$$Y < Y_z$$
,

$$X \boxtimes \boxtimes Z$$

$$(Y,d,X)$$

$$(Y_z,d_z,Z)$$
if $Y = Y_z$ and $d+dist(x,z) < d_z$,
$$d_z = d+dist(x,z)$$
.

Repeat until everyone has the same root.

- → In the case of a tie where multiple ports have equal smallest distance to the root, choose that with the smallest ID. (tie for a port)

 L>(neighbour's port)
 - \rightarrow The designated port is that with the shortest distance to the root port. If tie, break based on D. (tie for a LAN)
 - → Disable ports that are neither root port nor designated port.

 The distances can be tweaked manually.