(/)



# **Here When You Need Us**

# Replacing SBD device in a running Pacemaker cluster

This document (7021158) is provided subject to the <u>disclaimer</u> at the end of this document.

#### **Environment**

SUSE Linux Enterprise High Availability Extension 11 Service Pack 3 SUSE Linux Enterprise High Availability Extension 11 Service Pack 4 SUSE Linux Enterprise High Availability Extension 12

### **Situation**

In a cluster SBD (Storage Based Death) is being used for fencing and it is needed to switch from one SAN/Storage vendor/solution to another which in turn results in the need to use a completely new LUN for the SBD.

#### Resolution

Note that this procedure doesn't require cluster downtime.

1. Initialize SBD metadata on the new fencing device:

n4:~ # sbd -d /dev/disk/by-id/scsi-1494554000000000053ce5a88d47f0701d05896628d3ec6b1 create
Initializing device /dev/disk/by-id/scsi-1494554000000000053ce5a88d47f0701d05896628d3ec6b1
Creating version 2.1 header on device 4 (uuid: fbfb8767-bc0b-40c3-8cee-a99136e448d2)
Initializing 255 slots on device 4
Device /dev/disk/by-id/scsi-1494554000000000053ce5a88d47f0701d05896628d3ec6b1 is initialized.

If more than one SBD device is used, repeat the command above for the additional new devices.

2. Source SBD config file:

source /etc/sysconfig/sbd

3. Exit the SBD process:

n4:~ # sbd -d \$SBD\_DEVICE -D \$SBD\_OPTS message LOCAL exit

4. Edit the SBD config file and replace the  ${\tt SBD\_DEVICE}$  variable with your new device:

vim /etc/sysconfig/sbd

5. Source the SBD config file again with updated data:

n4:~ # source /etc/sysconfig/sbd

6. Start SBD process in watch mode:

sbd -d \$SBD\_DEVICE -D \$SBD\_OPTS watch

7. Repeat the procedure on the other node(s).

### Cause

Storage/LUN replacement.

## **Disclaimer**



Document ID:

## 7021158

Creation Date: **02-Aug-2017** 

03-Mar-2020

Modified Date:

SUSE Linux Enterprise High Availability Extension

< Back to Support Search (https://www.suse.com/support/kb/)

For questions or concerns with the SUSE Knowledgebase please contact: <a href="mailto:tidfeedback@suse.com">tidfeedback@suse.com</a> (mailto:tidfeedback@suse.com)

# **SUSE Support Forums**

## **Support Resources**

# **Open an Incident**

Get your questions answered by experienced Sys Ops or interact with other SUSE community experts.

Learn how to get the most from the technical support you receive with your SUSE Subscription, Premium Support, Academic Program, or Partner Program.

Open an incident with SUSE Technical Support, manage your subscriptions, download patches, or manage user access.

SUSE Customer Support Quick Reference Guide (/media/flyer/suse\_customer\_support\_quick\_reference\_guide\_flyer.pdf)

SUSE Technical Support Handbook (/support/handbook/)

Update Advisories (/support/update/)

Join Our Community
Support FAQ

(https://forums.suse.com/)
(/support/faq.html)

Go to Customer Center

(https://scc.suse.com/login)

Report a Software Vulnerability (/support/security/contact/)
Submit Tips, Tricks, and Tools (/communities/conversations/about/how-to-create-and-submit-content/)

Download Free Tools (/communities/blog/free\_tools/)

Careers (https://www.suse.com/company/careers/)

Feedback

About (https://www.suse.com/company/about/)

Communications Preferences (https://www.suse.com/company/subscribe/)

Contact (https://www.suse.com/contact/)

Let's Chat

(https://www.f/dwww.f/dwww.f/dww.febble/EMARichw.ide)mpany/

Sales Number: 00 08 000 501 480

Support Number: 91 80 4002 2990

© 2020 SUSE, All Rights Reserved

Privacy and Cookie Policy (https://www.suse.com/company/policies/privacy/)