


Arad ITC

Arad SMS Restful API

Developer's guide



www.arad-itc.com Arad ITC

Developer's guide



Preferences

Starting up	2
Basic concepts	
Parameters and Methods	
Send Method	3
Sending via URL	
Send method for VAS services	
GetCredit method	8
Error Code List	10

Developer's guide



Starting up

This document is intended for developers who wish to send and receive SMS in their software via Arad's messaging systems. All the required methods are described here.

After signing a contract with our sales department, your account will be activated. Afterwards, you will be provided with a username and a password. These items are private and personal and are used to login to your page at http://yourdomain.com.

Basic concepts

When assigning values to parameters, please note:

- Each SMS consists of at maximum 70 characters for Persian and 160 characters for English. If the SMS is bigger, it will be divided to two or more messages.
- All parameters are case sensitive.
- Mobile phone numbers should be in the format of 989*******.
- The sender's phone number does not require any prefixes.
- Text messages are sent in packets of 200.i.e. in each request you can send 200 messages. The requests will change based on the number of parts per each SMS. If SMS has one part, the number of recipient will be 200. If the message has 2 parts, the recipient's count will be 100 and so on.
- Your IP should be set in your user panel before you could call the methods in the API.

Developer's guide



Parameters and Methods

Send Method

Method's URL: http://your-server-ip:8080/Messages/Send

This method should be called using POST mechanism and parameters are set using JASON or XML.

Below you can find a sample input along with a brief description.

```
XML input:

<Sms>

<CheckId>C63DEE7C-7CD9-453F-8B58-357526D8A824 </CheckId>

<SmsText>hi</SmsText>

<Receivers>98912xxxxxxx,98913xxxxxxxx,... </Receivers>

<SenderId>6500</SenderId>

<IsFlash>true</IsFlash>

<UDH></UDH>

</Sms>

JSON input:

{"SmsText":"hi", Receivers":"98913xxxxxxxx,98912xxxxxxxx,...",

SenderId":"6500",IsUnicode:true,IsFlash:false,UDH:" ""CheckId":"",}
```

Developer's guide



Method			Send		
Input	Input				
Description	Required/	Parameter	Туре		
	Optional	Name	Туре	уре	
Sender number	Optional	SenderId	string		
text Message	Required	SmsText	string		
Mobile phone numbers of the recipients separated by ","	Required	Receivers	string		
ID which is assigned in user's system	Optional	CheckId	Guid		
Header which is defined by user	Optional	udh	string		
Display as flash	Optional	isflash	bool		
Please note username and password are	read from the	header of the r	equest.		
Output					
Description			Type	Parameter Name	
Request result			bool	IsSuccessful	
State code			int	StatusCode	
Registered Id in the SMS system			Guid	BatchId	

If you do not specify a SenderId, your message will be send using a default number which is set on your user account.

Developer's guide



Sending via URL

Send your parameters to the address below using GET mechanism:

http://your-server-ip:8080/Messages/SendViaURL

Method			SendViaURL	
Input				
Description	Required/ Optional	Parameter Name	Туре	
User name	Required	Username	string	
Password	Required	Password	string	
Sender number	Optional	SenderId	string	
text Message	Required	SmsText	string	
Mobile phone numbers of the recipients separated by ","	Required	Receivers	String	
Header which is defined by user	Optional	CheckId	Guid	
Header which is defined by user	Optional	udh	string	
Display as flash	Optional	isflash	bool	
Output				
Description			نوع پارامتر	نام پارامتر
Request result			bool	IsSuccessful
State code			int	StatusCode
Registered Id in the SMS system			Guid	BatchId

Developer's guide



For Example:

Send method for VAS services

Methods URL:

http://your-server-ip:8080/VASMessages/Send

This method should be called using POST mechanism and parameters are set using JASON or XML.

XML input:

```
<VAS>
<CheckId>C63DEE7C-7CD9-453F-8B58-357526D8A824 </CheckId>
<ServiceId>1234</ServiceId>
<SmsText>salam</SmsText>
<Receiver> [9891********] </Receiver>
<GroupId>1100</GroupId>
</VAS>
```

Developer's guide



Method	Send			
Input				
Description	Required/ Optional	Parameter Name	Туре	
Text message	Required	SmsText	string	
ID which is assigned in user's system	Optional	CheckId	Guid	
VAS service ID	Required	ServiceId	string	
Added value group code	required	GroupId	int	
The recipient number (if it is empty, the whole group will be receiving the text message)	optional	Receiver	String	
Please note username and password will be read from the header.				
Output				
Description	Param	Parameter Name		
Request result		IsSuccessful		
State code		StatusCode		
Registered Id in the SMS system	(BatchId		

If the operation is **successful**, the output will be in the format of:

```
<SendSms>
```

- <IsSuccessful>true</IsSuccessful>
- <StatusCode>0</StatusCode>
- <BatchId>4cbac7e3-5b24-489c-96cf-057639e87c01/BatchId>

</SendSms>

Developer's guide



IsSuccessful: states the result of the operation, if the operation is successful, it will be assigned the value 'true' otherwise 'false'.

StatusCode: this parameter will contain the error code in cases which the operation has not successful. A list of error codes can be viewed at the end of this document.

BatchId: If your operation is successful an Id will be returned.

If the operation **failes** the output will be in the format of:

- <ResponseMessage>
- <IsSuccessful>false</IsSuccessful>
- <StatusCode>7</StatusCode>
- <Message>Minimum length for receiver number is 12 characters. </Message>
- <StackTrace> Minimum length for receiver number is 12 characters. </StackTrace>
- </ResponseMessage>

It is worth mentioning that the correct format for receivers' number is 98913xxxxxxx.

GetCredit method

Methods URL: http://your-server-ip:8080/Messages/GetCredit

This method should be called using POST mechanism and parameters are set using JASON or XML.

The input for this method can be seen below:

Method			GetCredit	
Input				
Description	Required/ Optional	Parameter Name	Туре	
User name	Required	Username	string	
Password	Required	Password	string	

Developer's guide



A sample output has been shown below:

Developer's guide



Error Code List

StatusCode					
Error code	Title	Description	Points to notice		
0	None	No error	If the operation is successful, this value is set in status code.		
1	AccountIsInactive	Account is inactive			
2	AccountIsExpired	Account has expired			
3	AccountIsInvalid	Account is invalid			
4	BadRequest	The request is invalid			
5	InternalServerError	Server generated an error			
6	ReceiversIsEmpty	Recipient list is empty	The correct format for the recipient number is: 98913xxxxxxx		
7	ValidationNotValid	Input data is not valid	Parameter validation errors		
8	IPInvalid	IP is invalid			
9	ReceiverCountNotValid	The total number of recipients is invalid	Total number of recipients should be proportional to the number of SMS parts. Maximum 200 SMS		