# REXXGBLV - REXX function - Global variable support

## Contents

Changes in this build (063)	2
Short description	2
Syntax	3
Store and load variables to/from pool(s)	3
Save REXX variables to a pool	3
Clear an entire pool, then save REXX variables in the pool	3
Delete pool variables, then save REXX variables in the pool	3
Delete a pool, then save REXX variables to the pool	3
Load pool variables to REXX, then delete the variables from the pool	3
Load pool variables to REXX, then drop the pool	4
Add data directly to a pool variable	4
Return the value from a pool variable	4
Pool handling	4
List contents of a pool	4
Build a REXX stem containing the names of variables in a pool	4
Delete pool variables	5
Delete a pool	5
Save and load variables to/from external file	5
Export from a pool to file	5
Save REXX variables to a pool, then export the pool variables to file	5
Export REXX variables directly to file	5
Imports file to a pool	5
Import file to a pool, then load the pool variables to REXX	5
Imports REXX variables directly from file	5
REXX variable manipulation	5
Copy REXX variables with prefix	6
Build a stem containing the names of selected REXX variables	6
List contents of REXX variables	6
Index a REXX stem	6

Index a stem (old)	6
Other	6
Show build info	6
Map the internal memory storage structure	6
Parameter description	7
DD statements	7
Variables set at termination	7
Principles of operation	8
Storage	8
Samples	8
Save and retrieve REXX variables	8
Add a pool variable directly	9
Export and import directly to/from file	9
Build a stem of REXX variable names	10
Index a REXX stem	10
Installation	10
Initial verification	11
Performance	11
Comments etc	11

## Changes in this build (064)

- Fix function STEMIX.

## Short description

REXXGBLV addresses the lack of global storage in REXX. While REXX does provide some means of passing data to and retrieve data from subroutines, there is no easy method for storing data for later retrieval.

REXXGBLV provides a variable store external to the currently running REXX program. Variables can be saved and later retrieved by the same or another REXX process. The saved variables can be written to and retrieved from a disk file, so can be used across logons and even be shared amongst users.

The data is stored in a named pool in the home address space above the 16MB border.

Any number of pools can be created, till the virtual storage runs full.

The maximum length of a variable name is 250. There is no maximum data length. Export and import will split the data over more records if needed.

The program is re-entrant, so can be installed in LPALIB. See the 'Performance' section later for other options.

Additionally, REXXGBLV can index variables, copy variables and list variables (useful for debugging).

## **Syntax**

REXXGBLV must run as a function:

n= REXXGBLV('function parameters')

Refer to the section 'Parameter description' later for a detailed description of the parameters.

Store and load variables to/from pool(s)

Save REXX variables to a pool

SAVE VAR(name) [DATA(mask)] [POOL(pool)]

See sample 'Save and retrieve REXX variables'.

Clear an entire pool, then save REXX variables in the pool

CLRSAVE VAR(name) [POOL(pool)] This is a combined DEL \* and SAVE.

\*deprecated, use DROPSAVE instead.

Delete pool variables, then save REXX variables in the pool

CLRVSAVE VAR(name) [DATA(mask)] [POOL(pool)] \*deprecated\*
DELSAVE VAR(name) [DATA(mask)] [POOL(pool)]

This is a combined DEL and SAVE.

This call will delete all pool variables matching 'name', then save REXX variables matching 'name' in the pool. It can be useful if you previously have stored many variables and now wish to start from scratch.

Delete a pool, then save REXX variables to the pool

DROPSAVE VAR(name) [DATA(mask)] POOL(pool)

This is a combined DEL \* and SAVE.

Poolname is required. You cannot delete the internal pools.

Load pool variables to REXX

LOAD VAR(name) [DATA(mask)] [POOL(pool)] [PREFIX(prefix)]

REXX variables can optionally be prefixed, otherwise they are loaded (and replaced) with the pool variable name.

See sample 'Save and retrieve REXX variables'.

Load pool variables to REXX, then delete the variables from the pool

PULL VAR(name) [DATA(mask)] [POOL(pool)] [PREFIX(prefix)]

This is a combination of LOAD and DEL.

REXX variables can optionally be prefixed, otherwise they are loaded (and replaced) with the pool variable name.

#### Load pool variables to REXX, then drop the pool

LOADDROP VAR(name) [DATA(mask)] [POOL(pool)] [PREFIX(prefix)]

REXX variables can optionally be prefixed, otherwise they are loaded (and replaced) with the pool variable name.

## Add data directly to a pool variable

ADD VAR(name) VALUE(data) | VALVAR(varname) [POOL(pool)]

'data' can be a string of max 200 characters without parenthesis or other characters which can invalidate the parm string.

'varname' is the name of a variable containing the data. Use this instead of VALUE(data) if you are unsure of the data or if the data length is more than 200.

If the last chars of the name are '.+' then a new stem variable is created with suffix = name.0 + 1 and name.0 is updated. If name.0 does not exist it is created. This is intended for making a simple log feature.

See sample 'Add a pool variable directly'.

### Return the value from a pool variable

RETURN VAR(name) [POOL(pool)]

Null is returned if the variable is null, if the variable does not exist, or if the pool does not exist.

## Pool handling

### List contents of a pool

LIST VAR(name) [DATA(mask)] [POOL(pool)] [LENGTH] [NW(name-width)] [DW(data-width)] [LISTSTEM(listname)]

See the DW, NW, LENGTH and LISTSTEM operands later.

#### Build a REXX stem containing the names of variables in a pool

INDEX VAR(name) [DATA(mask)] STEM(stem) [POOL(pool)]

Build a stem containing the names of variables in a pool matching 'name'. Note the stem is built in REXX, not in the pool.

## Delete pool variables

DEL VAR(name) [POOL(pool)] The VAR parameter is required.

Delete a pool

DROP POOL(pool)

Releases storage.

Poolname is required. You cannot delete the internal pools.

Save and load variables to/from external file

Export from a pool to file

EXPORT DD(fileref) [POOL(pool)] [VAR(name)] [DATA(mask)]

Save REXX variables to a pool, then export the pool variables to file

SAVEEXP VAR(name) [DATA(mask)] [DD(fileref)] [POOL(pool)] This is a combination of SAVE and EXPORT.

Export REXX variables directly to file

REXPORT VAR(name) [DATA(mask)] [DD(fileref)]

Imports file to a pool

IMPORT DD(fileref) [POOL(pool)] [VAR(name)] File must have been created by the EXPORT/REXPORT function.

Import file to a pool, then load the pool variables to REXX

IMPLOAD DD(fileref) [POOL(pool)] [VAR(name)] [DATA(mask)] This is a combination of IMPORT and LOAD. File must have been created by the EXPORT/REXPORT function.

Imports REXX variables directly from file

RIMPORT [VAR(name)] [DATA(mask)] [DD(fileref)] File must have been created by the EXPORT/REXPORT function.

REXX variable manipulation

#### Copy REXX variables with prefix

```
COPY VAR(name) [DATA(mask)] PREFIX(prefix) 'name' must be generic, like MYVAR. or MYVAR*. 'prefix' can be any valid variable prefix.
```

### Build a stem containing the names of selected REXX variables

```
RINDEX VAR(name) [DATA(mask)] STEM(stem)
Create a listing of the variable names matching 'var' in stem 'stem'.
```

See sample 'Build a stem of REXX variable names'.

## List contents of REXX variables

```
RLIST VAR(name) [DATA(mask)] [LENGTH] [NW(name-width)] [DW(data-width)] LISTSTEM(listname)]
See the DW, NW, LENGTH and LISTSTEM operands later.
Default is to list to terminal, LISTSTEM can be used to save the list.
```

#### Index a RFXX stem

### STEMIX STEM(stem.)

Indexes a stem by taking the basename and putting a running number as the new suffix, plus .0 of course. This is intended to create an index over a stem with non-numeric suffixes.

#### Notes

- the stem is not sorted
- if the stem already has entries with numeric suffixes they may be overwritten. See sample 'Index a REXX stem'.

## Index a stem (old)

```
VARINDEX | VARIX VAR(var) STEM(stem) [POOL(pool)]

See INDEX for parameter syntax and usage notes.
*deprecated, use INDEX instead*
```

#### Other

#### Show build info

```
VERSION
Shows build id and date/time of assembly.
sample:
ver=REXXGBLV('version')
```

## Map the internal memory storage structure

## MAP [XTENDED] XTENDED will map storage entries. For debugging.

## Parameter description

DATA(mask) Data filter when name is generic.

Mask characters are \* for all or none, % for single.

Note that the mask is case sensitive.

i.e. DATA(K\*r\*)

DD(fileref) Optional fileref for export and import. Default is RXGVEXP.

DW(data-width) Width of data - LIST/RLIST functions. Default=85

If specified as 0 then the actual data width is used.

NW(name-width) Width of name - LIST/RLIST functions. Default=35

If specified as 0 then the actual name width is used.

LENGTH Show name- and data length for LIST and RLIST.

POOL(pool) Pool name, max length=16. The name is translated to uppercase, it may

contain any characters, but may not begin with '-', '(' or ')'.

PREFIX(p) Prefix for generated variable names. STEM(name) Stem name – do include the dot.

Maximum length is 250 bytes.

TRACE Writes a lot of diagnostic info.

VALUE(data) Data to store for the VAR(name) variable. Used with the ADD function.

Maximum length is 200 bytes, do not use parenthesis or quotes.

VALVAR(name) Name of variable containing data. Used with the ADD function when the

VALUE parameter would conflict with the syntax parser.

VAR(name) Variable name. Can contain wildcards '\*' for multiple or null characters and '%'

for a single character.

A trailing dot (.) defines a stem base.

Maximum length is 250 bytes.

#### DD statements

RXGVEXP Fileref for the EXPORT, IMPORT, REXPORT and RIMPORT functions.

RECFM=VB, LRECL should be half-track size. Make LRECL=27994 and BLKSIZE=27994

and you should be ok on a 3390 (like) disk.

Alternative DDname can be defined by the DD operand.

## Variables set at termination

Some information is externalized through the variables below. They are all returned, though most will contain zeroes.

REXXGBLV\_EXPORTN Number of entries exported to pool.

REXXGBLV\_IMPORTN Number of entries imported from pool.

REXXGBLV MAXDL Max data length

REXXGBLV\_MAXNDL Max name+data length
REXXGBLV\_MAXNL Max name length
REXXGBLV\_MSG Failure message

REXXGBLV_RLISTN	Number of REXX variables listed.
REXXGBLV_RLOADN	Number of REXX variables loaded.
REXXGBLV_VDELN	Number of pool variables deleted.
REXXGBLV_VLISTN	Number of pool entries listed
REXXGBLV_VLOADN	Number of REXX variables loaded.
REXXGBLV VSAVEN	Number of REXX variables saved.

## Principles of operation

REXXGBLV creates a storage areas and use IEANTCR services to build name/token pairs to save the information for the areas. The pool name can be set in the call to REXXGBLV, thus allowing a virtually unlimited number of variable stores.

## Storage

Pool storage is obtained from storage pool 131, so it survives till the TSO online- or batch session is terminated (step end) unless specifically freed.

All storage, except 64K used for I/O operations, is requested from above the line. Using 64-bit storage or data spaces has been deemed unnecessary so far.

The initial amount of storage for a pool is 1452 bytes. As the pool sees activity this will of course increase, actual amount depending on the number of variables saved and the combined size of the stored variables.

Storage is not necessarily released when a variable is deleted.

Depending on internal settings storage is released or moved to free queues from where it can be quickly reused. This is done as an attempt to avoid excessive getmain/freemain activity.

Not all storage is released when a pool is dropped. Some basic control blocks and a number of free elements are kept as an attempt to avoid excessive getmain/freemain activity. The maximum storage retained for a dropped pool is currently 11K.

There are 3 internal pools so assuming one user pool has been created used and dropped, the storage retained would be 44K.

## Samples

#### Save and retrieve REXX variables

Note that REXX variables are not necessarily shown in alphabetical order.

```
parse value 'Kilroy was here' with p1 p2 p3
cc=REXXGBLV('save pool(p1) var(p*)')
say 'List pool....'
cc=REXXGBLV('list pool(p1)') /* list stored */
say 'List actual...'
cc=REXXGBLV('rlist var(p*)') /* list actual */
p1='The president'
say 'List actual after setting P1'
cc=REXXGBLV('rlist var(p*)') /* list actual */
cc=REXXGBLV('load pool(p1)') /* reload */
say 'List actual after reload'
```

```
cc=REXXGBLV('rlist var(p*)') /* list actual */
  displays
    List pool.....
                                           Kilroy
     P2
                                           was
     Р3
                                           here
     # of records listed: 00000003
    List actual...
    Р1
                                           Kilroy
    P3
                                           here
     Р2
                                           was
    List actual after setting P1
                                          The president
    Р3
                                          here
     Р2
                                           was
    List actual after reload
                                          Kilroy
     Р3
                                          here
     Р2
                                           was
Add a pool variable directly
Callers code:
     cc=RexxGblv('del var(log.)')
     /*or cc=RexxGblv('add var(log.0) value(0)') */
     Call Sub1
     cc=RexxGblv('load var(log.)')
     do n=1 to log.0
       say log.n
     end
Sub1 code:
     cc=RexxGblv('add var(log.+) value('time() 'Program started)')
       .. some code ..
     cc=RexxGblv('add var(log.+) value('time() 'Program ended)')
     Return 0
Will show something like this:
     15:24:33 Program started
     15:24:34 Program ended
Export and import directly to/from file
Fileref
     //RXGVEXP DD RECFM=VB, LRECL=27994, SPACE=(TRK, (5,5)), UNIT=SYSDA,...
Program
            = 'Letter nr 01'
     Alpha
     Charlie = 'Letter nr 03'
     India = 'Letter nr 09'
     Juliet = 'Letter nr 10'
```

```
Romeo = 'Letter nr 18'
    Sierra = 'Letter nr 19'
    Tango = 'Letter nr 20'
            = 'Letter nr 26'
    cc=RexxGblv('rexport var(*ie*)')
    say REXXGBLV EXPORTN+0 'variables exported'
    drop alpha charlie india juliet romeo sierra tango zulu
    say alpha charlie india juliet romeo sierra tango zulu
    cc=RexxGblv('rimport var(*lie*)')
    say REXXGBLV IMPORTN+0 'variables imported'
    say alpha charlie india juliet romeo sierra tango zulu
    cc=RexxGblv('rimport')
    say REXXGBLV IMPORTN+0 'variables imported'
    say alpha charlie india juliet romeo sierra tango zulu
Shows
    3 variables exported
    ALPHA CHARLIE INDIA JULIET ROMEO SIERRA TANGO ZULU
    2 variables imported
    ALPHA Letter nr 03 INDIA Letter nr 10 ROMEO SIERRA TANGO ZULU
    3 variables imported
    ALPHA Letter nr 03 INDIA Letter nr 10 ROMEO Letter nr 19 TANGO ZULU
Build a stem of REXX variable names
    data.0 = 'zero'
    dataf = 'sixth letter in the alphabet'
    foxtrot = 'foxtrot is a dance'
    datad = 'delta'
    faulty = 'Faulty Towers'
    function = 'test filter'
    cc=REXXGBLV('rindex var(f*t*) stem(filter.)')
  creates
    FILTER.0 = '00000003'
    FILTER.1 = 'FAULTY'
    FILTER.2 = 'FUNCTION'
    FILTER.3 = 'FOXTROT'
Index a REXX stem
    CAR.BMW = 'german car make'
    CAR.FORD = 'USA car make'
    CAR.MAZDA = 'japanese car make'
    cc=RexxGblv('stemix stem(car.)')
  creates
    CAR.0 = '00000003'
    CAR.1 = 'BMW'
    CAR.2 = 'MAZDA'
    CAR.3 = 'FORD'
```

#### See member RXGVSAMP for more samples.

## Installation

See member REXXGBLV.

If you do not want to use the stay-in-JPAQ feature, then change the statement

CDEUCTZ2 dsect=N

to a comment.

## Initial verification

See members RXGVIVP (program) and RXGVIVP\$ (JCL). The REXXGBLV installation step is set up to execute the RXGVIVP member as well.

The IVP job can also be used for samples, but the RXGVSAMP member is probably more readable.

## Performance

REXXGBLV is fully reentrant, so can reside in LPALIB or linklist.

LPALIB is recommended. If run from JOBLIB or STEPLIB the program will reload itself, thus remaining in JPAQ - or in other words there will be only one program load for the entire session. See the 'Install' section for how to disable this feature.

## Comments etc

Comments can be sent as email to

Willy(at)harders-jensen(dot)com
Substituting (at) with @ and (dot) with .

Web

The newest version of REXXGBLV, plus much much more, is found at Http://harders-jensen.com/wjtech/programs.html

Have fun

Willy Jensen