
Analytical Electrochemistry: The Basic Concepts



b) Cyclic Voltammetry

ii) Important parameters in CV. Cyclic voltammograms are most often characterized by: a) the *location* of the forward and reverse peaks on the potential axis (E_p and ΔE_p , allowing the calculation of $E^{0'}$); b) the *ratio of currents* observed on the reverse and forward scans ($i_{p,rev}$ / $i_{p,fwd}$); and c) the *dependence of peak currents on the scan rate* (i_p vs. $v^{1/2}$). As before, an uncomplicated, chemically and electrochemically reversible redox system will first be described. Next, deviations from the reversible case will be presented, and the resulting changes in the appearance of the voltammograms obtained will be used as diagnostic criteria for electrode reaction mechanisms of varying types.

<u>Peak Location</u>. In the forward scan of a cyclic voltammogram, the conditions that exist at the surface of the electrode are the same as those we have previously described for linear scan voltammetry. For conditions that include an electrode product that is stable on the time scale of the potential scan, the presence of a return peak in cyclic voltammetry allows us to now determine the formal potential for a redox couple, E^{0} , by averaging the two peak potentials

$$E^{0'} = \frac{E_{p,f} + E_{p,r}}{2}$$

where $E_{p,r}$ and $E_{p,r}$ represent the forward and reverse peak potentials, respectively. The position of the E^{0} is characteristic of a redox species in much the same way that the wavelength of maximum absorbance is characteristic of a species in spectroscopic experiments.

The separation between the two peak potentials, ΔE_p , can be used determine the electrochemical reversibility for a redox couple, with

$$\Delta E_{p} = \frac{0.058}{n}$$

for the reversible case (ΔE_p in volts). This value is independent of the scan rate for fast electron transfer. Increasing values of ΔE_p as a function of increasing scan rate indicates the presence of electrochemical irreversibility. The value of ΔE_p can be used in the calculation of the heterogenous electron transfer rate constant (k_s) for the redox reaction.

In practice, the theoretical value of (58/n) mV for ΔE_p is seldom observed. A known reversible standard compound (like *ferrocene* or *ferricyanide*) is often helpful in the measurement of practical values for ΔE_p under the specific experimental conditions being used in the characterization of an unknown compound. The ΔE_p is also useful in the determination of n-values, as a two-electron transfer (n = 2) will give about 29 mV for the reversible case.


<u>Current ratios</u>. In cyclic voltammetry, we are given the opportunity to directly observe the stability of the electrochemically generated product. If the product is stable on the time scale of the experiment, the peak current observed for the return potential scan $(i_{p,r})$ should be equal to

that seen for the forward potential scan (i_{p,f}) given reversible electron transfer reactions in both directions.

$$\frac{\mathbf{i}_{p,r}}{\mathbf{i}_{p,f}} = 1.0$$

The measurement of peak current is sometimes complicated by the difficulty in locating a proper "baseline" from which to define the magnitude of a peak. If no other peaks are present, the baseline for the forward wave can generally be defined by extrapolating the zero current portion of the scan to a position under the forward peak. The reverse peak current is more often problematic, with baselines affected by the location of the switching potential, among other things. Proper extrapolation of baselines for peak current measurement in the absence of complications is shown at *left* in the *Figure 19*. Many computer-controlled potentiostats have data systems that can accurately and quickly make these types of measurements. For situations where baseline assignment is more complicated, the current ratio can sometimes be conveniently calculated using the empirical method of Nicholson⁷, which requires the measurement of the forward $(i_{p,f})$ and reverse peak currents (designated $(i_{p,r})_0$ to differentiate it from that used previously) from the same baseline, along with a third current, i_{λ} , which is the current measured at the switching potential. This method is illustrated at *right* in *Figure 19*. (DigiElch simulation conditions same as in *Figure 18*.)

Figure 19



The currents measured using the method of Nicholson can then be applied to the calculation of $(i_{p,r} / i_{p,f})$ by

$$\frac{i_{p,r}}{i_{p,f}} = \frac{(i_{p,r})_0}{i_{p,f}} + 0.48 \frac{i_{\lambda}}{i_{p,f}} + 0.086$$

<u>Scan Rate Dependence of Peak Current</u>. We learned in our discussion of LSV that the observed peak current on the forward potential scan is given for the case of reversible electron transfer by the Randles-Sevcik equation (at 25 °C)

$$i_p = (2.69 \text{ x } 10^5) \text{ n}^{3/2} \text{ A } D^{1/2} \text{ C}_i \text{ } v^{1/2}$$

Thus, peak currents will increase linearly as a function of the square root of the scan rate for reversible electron transfer. Plots of i_p vs. $v^{1/2}$ are useful in the characterization of electrochemically reversible redox systems. Deviations from linearity are indicative either of complications in the kinetics of the observed electron transfer, or the result of chemical changes which occur as a result of the electron transfer (homogeneous reactions).

A similar indicator of reversible electron transfer is called the *current function*, whose value is given by $(i_p / v^{1/2})$. The current function should be constant for all scan rates for which the electron transfer is fast enough to maintain the equilibrium ratio between the reduced and the oxidized forms of the redox couple predicted by the Nernst equation.

At this point, it is instructive to note that when describing electrochemical reversibility it is important to consider not only the value of k_s , the heterogeneous electron transfer rate constant, but the scan rate as well. It should be clear that even for large values of k_s there exists some values of scan rate for which Nernstian equilibrium cannot be maintained at the electrode surface. At these scan rates, the observed voltammetry will display characteristics of *quasi-reversible* or *irreversible* behavior, such as the drawing out of voltammetric peaks over wider potential ranges, decreased peak currents, and increased values for ΔE_p .