## **Chapter 10: Virtual Memory**






## **Chapter 10: Virtual Memory**

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples





## **Objectives**

- Define virtual memory and describe its benefits.
- Illustrate how pages are loaded into memory using demand paging.
- Apply the FIFO, optimal, and LRU page-replacement algorithms.
- Describe the working set of a process, and explain how it is related to program locality.
- Describe how Linux, Windows 10, and Solaris manage virtual memory.
- Design a virtual memory manager simulation in the C programming language.





## **Background**

- Code needs to be in memory to execute, but entire program rarely used
  - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
  - Program no longer constrained by limits of physical memory
  - Each program takes less memory while running -> more programs run at the same time
    - Increased CPU utilization and throughput with no increase in response time or turnaround time
  - Less I/O needed to load or swap programs into memory -> each user program runs faster





### Virtual memory

- Virtual memory separation of user logical memory from physical memory
  - Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows address spaces to be shared by several processes
  - Allows for more efficient process creation
  - More programs running concurrently
  - Less I/O needed to load or swap processes






## Virtual memory (Cont.)

- Virtual address space logical view of how process is stored in memory
  - Usually start at address 0, contiguous addresses until end of space
  - Meanwhile, physical memory organized in page frames
  - MMU must map logical to physical
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation



## Virtual Memory That is Larger Than Physical Memory








## Virtual-address Space


- Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up"
  - Maximizes address space use
  - Unused address space between the two is hole
    - No physical memory needed until heap or stack grows to a given new page
- Enables sparse address spaces with holes left for growth, dynamically linked libraries, etc.
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages readwrite into virtual address space
- Pages can be shared during fork(), speeding process creation







## **Shared Library Using Virtual Memory**







## **Demand Paging**


- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
  - Less I/O needed, no unnecessary I/O
  - Less memory needed
  - Faster response
  - More users
- Similar to paging system with swapping (diagram on right)
- Page is needed ⇒ reference to it
  - invalid reference ⇒ abort
  - not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
  - Swapper that deals with pages is a pager





## **Demand Paging**

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
  - Less I/O needed, no unnecessary I/O
  - Less memory needed
  - Faster response
  - More users
- Similar to paging system with swapping (diagram on right)







## **Basic Concepts**


- With swapping, pager guesses which pages will be used before swapping out again
- Instead, pager brings in only those pages into memory
- How to determine that set of pages?
  - Need new MMU functionality to implement demand paging
- If pages needed are already memory resident
  - No difference from non demand-paging
- If page needed and not memory resident
  - Need to detect and load the page into memory from storage
    - Without changing program behavior
    - Without programmer needing to change code





#### **Valid-Invalid Bit**


- With each page table entry a valid–invalid bit is associated
  (v ⇒ in-memory memory resident, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:




 During MMU address translation, if valid—invalid bit in page table entry is i ⇒ page fault



# Page Table When Some Pages Are Not in Main Memory







physical memory




## **Steps in Handling Page Fault**

- 1. If there is a reference to a page, first reference to that page will trap to operating system
  - Page fault
- 2. Operating system looks at another table to decide:
  - Invalid reference ⇒ abort
  - Just not in memory
- 3. Find free frame
- 4. Swap page into frame via scheduled disk operation
- Reset tables to indicate page now in memory Set validation bit = v
- 6. Restart the instruction that caused the page fault





## Steps in Handling a Page Fault (Cont.)





## **Aspects of Demand Paging**


- Extreme case start process with no pages in memory
  - OS sets instruction pointer to first instruction of process, nonmemory-resident -> page fault
  - And for every other process pages on first access
  - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
  - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
  - Pain decreased because of locality of reference
- Hardware support needed for demand paging
  - Page table with valid / invalid bit
  - Secondary memory (swap device with swap space)
  - Instruction restart





#### **Instruction Restart**

- Consider an instruction that could access several different locations
  - Block move



- Auto increment/decrement location
- Restart the whole operation?
  - What if source and destination overlap?





- depind de la un procesor la altul
- (1) PC-ul e copiat intr-un registru intern CPU inaintea executiei fiecarei instructiuni + registrele interne care salveaza incrementul/decrementul
- (2) microcodul CPU stocheaza starea interna pe stiva cand apare page-fault-ul
- (3) microcodul CPU are capacitate de roll-back la starea dinaintea executiei instructiunii (pp. existenta unui checkpoint intern)





#### **Free-Frame List**

- When a page fault occurs, the operating system must bring the desired page from secondary storage into main memory.
- Most operating systems maintain a free-frame list -- a pool of free frames for satisfying such requests.

head 
$$\longrightarrow$$
 7  $\longrightarrow$  97  $\longrightarrow$  15  $\longrightarrow$  126  $\cdots$   $\longrightarrow$  75

- Operating system typically allocate free frames using a technique known as zero-fill-on-demand -- the content of the frames zeroedout before being allocated.
- When a system starts up, all available memory is placed on the freeframe list.





- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
  - a) Wait in a queue for this device until the read request is serviced
  - b) Wait for the device seek and/or latency time
  - c) Begin the transfer of the page to a free frame





## **Stages in Demand Paging (Cont.)**

- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction





## **Performance of Demand Paging**

- Three major activities
  - Service the interrupt careful coding means just several hundred instructions needed
  - Read the page lots of time
  - Restart the process again just a small amount of time
- Page Fault Rate  $0 \le p \le 1$ 
  - if p = 0 no page faults
  - if p = 1, every reference is a fault
- Effective Access Time (EAT)

$$EAT = (1 - p) \times memory access$$

- + p (page fault overhead
- + swap page out
- + swap page in )






## **Demand Paging Example**

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- EAT =  $(1 p) \times 200 + p$  (8 milliseconds) =  $(1 - p \times 200 + p \times 8,000,000$ =  $200 + p \times 7,999,800$
- If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

- If want performance degradation < 10 percent</p>
  - 220 > 200 + 7,999,800 x p
    20 > 7,999,800 x p
  - p < .0000025
  - < one page fault in every 400,000 memory accesses</li>





## **Demand Paging Optimizations**

- Swap space I/O faster than file system I/O even if on the same device
  - Swap allocated in larger chunks, less management needed than file system
- Copy entire process image to swap space at process load time
  - Then page in and out of swap space
  - Used in older BSD Unix
- Demand page in from program binary on disk, but discard rather than paging out when freeing frame
  - Used in Solaris and current BSD
  - Still need to write to swap space
    - Pages not associated with a file (like stack and heap) anonymous memory
    - Pages modified in memory but not yet written back to the file system
- Mobile systems
  - Typically don't support swapping
  - Instead, demand page from file system and reclaim read-only pages (such as code)




## **Copy-on-Write**

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
  - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- In general, free pages are allocated from a pool of zero-fill-on-demand pages
  - Pool should always have free frames for fast demand page execution
    - Don't want to have to free a frame as well as other processing on page fault
  - Why zero-out a page before allocating it?
- vfork() variation on fork() system call has parent suspend and child using copy-on-write address space of parent
  - Designed to have child call exec()
  - Very efficient






## **Before Process 1 Modifies Page C**







## After Process 1 Modifies Page C







## What Happens if There is no Free Frame?

- Used up by process pages
- Also in demand from the kernel, I/O buffers, etc
- How much to allocate to each?
- Page replacement find some page in memory, but not really in use, page it out
  - Algorithm terminate? swap out? replace the page?
  - Performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times






## Page Replacement

- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory





## **Need For Page Replacement**







## **Basic Page Replacement**


- Find the location of the desired page on disk
- 2. Find a free frame:
  - If there is a free frame, use it
  - If there is no free frame, use a page replacement algorithm to select a **victim frame** 
    - Write victim frame to disk if dirty
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap

Note now potentially 2 page transfers for page fault – increasing EAT





## Page Replacement





memory



### Page and Frame Replacement Algorithms


- Frame-allocation algorithm determines
  - How many frames to give each process
  - Which frames to replace
- Page-replacement algorithm
  - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
  - String is just page numbers, not full addresses
  - Repeated access to the same page does not cause a page fault
  - Results depend on number of frames available
- In all our examples, the reference string of referenced page numbers is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1





### **Graph of Page Faults Versus the Number of Frames**








## First-In-First-Out (FIFO) Algorithm

- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- 3 frames (3 pages can be in memory at a time per process)




15 page faults

- Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
  - Adding more frames can cause more page faults!
    - Belady's Anomaly
- How to track ages of pages?
  - Just use a FIFO queue





# FIFO Illustrating Belady's Anomaly







#### **Explicatie anomalia lui Belady**

- FIFO nu e un algoritm de tip stiva (stack algorithm)
  - algoritmi pt care  $M(m,r) \subseteq M(m+1,r)$ unde M(m,r) = multimea frame-urilor dintr-o memorie de dimensiune m (nr. total de frame-uri) dupa un nr. r de referinte la memorie
  - la marirea dimensiunii memoriei cu un frame si rexecutarea procesului, la orice moment in timp, toate paginile care erau in memorie dupa r referinte in cazul memoriei mai mici sunt si acum in memorie plus o pagina aditionala
- ex algoritmi stiva: OPT (algoritmul optimal), LRU (Least Recently Used)
- pt. algoritmii stiva e convenabil sa se reprezinte secventa de referinte la memorie prin distanta fata de varful stivei a locului paginii inainte de referinta
- paginile nereferite inca nu sunt in stiva si au distanta ∞






#### Algoritmi stiva

- secventa de distante fata de varful stivei nu depinde doar de secventa de referinte de memorie, ci si de algoritmul de paginare
- proprietatile statistice ale secventei de distante induc performanta algoritmului de paginare
  - daca densitatea de probabilitate a intrarilor din secventa de distante e "stransa" (i.e., majoritatea distantelor < K) => K frame-uri sunt suficiente pt o rata redusa de page-fault-uri
  - daca, denstitatea de probabilitate e o functie "plata" => singura solutie pt a evita un nr mare de page-fault-uri este sa ai tot atatea frame-uri cate pagini sunt





#### Predictia ratei de page-fault-uri

- secventa de distante poate fi folosita la predictia ratei de page-fault-uri atunci cand variaza nr de pagini n
- algoritm:
  - scaneaza secventa de distante si calculeaza

 $C_i$  = nr de aparitii ale distantei *i* in secventa

 $C_{\infty}$  = nr de aparitii ale distantei  $\infty$  in secventa

calculeaza vectorul F

$$\mathsf{F}_{\mathsf{m}} = \sum_{k=m+1}^{n} C_k + C_{\infty}$$


adica nr de page-fault-uri care apar datorita secventei de distante intr-o memorie cu *m* frame-uri





#### **Optimal Algorithm**


- Replace page that will not be used for longest period of time
  - 9 is optimal for the example
- How do you know this?
  - Can't read the future
- Used for measuring how well your algorithm performs





#### Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Capitalizes on the locality of reference principle
- Associate time of last use with each page



- 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?





# LRU Algorithm (Cont.)


- Counter implementation
  - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
  - When a page needs to be changed, look at the counters to find smallest value
    - Search through table needed
- Stack implementation
  - Keep a stack of page numbers in a double link form:
  - Page referenced:
    - move it to the top
    - requires 6 pointers to be changed
  - But each update more expensive
  - No search for replacement





# LRU Algorithm (Cont.)

- LRU and OPT are cases of stack algorithms that don't have Belady's Anomaly
- Use Of A Stack to Record Most Recent Page References





# **LRU Approximation Algorithms**

- LRU needs special hardware and still slow
- Reference bit
  - With each page associate a bit, initially = 0
  - When page is referenced bit set to 1
  - Replace any with reference bit = 0 (if one exists)
    - We do not know the order, however





#### LRU Approximation Algorithms (cont.)


#### Second-chance algorithm

- Generally FIFO, plus hardware-provided reference bit
- Clock replacement
- If page to be replaced has
  - ▶ Reference bit = 0 -> replace it
  - reference bit = 1 then:
    - set reference bit 0, leave page in memory
    - replace next page, subject to same rules






## **Second-chance Algorithm**







## **Enhanced Second-Chance Algorithm**

- Sometimes also called Not Recently Used (NRU)
- Improve algorithm by using reference bit and modify bit (if available) in concert
- Algorithm starts with R=0 and M=0, periodically the R bits are set to 0
- Take ordered pair (reference, modify):
  - (0, 0) neither recently used not modified best page to replace
  - (0, 1) not recently used but modified not quite as good, must write out before replacement
  - (1, 0) recently used but clean probably will be used again soon
  - (1, 1) recently used and modified probably will be used again soon and need to write out before replacement
- When page replacement called for, use the clock scheme but use the four classes replace page in lowest non-empty class
  - Might need to search circular queue several times





#### **Counting Algorithms**

- Keep a counter of the number of references that have been made to each page (basically add the R bit, on each clock tick)
  - Not common
- Least Frequently Used (LFU) Algorithm (sometimes also called Not Frequently Used, NFU):
  - Replaces page with smallest count
  - doesn't properly reflect locality of reference (long-time ago accessed frames are kept in memory, while recently and frequently accessed frames risk eviction, "NFU doesn't forget anything")
- Most Frequently Used (MFU) Algorithm:
  - Based on the argument that the page with the smallest count was probably just brought in and has yet to be used





## **Aging**

- ajuta NFU sa reflecte mai corect localitatea temporala si sa aproximeze mai bine LRU
- la fiecare tact de ceas, contorul frame-ului e shiftat la dreapta cu 1 bit, iar R se aduna la cel mai semnificativ bit al rezultatului shiftarii
  - ⇒ shiftarea micsoreaza ponderea acceselor departate in timp, iar adunarea lui R tinde sa actualizeze corect gradul de utilizare recenta al paginii
- la page-fault se elimina frame-ul cu contorul cel mai mic
- diferente fata de LRU
  - la eliminarea a doua pagini cu acelasi prefix (eg 001) nu stim care pagina a fost referita ultima intre tactul 1 si 2
  - contorul frame-ului are reprezentare limitata (eg 8 biti) => nu se distinge intre doua pagini cu contor 0, desi una poate a fost referita mai recent decat alta





## **Page-Buffering Algorithms**

- Keep a pool of free frames, always
  - Then frame available when needed, not found at fault time
  - Read page into free frame and select victim to evict and add to free pool
  - When convenient, evict victim
- Possibly, keep list of modified pages
  - When backing store otherwise idle, write pages there and set to non-dirty
- Possibly, keep free frame contents intact and note what is in them
  - If referenced again before reused, no need to load contents again from disk
  - Generally useful to reduce penalty if wrong victim frame selected





# **Applications and Page Replacement**

- All of these algorithms have OS guessing about future page access
- Some applications have better knowledge i.e. databases
- Memory intensive applications can cause double buffering
  - OS keeps copy of page in memory as I/O buffer
  - Application keeps page in memory for its own work
- Operating system can given direct access to the disk, getting out of the way of the applications
  - Raw disk mode
- Bypasses buffering, locking, etc.





#### **Allocation of Frames**

- Each process needs *minimum* number of frames
- Example: IBM 370 6 pages to handle SS MOVE instruction:
  - instruction is 6 bytes, might span 2 pages
  - 2 pages to handle from
  - 2 pages to handle to
- Maximum of course is total frames in the system
- Two major allocation schemes
  - fixed allocation
  - priority allocation
- Many variations





#### **Fixed Allocation**

- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
  - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process
  - Dynamic as degree of multiprogramming, process sizes change
  - Prioritatea poate influenta fractiunea de pagini alocate

$$-s_i = \text{size of process } p_i$$

$$-S = \sum s_i$$

-m = total number of frames

$$= a_i = \text{allocation for } p_i = \frac{s_i}{S} \times m$$

$$m = 64$$


$$s_1 = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \cdot 62 \gg 4$$

$$a_2 = \frac{127}{137} \cdot 62 \gg 57$$





#### Global vs. Local Allocation

- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
  - But then process execution time can vary greatly
    - rata de page-fault-uri a procesului nu depinde doar de comportamentul sau, ci si de cele ale altor procese
  - But greater throughput so more common
- Local replacement each process selects from only its own set of allocated frames
  - More consistent per-process performance
    - rata de page-fault-uri depinde exclusiv de comportamentul procesului
  - But possibly underutilized memory






### **Reclaiming Pages**

- A strategy to implement global page-replacement policy
- All memory requests are satisfied from the free-frame list, rather than waiting for the list to drop to zero before we begin selecting pages for replacement,
- Page replacement is triggered when the list falls below a certain threshold.
- This strategy attempts to ensure there is always sufficient free memory to satisfy new requests.





## **Reclaiming Pages Example**








### **Non-Uniform Memory Access**

- So far, we assumed that all memory accessed equally
- Many systems are NUMA speed of access to memory varies
  - Consider system boards containing CPUs and memory, interconnected over a system bus
- NUMA multiprocessing architecture







# **Non-Uniform Memory Access (Cont.)**

- Optimal performance comes from allocating memory "close to" the CPU on which the process/thread is scheduled
  - And modifying the scheduler to schedule the thread on the same system board when possible
  - Alternativ, utilizatorul poate seta afinitatea de procesor (soft/hard)
  - Consecinta: cache hit ratio marit si timp de acces la memorie redus
  - For threads, solved by Solaris by creating Igroups
    - Structure to track CPU / Memory low latency groups
    - Used my schedule and pager
    - When possible schedule all threads of a process and allocate all memory for that process within the Igroup





#### **Thrashing**


- If a process does not have "enough" pages, the page-fault rate is very high
  - Page fault to get page
  - Replace existing frame
  - But quickly need replaced frame back
  - This leads to:
    - Low CPU utilization
    - Operating system thinking that it needs to increase the degree of multiprogramming
    - Another process added to the system






# **Thrashing (Cont.)**

Thrashing. A process is busy swapping pages in and out







### **Demand Paging and Thrashing**

Why does demand paging work?


#### **Locality model**

- Process migrates from one locality to another
- Definita ca seturi de pagini care se folosesc impreuna la un moment dat
  - Ex: apel de functie => localitatea se refera la accesele la instructiunile functiei, variabilele locale (stiva) si subsetul de date globale (data)
  - La iesirea din functie se paraseste localitatea
- Localities may overlap (ex: datele globale pot apartine mai multor localitati)
- Why does thrashing occur?
  - $\Sigma$  size of locality > total memory size
- Limit effects by using local or priority page replacement





# Locality In A Memory-Reference Pattern







### **Working-Set Model**


- Pp. alocam suficiente frame-uri pt localitatea curenta => nr limitat de page-fault-uri pana cand se schimba localitatea din nou
- Model bazat pe localitatea de referinta
- $\Delta \equiv$  working-set window  $\equiv$  a fixed number of page references Example: 10,000 instructions
  - Idee: se examineaza cele mai recente ∆ referinte la pagini
  - Daca pagina e activa, va fi in working set, altfel este eliminata
- $WSS_i$  (working set of Process  $P_i$ ) = total number of pages referenced in the most recent  $\Delta$  (varies in time)
  - if ∆ too small will not encompass entire locality
  - if  $\Delta$  too large will encompass several localities
  - if  $\Delta = \infty \Rightarrow$  will encompass entire program
- $D = \Sigma WSS_i \equiv \text{total demand frames}$ 
  - Approximation of locality






## Working-Set Model (Cont.)

- if  $D > m \Rightarrow$  Thrashing
- Policy if D > m, then suspend or swap out one of the processes







# **Keeping Track of the Working Set**


- Approximate with interval timer + a reference bit
- Example:  $\Delta = 10,000$ 
  - Timer interrupts after every 5000 time units
  - Keep in memory 2 bits for each page
  - Whenever a timer interrupts, copy and sets the values of all reference bits to 0
  - If one of the bits in memory =  $1 \Rightarrow$  page in working set
- Why is this not completely accurate?
- Improvement = 10 bits and interrupt every 1000 time units
  - Dezavantaj: nr crescut de intreruperi si overheadul aferent





#### **Page-Fault Frequency**


- More direct approach than WSS
- Establish "acceptable" page-fault frequency (PFF) rate and use local replacement policy
  - If actual rate too low, process loses frame
  - If actual rate too high, process gains frame





# **Working Sets and Page Fault Rates**

- Direct relationship between working set of a process and its page-fault rate
- Working set changes over time
- Peaks and valleys over time








#### Alocarea memoriei kernel

- harta memoriei dupa ce loaderul a incarcat imaginea kernelului
- editorul de legaturi a generat simboluri care delimiteaza sectiunile imaginii kernel: \_etext, \_edata, \_end
- codul de initializare a sistemului poate folosi \_end pt a localiza adresa de start a memoriei libere
- memoria disponibila se afla
  - fie ca valoare pasata codului de bootstrap
  - fie proband adresele dincolo de \_end







# Alocare memoriei kernel (cont'd)

- memoria disponibila e impartita in frames, si pusa in free list
  - paginile sunt gestionate de un alocator de pagini (page-level allocator)
- in timpul executiei, cand kernelul are nevoie de memorie pt structurile sale de date interne (PCB-uri, buffere de retea, buffere pt blocuri de disc, samd) cere o pagina (sau mai multe) alocatorului de pagini
- structurile de date ale kernelului pot fi adresate virtual, dar nu sunt swapabile
  - i.e., nu exista page-fault pt paginile kernel
  - page-fault-urile ar fi critice pe durata tratarii intreruperilor sau in timpul sectiunilor critice





#### **Allocating Kernel Memory**

- Treated differently from user memory
- Often allocated from a free-memory pool
  - Kernel requests memory for structures of varying sizes
  - Some kernel memory needs to be contiguous
    - ▶ i.e., for device I/O





#### Alocatorul de memorie kernel

- Kernel Memory Allocator (KMA)
- componenta a sistemului de operare care obtine pagini de la alocatorul de pagini si le foloseste pt satisfacerea cererilor de memorie neswapabila ale kernelului
- trebuie sa fie rapid
  - stiva kernel e mica si echivalentul variabilelor automatice din programe foloseste memoria KMA
  - KMA e apelat din handlere de intrerupere care au constrangeri critice de timp
  - KMA lent => degradarea performantei intregului sistem
- trebuie sa aiba interfata de programare simpla
  - de regula, memoria se aloca intr-o parte a kernelului si se dealoca in alta => free() trebuie proiectat a.i. sa nu stie dimensiunea alocarii





- trebuie sa fie eficient
  - sa aiba factor de utilizare mare(ideal 100%, in practica 50% e acceptabil)
  - factor de utilizare:  $\frac{memoria\ totala\ ceruta}{memoria\ totala\ necesara\ pt\ a\ satisface\ cererile}$
- trebuie sa fie capabil sa obtina pagini noi de la alocatorul de pagini cand free list e goala, respectiv sa dea inapoi pagini atunci cand nu mai sunt folosite
- trebuie sa fie capabil sa compacteze blocurile nealocate adiacente in vederea satisfacerii unor cereri viitoare de dimensiuni mari






#### **Buddy System**

- Allocates memory from fixed-size segment consisting of physicallycontiguous pages
- Memory allocated using power-of-2 allocator
  - Satisfies requests in units sized as power of 2
  - Request rounded up to next highest power of 2
  - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
    - Continue until appropriate sized chunk available
- For example, assume 256KB chunk available, kernel requests 21KB
  - Split into A<sub>I and</sub> A<sub>R</sub> of 128KB each
    - One further divided into B<sub>L</sub> and B<sub>R</sub> of 64KB
      - One further into C<sub>L</sub> and C<sub>R</sub> of 32KB each one used to satisfy request
- Advantage quickly coalesce unused chunks into larger chunk
- Disadvantage fragmentation




## **Buddy System Allocator**

#### physically contiguous pages







### Implementare Buddy System

- managerul de memorie mentine free lists pt toate puterile lui 2 pana la dimensiunea memoriei
- alocarea
  - rotunjita la urmatoarea putere a lui 2
  - daca nu exista in free lists segmentul corespunzator se merge la puteri mai mari; blocurile mari alocate se sparg succesiv in 2 buddies
- dealocarea
  - rotunjita la urmatoarea putere a lui 2
  - daca segmentul dealocat are un buddy adiacent, se compacteaza intr-un segment mai mare; daca segmental rezultat are si el un buddy, se compacteaza in continuare, samd
- regula de detectare buddies:

$$B_1$$
,  $B_2$  buddies  $\Leftrightarrow$  size( $B_1$ ) = size( $B_2$ ) =  $2^k$  &&  $2^{k+1}$  | adr( $B_1 + B_2$ )



### **Exemplu Buddy System**




Figure 5: Buddy system operation.





#### **Buddy System, pros & cons**

- avantaje
  - dealocare rapida (segmentele compactabile se identifica prin adresa si buddies nu se cauta decat in lista segmentelor cu aceeasi dimensiune ca si segmentul eliberat)
- dezavantaje
  - fragmentare interna (datorita rotunjirii de la alocare)
  - fragmentare externa

ex: dupa alocarea celor 1536 bytes, o cerere de 5KB nu poate fi satisfacuta, desi exista 5KB liberi in total






#### **Slab Allocator**

- Alternate strategy
- Slab is one or more physically contiguous pages
- Cache consists of one or more slabs
- Single cache for each unique kernel data structure
  - Each cache filled with objects instantiations of the data structure
- When cache created, filled with objects marked as free
- When structures stored, objects marked as used
- If slab is full of used objects, next object allocated from empty slab
  - If no empty slabs, new slab allocated
- Benefits include no fragmentation, fast memory request satisfaction





#### **Slab Allocation**







#### **Slab Allocator in Linux**

- For example process descriptor is of type struct task\_struct
- Approx 1.7KB of memory
- New task -> allocate new struct from cache
  - Will use existing free struct task\_struct
- Slab can be in three possible states
  - 1. Full all used
  - 2. Empty all free
  - 3. Partial mix of free and used
- Upon request, slab allocator
  - 1. Uses free struct in partial slab
  - 2. If none, takes one from empty slab
  - 3. If no empty slab, create new empty





### **Slab Allocator in Linux (Cont.)**

- Slab started in Solaris, now wide-spread for both kernel mode and user memory in various OSes
- Linux 2.2 had SLAB, now has both SLOB and SLUB allocators
  - SLOB for systems with limited memory
    - Simple List of Blocks maintains 3 list objects for small, medium, large objects
  - SLUB is performance-optimized SLAB removes per-CPU queues, metadata stored in page structure





#### **Other Considerations**

- Prepaging
- Page size
- TLB reach
- Inverted page table
- Program structure
- I/O interlock and page locking





#### **Prepaging**

- To reduce the large number of page faults that occurs at process startup
- Prepage all or some of the pages a process will need, before they are referenced
- But if prepaged pages are unused, I/O and memory was wasted
- Assume s pages are prepaged and  $\alpha$  of the pages is used
  - Is cost of s \* α save pages faults > or < than the cost of prepaging s \* (1- α) unnecessary pages?</li>
  - α near zero ⇒ prepaging loses





#### **Page Size**

- Sometimes OS designers have a choice
  - Especially if running on custom-built CPU
- Page size selection must take into consideration:
  - Fragmentation
  - Page table size
  - Resolution
  - I/O overhead
  - Number of page faults
  - Locality
  - TLB size and effectiveness
- Always power of 2, usually in the range 2<sup>12</sup> (4,096 bytes) to 2<sup>22</sup> (4,194,304 bytes)
- On average, growing over time





#### **TLB Reach**

- TLB Reach The amount of memory accessible from the TLB
- TLB Reach = (TLB Size) X (Page Size)
- Ideally, the working set of each process is stored in the TLB
  - Otherwise there is a high degree of page faults
- Increase the Page Size
  - This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes
  - This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation





#### **Program Structure**

- Program structure
  - int[128,128] data;
  - Each row is stored in one page
  - Program 1


for 
$$(j = 0; j < 128; j++)$$
  
for  $(i = 0; i < 128; i++)$   
data $[i,j] = 0;$ 

 $128 \times 128 = 16,384$  page faults

Program 2


128 page faults





#### I/O interlock

- I/O Interlock Pages must sometimes be locked into memory
- Consider I/O Pages that are used for copying a file from a device must be locked from being selected for eviction by a page replacement algorithm
- Pinning of pages to lock into memory








### **Operating System Examples**

- Windows
- Solaris





#### **Windows**

- Uses demand paging with clustering. Clustering brings in pages surrounding the faulting page
- Processes are assigned working set minimum and working set maximum
- Working set minimum is the minimum number of pages the process is guaranteed to have in memory
- A process may be assigned as many pages up to its working set maximum
- When the amount of free memory in the system falls below a threshold, automatic working set trimming is performed to restore the amount of free memory
- Working set trimming removes pages from processes that have pages in excess of their working set minimum






#### **Solaris**

- Maintains a list of free pages to assign faulting processes
- Lotsfree threshold parameter (amount of free memory) to begin paging
- Desfree threshold parameter to increasing paging
- Minfree threshold parameter to being swapping
- Paging is performed by pageout process
- Pageout scans pages using modified clock algorithm
- Scanrate is the rate at which pages are scanned. This ranges from slowscan to fastscan
- Pageout is called more frequently depending upon the amount of free memory available
- Priority paging gives priority to process code pages






### **Solaris 2 Page Scanner**





# **End of Chapter 10**







### **Performance of Demand Paging**


- Stages in Demand Paging (worse case)
- Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
  - 1. Wait in a queue for this device until the read request is serviced
  - Wait for the device seek and/or latency time
  - 3. Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction




#### **Need For Page Replacement**













#### **Priority Allocation**


- Use a proportional allocation scheme using priorities rather than size
- If process P<sub>i</sub> generates a page fault,
  - select for replacement one of its frames
  - select for replacement a frame from a process with lower priority number





#### **Memory Compression**

- Memory compression -- rather than paging out modified frames to swap space, we compress several frames into a single frame, enabling the system to reduce memory usage without resorting to swapping pages.
- Consider the following free-frame-list consisting of 6 frames



Assume that this number of free frames falls below a certain threshold that triggers page replacement. The replacement algorithm (say, an LRU approximation algorithm) selects four frames -- 15, 3, 35, and 26 to place on the free-frame list. It first places these frames on a modified-frame list. Typically, the modified-frame list would next be written to swap space, making the frames available to the free-frame list. An alternative strategy is to compress a number of frames{\mdash}say, three{\mdash}and store their compressed versions n a single page frame.



### **Memory Compression (Cont.)**

- An alternative to paging is memory compression.
- Rather than paging out modified frames to swap space, we compress several frames into a single frame, enabling the system to reduce memory usage without resorting to swapping pages.

