Getting Started with AWS Hosting a .NET Web App



Getting Started with AWS: Hosting a .NET Web App

Copyright © 2016 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

Hosting a .NET Web App	
Web App Hosting Architecture	1
Tutorial	. 3
Pricing	3
Setting Up	4
Sign Up for AWS	. 4
Create an IAM User	5
Create a Key Pair	. 6
Configure a Virtual Private Cloud (VPC)	. 7
Select or Create a VPC	7
Add Private Subnets to Your VPC	8
Step 1: Create a Bucket	9
Step 2: Create an Application Server	11
Create a Security Group for Your Amazon EC2 Instance	11
Create an IAM Role	12
Launch Your EC2 Instance	13
Step 3: Create a Database Server	
Create a Security Group for Your DB Instance	14
Launch a DB Instance	15
Step 4: Deploy Your App	19
Connect to Your EC2 Instance	_
Configure Your EC2 Instance	20
Configure the Sample App	21
Create a Custom Windows AMI	23
Step 5: Scale and Load-Balance Your Web App	24
Configure Auto Scaling and Load Balancing	24
Test Your Load Balancer	
Step 6: Associate a Domain Name with Your Website	28
Register a Domain Name	
Create a Hosted Zone for Your Domain	
Create Resource Record Sets for Your Domain and Subdomain	29
Set Up a DNS Provider	29
Step 7: Clean Up	
Delete the Amazon Route 53 Hosted Zone	31
Delete the Auto Scaling Group	
Delete the Load Balancer	
Delete Your Custom AMI	
Terminate the DB Instance	
Delete the Amazon S3 Bucket	33
Related Resources	34

Hosting a .NET Web App on Amazon Web Services

A web app is any software that users access through a web browser or specialized web client. Web apps are typically structured into logical tiers. For example, a common structure uses three tiers. The first tier is the web browser, which is responsible for presenting the user interface. The middle tier is an application server, which is responsible for the application's functionality. The third tier is a database server or file system, which is responsible for data storage.

This tutorial walks you through the process of hosting a scalable, robust web app on AWS infrastructure. We'll deploy a sample .NET app, demonstrating best practices. By the end of this tutorial, you should be able to do the following:

- Create a location, called a bucket, and use it to store the static files for your web app, such as HTML, CSS, JavaScript, and images.
- Create a virtual server, called an EC2 instance, and use it as an application server in the cloud.
- Create a database server, called a DB instance.
- Deploy a sample .NET web app to the application server.
- Set up scaling and load balancing to distribute traffic across a minimum number of application servers.
- Associate a domain name with your web app.


Web App Hosting Architecture

Before you create and deploy a web app, you must design your architecture to ensure that it meets your requirements. The following table shows how Amazon EC2, Amazon EBS, Amazon S3, Auto Scaling, Elastic Load Balancing, Amazon CloudWatch, Amazon Route 53, and Amazon CloudFront work together to provide a seamless and cost-effective architecture.

Getting Started with AWS Hosting a .NET Web App Web App Hosting Architecture

Requirement	Solution
Low-cost, reliable application and database servers	Amazon EC2 provides virtual servers in the cloud. You control the protocols, ports, and source IP address ranges that can access your virtual servers.
	 Amazon EBS provides a persistent file system for Amazon EC2 virtual servers.
	Amazon RDS provides a cost-efficient and resizable database server that's easy to administer.
An easy way to provision servers to handle peak capacity without incurring costs when the extra capacity isn't needed	• Elastic Load Balancing supports health checks on hosts, distributes traffic to virtual servers across multiple isolated locations, known as <i>Availability Zones</i> , and dynamically adds or removes virtual servers from the load-balancing rotation.
	Auto Scaling supports groups of servers that can grow or shrink on demand.
	CloudWatch collects metrics data for your virtual servers, which can be used by Auto Scaling.
A reliable and cost-effective way to route users to your web app	Amazon Route 53 maps human-readable domain names to IP addresses.

The following diagram shows an example architecture for a web app that employs the services described in the previous table. The web and application tiers run on EC2 instances in your VPC. Access to the EC2 instances over RDP is controlled by a security group, which acts as a firewall. The Auto Scaling group maintains a fleet of EC2 instances that can scale to handle the current load. This Auto Scaling group spans multiple Availability Zones to protect against the potential failure of a single Availability Zone. The load balancer distributes traffic evenly among the EC2 instances. When the Auto Scaling group launches or terminates instances based on load, the load balancer automatically adjusts accordingly. The database tier consists of DB instances in your VPC, including a master and a local slave, located in multiple Availability Zones for failover protection. Access to the DB instances from the EC2 instances is controlled by a security group. Amazon S3 stores the static content for the app. Amazon Route 53 provides secure and reliable routing of your domain name to your infrastructure hosted on AWS.



Tutorial

This tutorial walks you through the process of hosting a .NET web app on AWS. We'll deploy a sample app that enables users to upload and browse photos. We'll use the AWS Management Console to access AWS.

- 1. Create a Bucket for the Files for Your Web App (p. 9)
- 2. Create an Application Server (p. 11)
- 3. Create a Database Server (p. 14)
- 4. Deploy an App to Your Application Server (p. 19)
- 5. Scale and Load-Balance Your Web App (p. 24)
- 6. Associate a Domain Name with Your Website (p. 28)
- 7. Clean Up (p. 31)

Alternatively, you can use Elastic Beanstalk to create, load balance, scale, and monitor your servers. For more information, see *Getting Started with AWS: Deploying a Web App* or the *AWS Elastic Beanstalk Developer Guide*.

Pricing

You can use the AWS Simple Monthly Calculator to estimate what it would cost to host your web app on AWS.

Note that if you created your AWS account within the last 12 months, you are eligible for the AWS Free Tier.

For more information about AWS pricing, see Pricing.

Setting Up to Host a Web App on AWS

Before you start this tutorial, complete the following tasks if you haven't already.

Tasks

- Sign Up for AWS (p. 4)
- Create an IAM User (p. 5)
- Create a Key Pair (p. 6)
- Configure a Virtual Private Cloud (VPC) (p. 7)

Sign Up for AWS

When you sign up for Amazon Web Services (AWS), your AWS account is automatically signed up for all services in AWS and you can start using them immediately. You are charged only for the services that you use.

If you created your AWS account less than 12 months ago, you can get started with AWS for free. For more information, see AWS Free Tier.

If you have an AWS account already, skip to the next step. If you don't have an AWS account, use the following procedure to create one.

To create an AWS account

- 1. Open http://aws.amazon.com/, and then choose Create an AWS Account.
- 2. Follow the online instructions.

Part of the sign-up procedure involves receiving a phone call and entering a PIN using the phone keypad.

Create an IAM User

Services in AWS require that you provide credentials when you access them, so that the service can determine whether you have permission to access its resources. The console requires your password. You can create access keys for your AWS account to access the command line interface or API. However, we don't recommend that you access AWS using the credentials for your AWS account; we recommend that you use AWS Identity and Access Management (IAM) instead in order to better protect your AWS resources from unauthorized access.

Create an IAM user, and then add the user to an IAM group with administrative permissions or and grant this user administrative permissions. You can then access AWS using a special URL and the credentials for the IAM user.

If you signed up for AWS but have not created an IAM user for yourself, you can create one using the IAM console.

To create a group for administrators

- Sign in to the Identity and Access Management (IAM) console at https://console.aws.amazon.com/ iam/.
- 2. In the navigation pane, choose **Groups**, and then choose **Create New Group**.
- 3. For **Group Name**, type a name for your group, such as Administrators, and then choose **Next Step**.
- 4. In the list of policies, select the check box next to the **AdministratorAccess** policy. You can use the **Filter** menu and the **Search** box to filter the list of policies.
- 5. Choose Next Step, and then choose Create Group.

Your new group is listed under **Group Name**.

To create an IAM user for yourself, add the user to the administrators group, and create a password for the user

- 1. In the navigation pane, choose **Users**, and then choose **Create New Users**.
- 2. In box 1, type a user name.
- 3. Clear the check box next to Generate an access key for each user.
- 4. Choose Create.
- 5. In the list of users, choose the name (not the check box) of the user you just created. You can use the **Search** box to search for the user name.
- 6. Choose the **Groups** tab and then choose **Add User to Groups**.
- 7. Select the check box next to the administrators group. Then choose **Add to Groups**.
- 8. Choose the Security Credentials tab. Under Sign-In Credentials, choose Manage Password.
- 9. Select **Assign a custom password**. Then type a password in the **Password** and **Confirm Password** boxes. When you are finished, choose **Apply**.

To sign in as this new IAM user, sign out of the AWS console, then use the following URL, where *your_aws_account_id* is your AWS account number without the hyphens (for example, if your AWS account number is 1234-5678-9012, your AWS account ID is 123456789012):

```
https://your_aws_account_id.signin.aws.amazon.com/console/
```

Enter the IAM user name and password that you just created. When you're signed in, the navigation bar displays "your_user_name @ your_aws_account_id".

Getting Started with AWS Hosting a .NET Web App Create a Key Pair

If you don't want the URL for your sign-in page to contain your AWS account ID, you can create an account alias. From the IAM dashboard, click **Customize** and enter an alias, such as your company name. To sign in after you create an account alias, use the following URL:

```
https://your_account_alias.signin.aws.amazon.com/console/
```

To verify the sign-in link for IAM users for your account, open the IAM console and check under **IAM** users sign-in link on the dashboard.

Create a Key Pair

AWS uses public-key cryptography to secure the login information for your instance. You specify the name of the key pair when you launch your instance, then provide the private key to obtain the administrator password for your Windows instance so you can log in using RDP.

If you haven't created a key pair already, you can create one using the Amazon EC2 console.

To create a key pair

- 1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
- 2. From the navigation bar, in the region selector, click US West (Oregon).
- 3. In the navigation pane, click **Key Pairs**.
- 4. Click Create Key Pair.
- 5. Enter a name for the new key pair in the **Key pair name** field of the **Create Key Pair** dialog box, and then click **Create**. Choose a name that is easy for you to remember.
- 6. The private key file is automatically downloaded by your browser. The base file name is the name you specified as the name of your key pair, and the file name extension is .pem. Save the private key file in a safe place.

Important

This is the only chance for you to save the private key file. You'll need to provide the name of your key pair when you launch an instance and the corresponding private key each time you connect to the instance.

- 7. Prepare the private key file. This process depends on the operating system of the computer that you're using.
 - If your computer runs Mac OS X or Linux, use the following command to set the permissions of your private key file so that only you can read it.

```
$ chmod 400 my-key-pair.pem
```

- If your computer runs Windows, use the following steps to convert your .pem file to a .ppk file for use with PuTTY.
 - Download and install PuTTY from http://www.chiark.greenend.org.uk/~sgtatham/putty/. Be sure to install the entire suite.
 - b. Start PuTTYgen (for example, from the **Start** menu, click **All Programs > PuTTY > PuTTYgen**).
 - c. Under Type of key to generate, select SSH-2 RSA.
 - d. Click **Load**. By default, PuTTYgen displays only files with the extension .ppk. To locate your .pem file, select the option to display files of all types.
 - e. Select your private key file and then click **Open**. Click **OK** to dismiss the confirmation dialog box.

Getting Started with AWS Hosting a .NET Web App Configure a Virtual Private Cloud (VPC)

- f. Click Save private key. PuTTYgen displays a warning about saving the key without a passphrase. Click Yes.
- g. Specify the same name that you used for the key pair (for example, my-key-pair) and then click **Save**. PuTTY automatically adds the .ppk file extension.

Configure a Virtual Private Cloud (VPC)

Amazon VPC enables you to launch AWS resources into a virtual network that you've defined, called a *virtual private cloud (VPC)*. This tutorial requires the use of a VPC. For more information about Amazon VPC, see the *Amazon VPC User Guide*.

Select or Create a VPC

If your AWS account has a default VPC, you can use it for this tutorial. A default VPC is configured with one public subnet per Availability Zone. Otherwise, you can create a VPC with public subnets for use with this tutorial.

To test whether you have a default VPC

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation bar, verify that **US West (Oregon)** is the selected region.
- 3. In the navigation pane, click Your VPCs.
- 4. One of the following is true:
 - The list is empty, so you do not have a default VPC.
 - The list has a default VPC (a VPC with a CIDR block of 172.31.0.0/16).
 - The list has one or more non-default VPCs (a VPC with a CIDR block that is not 172.31.0.0/16).

If you do not have a default VPC, use the following procedure to create a VPC with two public subnets, as required by Elastic Load Balancing load balancers.

To create a VPC with two public subnets

- 1. On the VPC dashboard, click Start VPC Wizard.
- 2. On the Step 1: Select a VPC Configuration page, ensure that VPC with a Single Public Subnet is selected, and click Select.
- 3. On the Step 2: VPC with a Single Public Subnet page, do the following:
 - a. In **VPC name**, enter a friendly name for your VPC.
 - b. In Availability Zone, select the first Availability Zone from the list.
 - c. In Subnet name, update the name from Public subnet to Public subnet 1.
 - d. Leave the other default configuration settings, and click Create VPC.
 - e. On the confirmation page, click **OK**.
- 4. In the navigation pane, click **Route Tables**. Find the route table where the **Main** column is **Yes**. This is the main route table. Click the **Name** column for the main route table, enter **Main**, and press Enter. Click the **Name** column for the other route table, enter **Custom**, and press Enter.

Getting Started with AWS Hosting a .NET Web App Add Private Subnets to Your VPC

- Add a second public subnet as follows, so that you'll have public subnets for your load balancer in two Availability Zones. (Note that a default VPC already has a public subnet for each Availability Zone by default.)
 - a. In the navigation pane, click Subnets.
 - b. Click Create Subnet
 - c. In Name tag, enter the name Public subnet 2.
 - d. In **VPC**, select your VPC.
 - e. In Availability Zone, select the second Availability Zone from the list.
 - f. In CIDR block, enter 10.0.1.0/24.
 - g. Click Yes, Create.
 - h. Select the subnet named Public subnet 2, and then select the **Route Table** tab. Click **Edit**, select the route table named Custom from **Change to**, and then click **Save**. Note that this step is necessary to make this subnet a public subnet with a route to the Internet.

Add Private Subnets to Your VPC

Use the following procedure to add private subnets (one per Availability Zone) to your default VPC or the VPC that you just created. You will launch your database servers in private subnets for added security. You can also use these private subnets for your application servers, because the load balancer forwards traffic to them from the Internet, or you can use the public subnets for your application servers if you need them to send or receive traffic from the Internet.

To add two private subnets to your VPC

- 1. In the navigation pane, click **Subnets**.
- 2. Click Create Subnet
- 3. In Name tag, enter the name Private subnet 1.
- 4. In VPC, select your VPC.
- 5. In **Availability Zone**, select the first Availability Zone from the list.
- 6. In **CIDR block**, enter an address range for your subnet. For example, for a nondefault VPC, use 10.0.2.0/24. For a default VPC, use 172.31.100.0/24.
- 7. Click Yes, Create.
- 8. Click Create Subnet
- 9. In Name tag, enter the name Private subnet 2.
- 10. In VPC, select your VPC.
- 11. In Availability Zone, select the second Availability Zone from the list.
- 12. In **CIDR block**, enter an address range for your subnet. For example, for a nondefault VPC, use 10.0.3.0/24. For a default VPC, use 172.31.200.0/24.
- 13. Click Yes, Create.

Step 1: Create a Bucket for the Files for Your App

You can use Amazon Simple Storage Service (Amazon S3) to store the photos for our app. Because storage from Amazon S3 can be redundant across multiple data centers, it provides very high levels of durability for a low cost. Each file is stored in Amazon S3 as an *object* in a location called a *bucket*.


Note

You are not charged when you create a bucket; you are charged when you store objects in the bucket and when you transfer objects in and out of the bucket. For more information, see Amazon S3 Pricing.

Create a bucket for the static content for your app. We'll add objects to this bucket when we deploy the app.

To create a bucket for your app

- 1. Open the Amazon S3 console at https://console.aws.amazon.com/s3/.
- Click Create Bucket.
- 3. In the Create a Bucket Select a Bucket Name and Region dialog box, do the following:
 - a. In the **Bucket Name** box, specify a name for the bucket. This name must be unique across all existing bucket names in Amazon S3. One way to help ensure uniqueness is to prefix your bucket names with the name of your organization. In some AWS regions, there might be additional restrictions on bucket names. For more information, see Bucket Restrictions and Limitations in the Amazon Simple Storage Service Developer Guide.
 - b. In the **Region** box, select **Oregon**.
 - c. Click Create.



Step 2: Create an Application Server

You can use Amazon EC2 to create a virtual server to run your web app. These virtual servers are called *EC2 instances*. Typically, you start from a base image called an *Amazon Machine Image (AMI)*.

To create a virtual server using Amazon EC2, complete the following tasks.

Tasks

- Create a Security Group for Your Amazon EC2 Instance (p. 11)
- Create an IAM Role (p. 12)
- Launch Your EC2 Instance (p. 13)

Create a Security Group for Your Amazon EC2 Instance

A security group acts as a firewall that controls the traffic allowed to reach one or more EC2 instances. When you launch an instance, you can assign it one or more security groups. You add rules to each security group that control the traffic allowed to reach the instances to which the security group is assigned. Note that you can modify the rules for a security group at any time; the new rules take effect immediately.

For this tutorial, we'll create a security group and add the following rules:

- Allow inbound HTTP access from anywhere
- Allow inbound RDP traffic from your computer's public IP address so that you can connect to your instance

To create and configure your security group

Decide who requires access to your instance; for example, a single computer or all the computers
on a network that you trust. For this tutorial, you can use the public IP address of your computer,
which you can get using a service. For example, AWS provides the following service: http://
checkip.amazonaws.com. To locate another service that provides your IP address, use the search
phrase "what is my IP address".

Getting Started with AWS Hosting a .NET Web App Create an IAM Role

If you are connecting through an ISP or from behind your firewall without a static IP address, you need to find out the range of IP addresses used by client computers. If you don't know this address range, you can use 0.0.0.0/0 for this tutorial. However, this is unsafe for production environments because it allows everyone to access your instance using **RDP**.

2. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.

Important

Be sure that you are using the Amazon EC2 console. If you're using the Amazon VPC console instead of the Amazon EC2 console, these directions will not match what you see.

- 3. In the navigation bar, verify that **US West (Oregon)** is the selected region.
- 4. In the navigation pane, click Security Groups, and then click Create Security Group.
- 5. Enter webserversg as the name of the security group, and provide a description.
- 6. Select your VPC from the list.
- 7. On the **Inbound** tab, add the rules as follows:
 - a. Click Add Rule, and then select RDP from the Type list. Under Source, select Custom IP and enter the public IP address range that you decided on in step 1 in the text box.
 - b. Click Add Rule, and then select HTTP from the Type list.
- 8. Click Create.

For more information, see Security Groups in the Amazon EC2 User Guide for Microsoft Windows Instances.

Create an IAM Role

All requests to AWS must be cryptographically signed using credentials issued by AWS. Therefore, you need a strategy for managing credentials for software that runs on an EC2 instance. You must distribute, store, and rotate these credentials in a way that keeps them secure but also accessible to the software.

We designed IAM roles so that you can effectively manage AWS credentials for software running on your instances. You create an IAM role and configure it with the permissions that the software requires. For more information about the benefits of this approach, see IAM Roles for Amazon EC2 in the Amazon EC2 User Guide for Microsoft Windows Instances and Roles (Delegation and Federation) in IAM User Guide.

The following procedure creates an IAM role that grants the web app full access to AWS. In production, you can restrict the services and resources that a web app can access.

To create an IAM role with full access to AWS

- 1. Open the Identity and Access Management (IAM) console at https://console.aws.amazon.com/iam/.
- 2. In the navigation pane, click **Roles**, and then click **Create New Role**.
- 3. On the **Set Role Name** page, enter a name for the role, and then click **Next Step**. Remember this name, as you'll need it when you launch your instance.
- 4. On the Select Role Type page, under AWS Service Roles, select Amazon EC2.
- 5. On the Attach Policy page, select the PowerUserAccess policy, and then click Next Step.
- 6. Review the role information and then click Create Role.

Launch Your EC2 Instance

Now that you've created your key pair, security group, and IAM role, you're ready to launch your instance.

Important

If you created your AWS account less than 12 months ago, and have not already exceeded the free tier benefits for Amazon EC2 and Amazon EBS, this instance will not cost you anything, because we help you select options that are within the free tier benefits. Otherwise, you'll incur the standard Amazon EC2 usage fees for this instance from the time that you launch it until you terminate it, even if it remains idle. The total charges are minimal if you complete the tutorial without interruption and terminate your instance when you are finished. For more information, see Amazon EC2 Pricing.

To launch an EC2 instance

- 1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
- 2. In the navigation bar, verify that **US West (Oregon)** is the selected region.
- 3. In the navigation pane, click **Instances**, and then click **Launch Instance**.
- On the Choose an Amazon Machine Image page, click Free tier only and then select a Windows AMI. Note that the directions in this tutorial assume that you're running Windows Server 2012 R2.
- 5. On the **Choose an Instance Type** page, the t2.micro instance is selected by default. To stay within the free tier, keep this instance type. Click **Next: Configure Instance Details**.
- 6. On the Configure Instance Details page, do the following:
 - T2 instances must be launched into a subnet. Select your VPC from Network and select one
 of your public subnets from Subnet.
 - b. Ensure that for **Auto-assign Public IP**, **Enable** is selected in the list. Otherwise, your instance will not get a public IP address or a public DNS name.
 - c. Select your IAM role from **IAM role**. Note that you must select an IAM role when you launch an instance; you can't add a role to a running instance.
 - d. Click Review and Launch. If you are prompted to specify the type of root volume, make your selection and then click Next.
- 7. On the Review Instance Launch page, click Edit security groups. On the Configure Security Group page, click Select an existing security group, select the WebServersG security group that you created, and then click Review and Launch.
- 8. On the Review Instance Launch page, click Launch.
- 9. In the Select an existing key pair or create a new key pair dialog box, select Choose an existing key pair, then select the key pair you created in Setting Up to Host a Web App on AWS (p. 4). Click the acknowledgment check box, and then click Launch Instances.
- 10. In the navigation pane, click **Instances** to see the status of your instance. Initially, the status of your instance is pending. After the status changes to running, your instance is ready for use.

Step 3: Create a Database Server

You can use Amazon Relational Database Service (Amazon RDS) to run your database server. In this step, you launch a *Multi-AZ DB instance*. This means that Amazon RDS automatically provisions and maintains a synchronous standby replica in a different Availability Zone. Updates to your DB instance are synchronously replicated across Availability Zones to the standby in order to keep them in sync and protect your latest database updates against DB instance failure. During certain types of planned maintenance, or in the event of DB instance failure or Availability Zone failure, Amazon RDS automatically fails over to the standby. Because the name record for your DB instance remains the same, your app can resume database operation without the need for manual administrative steps.

Tasks

- Create a Security Group for Your DB Instance (p. 14)
- Launch a DB Instance (p. 15)

Create a Security Group for Your DB Instance

Create a security group that allows your application server to access your database server.

To create a security group for your DB instance

1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.

Important

Be sure that you are using the Amazon EC2 console. If you're using the Amazon VPC console instead of the Amazon EC2 console, these directions will not match what you see.

- 2. In the navigation bar, verify that **US West (Oregon)** is the selected region.
- 3. In the navigation pane, click Security Groups, and then click Create Security Group.
- 4. Enter DBServerSG as the name of the security group, and provide a description.
- 5. Select your VPC from the list.
- 6. On the **Inbound** tab, click **Add Rule**. Select MYSQL/Aurora from the **Type** list. Under **Source**, select **Custom IP**, start typing **WebServerSG** in the text box, and then select the WebServerSG security group.

Getting Started with AWS Hosting a .NET Web App Launch a DB Instance



Click Create.

Launch a DB Instance

Now that you've created your security group, you're ready to launch your instance


Important

You'll incur the standard Amazon RDS usage fees for this instance from the time that you launch it until you terminate it, even if it remains idle. The total charges are minimal if you complete the tutorial without interruption and terminate your DB instance when you are finished. For more information, see Amazon RDS Pricing.

To launch an instance


- 1. Open the Amazon RDS console at https://console.aws.amazon.com/rds/.
- 2. In the navigation bar, verify that US West (Oregon) is the selected region.
- 3. In the navigation pane, click **Subnet Groups**, and then click **Create DB Subnet Group**.
- 4. Complete the Create DB Subnet Group page as follows:
 - a. Enter a name in Name. For example, my-db-subnet-group.
 - b. Enter a description in **Description**.
 - c. Select your VPC from VPC ID.
 - In Availability Zone, select the first Availability Zone from the list. Select the private subnet from Subnet ID, and then click Add.
 - e. In **Availability Zone**, select the second Availability Zone from the list. Select the private subnet from **Subnet ID**, and then click **Add**.
 - f. Click Create.
- 5. In the navigation pane, click **Instances**, and then click **Launch DB Instance**.
- 6. On the Select Engine page, select the MySQL tab, and then click Select.

Getting Started with AWS Hosting a .NET Web App Launch a DB Instance




- 7. On the **Do you plan to use this database for production purposes** page, under **Production**, select **MySQL**, and then click **Next Step**.
- 8. On the **Specify DB Details** page, do the following:
 - a. Keep the default license model and the default DB engine version.
 - b. Select db.t2.micro from DB Instance Class.
 - c. In **Multi-AZ Deployment**, select **Yes**. Although the Multi-AZ deployment is more expensive, it is a best practice.
 - d. Select General Purpose (SSD) from Storage Type and keep the default value for Allocated Storage.
 - e. In **DB Instance Identifier**, enter my-db-instance.
 - f. In Master Username, enter db_user.
 - g. Enter a password in **Master Password** and **Confirm Password**. Record your password in a safe place.
 - h. Click Next Step.

Specify DB Details



- 9. On the **Configure Advanced Settings** page, do the following:
 - Under Network & Security, select your VPC from VPC and select DBServerSG from VPC Security Groups.
 - b. Under Database Options, in Database Name, enter my_database.
 - Click Launch DB Instance.

Configure Advanced Settings



Getting Started with AWS Hosting a .NET Web App Launch a DB Instance

 Launching can take a few minutes to complete. When you see the notice that your instance is being created, click View Your DB Instances.
Initially, the status of your DB instance is creating. After the status changes to available, your DB instance ready for use.

Step 4: Deploy Your App

Deploy the sample .NET app to your EC2 instance by completing the following tasks.

Tasks

- Connect to Your EC2 Instance (p. 19)
- Configure Your EC2 Instance (p. 20)
- Configure the Sample App (p. 21)
- Create a Custom Windows AMI (p. 23)

Connect to Your EC2 Instance

After you launch your EC2 instance, you can connect to it and use it the way that you'd use a computer sitting in front of you.

To connect to a Windows instance, you must retrieve the initial administrator password and then specify this password when you connect to your instance using Remote Desktop.

The name of the administrator account depends on the language of the operating system. For example, for English, it's Administrator, for French it's Administrateur, and for Portuguese it's Administrator. For more information, see Localized Names for Administrator Account in Windows in the Microsoft TechNet Wiki.

To connect to your Windows instance

- 1. Wait a few minutes after the instance is running, and then retrieve the auto-generated administrator password for the instance as follows:
 - a. On the **Instances** page, select your instance, and then click **Connect**.
 - b. In the Connect To Your Instance dialog box, click Get Password.
 - c. Click Browse or Choose File and locate the private key file (.pem) that you saved when you created your key pair, and then click Open.
 - d. Click **Decrypt Password**. The console displays the default administrator password for the instance
 - e. Save the password or copy it to the clipboard. You need this password to connect to the instance.

Getting Started with AWS Hosting a .NET Web App Configure Your EC2 Instance

- Click **Download Remote Desktop File**. Your browser prompts you to either open or save the .rdp file. Either option is fine.
 - If you opened the .rdp file, you'll see the **Remote Desktop Connection** dialog box.
 - If you saved the .rdp file, navigate to your downloads directory, and double-click the .rdp file to display the **Remote Desktop Connection** dialog box.
- 3. You might get a warning that the publisher of the remote connection is unknown. Click **Connect** to connect to your instance.
- 4. When prompted, log in to the instance, using the administrator account for the operating system and the password that you saved or copied.

Tip

Sometimes copying and pasting content can corrupt it. If you encounter a "Password Failed" error when you log in, try typing in the password manually.

- 5. Due to the nature of self-signed certificates, you may get a warning that the security certificate could not be authenticated. Click **Yes** to continue.
- After you've connected to your instance, you can click Close to dismiss the Connect To Your Instance dialog box.
- 7. (Optional) You can change the password for the administrator account for your instance. From the instance, open a Command Prompt window (press Windows logo key+R, type cmd, and then press Enter) and run the following command:

C:\> net user Administrator new_password


Configure Your EC2 Instance

To configure the instance, we'll install required server components and start the web server.


To start the web server

- 1. From the instance, on the taskbar, click Server Manager.
- 2. Click Add roles and features.
- 3. On the Before you begin page, click Next.
- 4. On the **Select installation type** page, select **Role-based or feature-based installation**, and then click **Next**.
- On the Select destination server page, select your instance from the server pool, and then click Next.
- 6. On the Select server roles page, select Web Server (IIS), click Add features, and then click Next.
- 7. On the **Select features** page, expand **.NET Framework 4.5 Features**, select **ASP.NET 4.5**, and then click **Next**.
- 8. On the Web Server Role (IIS) page, click Next.
- On the Select role services page, select Application Development, select the following features, and then click Next.

Getting Started with AWS Hosting a .NET Web App Configure the Sample App



- 10. On the **Confirm installation selections** page, select **Restart the destination server automatically if required**. When prompted for confirmation, click **Yes**. Click **Install**.
- 11. After the installation is complete, click Close.
- 12. Before you continue to the next step, verify that the web server is running. On your computer, in the Amazon EC2 console, select the instance from the **Instances** page. From the **Description** tab, copy the public DNS name. In a web browser, paste the public DNS name of your instance into the address bar and press Enter. This displays a welcome page for IIS, such as the one shown in the following image. If you don't see a welcome page for IIS, verify that your security group allows HTTP traffic.



Configure the Sample App

First, download the sample app to your instance.

Getting Started with AWS Hosting a .NET Web App Configure the Sample App

To download the sample app

- 1. Open Internet Explorer and download BaseImageGallery.zip.
- When prompted about what to do with BaseImageGallery.zip, click Open to open the file in Windows Explorer.
- 3. Select the entire contents of this folder, and then press Ctrl+C to copy the files. Navigate to the local C:\inetpub\wwwroot folder, and then press Ctrl+V to paste the files into this folder.
- 4. Right-click, point to New, and select Folder. Name the folder Upload and press Enter.
- 5. Right-click the upload folder, select **Properties**, and then select the **Security** tab. Click **Edit**, select **IIS_IUSRS**, allow full control, and then click **OK**.

Next, update the app so that the images are published to your Amazon S3 bucket automatically and to connect to your Amazon RDS database. You need the name of your bucket and information about your DB instance. To find information about your DB instance, select it from the **DB Instances** page of the RDS console.

To configure the app to use your bucket and database server

- 1. Open Default.aspx.cs in a text editor (right-click the file, click **Open with**, click **Try an app on this PC**, and then select Notepad).
- 2. Replace my-bucket-name with the name of your bucket in the following code.

```
private const string ImageBucketName = "my-bucket-name";
```

3. Replace my-database-instance with the database endpoint in the following code. (To find this endpoint, select the DB instance in the Amazon RDS console. Do not include the :3306.)

```
private string dbinstance = "my-database-instance";
```

4. Replace *master-user* with the master user in the following code.

```
private string userid ="master-user";
```

5. Replace master-password with the database master password in the following code.

```
private string password = "master-password";
```

6. Replace database-name with the database name in the following code.

```
private string database = "database-name";
```

7. Save the Default.aspx.cs file.

Now you're ready to restart your website and test it.

To test your website

- 1. Click the Start menu, click **Administrative Tools**, and then double-click **Internet Information Services (IIS) Manager**.
- 2. In **IIS Manager**, expand the node for your server, and then expand the **Sites** node.

Getting Started with AWS Hosting a .NET Web App Create a Custom Windows AMI

- 3. Right-click Default Web Site, point to Manage Website, and then click Restart.
- 4. In the home pane, under IIS, double-click **Default Document**, and then select **Default.aspx**. From the **Actions** pane, click **Move Up** until **Default.aspx** is the first entry in the list.
- 5. On your computer, in the Amazon EC2 console, select the instance from the **Instances** page. From the **Description** tab, copy the public DNS name. In a web browser, paste the public DNS name of your instance into the address bar and then press Enter. This displays the user interface for the Photo Gallery app. The control displayed depends on the browser that you use. The app might have a **Browse** button, as shown in the following image, or it might have a **Choose File** button.



6. If you'd like, you can upload an image using the app. Under **Upload an image**, click the button (**Browse** or **Choose File**), and then double-click an image file from your local computer. The name of the image file is displayed. Click **Upload**, which uploads the image file to your Amazon S3 bucket, stores information about the image in your DB instance, and displays a thumbnail image in the user interface. Note that the image must be less than 4 MB or the app fails with the error Maximum request length exceeded.

Create a Custom Windows AMI

Now that you have customized your EC2 instance, you can create your own AMI. With your own AMI, you can quickly launch a new EC2 instance with the same configuration as this one.

To create an AMI from a running Amazon EBS-backed instance

- 1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
- 2. In the navigation pane, click Instances.
- On the Instances page, select your EC2 instance. Click Actions, select Image, and then click Create Image.
- 4. In the **Create Image** dialog box, specify a unique image name and an optional description of the image (up to 255 characters), and then click **Create Image**.

To view the status of your AMI, go to the **AMIs** page. While the AMI is being created, its status is pending. If you go to the **Snapshots** page, you'll see that we created a snapshot that is used to create the root device volume of any instance that you launch using your new AMI.

Now that you have an AMI, you no longer need the instance that you created it from, as we'll use Auto Scaling to launch new instances in the next step. To terminate the instance, select it, click **Actions**, select **Instance State**, and then click **Terminate**.

Step 5: Scale and Load-Balance Your Web App

In this step you'll configure Auto Scaling and Elastic Load Balancing for your application servers. Auto Scaling is designed to launch or terminate EC2 instances automatically based on the needs of your application. Auto Scaling launches or terminates instances based on the scaling policies that you create. For example, you can set up Auto Scaling to launch an additional instance whenever CPU usage exceeds 60 percent for ten minutes, or you could tell Auto Scaling to terminate half of your instances over the weekend when you expect traffic to be low. You can also monitor your instances to ensure that they are performing optimally and that you always have at least one healthy instance running. For more information, see Auto Scaling.

Elastic Load Balancing is designed to help you improve the availability and scalability of your application. It makes it easy for you to distribute and balance incoming application traffic between two or more EC2 instances. You can dynamically add or remove instances from the load balancer as the capacity requirements of your application change.

As soon as your load balancer becomes available, you're billed for each hour or partial hour that you keep the load balancer running. Note that load balancing is a small cost relative to instance hours.

For more information, see Elastic Load Balancing Pricing. For more information about load balancers, see the Elastic Load Balancing User Guide.

Tasks

- Configure Auto Scaling and Load Balancing (p. 24)
- Test Your Load Balancer (p. 26)

Configure Auto Scaling and Load Balancing

Now, you'll set up the basic infrastructure for a web app that is load-balanced and auto-scaled with a minimum number of one instance and maximum number of one instance, so that you are only charged for one instance. We configure Auto Scaling to scale out by one whenever there is a change in capacity. We create a CloudWatch alarm to automatically add instances when CPU utilization is high. When you deploy your own web app, you should follow best practices to ensure that your app can run even if it loses one Availability Zone. You can also create additional policies, such as a scale-in policy.

Getting Started with AWS Hosting a .NET Web App Configure Auto Scaling and Load Balancing

To scale and load-balance your app


- 1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
- 2. In the navigation bar, verify that **US West (Oregon)** is the selected region.
- 3. In the navigation pane, click Load Balancers, and then click Create Load Balancer.
- 4. On the **Define Load Balancer** page, do the following:
 - a. Enter a name for the load balancer. For example, my-1b.
 - b. Select your VPC from the Create LB Inside list.
 - c. If you selected a nondefault VPC, you are prompted to select subnets under **Select Subnets**. Select your two public subnets.
 - d. Click Next: Assign Security Groups.
- 5. On the Assign Security Groups page, click Select an existing security group, and then select your WebServerSG security group. Click Next: Configure Security Settings.
- 6. We are creating a basic load balancer, so you can click **Next: Configure Health Check** to continue to the next step.
- 7. On the **Configure Health Check** page, do the following:
 - a. Leave Ping Protocol and Ping Port at their default values.
 - b. Set **Ping Path** to /. This sends queries to your default page, whether it is named index.html or something else.
 - c. Set Healthy Threshold to 2.
 - d. Click Next: Add EC2 Instances.
- 8. Click **Next: Add Tags** to skip the **Add Instances to Load Balancer** page. We'll use Auto Scaling to add our EC2 instances to the load balancer.
- 9. Click Review and Create to skip adding tags.
- 10. Review your settings and then click Create. After the load balancer is created, click Close.
- 11. In the navigation pane, click **Launch Configurations**. If you are new to Auto Scaling, you see a welcome page; click **Create Auto Scaling group**.
- 12. Click Create a new launch configuration, and then click Next Step.
- 13. On the **Choose AMI** page, select the **My AMIs** tab, and then select the AMI that you created in Create a Custom Windows AMI (p. 23).
- 14. On the Choose Instance Type page, select the General purpose tab, select the t2.micro instance type, and then click Next: Configure details.
- 15. On the **Configure details** page, do the following:
 - a. Under Create Launch Configuration, enter a name for your launch configuration (for example, my-lc) and select your IAM role from IAM role.
 - b. Expand Advanced Details.
 - c. Select Assign a public IP address to every instance.
 - d. Click Skip to review.
- 16. On the **Review** page, click **Edit security groups**. Click **Select an existing security group**, select the **WebServersG** security group that you created, and then click **Review**.
- 17. On the Review page, click Create launch configuration.
- 18. In the Select an existing key pair or create a new key pair dialog box, select Choose an existing key pair, then select the key pair you created in Setting Up to Host a Web App on AWS (p. 4). Click the acknowledgment check box, and then click Create launch configuration.

Getting Started with AWS Hosting a .NET Web App Test Your Load Balancer

- 19. On the Configure Auto Scaling group details page, do the following:
 - a. Enter a name for the Auto Scaling group. For example, my-asg.
 - b. In **Group size**, type 2 in the text box.
 - c. Select your VPC from the **Network** list. Select two subnets for your application servers from the **Subnet** list (either your private subnets or your public subnets, depending on your use case). This is a best practice for building fault-tolerant apps. If one Availability Zone experiences an outage, traffic can still be routed to the other Availability Zone.
 - d. Expand Advanced Details. Select Receive traffic from Elastic Load Balancer(s). Select your load balancer from the text field.
 - e. Click Next: Configure scaling policies.
- 20. On the Configure scaling policies page, do the following:
 - a. Select Use scaling policies to adjust the capacity of this group.
 - b. Under Increase Group Size, click Add new alarm.
 - c. In the Create Alarm dialog box, click create topic. Enter a name for the SNS topic and an email address for the recipient. Leave the default settings for Whenever (Average of CPU Utilization). For Is, select > and specify 60 percent. For For at least, specify 2 consecutive periods of 5 Minutes. Click Create Alarm.
 - d. Under Increase Group Size, in Take the action, type 1 in the middle box. This means that the alarm adds 1 instance to the Auto Scaling group whenever the CPU utilization threshold that you set is reached.
 - e. (Optional) Under Decrease Group Size, you can use similar steps to create a policy for scaling down.
 - f. Click Review.
- 21. On the Review page, click Create Auto Scaling group.
- 22. Click Close.

Test Your Load Balancer


First, verify that your instances are ready. From the **Auto Scaling Groups** page, select your Auto Scaling group, and then select the **Instances** tab.



Initially, your instances are in the Pending state. When their states are InService, they are ready for use.

Getting Started with AWS Hosting a .NET Web App Test Your Load Balancer

Next, verify that your instances are registered with the load balancer. From the **Load Balancers** page, select your load balancer, and then select the **Instances** tab.



If the state of your instances is <code>OutOfService</code>, it's possible that they are still registering. When their states are <code>InService</code>, they are ready for use. After your instances are ready, you can test your load balancer as follows.

To test your load balancer

- 1. From the **Load Balancers** page, select your load balancer.
- 2. On the **Description** tab, locate the DNS name. This name has the following form:

```
my-lb-xxxxxxxxx.us-east-1.elb.amazonaws.com
```

3. In a web browser, paste the DNS name for the load balancer into the address bar and press Enter. You'll see your website displayed.

Step 6: Associate a Domain Name with Your Website Using Amazon Route 53

The easiest way for your customers to access your website is through a memorable domain name. In the procedures on this page, replace "example.com" with your domain name.

Amazon Route 53 is a highly available and scalable Domain Name System (DNS) web service. It is designed as an extremely reliable and cost-effective way to route visitors to websites by translating domain names (such as www.example.com) into the numeric IP addresses (such as 192.0.2.1) that computers use to connect to each other. With Amazon Route 53, you pay only for the domains you configure and the number of queries that the service answers. For more information, see Amazon Route 53.

To associate a domain name with your website, use Amazon Route 53 to complete the following tasks.

Tasks

- Register a Domain Name (p. 28)
- Create a Hosted Zone for Your Domain (p. 29)
- Create Resource Record Sets for Your Domain and Subdomain (p. 29)
- Set Up a DNS Provider (p. 29)

Register a Domain Name

If you haven't already done so, register your domain name. The Internet Corporation for Assigned Names and Numbers (ICANN) manages domain names on the Internet. You register a domain name using a domain name registrar, an ICANN-accredited organization that manages the registry of domain names. The website for your registrar will provide detailed instructions and pricing information for registering your domain name. For more information, see the following resources:

- To use Amazon Route 53 to register a domain name, see Registering Domain Names Using Amazon Route 53 in the *Amazon Route 53 Developer Guide*.
- For a list of accredited registrars, see the Accredited Registrar Directory.

Create a Hosted Zone for Your Domain

A hosted zone is a container for the information about how you want to route traffic on the Internet for a domain (such as example.com) and its subdomains (such as www.example.com).

To create a hosted zone

- 1. Open the Amazon Route 53 console at https://console.aws.amazon.com/route53/.
- If you are new to Amazon Route 53, you see a welcome page; click Get Started Now under DNS Management. Otherwise, click Hosted Zones in the navigation pane.
- 3. Click Create Hosted Zone.
- 4. In **Domain Name**, enter your domain name.
- Click Create.

Create Resource Record Sets for Your Domain and Subdomain

Create an alias resource record set that routes queries for your domain name to your load balancer.

To configure the alias record set for your root domain

- 1. On the **Hosted Zones** page, select the hosted zone that you created for your domain.
- 2. Click Go to Record Sets.
- 3. Click Create Record Set.
- 4. Under Create Record Set, do the following:
 - a. Leave the default name, which is the root domain.
 - b. From Type, select A IPv4 address.
 - c. In **Alias**, click **Yes**. An alias enables Amazon Route 53 to associate your domain name with an AWS resource, such as an Elastic Load Balancing load balancer or an Amazon S3 bucket.
 - d. Click Alias Target. Select the endpoint for your load balancer from the list.
 - e. From Routing Policy, select Simple.
 - f. Leave Evaluate Target Health set to No.
 - g. Click Create.

Set Up a DNS Provider

If you registered a new domain name and have used that name while doing this tutorial, you're ready to set up Amazon Route 53 as your DNS provider.

Alternatively, if you're reusing a domain name that was previously associated with another website, you might need to transfer other DNS records from your current DNS provider to Amazon Route 53 in order to ensure the continued availability of the services hosted under the domain name. To determine which DNS records you must replicate in Amazon Route 53, check the DNS record settings configured for the domain in your current DNS provider. Two records that you should not transfer to Amazon Route 53 are the Start of Authority (SOA) and Name Server (NS) records. These records were set by Amazon Route 53 when the name servers were allocated, and they should not be changed.

Getting Started with AWS Hosting a .NET Web App Set Up a DNS Provider

First, log into the domain name registrar that you used to register your domain name. Use the web interface provided by the registrar to set the name servers for your domain to the name server values displayed under **Name Servers** in the details for the hosted zone. How you do this depends on the registrar that you used.

Wait between two to 48 hours for the Internet DNS resolver network to propagate name server changes. To see if the name server change has gone through, use a command line utility such as dig (for Mac OS X, Unix, or Linux) or nslookup (for Windows). The following example shows how use dig to see which name servers are associated with your domain.

```
dig example.com
```

When the AUTHORITY SECTION of the output shows the AWS name servers that you allocated using Amazon Route 53, the DNS changes have propagated through the DNS resolver network.

```
;; AUTHORITY SECTION:
example.com. 118928 IN NS ns-806.awsdns-36.net.
example.com. 118928 IN NS ns-1456.awsdns-54.org.
example.com. 118928 IN NS ns-1713.awsdns-22.co.uk.
example.com. 118928 IN NS ns-105.awsdns-13.com.
```

After your DNS changes have propagated, you'll be able to view your website using your custom domain name.

If you open your www subdomain (such as www.example.com) in your web browser, it redirects to your domain (such as example.com).

Step 7: Clean Up

After completing this tutorial, be sure to delete the AWS resources that you created so that you no longer accrue charges.

Tasks

- Delete the Amazon Route 53 Hosted Zone (p. 31)
- Delete the Auto Scaling Group (p. 32)
- Delete the Load Balancer (p. 32)
- Delete Your Custom AMI (p. 32)
- Terminate the DB Instance (p. 33)
- Delete the Amazon S3 Bucket (p. 33)

Delete the Amazon Route 53 Hosted Zone

Before you delete the hosted zone, you must delete the record sets that you created. You do not need to delete the NS and SOA records; these are automatically deleted when you delete the hosted zone.

To delete the record sets

- 1. Open the Amazon Route 53 console at https://console.aws.amazon.com/route53/.
- 2. In the list of hosted zones, click the name of your hosted zone.
- In the list of record sets, select the check boxes that correspond to the A records that you created.
 The type of each record set is listed in the Type column.
- 4. Click Delete Record Set.
- 5. When prompted for confirmation, click **Confirm**.

To delete an Amazon Route 53 hosted zone

- 1. Continuing from the previous procedure, click Back to Hosted Zones.
- 2. Select the check box that corresponds to your hosted zone, and then click **Delete Hosted Zone**.
- 3. When prompted for confirmation, click **Confirm**.

Delete the Auto Scaling Group

If you decide that you no longer need an Auto Scaling group, you can delete it. Deleting an Auto Scaling group using the console terminates all EC2 instances in the Auto Scaling group and any CloudWatch alarms for your scaling policies. After you delete the Auto Scaling group, you can delete the launch configuration.

To delete the Auto Scaling group

- 1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
- In the navigation bar, verify that US West (Oregon) is the selected region.
- 3. In the navigation pane, click Auto Scaling Groups.
- 4. Select your Auto Scaling group, click Actions, and then click Delete.
- 5. When prompted for confirmation, click **Yes, Delete**. The values of the **Desired**, **Min**, and **Max** columns change to 0 and the EC2 instances enter the terminating state.

To delete the launch configuration

- 1. In the navigation pane, click Launch Configurations.
- 2. Select your launch configuration, click Actions, and then click Delete launch configuration.
- 3. When prompted for confirmation, click Yes, Delete.

Delete the Load Balancer

If you decide that you no longer need the load balancer that you created in the US West (Oregon) region earlier, you can delete it.

Important

The EC2 instances associated with the load balancer continue to run after you delete the load balancer. You continue to accrue charges for the instances while they are running.

To delete your load balancer

- 1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
- 2. In the navigation bar, verify that US West (Oregon) is the selected region.
- 3. In the navigation pane, click Load Balancers.
- 4. Select the load balancer, click **Actions**, and then click **Delete**.
- 5. When prompted for confirmation, click Yes, Delete.

Delete Your Custom AMI

If you decide that you no longer need an AMI, you can deregister it. After you deregister an AMI, you can't use it to launch new instances. However, it doesn't affect any instances that you already launched from the AMI. It also doesn't affect the snapshot that was created when you created the AMI. You'll continue to accrue charges for the snapshot until you delete it.

To deregister an AMI and delete the associated snapshot

- 1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
- In the navigation bar, verify that US West (Oregon) is the selected region.

Getting Started with AWS Hosting a .NET Web App Terminate the DB Instance

- 3. In the navigation pane, click AMIs.
- Select the AMI, click Actions, and then click Deregister. When prompted for confirmation, click Continue.
- 5. In the navigation pane, click Snapshots.
- Select the snapshot, click Actions, and then click Delete. When prompted for confirmation, click Yes, Delete.

Terminate the DB Instance

If you decide that you no longer need a DB instance, you can terminate it. As soon as the status of the DB instance changes to deleted, you stop accruing charges for the DB instance.

To terminate your DB instance

- Open the Amazon RDS console at https://console.aws.amazon.com/rds/.
- In the navigation bar, verify that US West (Oregon) is the selected region.
- 3. In the navigation pane, click Instances.
- 4. Select the DB instance, click Instance Actions, and then click Delete.
- 5. On the **Delete DB Instance** dialog box, select **No** from the **Create final snapshot?** list, and then click **Yes, Delete**.

If this were a production database, we would recommend that you create a final snapshot so that you could restore the DB instance later if needed.

Delete the Amazon S3 Bucket

Before you delete your Amazon S3 bucket, you should ensure that logging is disabled for the bucket; otherwise, we will continue to write logs to your bucket as you delete it.

To disable logging for a bucket

- 1. Open the Amazon S3 console at https://console.aws.amazon.com/s3/.
- 2. Select your bucket and then click **Properties**.
- 3. In the Properties pane, click Logging.
- 4. Clear the **Enabled** check box.
- 5. Click Save.

To delete a bucket

- 1. Open the Amazon S3 console at https://console.aws.amazon.com/s3/.
- Open the context (right-click) menu for the bucket and click Delete Bucket.
- 3. When prompted for confirmation, type the name of the bucket in the field, and then click **Delete**.

Related Resources

The following table lists some of the AWS resources that you'll find useful as you work with AWS.

Resource	Description
AWS Products & Services	Information about the products and services that AWS offers.
AWS Documentation	Official documentation for each AWS product, including service introductions, service features, and API reference.
AWS Discussion Forums	Community-based forums for discussing technical questions about Amazon Web Services.
Contact Us	A central contact point for account questions such as billing, events, and abuse. For technical questions, use the forums.
AWS Support Center	The hub for creating and managing your AWS Support cases. Also includes links to other helpful resources, such as forums, technical FAQs, service health status, and AWS Trusted Advisor.
AWS Support	The home page for AWS Support, a one-on-one, fast-response support channel to help you build and run applications in the cloud.
AWS Architecture Center	Provides the necessary guidance and best practices to build highly scalable and reliable applications in the AWS cloud. These resources help you understand the AWS platform, its services and features. They also provide architectural guidance for design and implementation of systems that run on the AWS infrastructure.
AWS Security Center	Provides information about security features and resources.
AWS Economics Center	Provides access to information, tools, and resources to compare the costs of Amazon Web Services with IT infrastructure alternatives.
AWS Technical Whitepapers	Provides technical whitepapers that cover topics such as architecture, security, and economics. These whitepapers have been written by the Amazon team, customers, and solution providers.

Getting Started with AWS Hosting a .NET Web App

Resource	Description
AWS Blogs	Provides blog posts that cover new services and updates to existing services.
AWS Podcast	Provides podcasts that cover new services, existing services, and tips.