# **Qt Serial Port**

From Qt Wiki

**En** Ar Bg De El Es Fa Fi Fr Hi Hu It Ja Kn Ko Ms Nl Pl Pt **Ru** Th Tr Uk Zh

NOTE: As of Qt 5.1, Qt Serial Port is now officially part of Qt. You no longer need to build Qt Serial Port manually; simply install Qt 5.1 or later and go to section Usage

## **Brief description**

The QtSerialPort (http://doc.qt.io/qt-5/qtserialport-index.html) module is an add-on module for the Qt5 library, providing a single interface for both hardware and virtual serial ports.

Note: Also added support for Qt4.

Serial interfaces, due to their simplicity and reliability, are still popular in some industries like the development of embedded systems, robotics, etc.

Using the QtSerialPort (http://doc.qt.io/qt-5/qtserialport-index.html) module, developers can significantly reduce the time needed to implement Qt applications that require access to a serial interface.

#### **Functionality**

Currently, the module API contains two classes: QSerialPort (http://doc.qt.io/qt-5/qserialport.html) and QSerialPortInfo (http://doc.qt.io/qt-5/qserialportinfo.html).

#### **QSerialPort**

QSerialPort (http://doc.qt.io/qt-5/qserialport.html) is the base class of the module and provides a set of basic methods and properties to access resources on serial ports.

Supports the following operating systems:

Operating system	Support state	Note
Windows XP/Vista/7/8	YES	Full support
Windows CE	YES	Tested only on 5 and 6 platforms in the emulator
Gnu/Linux	YES	Full support
MacOSX	YES	Full support
Others Unix	YES	All POSIX-compatible

Partial Android Support 1 (http://www.qtcentre.org/threads/57928-Serial-Port-in-Android) 2 (https://forum.qt.io/topic/34000/does-qt-support-serialport-in-android-system/19).

#### **QSerialPortInfo**

QSerialPortInfo (http://doc.qt.io/qt-5/qserialportinfo.html) is a helper class. It provides information on the available serial ports on the system.

Supports the following operating systems:

#### **Contents**

- 1 Brief description
- 2 Functionality
  - 2.1 QSerialPort
  - 2.2 QSerialPortInfo
- 3 Getting the source code
- 4 Building and Installing
  - 4.1 Build and install from command line
  - 4.2 Build and install from QtCreator
- 5 Usage
  - 5.1 Qt4
  - 5.2 Qt5
  - 5.3 Simple example
- 6 Documentation generation
- 7 For those wishing to contribute to the development
- 8 Possible problems
- 9 Bug Tracking

Operating system	Support state	Note
Windows XP/Vista/7/8	YES	Full support (using SetupAPI)
Windows CE	YES	Tested only on 5 and 6 platforms in the emulator
Gnu/Linux	YES	Full support (using libudev, sysfs or simple search in /dev)
MacOSX	YES	Full support
Others Unix	YES	All POSIX-compatible (only simple search in /dev)

# **Getting the source code**

You should clone from the official mirror (http://code.qt.io/) and track changes from there in order to keep the load on Gerrit down.

\$ git clone git://code.qt.io/qt/qtserialport.git
\$ cd qtserialport

This repository contains both versions for Qt4 and Qt5.

To take the version for Qt4 it is necessary to  $do^{[1]}$ :

git checkout qt4-dev

To take the version for Qt5 it is necessary to do:

git checkout qt5.x.y

where x and y is a versions of available branches, which can be displayed after:

git branch -a

### **Building and Installing**

There are two simple methods to compile and install library using the command line or the QtCreator (http://doc.qt.io/qtcreator/).

Before building you need to install Perl.

**Note:** Perl is required only in the case of Qt5, see here (http://wiki.qt.io/Building\_Qt\_5\_from\_Git). When using Qt4 just skip this point.

#### Build and install from command line

*Note:* ensure that the environment variables are set correctly:

- correctly specified the path to the installed Qt4/Qt5
- correctly specified the path to use the compiler
- correctly specified the path to Perl

The following are the recommended steps for building the QtSerialPort (http://doc.qt.io/qt-5/qtserialport-index.html) library for Qt4/Qt5 from the command line.

\$ git clone git://code.qt.io/qt/qtserialport.git
\$ mkdir qtserialport-build
\$ cd qtserialport-build
\$ qmake ../qtserialport/qtserialport.pro

and next if you use GCC compiler then to do:
\$ make \$ make install
Note: on unix-like systems super user privileges might be required:
\$ sudo make install
if you use MinGW compiler then to do:
\$ mingw32-make \$ mingw32-make install
if you use MSVC compiler then to do:
\$ nmake \$ nmake install
Build and install from QtCreator
Using QtCreator (http://doc.qt.io/qtcreator/) is the simplest and fastest way to manually install the library. Before building you need to check that the desired toolchains (kits) of QtCreator (http://doc.qt.io/qtcreator/) have been correctly configured.
Recommended steps to build the QtSerialPort (http://doc.qt.io/qt-5/qtserialport-index.html) library for Qt4/Qt5 from QtCreator (http://doc.qt.io/qtcreator/):
<ul> <li>download and unpack the QtSerialPort (http://doc.qt.io/qt-5/qtserialport-index.html) sources</li> <li>run QtCreator (http://doc.qt.io/qtcreator/) and open the root "qtserialport.pro" project file</li> <li>get to "Projects-&gt;(Your Kit)-&gt;Build-&gt;Build Steps"</li> <li>add a new make "Build Step" and write to the "Make arguments" the install target</li> <li>from the menus, select "Rebuild Project qtserialport"</li> </ul>
As a result, the QtSerialPort (http://doc.qt.io/qt-5/qtserialport-index.html) library will be automatically compiled and installed into the desired Qt instance (according to the selected Kit).
Note: on unix-like systems this method can be failed if Qt was installed into system directories. Super user privileges may be required for "install" target, so need to do:
sudo make install
from the shadow directory.
Usage
To use the library, add serialport to the *.pro file of your project:
Qt4
CONFIG += serialport
Qt5
QT += serialport
Include the header files of QtSerialPort (http://doc.qt.io/qt-5/qtserialport-index.html) where appropriate:

```
#include <QSerialPort>
#include <QSerialPortInfo>
```

#### Simple example

Below is a simple example of *main.cpp*:

```
#include <QDebug>
#include <QSerialPort>
#include <QSerialPortInfo>
QT_USE_NAMESPACE
int main(int argc, char *argv[])
   QCoreApplication a(argc, argv);
    // Example use QSerialPortInfo
    foreach (const QSerialPortInfo &info, QSerialPortInfo::availablePorts()) {
        qDebug() << "Name : " << info.portName();</pre>
        qDebug() << "Description : " << info.description();
qDebug() << "Manufacturer: " << info.manufacturer();</pre>
        // Example use QSerialPort
        QSerialPort serial;
        serial.setPort(info);
        if (serial.open(QIODevice::ReadWrite))
             serial.close();
   return a.exec();
```

#### **Documentation generation**

There is no need to build the documentation, because the documentation is available here (http://doc-snapshot.qt.io/qt5-stable/qtserialport-index.html).

### For those wishing to contribute to the development

All development is done through Gerrit (http://wiki.qt.io/Setting\_up\_Gerrit). Therefore, those wishing to be involved in the development process must have a Qt developer account.

More information about the registration process and development can be found here (http://wiki.qt.io/Code Reviews)

### Possible problems

'm up

## **Bug Tracking**

Use bugreports.qt.io (https://bugreports.qt.io), Project "Qt", Component "Serial Port".

1. ↑ Now QtSerialPort has a separate branch for Qt4 (similar to Qt4 itself), which will be only in one instance.

Retrieved from "http://wiki.qt.io/index.php?title=Qt\_Serial\_Port&oldid=18165"

- This page was last modified on 27 June 2015, at 18:28.
- This page has been accessed 82,862 times.