
# Data Link Layer: Error Detection

Kameswari Chebrolu

# Recap

- Frame-by-Frame next-hop delivery
- Covered framing and overview of error-control
  - Hamming distance of a code determines the error detection and correction capabilities




### **General Approach**

- Add redundant information to a frame
- At Sender:
  - Add k bits of redundant data to a m bit message
  - $k \ll m; k = 32; m = 12,000 \text{ for Ethernet}$
  - k derived from original message through some algorithm
- At Receiver:
  - Reapply same algorithm as sender to detect errors; take corrective action if necessary

# **Parity Bit**

- Even Parity: 1100, send 1100<u>0</u>
- Detects odd number of errors

## Two Dimensional Parity



Parity Bits

Data

- Used by BISYNC protocol for ASCII characters
- "N + 8" bits of redundancy for "N" ASCII characters (character is 7 bits)
- Catches all 1, 2, 3 bit errors and most 4 bit errors

#### **Internet Checksum**

• Used at the network layer (IP header)

#### • Algorithm:

- View data to be transmitted as a sequence of 16-bit integers.
- Add the integers using 16 bit one's complement arithmetic.
- Take the one's complement of the result this result is the checksum
- Receiver performs same calculation on received data and compares result with received checksum

### **Example**

- Sender: IPV4 header in hexadecimal
  - 4500 0073 0000 4000 4011 c0a8 0001 c0a8 00c7 (16-bit words)
  - Sum up the words (can use 32 bits): 0002 479c
  - Add carry to the 16-bit sum: 479e
  - Take the complement:  $b861 \rightarrow checksum$
- Receiver:
  - Sum up the words including checksum (use 32 bits): 2fffd
  - Add carry to the 16 bit sum: ffff (= 0 in 1's complement) → no error was detected

#### **Internet Checksum**

- Not very strong in detecting errors
  - Pair of single-bit errors, one which increments a word, other decrements a word by same amount
- Why is it used still?
  - Very easy to implement in software
  - Majority of errors picked by CRC at link-level (implemented in hardware)

### Cyclic Redundancy Check (CRC)

- Used by many link-level protocols: HDLC, DDCMP, Ethernet, Token-Ring
- Uses powerful math based on finite fields
- Background: Polynomial Arithmetic

### **Polynomial Arithmetic**

- Represent a m bit message with a polynomial of degree "m-1"
- $-11000101 = x^7 + x^6 + x^2 + 1$
- Arithmetic over the field of integers modulo 2 (coefficients are 1 or 0)
- Addition or subtraction are identical: XOR

### **Polynomial Arithmetic**

- Polynomial division (very similar to integer division)
  - X/Y is X = q\*Y + r
  - For integers: 0<=r<Y</pre>
  - For polynomials: degree of r (remainder polynomial) is less than divisor polynomial

### Cyclic Redundancy Check (CRC)

- Message polynomial M(x): m bit message represented with a polynomial of degree "m-1";
  - $-11000101 = x^7 + x^6 + x^2 + 1$
- Sender and receiver agree on a divisor polynomial C(x) of degree k
  - k: Number of redundancy bit
  - E.g.  $C(x) = x^3 + x^2 + 1$  (degree k = 3)
  - Choice of C(x) significantly effects error detection and is derived carefully based on observed error patterns
  - Ethernet uses CRC of 32 bits, HDLC, DDCMP use 16 bits
  - Ethernet:  $x^{32}+x^{26}+x^{23}+x^{22}+x^{16}+x^{12}+x^{11}+x^{10}+x^8+x^7+x^5+x^4+x^2+x+1$

#### Idea

- Sender sends m+k bits => Transmitted message P(x)
- Contrive to make P(x) exactly divisibly by C(x)
- Received message R(x)
  - No errors: R(x) = P(x), exactly divisible by C(x)
  - Errors:  $R(x) \sim P(x)$ ; likely not divisible by C(x)

#### **Generate P(x)**

- You have M(x) and C(x). Generate P(x)
- Multiply M(x) by  $x^k$  to get T(x)
  - Add k zeros at the end of the message
- Divide T(x) by C(x) to get remainder R(x)
- Subtract remainder R(x) from T(x) to get P(x)
- P(x) is now exactly divisible by C(x)

#### **Details**

- $T(x) = x^k M(x) = Q(x) C(x) + R(x)$
- $P(x) = x^k M(x) R(x) = x^k M(x) + R(x)$ = Q(x)C(x)
  - Coefficients of R(x) are the redundant bits
  - Transmitted Bits: Messaged (n) bits, followed by redundant bits (k)

## **Example**

- Message (M): 11001011
- Divisor (C): 1101
- T: 11001011000
- Remainder (R): 101
- Transmitted Bits (P): 11001011101

#### **Error Detection**

- Received polynomial = P(x) + E(x)
  - E(x) captures bit map of the positions of errors
- Cannot detect errors if E(x) is also divisible by C(x)
- Goal: Design C(x) such that for anticipated error patterns, E(x) is not divisible by C(x)

### Example

- Detect all instances of odd number of bit errors
- E(x) contains odd number of terms with coefficient of '1'
  - Implies E(1) = 1
- If C(x) were a factor of E(x), then C(1) would also have to be 1
- If C(1) = 0, we can conclude C(x) does not divide E(x)
- If C(x) has some factor of the form  $x^i+1$ , then C(1)=0

# **Capabilities**

- All single-bit errors, if x<sup>k</sup> and x<sup>0</sup> have non-zero coefficients
  - All double-bit errors, if C(x) has at least three terms
- All odd bit errors, if C(x) contains the factor (x+1)
- Any bursts of length <= k, if C(x) includes a constant term (x<sup>0</sup> term)
- · CRC is easily implementable on shift registers

# Summary

- Important to detect errors in frames
- Many techniques exist (simple to complex)
  - Parity, Checksum, CRC
- Going Forward: Error Recovery