

THOUGHTWAVEAI

Installation Guide

Windows Setup

What this guide covers Account setup, LLM configuration, local speech setup, speech-model download, and final verification.

Before You Begin

ThoughtWaveAI checks the required local speech components during setup. You do not need to prepare them in advance, but an internet connection is required while Python, Whisper, or the speech model is being downloaded.

- Requires 64-bit Python 3.10–3.13. ThoughtWaveAI prompts you if a compatible version is not available.
- Creates a .venv-whisper folder inside ThoughtWaveAI app data for the managed local speech environment.
- Installs Whisper into that environment using pip; administrator rights are not normally required.
- Downloads and load-verifies the required base speech model before setup can finish.

Important “Installed” is not the same as “Ready.” ThoughtWaveAI verifies the Python runtime, PyTorch, Whisper and the speech model before setup can continue.

Step 1 — Terms & Privacy

Review and accept the Terms of Use and Privacy Notice.

Step 2 — Welcome

A short introduction to ThoughtWaveAI and the one-time setup.

Step 3 — Account Setup

Enter a valid email address for your ThoughtWaveAI access.

Step 4 — LLM Configuration


Choose Gemini, OpenAI, or Anthropic, add the API key for the selected provider, select a supported model, and run the compatibility test before continuing.

Tip — Prefer a fast inference model for live use. ThoughtWaveAI is designed to surface intelligence while the conversation is happening. For the best live experience, choose a supported model with low latency and fast inference. Larger or more reasoning-intensive models may provide deeper responses but can introduce additional delay.

You can change the provider or model later in ThoughtWaveAI settings.

Step 5 of 7 — Local Speech Setup

ThoughtWaveAI first checks whether a healthy local speech runtime already exists. If no verified runtime is available, the screen shows Setup required.




If no healthy local speech runtime is detected, choose Install Whisper now.

1. Click Install Whisper now.
2. ThoughtWaveAI checks Python, creates the managed .venv-whisper environment, installs Whisper and verifies PyTorch and Whisper imports.
3. Wait for verification to complete. Continue becomes available once the runtime is installed and verified.

Expected behavior Continue should enable automatically after successful verification. You should not need to go Back and return to this page.

If Python is missing or outdated


If ThoughtWaveAI finds Python 3.8 or another incompatible runtime, setup is blocked until a supported 64-bit Python version is available.



Illustrative setup screenshot: an earlier build may show “Python 3.10 or later.” Current builds require a supported 64-bit Python version from 3.10 through 3.13.

Install a supported Python version


4. Click Download Python to open the Python for Windows downloads page.
5. Choose a Windows installer (64-bit) for a supported Python 3.10–3.13 release.




Example: choose the 64-bit Windows installer for the supported Python release.

Complete the Python installation

Run the installer and allow setup to finish. The screenshots below show the validated Python 3.12.10 (64-bit) installation path.



Installation in progress.




Setup completed successfully.

Return to ThoughtWaveAI Close the Python installer, return to ThoughtWaveAI, and click Check Again.

If ThoughtWaveAI still reports the previous Python version after Check Again, close ThoughtWaveAI completely and reopen it once. This refreshes the process environment before setup continues.

Step 5 complete — Runtime verified

After installation, ThoughtWaveAI performs runtime health checks and shows Installed & verified when the local speech environment is ready.




Local speech runtime installed and verified. Continue is enabled automatically.

What is verified A usable Python runtime, PyTorch import, Whisper import and the managed Whisper command are checked before this step is considered ready.

Step 6 of 7 — Speech Model Download


If the required base model is not already present, the page shows Download required. Click Download speech model.



Download the base model if it is not installed.

Download and verify the speech model

6. Click Download speech model.
7. Wait while the model downloads.
8. ThoughtWaveAI loads the model to verify that it is usable.
9. When Model ready appears and Continue is enabled, click Continue.




The base model has downloaded and passed load verification.

Do not close setup during verification The model is not considered ready until ThoughtWaveAI has successfully load-verified it.

Step 7 of 7 — You're All Set

The final page confirms that your account, AI provider configuration and local speech setup are ready, and gives a short orientation for your first session.



Illustrative final setup screenshot. Account, provider, and model labels may differ in the current build.

Click Finish to complete setup and open ThoughtWaveAI.

Need help? If you run into a setup issue that is not covered here, contact ThoughtWaveAI support and include the error code shown by the app when available.