
Physical Organization of Parallel Platforms


We begin this discussion with an ideal parallel machine called Parallel Random Access Machine, or PRAM.



MEMORY HIERARCHY DESIGN

Architecture of an Ideal Parallel Computer

- A natural extension of the Random Access Machine (RAM) serial architecture is the Parallel Random Access Machine, or PRAM.
- PRAMs consist of p processors and a global memory of unbounded size that is uniformly accessible to all processors.
- Processors share a common clock but may execute different instructions in each cycle.



Architecture of an Ideal Parallel Computer

Depending on how simultaneous memory accesses are handled, PRAMs can be divided into four subclasses.

- Exclusive-read, exclusive-write (EREW) PRAM.
- Concurrent-read, exclusive-write (CREW) PRAM.
- Exclusive-read, concurrent-write (ERCW) PRAM.
- Concurrent-read, concurrent-write (CRCW) PRAM.

Architecture of an Ideal Parallel Computer

What does concurrent write mean, anyway?

- Common: write only if all values are identical.
- Arbitrary: write the data from a randomly selected processor.
- Priority: follow a predetermined priority order.
- Sum: Write the sum of all data items.


Physical Complexity of an Ideal Parallel Computer

- Processors and memories are connected via switches.
- Since these switches must operate in O(1) time at the level of words, for a system of p processors and m words, the switch complexity is O(mp).
- Clearly, for meaningful values of p and m, a true PRAM is not realizable.

Interconnection Networks for Parallel Computers

- Interconnection networks carry data between processors and to memory.
- Interconnects are made of switches and links (wires, fiber).
- Interconnects are classified as static or dynamic.
- Static networks consist of point-to-point communication links among processing nodes and are also referred to as direct networks.
- Dynamic networks are built using switches and communication links. Dynamic networks are also referred to as indirect networks.

Static and Dynamic Interconnection Networks



Classification of interconnection networks: (a) a static network; and (b) a dynamic network.

Interconnection Networks

- Switches map a fixed number of inputs to outputs.
- The total number of ports on a switch is the *degree* of the switch.
- The cost of a switch grows as the square of the degree of the switch, the peripheral hardware linearly as the degree, and the packaging costs linearly as the number of pins.

Interconnection Networks: Network Interfaces

- Processors talk to the network via a network interface.
- The network interface may hang off the I/O bus or the memory bus.
- In a physical sense, this distinguishes a cluster from a tightly coupled multicomputer.
- The relative speeds of the I/O and memory buses impact the performance of the network.


Network Topologies

- A variety of network topologies have been proposed and implemented.
- These topologies tradeoff performance for cost.
- Commercial machines often implement hybrids of multiple topologies for reasons of packaging, cost, and available components.

Network Topologies: Buses

- Some of the simplest and earliest parallel machines used buses.
- All processors access a common bus for exchanging data.
- The distance between any two nodes is O(1) in a bus. The bus also provides a convenient broadcast media.
- However, the bandwidth of the shared bus is a major bottleneck.
- Typical bus based machines are limited to dozens of nodes.
 Sun Enterprise servers and Intel Pentium based shared-bus multiprocessors are examples of such architectures.

Network Topologies: Buses




Bus-based interconnects (a) with no local caches; (b) with local memory/caches.

Since much of the data accessed by processors is local to the processor, a local memory can improve the performance of busbased machines.

Network Topologies: Crossbars

A crossbar network uses an $p \times m$ grid of switches to connect p inputs to m outputs in a non-blocking manner.




A completely non-blocking crossbar network connecting p processors to b memory banks.

Network Topologies: Crossbars

- The cost of a crossbar of p processors grows as $O(p^2)$.
- This is generally difficult to scale for large values of p.
- Examples of machines that employ crossbars include the Sun Ultra HPC 10000 and the Fujitsu VPP500.

- Crossbars have excellent performance scalability but poor cost scalability.
- Buses have excellent cost scalability, but poor performance scalability.
- Multistage interconnects strike a compromise between these extremes.




The schematic of a typical multistage interconnection network.

- One of the most commonly used multistage interconnects is the Omega network.
- This network consists of $\log p$ stages, where p is the number of inputs/outputs.
- At each stage, input i is connected to output j if:

$$j = \begin{cases} 2i, & 0 \le i \le p/2 - 1 \\ 2i + 1 - p, & p/2 \le i \le p - 1 \end{cases}$$

Each stage of the Omega network implements a perfect shuffle as follows:




A perfect shuffle interconnection for eight inputs and outputs.

- The perfect shuffle patterns are connected using 2×2 switches.
- The switches operate in two modes crossover or passthrough.



Two switching configurations of the 2×2 switch: (a) Pass-through; (b) Cross-over

A complete Omega network with the perfect shuffle interconnects and switches can now be illustrated:




A complete omega network connecting eight inputs and eight outputs.

An omega network has $p/2 \times \log p$ switching nodes, and the cost of such a network grows as $\Theta(p \log p)$.

Network Topologies: Multistage Omega Network – Routing

- Let s be the binary representation of the source and d be that of the destination processor
- The data traverses the link to the first switching node. If the most significant bits of *s* and *t* are the same, then the data is routed in pass-through mode by the switch else, it switches to crossover.
- This process is repeated for each of the $\log p$ switching stages.
- Note that this is not a non-blocking switch.

Network Topologies: Multistage Omega Network – Routing




An example of blocking in omega network: one of the messages (010 to 111 or 110 to 100) is blocked at link AB.

Network Topologies: Completely Connected Network

- Each processor is connected to every other processor.
- The number of links in the network scales as $O(p^2)$.
- While the performance scales very well, the hardware complexity is not realizable for large values of p.
- In this sense, these networks are static counterparts of crossbars.

Network Topologies: Completely Connected and Star Connected Networks

Example of an 8-node completely connected network.



(a) A completely-connected network of eight nodes; (b) a Star connected network of nine nodes.

Network Topologies: Star Connected Network

- Every node is connected only to a common node at the center.
- Distance between any pair of nodes is O(1). However, the central node becomes a bottleneck.
- In this sense, star connected networks are static counterparts of buses.

Network Topologies: Linear Arrays, Meshes, and *k-d* **Meshes**


- In a linear array, each node has two neighbors, one to its left and one to its right. If the nodes at either end are connected, we refer to it as a 1-D torus or a ring.
- A generalization to 2 dimensions has nodes with 4 neighbors, to the north, south, east, and west.
- A further generalization to d dimensions has nodes with 2d neighbors.
- A special case of a d-dimensional mesh is a hypercube. Here, $d = \log p$, where p is the total number of nodes.

Network Topologies: Linear Arrays




Linear arrays: (a) with no wraparound links; (b) with wraparound links.

Network Topologies: Two- and Three Dimensional Meshes



Two and three dimensional meshes: (a) 2-D mesh with no wraparound; (b) 2-D mesh with wraparound link (2-D torus); and (c) a 3-D mesh with no wraparound.

Network Topologies: Hypercubes and their Construction




Construction of hypercubes from hypercubes of lower dimension.

Network Topologies: Properties of Hypercubes

- The distance between any two nodes is at most $\log p$.
- Each node has log p neighbors.
- The distance between two nodes is given by the number of bit positions at which the two nodes differ.

Network Topologies: Tree-Based Networks




Complete binary tree networks: (a) a static tree network; and (b) a dynamic tree network.

Network Topologies: Tree Properties

- The distance between any two nodes is no more than $2 \log p$.
- Links higher up the tree potentially carry more traffic than those at the lower levels.
- For this reason, a variant called a fat-tree, fattens the links as we go up the tree.
- Trees can be laid out in 2D with no wire crossings. This is an attractive property of trees.

Network Topologies: Fat Trees



A fat tree network of 16 processing nodes.

Evaluating Static Interconnection Networks

- Diameter: The distance between the farthest two nodes in the network. The diameter of a linear array is p-1, that of a mesh is $2(\sqrt[N]{p}-1)$, that of a tree and hypercube is $\log p$, and that of a completely connected network is O(1).
- Bisection Width: The minimum number of wires you must cut to divide the network into two equal parts. The bisection width of a linear array and tree is 1, that of a mesh is $\sqrt[n]{p}$, that of a hypercube is p/2 and that of a completely connected network is $p^2/4$.
- Cost: The number of links or switches (whichever is asymptotically higher) is a meaningful measure of the cost. However, a number of other factors, such as the ability to lay out the network, the length of wires, etc., also factor in to the cost.

Evaluating Static Interconnection Networks

Network	Diameter	Bisectio n Width	Arc Connectivity	Cost (No. of links)
Completely-connected	1	p ² /4	p – 1	p(p-1)/2
Star	2	1	1	p-1
Complete binary tree	$2\log((p + 1)/2)$	1	1	p-1
Linear array	$\rho - 1$	1/	1	p-1
2-D mesh, no wraparound	$2(\sqrt[N]{p-1})$	$^{V}\boldsymbol{p}_{\!_{l}}$	2	$2(p-^{\gamma}p)$
2-D wra paround mesh	2[^{\(p/2\)}	$2^{\gamma}p^{-}$	4	2 <i>p</i>
Hypercube	log p	p/2	log p	$(p \log p)/2$
Wra paround k -ary d-cube	d[k/2]	2 <i>k</i> ^{d-1}	2 <i>d</i>	dp

Evaluating Dynamic Interconnection Networks


1pt		Bisection	Arc	Cost
Network	Diameter	Width	Connectivity	(No. of links)
Crossbar	1	р	1	p^2
Omega Network	log p	p/2	2	p/2
Dynamic Tree	2 log <i>p</i>	1	2	p - 1

Cache Coherence in Multiprocessor Systems

- Interconnects provide basic mechanisms for data transfer.
- In the case of shared address space machines, additional hardware is required to coordinate access to data that might have multiple copies in the network.
- The underlying technique must provide some guarantees on the semantics.
- This guarantee is generally one of serializability, i.e., there exists some serial order of instruction execution that corresponds to the parallel schedule.

Cache Coherence in Multiprocessor Systems

When the value of a variable is changes, all its copies must either be invalidated or updated.



Cache coherence in multiprocessor systems: (a) Invalidate protocol; (b) Update protocol for shared variables.


Cache Coherence: Update and Invalidate Protocols

- If a processor just reads a value once and does not need it again, an update protocol may generate significant overhead.
- If two processors make interleaved test and updates to a variable, an update protocol is better.
- Both protocols suffer from false sharing overheads (two words that are not shared, however, they lie on the same cache line).
- Most current machines use invalidate protocols.

Maintaining Coherence Using Invalidate Protocols

- Each copy of a data item is associated with a state.
- One example of such a set of states is, shared, invalid, or dirty.
- In shared state, there are multiple valid copies of the data item (and therefore, an invalidate would have to be generated on an update).
- In dirty state, only one copy exists and therefore, no invalidates need to be generated.
- In invalid state, the data copy is invalid, therefore, a read generates a data request (and associated state changes).

Maintaining Coherence Using Invalidate Protocols



State diagram of a simple three-state coherence protocol.

Maintaining Coherence Using Invalidate Protocols


Time	Instruction at Processor 0	Instruction at Processor 1	Variables and their states at Processor 0		
V					x = 5, D
					y = 12, D
	read x		x = 5, S		x = 5, S
		read y		y = 12, S	y = 12, S
	x = x + 1		x = 6, D		x = 5, I
		y = y + 1		y = 13, D	y = 12, I
	read y		_	y = 13, S	- 1
		read x	x = 6, S	x = 6, S	x = 6, S
	x = x + y		x = 19, D	x = 6, I	x = 6, I
		y = x + y	y = 13, I	y = 19, D	y = 13, I
	x = x + 1		x = 20, D		x = 6, I
		y = y + 1		y = 20, D	y = 13, I

Example of parallel program execution with the simple three-state coherence protocol.

Snoopy Cache Systems

How are invalidates sent to the right processors?

In snoopy caches, there is a broadcast media that listens to all invalidates and read requests and performs appropriate coherence operations locally.



A simple snoopy bus based cache coherence system.


Performance of Snoopy Caches

- Once copies of data are tagged dirty, all subsequent operations can be performed locally on the cache without generating external traffic.
- If a data item is read by a number of processors, it transitions to the shared state in the cache and all subsequent read operations become local.
- If processors read and update data at the same time, they generate coherence requests on the bus – which is ultimately bandwidth limited.

Directory Based Systems

- In snoopy caches, each coherence operation is sent to all processors. This is an inherent limitation.
- Why not send coherence requests to only those processors that need to be notified?
- This is done using a directory, which maintains a presence vector for each data item (cache line) along with its global state.

Directory Based Systems



Architecture of typical directory based systems: (a) a centralized directory; and (b) a distributed directory.

Performance of Directory Based Schemes

- The need for a broadcast media is replaced by the directory.
- The additional bits to store the directory may add significant overhead.
- The underlying network must be able to carry all the coherence requests.
- The directory is a point of contention, therefore, distributed directory schemes must be used.