Amazon Virtual Private Cloud VPC Peering Guide



Amazon Virtual Private Cloud: VPC Peering Guide

Copyright © 2017 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.


Table of Contents

What is VPC Peering?	1
VPC Peering Basics	2
VPC Peering Connection Lifecycle	2
Multiple VPC Peering Connections	
Pricing for a VPC Peering Connection	4
VPC Peering Limitations	4
Working with VPC Peering Connections	
Create and Accept	5
Creating a VPC Peering Connection with Another VPC in Your Account	
Creating a VPC Peering Connection with a VPC in Another AWS Account	6
Accepting a VPC Peering Connection	7
Viewing Your VPC Peering Connections	7
Reject	8
Update Route Tables	
Reference Peer VPC Security Groups	10
Identifying Your Referenced Security Groups	11
Working with Stale Security Group Rules	. 11
Modify Peering Options	
Enabling DNS Resolution Support for a VPC Peering Connection	13
Delete	13
Controlling Access to VPC Peering Connections	14
VPC Peering Scenarios	15
Peering Two or More VPCs to Provide Full Access to Resources	15
Peering to One VPC to Access Centralized Resources	16
Peering with ClassicLink	
VPC Peering Configurations	17
Configurations with Routes to an Entire CIDR Block	
Two VPCs Peered Together	17
One VPC Peered with Two VPCs	19
Three VPCs Peered Together	
One VPC Peered with Multiple VPCs	23
Multiple VPCs Peered Together	
Configurations with Specific Routes	35
Two VPCs Peered to Two Subnets in One VPC	36
One VPC Peered to Specific Subnets in Two VPCs	
Instances in One VPC Peered to Instances in Two VPCs	43
One VPC Peered with Two VPCs Using Longest Prefix Match	45
Multiple VPC Configurations	46
Configurations with ClassicLink	48
Enabling Communication Between a ClassicLink Instance and a Peer VPC	
Invalid VPC Peering Connection Configurations	
Overlapping CIDR blocks	
Transitive Peering	
Edge to Edge Routing Through a Gateway or Private Connection	56

What is VPC Peering?

Amazon Virtual Private Cloud (Amazon VPC) enables you to launch Amazon Web Services (AWS) resources into a virtual network that you've defined.

A VPC peering connection is a networking connection between two VPCs that enables you to route traffic between them using private IPv4 addresses or IPv6 addresses. Instances in either VPC can communicate with each other as if they are within the same network. You can create a VPC peering connection between your own VPCs, or with a VPC in another AWS account. In both cases, the VPCs must be in the same region.



AWS uses the existing infrastructure of a VPC to create a VPC peering connection; it is neither a gateway nor a VPN connection, and does not rely on a separate piece of physical hardware. There is no single point of failure for communication or a bandwidth bottleneck.

A VPC peering connection can help you to facilitate the transfer of data; for example, if you have more than one AWS account, you can peer the VPCs across those accounts to create a file sharing network. You can also use a VPC peering connection to allow other VPCs to access resources you have in one of your VPCs.

For more information, see the following topics:

• VPC Peering Basics (p. 2)

- Working with VPC Peering Connections (p. 5)
- VPC Peering Scenarios (p. 15)
- Configurations with Routes to an Entire CIDR Block (p. 17)
- Configurations with Specific Routes (p. 35)
- Invalid VPC Peering Connection Configurations (p. 55)

VPC Peering Basics


To establish a VPC peering connection, you do the following:

- 1. The owner of the *requester VPC* sends a request to the owner of the *accepter VPC* to create the VPC peering connection. The accepter VPC can be owned by you, or another AWS account, and cannot have a CIDR block that overlaps with the requester VPC's CIDR block.
- 2. The owner of the accepter VPC accepts the VPC peering connection request to activate the VPC peering connection.
- 3. To enable the flow of traffic between the VPCs using private IP addresses, the owner of each VPC in the VPC peering connection must add a route to one or more of their VPC's route tables that points to the IP address range of the other VPC (the peer VPC).
- 4. If required, update the security group rules that are associated with your instance to ensure that traffic to and from the peer VPC is not restricted. You can reference a security group from the peer VPC as a source or destination for ingress or egress rules in your security group rules.
- 5. If required, modify your VPC connection to enable DNS hostname resolution. By default, if instances on either side of a VPC peering connection address each other using a public DNS hostname, the hostname resolves to the instance's public IP address.

For more information about creating and working with VPC peering connections, see Working with VPC Peering Connections (p. 5).

VPC Peering Connection Lifecycle

A VPC peering connection goes through various stages starting from when the request is initiated. At each stage, there may be actions that you can take, and at the end of its lifecycle, the VPC peering connection remains visible in the Amazon VPC console and API or command line output for a period of time.




- Initiating-request: A request for a VPC peering connection has been initiated. At this stage, the peering connection may fail or may go to pending-acceptance.
- Failed: The request for the VPC peering connection has failed. During this state, it cannot be accepted or rejected. The failed VPC peering connection remains visible to the requester for 2 hours.
- **Pending-acceptance**: The VPC peering connection request is awaiting acceptance from the owner of the accepter VPC. During this state, the owner of the requester VPC can delete the request, and the owner of the accepter VPC can accept or reject the request. If no action is taken on the request, it expires after 7 days.
- **Expired**: The VPC peering connection request has expired, and no action can be taken on it by either VPC owner. The expired VPC peering connection remains visible to both VPC owners for 2 days.
- Rejected: The owner of the accepter VPC has rejected a pending-acceptance VPC peering connection
 request. During this state, the request cannot be accepted. The rejected VPC peering connection
 remains visible to the owner of the requester VPC for 2 days, and visible to the owner of the accepter
 VPC for 2 hours. If the request was created within the same AWS account, the rejected request remains
 visible for 2 hours.
- Provisioning: The VPC peering connection request has been accepted, and will soon be in the active state.
- Active: The VPC peering connection is active. During this state, either of the VPC owners can delete the VPC peering connection, but cannot reject it.
- Deleted: An active VPC peering connection has been deleted by either of the VPC owners, or a pending-acceptance VPC peering connection request has been deleted by the owner of the requester VPC. During this state, the VPC peering connection cannot be accepted or rejected. The VPC peering connection remains visible to the party that deleted it for 2 hours, and visible to the other party for 2 days. If the VPC peering connection was created within the same AWS account, the deleted request remains visible for 2 hours.

Multiple VPC Peering Connections

A VPC peering connection is a one to one relationship between two VPCs. You can create multiple VPC peering connections for each VPC that you own, but transitive peering relationships are not supported: you do not have any peering relationship with VPCs that your VPC is not directly peered with.

The following diagram is an example of one VPC peered to two different VPCs. There are two VPC peering connections: VPC A is peered with both VPC B and VPC C. VPC B and VPC C are not peered, and you cannot use VPC A as a transit point for peering between VPC B and VPC C. If you want to enable routing of traffic between VPC B and VPC C, you must create a unique VPC peering connection between them.



Pricing for a VPC Peering Connection

The charges for transferring data within a VPC peering connection are the same as the charges for transferring data across Availability Zones. For more information, see Amazon EC2 Pricing.

VPC Peering Limitations

To create a VPC peering connection with another VPC, you need to be aware of the following limitations and rules:

- You cannot create a VPC peering connection between VPCs that have matching or overlapping IPv4
 or IPv6 CIDR blocks. Amazon always assigns your VPC a unique IPv6 CIDR block. If your IPv6 CIDR
 blocks are unique but your IPv4 blocks are not, you cannot create the peering connection.
- You cannot create a VPC peering connection between VPCs in different regions.
- You have a limit on the number active and pending VPC peering connections that you can have per VPC. For more information, see Amazon VPC Limits in the Amazon VPC User Guide.
- VPC peering does not support transitive peering relationships; in a VPC peering connection, your VPC does not have access to any other VPCs that the peer VPC may be peered with. This includes VPC peering connections that are established entirely within your own AWS account. For more information about unsupported peering relationships, see Invalid VPC Peering Connection Configurations (p. 55).
 For examples of supported peering relationships, see VPC Peering Scenarios (p. 15).
- You cannot have more than one VPC peering connection between the same two VPCs at the same time.
- A placement group can span peered VPCs; however, you do not get full-bisection bandwidth between
 instances in peered VPCs. For more information about placement groups, see Placement Groups in the
 Amazon EC2 User Guide for Linux Instances.
- Unicast reverse path forwarding in VPC peering connections is not supported. For more information, see Routing for Response Traffic (p. 41).
- You can enable resources on either side of a VPC peering connection to communicate with each other
 over IPv6; however, IPv6 communication is not automatic. You must associate an IPv6 CIDR block with
 each VPC, enable the instances in the VPCs for IPv6 communication, and add routes to your route tables
 that route IPv6 traffic intended for the peer VPC to the VPC peering connection. For more information,
 see Your VPC and Subnets in the Amazon VPC User Guide.

Working with VPC Peering Connections

You can use the Amazon VPC console to create and work with VPC peering connections.

Topics

- Creating and Accepting a VPC Peering Connection (p. 5)
- Rejecting a VPC Peering Connection (p. 8)
- Updating Your Route Tables for a VPC Peering Connection (p. 8)
- Updating Your Security Groups to Reference Peer VPC Groups (p. 10)
- Modifying VPC Peering Connection Options (p. 12)
- Deleting a VPC Peering Connection (p. 13)
- Controlling Access to VPC Peering Connections (p. 14)

Creating and Accepting a VPC Peering Connection

To create a VPC peering connection, first create a request to peer with another VPC. You can request a VPC peering connection with another VPC in your account, or with a VPC in a different AWS account. To activate the request, the owner of the accepter VPC must accept the request.

Topics

- Creating a VPC Peering Connection with Another VPC in Your Account (p. 5)
- Creating a VPC Peering Connection with a VPC in Another AWS Account (p. 6)
- Accepting a VPC Peering Connection (p. 7)
- Viewing Your VPC Peering Connections (p. 7)

Creating a VPC Peering Connection with Another VPC in Your Account

To request a VPC peering connection with a VPC in your account, ensure that you have the IDs of the VPCs with which you are creating the VPC peering connection. You must both create and accept the VPC peering connection request yourself to activate it.

To create a VPC peering connection in your account

- Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose **Peering Connections**, **Create Peering Connection**.
- 3. Configure the following information, and choose Create Peering Connection when you are done:
 - Peering connection name tag: You can optionally name your VPC peering connection. Doing so creates a tag with a key of Name and a value that you specify.
 - VPC (Requester): Select the VPC in your account with which you want to create the VPC peering connection.
 - Under **Select another VPC to peer with**: Ensure **My account** is selected, and select another of your VPCs from **VPC (Accepter)**. Only VPCs in the current region are displayed.

Important

Ensure that your VPCs do not have overlapping IPv4 CIDR blocks. If they do, the status of the VPC peering connection immediately goes to failed. This limitation applies even if the VPCs have unique IPv6 CIDR blocks.

- 4. In the confirmation dialog box, choose **OK**.
- 5. Select the VPC peering connection that you've created, and choose Actions, Accept Request.
- 6. In the confirmation dialog, choose **Yes, Accept**. A second confirmation dialog displays; choose **Modify my route tables now** to go directly to the route tables page, or choose **Close** to do this later.

Now that your VPC peering connection is active, you must add an entry to your VPC route tables to enable traffic to be directed between the peered VPCs. For more information, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

Creating a VPC Peering Connection with a VPC in Another AWS Account

You can request a VPC peering connection with a VPC that's in another AWS account. Before you begin, ensure that you have the AWS account number and VPC ID of the VPC to peer with. After you've created the request, the owner of the accepter VPC must accept the VPC peering connection to activate it.

To create a VPC peering connection with a VPC in another account

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose Peering Connections, Create Peering Connection.
- 3. In the dialog, configure the information as follows, and choose **Create Peering Connection** when you are done:
 - Peering connection name tag: You can optionally name your VPC peering connection. Doing
 so creates a tag with a key of Name and a value that you specify. This tag is only visible to you; the
 owner of the peer VPC can create their own tags for the VPC peering connection.
 - VPC (Requester): Select the VPC in your account with which to create the VPC peering connection.
 - Under Select another VPC to peer with: Choose Another account, and enter the AWS account ID
 and the ID of the VPC with which to create the VPC peering connection.

Important

If your VPC and the peer VPC have overlapping IPv4 CIDR blocks, or if the account ID and VPC ID are incorrect or do not correspond with each other, the status of the VPC peering connection immediately goes to failed.

4. In the confirmation dialog box, choose **OK**.

The VPC peering connection that you've created is not active. To activate it, the owner of the accepter VPC must accept the VPC peering connection request. To enable traffic to be directed to the peer VPC, update your VPC route table. For more information, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

To create a VPC peering connection using the command line or an API

- create-vpc-peering-connection (AWS CLI)
- New-EC2VpcPeeringConnection (AWS Tools for Windows PowerShell)
- CreateVpcPeeringConnection (Amazon EC2 Query API)

Accepting a VPC Peering Connection

A VPC peering connection that's in the <code>pending-acceptance</code> state must be accepted by the owner of the accepter VPC to be activated. You cannot accept a VPC peering connection request that you've sent to another AWS account. If you are creating a VPC peering connection in the same AWS account, you must both create and accept the request yourself.

Important

Do not accept VPC peering connections from AWS accounts that you do not know. A malicious user may have sent you a VPC peering connection request to gain unauthorized network access to your VPC. This is known as peer phishing. You can safely reject unwanted VPC peering connection requests without any risk of the requester gaining access to any information about your AWS account or your VPC. For more information, see Rejecting a VPC Peering Connection (p. 8). You can also ignore the request and let it expire; by default, requests expire after 7 days.

To accept a VPC peering connection

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose **Peering Connections**.
- Select a pending VPC peering connection (the status is pending-acceptance), and choose Actions, Accept Request.
- 4. In the confirmation dialog box, choose **Yes, Accept**. A second confirmation dialog displays; choose **Modify my route tables now** to go directly to the route tables page, or choose **Close** to do this later.

Now that your VPC peering connection is active, you must add an entry to your VPC route table to enable traffic to be directed to the peer VPC. For more information, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

To accept a VPC peering connection using the command line or an API

- accept-vpc-peering-connection (AWS CLI)
- Approve-EC2VpcPeeringConnection (AWS Tools for Windows PowerShell)
- AcceptVpcPeeringConnection (Amazon EC2 Query API)

Viewing Your VPC Peering Connections

You can view all of your VPC peering connections in the Amazon VPC console. By default, the console displays all VPC peering connections in different states, including those that may have been recently deleted or rejected. For more information about the lifecycle of a VPC peering connection, see VPC Peering Connection Lifecycle (p. 2).

To view your VPC peering connections

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose **Peering Connections**.
- 3. All of your VPC peering connections are listed. Use the filter search bar to narrow your results.

To describe a VPC peering connection using the command line or an API

- describe-vpc-peering-connections (AWS CLI)
- Get-EC2VpcPeeringConnections (AWS Tools for Windows PowerShell)
- DescribeVpcPeeringConnections (Amazon EC2 Query API)

Rejecting a VPC Peering Connection

You can reject any VPC peering connection request that you've received that's in the <code>pending-acceptance</code> state. You should only accept VPC peering connections from AWS accounts that you know and trust; you can reject any unwanted requests.

To reject a VPC peering connection

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose **Peering Connections**.
- 3. Select the VPC peering connection, and choose Actions, Reject Request.
- 4. In the confirmation dialog box, choose Yes, Reject.

To reject a VPC peering connection using the command line or an API

- reject-vpc-peering-connection (AWS CLI)
- Deny-EC2VpcPeeringConnection (AWS Tools for Windows PowerShell)
- RejectVpcPeeringConnection (Amazon EC2 Query API)

Updating Your Route Tables for a VPC Peering Connection

To send traffic from your instance to an instance in a peer VPC using private IPv4 addresses, you must add a route to the route table that's associated with the subnet in which the instance resides. The route points to the CIDR block (or portion of the CIDR block) of the other VPC in the VPC peering connection.

Similarly, if the VPCs in the VPC peering connection have associated IPv6 CIDR blocks, you can add a route to your route table to enable communication with the peer VPC over IPv6.

Note

If a subnet is not explicitly associated with a route table, it uses the main route table by default.

The owner of the other VPC in the peering connection must also add a route to their subnet's route table to direct traffic back to your VPC. For more information about supported route table configurations for VPC peering connections, see VPC Peering Configurations (p. 17).

You can add a route for a VPC peering connection that's in the <code>pending-acceptance</code> state; however, the route will have a state of <code>blackhole</code> and have no effect until the VPC peering connection is in the <code>active</code> state.

Warning

If you have a VPC peered with multiple VPCs that have overlapping or matching IPv4 CIDR blocks, ensure that your route tables are configured to avoid sending response traffic from your VPC to the incorrect VPC. AWS currently does not support unicast reverse path forwarding in VPC peering connections that checks the source IP of packets and routes reply packets back to the source. For more information, see Routing for Response Traffic (p. 41).


To add an IPv4 route for a VPC peering connection

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose Route Tables.
- 3. Select the route table that's associated with the subnet in which your instance resides.

Note

If you do not have a route table associated with that subnet, select the main route table for the VPC, as the subnet then uses this route table by default.

- 4. Choose Routes. Edit. Add Route.
- 5. For **Destination**, enter the IPv4 address range to which the network traffic in the VPC peering connection must be directed. You can specify the entire IPv4 CIDR block of the peer VPC, a specific range, or an individual IPv4 address, such as the IP address of the instance with which to communicate. For example, if the CIDR block of the peer VPC is 10.0.0.0/16, you can specify a portion 10.0.0.0/28, or a specific IP address 10.0.0.7/32.
- 6. Select the VPC peering connection from Target, and then choose Save.



If both VPCs in the VPC peering connection have IPv6 CIDR blocks, and the resources in the VPC are enabled to use IPv6, you can also add a route for IPv6 communication.

To add an IPv6 route for a VPC peering connection

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- In the navigation pane, choose Route Tables and select the route table that's associated with your subnet.
- 3. On the **Routes** tab, choose **Edit**, **Add another route**.
- 4. For **Destination**, enter the IPv6 address range for the peer VPC. You can specify the entire IPv6 CIDR block of the peer VPC, a specific range, or an individual IPv6 address. For example, if the CIDR block of the peer VPC is 2001:db8:1234:1a00::/56, you can specify a portion 2001:db8:1234:1a00::/64, or a specific IP address 2001:db8:1234:1a00::123/128.
- 5. Select the VPC peering connection from **Target** and choose **Save**.

For more information, see Route Tables in the Amazon VPC User Guide.

To add or replace a route using the command line or an API

create-route (AWS CLI)

- New-EC2Route (AWS Tools for Windows PowerShell)
- CreateRoute (Amazon EC2 Query API)
- replace-route (AWS CLI)
- Set-EC2Route (AWS Tools for Windows PowerShell)
- ReplaceRoute (Amazon EC2 Query API)

Updating Your Security Groups to Reference Peer VPC Groups

You can update the inbound or outbound rules for your VPC security groups to reference security groups in the peered VPC. Doing so allows traffic to flow to and from instances that are associated with the referenced security group in the peered VPC.

To update your security group rules

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose Security Groups.
- Select the security group, and choose Inbound Rules. If you're modifying the outbound rules, choose Outbound Rules.
- 4. Choose Edit, Add another rule.
- 5. Specify the type, protocol, and port range as required. For **Source** (or **Destination** for an outbound rule), enter the ID of the security group in the peer VPC.
- 6. Choose Save.

Alternatively, you can use the following commands.

Action	Commands
Authorize inbound rules	authorize-security-group-ingress (AWS CLI)
	Grant-EC2SecurityGroupIngress (AWS Tools for Windows PowerShell)
Authorize outbound rules	authorize-security-group-egress (AWS CLI)
	Grant-EC2SecurityGroupEgress (AWS Tools for Windows PowerShell)
Revoke inbound rules	revoke-security-group-ingress (AWS CLI)
	Revoke-EC2SecurityGroupIngress (AWS Tools for Windows PowerShell)
Revoke outbound rules	revoke-security-group-egress (AWS CLI)
	Revoke-EC2SecurityGroupEgress (AWS Tools for Windows PowerShell)

For example, to update your security group ${\tt sg-aaaa111}$ to allow inbound access over HTTP from ${\tt sg-bbbb2222}$ that's in a peer VPC, you can use the following AWS CLI command:

Amazon Virtual Private Cloud VPC Peering Guide Identifying Your Referenced Security Groups

```
aws ec2 authorize-security-group-ingress --group-id sg-aaaa1111 --protocol tcp --port 80 --source-group sg-bbbb2222
```

After you've updated the security group rules, use the describe-security-groups command to view the referenced security group in your security group rules.

Identifying Your Referenced Security Groups

To determine if your security group is being referenced in the rules of a security group in a peer VPC, use one of the following commands for one or more security groups in your account.

- describe-security-group-references (AWS CLI)
- Get-EC2SecurityGroupReference (AWS Tools for Windows PowerShell)
- DescribeSecurityGroupReferences (Amazon EC2 Query API)

In the following example, the response indicates that security group sg-bbbb2222 is being referenced by a security group in VPC vpc-aaaaaaaaa:

```
aws ec2 describe-security-group-references --group-id sg-bbbb2222
```

```
{
    "SecurityGroupsReferenceSet": [
      {
          "ReferencingVpcId": "vpc-aaaaaaaaa ",
          "GroupId": "sg-bbbbb22222",
          "VpcPeeringConnectionId": "pcx-b04deed9"
      }
    }
}
```

Note

Currently, you cannot identify security group references using the Amazon VPC or Amazon EC2 consoles.

If the VPC peering connection is deleted, or if the owner of the peer VPC deletes the referenced security group, the security group rule becomes stale.

Working with Stale Security Group Rules

A stale security group rule is a rule that references a security group in a peer VPC where the VPC peering connection has been deleted or the security group in the peer VPC has been deleted. When a security group rule becomes stale, it's not automatically removed from your security group—you must manually remove it. If a security group rule is stale because the VPC peering connection was deleted, it will no longer be marked as stale if you create a new VPC peering connection with the same VPCs.

You can view and delete the stale security group rules for a VPC using the Amazon VPC console.

To view and delete stale security group rules

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- In the navigation pane, choose Security Groups.
- Choose View your stale rules in the notification icon on the right (this icon only displays if you have stale security group rules).

- To delete a stale rule, choose Edit, and then delete the rule. Choose Save Rules. You can check for stale rules in another VPC by entering the VPC ID in the VPC field.
- 5. When you are done, choose Close.

To describe your stale security group rules using the command line or an API

- describe-stale-security-groups (AWS CLI)
- Get-EC2StaleSecurityGroup (AWS Tools for Windows PowerShell)
- DescribeStaleSecurityGroups (Amazon EC2 Query API)

In the following example, VPC A (vpc-aaaaaaaa) and VPC B were peered, and the VPC peering connection was deleted. Your security group sg-aaaa1111 in VPC A references sg-bbbb2222 in VPC B. When you run the describe-stale-security-groups command for your VPC, the response indicates that security group sg-aaaa1111 has a stale SSH rule that references sg-bbbb2222.

```
aws ec2 describe-stale-security-groups --vpc-id vpc-aaaaaaaa
```

```
"StaleSecurityGroupSet": [
        "VpcId": "vpc-aaaaaaaa",
        "StaleIpPermissionsEgress": [],
        "GroupName": "Access1",
        "StaleIpPermissions": [
                 "ToPort": 22,
                 "FromPort": 22,
                 "UserIdGroupPairs": [
                         "VpcId": "vpc-bbbbbbbbb",
                         "PeeringStatus": "deleted",
                         "UserId": "123456789101",
                         "GroupName": "Prod1",
                         "VpcPeeringConnectionId": "pcx-b04deed9",
                         "GroupId": "sg-bbbb2222"
                ],
                 "IpProtocol": "tcp"
            }
        "GroupId": "sg-aaaa1111",
        "Description": "Reference remote SG"
    }
]
```

After you've identified the stale security group rules, you can delete them using the revoke-security-groupingress or revoke-security-group-egress commands.

Modifying VPC Peering Connection Options

You can modify a VPC peering connection to do the following:

• Enable one or more EC2-Classic instances that are linked to your VPC via ClassicLink to communicate with instances in the peer VPC, or to enable instances in your VPC to communicate with linked EC2-

Amazon Virtual Private Cloud VPC Peering Guide Enabling DNS Resolution Support for a VPC Peering Connection

Classic instances in the peer VPC. For more information, see Configurations with ClassicLink (p. 48). You cannot enable EC2-Classic instances to communicate with instances in a peer VPC over IPv6.

• Enable a VPC to resolve public IPv4 DNS hostnames to private IPv4 addresses when queried from instances in the peer VPC. For more information, see Enabling DNS Resolution Support for a VPC Peering Connection (p. 13).

Enabling DNS Resolution Support for a VPC Peering Connection

To enable a VPC to resolve public IPv4 DNS hostnames to private IPv4 addresses when queried from instances in the peer VPC, you must modify the peering connection.

Both VPCs must be enabled for DNS hostnames and DNS resolution.

To enable DNS resolution support for the peering connection

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose **Peering Connections**.
- 3. Select the VPC peering connection, and choose Actions, Edit DNS Settings.
- 4. To ensure that queries from the peer VPC resolve to private IP addresses in your local VPC, choose the option to enable DNS resolution for queries from the peer VPC.
- 5. If the peer VPC is in the same AWS account, you can choose the option to enable DNS resolution for queries from the local VPC. This ensures that queries from the local VPC resolve to private IP addresses in the peer VPC. This option is not available if the peer VPC is in a different AWS account.
- 6. Choose Save.
- 7. If the peer VPC is in a different AWS account, the owner of the peer VPC must sign into the VPC console, perform steps 2 through 4, and choose **Save**.

To enable DNS resolution using the command line or an API

- modify-vpc-peering-connection-options (AWS CLI)
- Edit-EC2VpcPeeringConnectionOption (AWS Tools for Windows PowerShell)
- ModifyVpcPeeringConnectionOptions (Amazon EC2 Query API)

You must modify the requester VPC peering options if you are the requester of the VPC peering connection, and you must modify the accepter VPC peering options if you are the accepter of the VPC peering connection. You can use the describe-vpc-peering-connections or Get-EC2VpcPeeringConnections commands to verify which VPC is the accepter and the requester for a VPC peering connection.

In this example, you are the requester of the VPC peering connection, therefore modify the peering connection options using the AWS CLI as follows:

aws ec2 modify-vpc-peering-connection-options --vpc-peering-connection-id pcx-aaaabbbb --requester-peering-connection-options AllowDnsResolutionFromRemoteVpc=true

Deleting a VPC Peering Connection

Either owner of a VPC in a peering connection can delete the VPC peering connection at any time. You can also delete a VPC peering connection that you've requested that is still in the pending-acceptance state.

Note

Deleting a VPC in the Amazon VPC console that's part of an active VPC peering connection also deletes the VPC peering connection. If you have requested a VPC peering connection with a VPC in another account, and you delete your VPC before the other party has accepted the request, the VPC peering connection is also deleted. You cannot delete a VPC for which you have a pending-acceptance request from a VPC in another account. You must first reject the VPC peering connection request.

To delete a VPC peering connection

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose **Peering Connections**.
- 3. Select the VPC peering connection, and choose Actions, Delete VPC Peering Connection.
- 4. In the confirmation dialog box, choose **Yes, Delete**.

To delete a VPC peering connection using the command line or an API

- delete-vpc-peering-connection (AWS CLI)
- Remove-EC2VpcPeeringConnection (AWS Tools for Windows PowerShell)
- DeleteVpcPeeringConnection (Amazon EC2 Query API)

Controlling Access to VPC Peering Connections

By default, IAM users cannot create or modify VPC peering connections. You can create an IAM policy that grants users permission to work with VPC peering connections, and you can control which resources users have access to during those requests. For example policies for working with VPC peering connections, see Controlling Access to Amazon VPC Resources in the Amazon VPC User Guide. For more information about IAM policies for Amazon EC2, see IAM Policies for Amazon EC2 in the Amazon EC2 User Guide for Linux Instances.

VPC Peering Scenarios

There are a number of reasons you may need to set up VPC peering connection between your VPCs, or between a VPC that you own and a VPC in a different AWS account. The following scenarios can help you determine which configuration is best suited to your networking requirements.

Topics

- Peering Two or More VPCs to Provide Full Access to Resources (p. 15)
- Peering to One VPC to Access Centralized Resources (p. 16)
- Peering with ClassicLink (p. 16)

Peering Two or More VPCs to Provide Full Access to Resources

In this scenario, you have two or more VPCs that you want to peer to enable full sharing of resources between all VPCs. The following are some examples:

- Your company has a VPC for the finance department, and another VPC for the accounting department.
 The finance department requires access to all resources that are in the accounting department, and the accounting department requires access to all resources in the finance department.
- Your company has multiple IT departments, each with their own VPC. Some VPCs are located within
 the same AWS account, and others in a different AWS account. You want to peer together all VPCs to
 enable the IT departments to have full access to each others' resources.

For more information about how to set up the VPC peering connection configuration and route tables for this scenario, see the following topics:

- Two VPCs Peered Together (p. 17)
- Three VPCs Peered Together (p. 21)
- Multiple VPCs Peered Together (p. 27)

For more information about creating and working with VPC peering connections in the Amazon VPC console, see Working with VPC Peering Connections (p. 5).

Peering to One VPC to Access Centralized Resources

In this scenario, you have a central VPC that contains resources that you want to share with other VPCs. Your central VPC may require full or partial access to the peer VPCs, and similarly, the peer VPCs may require full or partial access to the central VPC. The following are some examples:

- Your company's IT department has a VPC for file sharing. You want to peer other VPCs to that central VPC, however, you do not want the other VPCs to send traffic to each other.
- Your company has a VPC that you want to share with your customers. Each customer can create a VPC
 peering connection with your VPC, however, your customers cannot route traffic to other VPCs that are
 peered to yours, nor are they aware of the other customers' routes.
- You have a central VPC that is used for Active Directory services. Specific instances in peer VPCs send
 requests to the Active Directory servers and require full access to the central VPC. The central VPC does
 not require full access to the peer VPCs; it only needs to route response traffic to the specific instances.

For more information about how to set up the VPC peering connection configuration and route tables for this scenario, see the following topics:

- One VPC Peered with Two VPCs (p. 19)
- One VPC Peered with Multiple VPCs (p. 23)
- Two VPCs Peered to Two Subnets in One VPC (p. 36)
- One VPC Peered to Specific Subnets in Two VPCs (p. 39)
- Instances in One VPC Peered to Instances in Two VPCs (p. 43)
- One VPC Peered with Two VPCs Using Longest Prefix Match (p. 45)

For more information about creating and working with VPC peering connections in the Amazon VPC console, see Working with VPC Peering Connections (p. 5).

Peering with ClassicLink

You can modify a VPC peering connection to enable one or more EC2-Classic instances that are linked to your VPC via ClassicLink to communicate with instances in the peer VPC. Similarly, you can modify a VPC peering connection to enable instances in your VPC to communicate with linked EC2-Classic instances in the peer VPC.

For more information about how to set up the VPC peering connection configuration and route tables for this scenario, see Configurations with ClassicLink (p. 48).

VPC Peering Configurations

The following sections describe supported VPC peering configurations. You may require a configuration that allows routing between the entire CIDR block of each VPC, or a configuration that limits routing to specific subnets or IP addresses.

Topics

- Configurations with Routes to an Entire CIDR Block (p. 17)
- Configurations with Specific Routes (p. 35)
- Configurations with ClassicLink (p. 48)

Configurations with Routes to an Entire CIDR Block

This section demonstrates the configuration for VPC peering connections in which you configure your route tables to access to the entire CIDR block of the peer VPC. For more information about scenarios in which you might need a specific VPC peering connection configuration, see VPC Peering Scenarios (p. 15). For more information about creating and working with VPC peering connections in the Amazon VPC console, see Working with VPC Peering Connections (p. 5).

Topics

- Two VPCs Peered Together (p. 17)
- One VPC Peered with Two VPCs (p. 19)
- Three VPCs Peered Together (p. 21)
- One VPC Peered with Multiple VPCs (p. 23)
- Multiple VPCs Peered Together (p. 27)

Two VPCs Peered Together

You have a VPC peering connection (pcx-11112222) between VPC A and VPC B, which are in the same AWS account, and do not have overlapping CIDR blocks.



You may want to use this kind of configuration when you have a two VPCs that require access to each others' resources. For example, you set up VPC A for your accounting records, and VPC B for your financial records, and now you want each VPC to be able to access each others' resources without restriction.


The route tables for each VPC point to the relevant VPC peering connection to access the entire CIDR block of the peer VPC.

Route table	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.0/16	pcx-11112222
VPC B	10.0.0.0/16	Local
	172.16.0.0/16	pcx-11112222

For more information about updating your route tables, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

Two VPCs Peered Together for IPv6

You have the same two VPCs in the VPC peering configuration as above. In this example, VPC A and VPC B both have associated IPv6 CIDR blocks.



The route tables for each VPC point to the VPC peering connection to access the entire IPv6 CIDR block of the peer VPC.

Route table	Destination	Target
VPC A	172.16.0.0/16	Local
	2001:db8:1234:aa00::/56	Local
	10.0.0.0/16	pcx-11112222
	2001:db8:5678:bb00::/56	pcx-11112222
VPC B	10.0.0.0/16	Local


Amazon Virtual Private Cloud VPC Peering Guide One VPC Peered with Two VPCs

Route table	Destination	Target
	2001:db8:5678:bb00::/56	Local
	172.16.0.0/16	pcx-11112222
	2001:db8:1234:aa00::/56	pcx-11112222

For more information about IPv6 in your VPC, see Your VPC and Subnets in the Amazon VPC User Guide.

One VPC Peered with Two VPCs

You have a central VPC (VPC A), and you have a VPC peering connection between VPC A and VPC B (pcx-12121212), and between VPC A and VPC C (pcx-23232323). The VPCs are in the same AWS account, and do not have overlapping CIDR blocks.



You may want to use this 'flying V' configuration when you have resources on a central VPC, such as a repository of services, that other VPCs need to access. The other VPCs do not need access to each others' resources; they only need access to resources on the central VPC.

Note

VPC B and VPC C cannot send traffic directly to each other through VPC A. VPC peering does not support transitive peering relationships, nor edge to edge routing. You must create a VPC peering connection between VPC B and VPC C in order to route traffic directly between them. For more information, see Three VPCs Peered Together (p. 21). For more information about unsupported peering scenarios, see Invalid VPC Peering Connection Configurations (p. 55).

The route tables for each VPC point to the relevant VPC peering connection to access the entire CIDR block of the peer VPC.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.0/16	pcx-12121212
	192.168.0.0/16	pcx-23232323
VPC B	10.0.0.0/16	Local


Amazon Virtual Private Cloud VPC Peering Guide One VPC Peered with Two VPCs

Route Table	Destination	Target
	172.16.0.0/16	pcx-12121212
VPC C	192.168.0.0/16	Local
	172.16.0.0/16	pcx-23232323

For more information about updating your route tables, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

One VPC Peered with Two VPCs for IPv6

You have the same three VPCs in the VPC peering configuration as above. In this example, all three VPCs have associated IPv6 CIDR blocks.



The route tables for each VPC point to the VPC peering connection to access the entire IPv6 CIDR block of the peer VPC.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	2001:db8:1234:aa00::/56	Local
	10.0.0.0/16	pcx-12121212
	192.168.0.0/16	pcx-23232323
	2001:db8:1234:bb00::/56	pcx-12121212
	2001:db8:1234:cc00::/56	pcx-23232323
VPC B	10.0.0.0/16	Local
	2001:db8:1234:bb00::/56	Local
	172.16.0.0/16	pcx-12121212
	2001:db8:1234:aa00::/56	pcx-12121212


Amazon Virtual Private Cloud VPC Peering Guide Three VPCs Peered Together

Route Table	Destination	Target
VPC C	192.168.0.0/16	Local
	2001:db8:1234:cc00::/56	Local
	172.16.0.0/16	pcx-23232323
	2001:db8:1234:aa00::/56	pcx-23232323

Three VPCs Peered Together

You have peered three VPCs together in a full mesh configuration. The VPCs are in the same AWS account and do not have overlapping CIDR blocks:

- VPC A is peered to VPC B through VPC peering connection pcx-aaaabbbb
- VPC A is peered to VPC C through VPC peering connection pcx-aaaacccc
- VPC B is peered to VPC C through VPC peering connection pex-bbbbcccc



You may want to use this full mesh configuration when you have separate VPCs that need to share resources with each other without restriction; for example, as a file sharing system.

The route tables for each VPC point to the relevant VPC peering connection to access the entire CIDR block of the peer VPCs.

Route Tables	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.0/16	pcx-aaaabbbb
	192.168.0.0/16	рсх-аааасссс
VPC B	10.0.0.0/16	Local
	172.16.0.0/16	pcx-aaaabbbb
	192.168.0.0/16	pcx-bbbbcccc
VPC C	192.168.0.0/16	Local


Amazon Virtual Private Cloud VPC Peering Guide Three VPCs Peered Together

Route Tables	Destination	Target
	172.16.0.0/16	рсх-аааасссс
	10.0.0.0/16	pcx-bbbbcccc

For more information about updating your route tables, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

Three VPCs Peered for IPv6

You have the same three VPCs in the VPC peering configuration as above. In this example, VPC A and VPC B both have associated IPv6 CIDR blocks. VPC C does not have an associated IPv6 CIDR block.



The route tables for VPC A and VPC B include routes that point to VPC peering connection pcx-aaaabbbb to access the entire IPv6 CIDR block of the peer VPC. VPC A and VPC B can communicate using IPv6 over the VPC peering connection. VPC C cannot communicate using IPv6 with either VPC A or VPC B.

Route Tables	Destination	Target
VPC A	172.16.0.0/16	Local
	2001:db8:1234:aa00::/56	Local
	10.0.0.0/16	pcx-aaaabbbb
	192.168.0.0/16	рсх-аааасссс
	2001:db8:1234:bb00::/56	pcx-aaaabbbb
VPC B	10.0.0.0/16	Local
	2001:db8:1234:bb00::/56	Local
	172.16.0.0/16	pcx-aaaabbbb
	192.168.0.0/16	pcx-bbbbcccc
	2001:db8:1234:aa00::/56	pcx-aaaabbbb
VPC C	192.168.0.0/16	Local

Amazon Virtual Private Cloud VPC Peering Guide One VPC Peered with Multiple VPCs

Route Tables	Destination	Target
	172.16.0.0/16	рсх-аааасссс
	10.0.0.0/16	pcx-bbbbcccc

The owner of VPC C associates an IPv6 CIDR block with the VPC (2001:db8:1234:cc00::/56). VPC C can now communicate over IPv6 with both VPC A and VPC B using the existing VPC peering connection. To enable this, the following routes must be added to the existing route tables:

Route Tables	Destination	Target
VPC A	2001:db8:1234:cc00::/56	рсх-аааасссс
VPC B	2001:db8:1234:cc00::/56	pcx-bbbbcccc
VPC C	2001:db8:1234:aa00::/56	рсх-ааааасссс
	2001:db8:1234:bb00::/56	pcx-bbbbcccc

For more information about IPv6 in your VPC, see Your VPC and Subnets in the Amazon VPC User Guide.

One VPC Peered with Multiple VPCs


You have a central VPC (VPC A) that's peered to the following VPCs:

- VPC B through pcx-aaaabbbb
- VPC C through pcx-aaaacccc
- VPC D through pcx-aaaadddd
- VPC E through pcx-aaaaeeee
- VPC F through pcx-aaaaffff
- VPC G through pcx-aaaagggg

VPC A is peered with all other VPCs, but the other VPCs are not peered to each other. The VPCs are in the same AWS account and do not have overlapping CIDR blocks.

Note

None of the other VPCs can send traffic directly to each other through VPC A. VPC peering does not support transitive peering relationships, nor edge to edge routing. You must create a VPC peering connection between the other VPCs in order to route traffic between them. For more information, see Multiple VPCs Peered Together (p. 27). For more information about unsupported peering scenarios, see Invalid VPC Peering Connection Configurations (p. 55).



You may want to use this spoke configuration when you have resources on a central VPC, such as a repository of services, that other VPCs need to access. The other VPCs do not need access to each others' resources; they only need access to resources on the central VPC.

The route tables for each VPC point to the relevant VPC peering connection to access the entire CIDR block of the peer VPC.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.0/16	pcx-aaaabbbb
	192.168.0.0/16	рсх-аааасссс
	10.2.0.0/16	pcx-aaaadddd
	10.3.0.0/16	pcx-aaaaeeee
	172.17.0.0/16	pcx-aaaaffff
	10.4.0.0/16	pcx-aaaagggg
VPC B	10.0.0.0/16	Local
	172.16.0.0/16	pcx-aaaabbbb
VPC C	192.168.0.0/16	Local


Amazon Virtual Private Cloud VPC Peering Guide One VPC Peered with Multiple VPCs

Route Table	Destination	Target
	172.16.0.0/16	рсх-аааасссс
VPC D	10.2.0.0/16	Local
	172.16.0.0/16	pcx-aaaadddd
VPC E	10.3.0.0/16	Local
	172.16.0.0/16	pcx-aaaaeeee
VPC F	172.17.0.0/16	Local
	172.16.0.0/16	pcx-aaaaffff
VPC G	10.4.0.0/16	Local
	172.16.0.0/16	pcx-aaaagggg

For more information about updating your route tables, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

One VPC Peered with Multiple VPCs for IPv6

You have the same VPCs in the VPC peering configuration as above. All VPCs have associated IPv6 CIDR blocks.



The route tables for each VPC point to the relevant VPC peering connection to access the entire IPv6 CIDR block of the peer VPC.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	2001:db8:1234:aa00::/56	Local
	10.0.0.0/16	pcx-aaaabbbb
	2001:db8:1234:bb00::/56	pcx-aaaabbbb
	192.168.0.0/16	рсх-аааасссс
	2001:db8:1234:cc00::/56	рсх-аааасссс
	10.2.0.0/16	pcx-aaaadddd
	2001:db8:1234:dd00::/56	pcx-aaaadddd
	10.3.0.0/16	pcx-aaaaeeee
	2001:db8:1234:ee00::/56	рсх-ааааееее
	172.17.0.0/16	pcx-aaaaffff

Amazon Virtual Private Cloud VPC Peering Guide Multiple VPCs Peered Together

Route Table	Destination	Target
	2001:db8:1234:ff00::/56	pcx-aaaaffff
	10.4.0.0/16	pcx-aaaagggg
	2001:db8:1234:7700::/56	pcx-aaaagggg
VPC B	10.0.0.0/16	Local
	2001:db8:1234:bb00::/56	Local
	172.16.0.0/16	pcx-aaaabbbb
	2001:db8:1234:aa00::/56	pcx-aaaabbbb
VPC C	192.168.0.0/16	Local
	2001:db8:1234:cc00::/56	Local
	172.16.0.0/16	рсх-аааасссс
	2001:db8:1234:aa00::/56	рсх-аааасссс
VPC D	10.2.0.0/16	Local
	2001:db8:1234:dd00::/56	Local
	172.16.0.0/16	pcx-aaaadddd
	2001:db8:1234:aa00::/56	pcx-aaaadddd
VPC E	10.3.0.0/16	Local
	2001:db8:1234:ee00::/56	Local
	172.16.0.0/16	рсх-ааааееее
	2001:db8:1234:aa00::/56	pcx-aaaaeeee
VPC F	172.17.0.0/16	Local
	2001:db8:1234:ff00::/56	Local
	172.16.0.0/16	pcx-aaaaffff
	2001:db8:1234:aa00::/56	pcx-aaaaffff
VPC G	10.4.0.0/16	Local
	2001:db8:1234:7700::/56	Local
	172.16.0.0/16	pcx-aaaagggg
	2001:db8:1234:aa00::/56	pcx-aaaagggg


Multiple VPCs Peered Together

You have peered seven VPCs together in a full mesh configuration:

Amazon Virtual Private Cloud VPC Peering Guide Multiple VPCs Peered Together

VPCs	VPC Peering Connection
A and B	pcx-aaaabbbb
A and C	рсх-аааасссс
A and D	pcx-aaaadddd
A and E	рсх-ааааееее
A and F	pcx-aaaaffff
A and G	pcx-aaaagggg
B and C	pcx-bbbbcccc
B and D	pcx-bbbbdddd
B and E	pcx-bbbbeeee
B and F	pcx-bbbbffff
B and G	pcx-bbbbgggg
C and D	pcx-cccdddd
C and E	pcx-ccceeee
C and F	pcx-cccdffff
C and G	pcx-cccgggg
D and E	pcx-ddddeeee
D and F	pcx-ddddffff
D and G	pcx-ddddgggg
E and F	pcx-eeeeffff
E and G	pcx-eeeegggg
F and G	pcx-ffffgggg

The VPCs are in the same AWS account and do not have overlapping CIDR blocks.



You may want to use this full mesh configuration when you have multiple VPCs that must be able to access each others' resources without restriction; for example, as a file sharing network.

The route tables for each VPC point to the relevant VPC peering connection to access the entire CIDR block of the peer VPC.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.0/16	pcx-aaaabbbb
	192.168.0.0/16	рсх-аааасссс
	10.2.0.0/16	pcx-aaaadddd
	10.3.0.0/16	pcx-aaaaeeee
	172.17.0.0/16	pcx-aaaaffff
	10.4.0.0/16	pcx-aaaagggg
VPC B	10.0.0.0/16	Local
	172.16.0.0/16	pcx-aaaabbbb
	192.168.0.0/16	pcx-bbbbcccc

Amazon Virtual Private Cloud VPC Peering Guide Multiple VPCs Peered Together

Route Table	Destination	Target
	10.2.0.0/16	pcx-bbbbdddd
	10.3.0.0/16	pcx-bbbbeeee
	172.17.0.0/16	pcx-bbbbffff
	10.4.0.0/16	pcx-bbbbgggg
VPC C	192.168.0.0/16	Local
	172.16.0.0/16	рсх-аааасссс
	10.0.0.0/16	pcx-bbbbcccc
	10.2.0.0/16	pcx-cccdddd
	10.3.0.0/16	pcx-ccceeee
	172.17.0.0/16	pcx-cccffff
	10.4.0.0/16	pcx-cccgggg
VPC D	10.2.0.0/16	Local
	172.16.0.0/16	pcx-aaaadddd
	10.0.0.0/16	pcx-bbbbdddd
	192.168.0.0/16	pcx-cccdddd
	10.3.0.0/16	pcx-ddddeeee
	172.17.0.0/16	pcx-ddddffff
	10.4.0.0/16	pcx-ddddgggg
VPC E	10.3.0.0/16	Local
	172.16.0.0/16	рсх-ааааееее
	10.0.0.0/16	pcx-bbbbeeee
	192.168.0.0/16	pcx-ccceeee
	10.2.0.0/16	pcx-ddddeeee
	172.17.0.0/16	pcx-eeeeffff
	10.4.0.0/16	pcx-eeeegggg
VPC F	172.17.0.0/16	Local
	172.16.0.0/16	pcx-aaaaffff
	10.0.0.0/16	pcx-bbbbffff
	192.168.0.0/16	pcx-cccffff
	10.2.0.0/16	pcx-ddddffff
	10.3.0.0/16	pcx-eeeeffff


Amazon Virtual Private Cloud VPC Peering Guide Multiple VPCs Peered Together

Route Table	Destination	Target
	10.4.0.0/16	pcx-ffffgggg
VPC G	10.4.0.0/16	Local
	172.16.0.0/16	pcx-aaaagggg
	10.0.0.0/16	pcx-bbbbgggg
	192.168.0.0/16	pcx-cccgggg
	10.2.0.0/16	pcx-ddddgggg
	10.3.0.0/16	pcx-eeeegggg
	172.17.0.0/16	pcx-ffffgggg

For more information about updating route tables, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

Multiple VPCs Peered Together for IPv6

You have the same VPCs in the VPC peering configuration as above. All VPCs have associated IPv6 CIDR blocks.



The route tables for each VPC point to the VPC peering connection to access the entire IPv6 CIDR block of the peer VPC.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	2001:db8:1234:aa00::/56	Local
	10.0.0.0/16	pcx-aaaabbbb
	2001:db8:1234:bb00::/56	pcx-aaaabbbb
	192.168.0.0/16	рсх-аааасссс
	2001:db8:1234:cc00::/56	рсх-аааасссс
	10.2.0.0/16	pcx-aaaadddd
	2001:db8:1234:dd00::/56	pcx-aaaadddd
	10.3.0.0/16	рсх-ааааееее

Amazon Virtual Private Cloud VPC Peering Guide Multiple VPCs Peered Together

Route Table	Destination	Target
	2001:db8:1234:ee00::/56	рсх-ааааееее
	172.17.0.0/16	pcx-aaaaffff
	2001:db8:1234:ff00::/56	pcx-aaaaffff
	10.4.0.0/16	pcx-aaaagggg
	2001:db8:1234:7700::/56	pcx-aaaagggg
VPC B	10.0.0.0/16	Local
	2001:db8:1234:bb00::/56	Local
	172.16.0.0/16	pcx-aaaabbbb
	2001:db8:1234:aa00::/56	pcx-aaaabbbb
	192.168.0.0/16	pcx-bbbbcccc
	2001:db8:1234:cc00::/56	pcx-bbbbcccc
	10.2.0.0/16	pcx-bbbbdddd
	2001:db8:1234:dd00::/56	pcx-bbbbdddd
	10.3.0.0/16	pcx-bbbbeeee
	2001:db8:1234:ee00::/56	pcx-bbbbeeee
	172.17.0.0/16	pcx-bbbbffff
	2001:db8:1234:ff00::/56	pcx-bbbbffff
	10.4.0.0/16	pcx-bbbbgggg
	2001:db8:1234:7700::/56	pcx-bbbbgggg
VPC C	192.168.0.0/16	Local
	2001:db8:1234:cc00::/56	Local
	172.16.0.0/16	рсх-аааасссс
	2001:db8:1234:aa00::/56	рсх-аааасссс
	10.0.0.0/16	pcx-bbbbcccc
	2001:db8:1234:bb00::/56	pcx-bbbbcccc
	10.2.0.0/16	pcx-cccdddd
	2001:db8:1234:dd00::/56	pcx-cccdddd
	10.3.0.0/16	pcx-ccceeee
	2001:db8:1234:ee00::/56	pcx-ccceeee
	172.17.0.0/16	pcx-ccccffff
	2001:db8:1234:ff00::/56	pcx-ccccffff

Amazon Virtual Private Cloud VPC Peering Guide Multiple VPCs Peered Together

Route Table	Destination	Target
	10.4.0.0/16	pcx-cccgggg
	2001:db8:1234:7700::/56	pcx-cccgggg
VPC D	10.2.0.0/16	Local
	2001:db8:1234:dd00::/56	Local
	172.16.0.0/16	pcx-aaaadddd
	2001:db8:1234:aa00::/56	pcx-aaaadddd
	10.0.0.0/16	pcx-bbbbdddd
	2001:db8:1234:bb00::/56	pcx-bbbbdddd
	192.168.0.0/16	pcx-cccdddd
	2001:db8:1234:cc00::/56	pcx-cccdddd
	10.3.0.0/16	pcx-ddddeeee
	2001:db8:1234:ee00::/56	pcx-ddddeeee
	172.17.0.0/16	pcx-ddddffff
	2001:db8:1234:ff00::/56	pcx-ddddffff
	10.4.0.0/16	pcx-ddddgggg
	2001:db8:1234:7700::/56	pcx-ddddgggg
VPC E	10.3.0.0/16	Local
	2001:db8:1234:ee00::/56	Local
	172.16.0.0/16	pcx-aaaaeeee
	2001:db8:1234:aa00::/56	pcx-aaaaeeee
	10.0.0.0/16	pcx-bbbbeeee
	2001:db8:1234:bb00::/56	pcx-bbbbeeee
	192.168.0.0/16	pcx-ccceeee
	2001:db8:1234:cc00::/56	pcx-ccceeee
	10.2.0.0/16	pcx-ddddeeee
	2001:db8:1234:dd00::/56	pcx-ddddeeee
	172.17.0.0/16	pcx-eeeeffff
	2001:db8:1234:ff00::/56	pcx-eeeeffff
	10.4.0.0/16	pcx-eeeegggg
	2001:db8:1234:7700::/56	pcx-eeeegggg
VPC F	172.17.0.0/16	Local

Route Table	Destination	Target
	2001:db8:1234:ff00::/56	Local
	172.16.0.0/16	pcx-aaaaffff
	2001:db8:1234:aa00::/56	pcx-aaaaffff
	10.0.0.0/16	pcx-bbbbffff
	2001:db8:1234:bb00::/56	pcx-bbbbffff
	192.168.0.0/16	pcx-cccffff
	2001:db8:1234:cc00::/56	pcx-cccffff
	10.2.0.0/16	pcx-ddddffff
	2001:db8:1234:dd00::/56	pcx-ddddffff
	10.3.0.0/16	pcx-eeeeffff
	2001:db8:1234:ee00::/56	pcx-eeeeffff
	10.4.0.0/16	pcx-ffffgggg
	2001:db8:1234:7700::/56	pcx-ffffgggg
VPC G	10.4.0.0/16	Local
	2001:db8:1234:7700::/56	Local
	172.16.0.0/16	pcx-aaaagggg
	2001:db8:1234:aa00::/56	pcx-aaaagggg
	10.0.0.0/16	pcx-bbbbgggg
	2001:db8:1234:bb00::/56	pcx-bbbbgggg
	192.168.0.0/16	pcx-cccgggg
	2001:db8:1234:cc00::/56	pcx-cccgggg
	10.2.0.0/16	pcx-ddddgggg
	2001:db8:1234:dd00::/56	pcx-ddddgggg
	10.3.0.0/16	pcx-eeeegggg
	2001:db8:1234:ee00::/56	pcx-eeeegggg
	172.17.0.0/16	pcx-ffffgggg
	2001:db8:1234:ff00::/56	pcx-ffffgggg

Configurations with Specific Routes

This section demonstrates the configurations for VPC peering connections in which you provide access to part of the CIDR block or a specific instance within the peer VPC. In these examples, a central VPC is peered to two or more VPCs that have overlapping CIDR blocks. For examples of scenarios in which you


might need a specific VPC peering connection configuration, see VPC Peering Scenarios (p. 15). For more information about creating and working with VPC peering connections in the Amazon VPC console, see Working with VPC Peering Connections (p. 5). For more information about updating your route tables, see Updating Your Route Tables for a VPC Peering Connection (p. 8).

Topics

- Two VPCs Peered to Two Subnets in One VPC (p. 36)
- One VPC Peered to Specific Subnets in Two VPCs (p. 39)
- Instances in One VPC Peered to Instances in Two VPCs (p. 43)
- One VPC Peered with Two VPCs Using Longest Prefix Match (p. 45)
- Multiple VPC Configurations (p. 46)

Two VPCs Peered to Two Subnets in One VPC

You have a central VPC (VPC A), and you have a VPC peering connection between VPC A and VPC B (pcx-aaaabbbb), and between VPC A and VPC C (pcx-aaaacccc). VPC A has two subnets: one for each VPC peering connection.



You may want to use this kind of configuration when you have a central VPC with separate sets of resources in different subnets. Other VPCs may require access to some of the resources, but not all of them.


The route table for subnet X points to VPC peering connection pcx-aaaabbbb to access the entire CIDR block of VPC B. VPC B's route table points to pcx-aaaabbbb to access the CIDR block of only subnet X in VPC A. Similarly, the route table for subnet Y points to VPC peering connection pcx-aaaacccc to access

the entire CIDR block of VPC C. VPC C's route table points to pcx-aaaacccc to access the CIDR block of only subnet Y in VPC A.

Route Table	Destination	Target
Subnet X in VPC A	172.16.0.0/16	Local
	10.0.0.0/16	pcx-aaaabbbb
Subnet Y in VPC A	172.16.0.0/16	Local
	10.0.0.0/16	рсх-аааасссс
VPC B	10.0.0.0/16	Local
	172.16.0.0/24	pcx-aaaabbbb
VPC C	10.0.0.0/16	Local
	172.16.1.0/24	рсх-аааасссс

Two VPCs Peered to Two Subnets in One VPC for IPv6

You have the same VPC peering configuration as above. VPC A and VPC B are enabled for IPv6—both VPCs have associated IPv6 CIDR blocks, and subnet X in VPC A has an associated IPv6 CIDR block.




You can enable VPC B to communicate with subnet X in VPC A over IPv6 using the VPC peering connection. To do this, add a route to the route table for VPC A with a destination of the IPv6 CIDR block for VPC B, and a route to the route table for VPC B with a destination of the IPv6 CIDR of subnet X in VPC A.

Route Table	Destination	Target	Notes
Subnet X in VPC A	172.16.0.0/16	Local	
	2001:db8:abcd:aa00::/56	Local	Local route that's automatically added for IPv6 communication within the VPC.
	10.0.0.0/16	pcx-aaaabbbb	
	2001:db8:1234:bb00::/56	pcx-aaaabbbb	Route to the IPv6 CIDR block of VPC B.
Subnet Y in VPC A	172.16.0.0/16	Local	
	2001:db8:abcd:aa00::/56	Local	Local route that's automatically added for

Route Table	Destination	Target	Notes
			IPv6 communication within the VPC.
	10.0.0.0/16	рсх-аааасссс	
VPC B	10.0.0.0/16	Local	
	2001:db8:1234:bb00::/56	Local	Local route that's automatically added for IPv6 communication within the VPC.
	172.16.0.0/24	pcx-aaaabbbb	
	2001:db8:abcd:aa00::/64	pcx-aaaabbbb	Route to the IPv6 CIDR block of VPC A.
VPC C	10.0.0.0/16	Local	
	172.16.1.0/24	рсх-аааасссс	

One VPC Peered to Specific Subnets in Two VPCs

You have a central VPC (VPC A) with one subnet, and you have a VPC peering connection between VPC A and VPC B (pcx-aaaabbbb), and between VPC A and VPC C (pcx-aaaacccc). VPC B and VPC C each have two subnets, and only one in each is used for the peering connection with VPC A.



You may want to use this kind of configuration when you have a central VPC that has a single set of resources, such as Active Directory services, that other VPCs need to access. The central VPC does not require full access to the VPCs that it's peered with.

The route table for VPC A points to both VPC peering connections to access only specific subnets in VPC B and VPC C. The route tables for the subnets in VPC B and VPC C point to their VPC peering connections to access the VPC A subnet.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.0/24	pcx-aaaabbbb
	10.0.1.0/24	рсх-аааасссс
Subnet A in VPC B	10.0.0.0/16	Local
	172.16.0.0/24	pcx-aaaabbbb

Amazon Virtual Private Cloud VPC Peering Guide One VPC Peered to Specific Subnets in Two VPCs


Route Table	Destination	Target
Subnet B in VPC C	10.0.0.0/16	Local
	172.16.0.0/24	рсх-аааасссс

Routing for Response Traffic

If you have a VPC peered with multiple VPCs that have overlapping or matching CIDR blocks, ensure that your route tables are configured to avoid sending response traffic from your VPC to the incorrect VPC. AWS currently does not support unicast reverse path forwarding in VPC peering connections that checks the source IP of packets and routes reply packets back to the source.

For example, VPC A is peered with VPC B and VPC C. VPC B and VPC C have matching CIDR blocks, and their subnets have matching CIDR blocks. The route table for subnet B in VPC B points to the VPC peering connection pcx-aaaabbbb to access the VPC A subnet. The VPC A route table is configured to send 10.0.0.0/16 traffic to peering connection pcx-aaaaccccc.

Route Table	Destination	Target
Subnet B in VPC B	10.0.0.0/16	Local
	172.16.0.0/24	pcx-aaaabbbb
VPC A	172.16.0.0/24	Local
	10.0.0.0/16	рсх-аааасссс



An instance in subnet B in VPC B with a private IP address of 10.0.1.66/32 sends traffic to the Active Directory server in VPC A using VPC peering connection pcx-aaaabbbb. VPC A sends the response traffic to 10.0.1.66/32. However, the VPC A route table is configured to send all traffic within the 10.0.0.0/16 range of IP addresses to VPC peering connection pcx-aaaacccc. If subnet B in VPC C has an instance with an IP address of 10.0.1.66/32, it receives the response traffic from VPC A. The instance in subnet B in VPC B does not receive a response to its request to VPC A.

To prevent this, you can add a specific route to VPC A's route table with a destination of 10.0.1.0/24 and a target of pcx-aaaabbbb. The route for 10.0.1.0/24 traffic is more specific, therefore traffic destined for the 10.0.1.0/24 IP address range goes via VPC peering connection pcx-aaaabbbb

Alternatively, in the following example, VPC A's route table has a route for each subnet for each VPC peering connection. VPC A can communicate with subnet B in VPC B and with subnet A in VPC C. This scenario is useful if you need to add another VPC peering connection with another subnet that falls within the 10.0.0.0/16 IP address range —you can simply add another route for that specific subnet.

Amazon Virtual Private Cloud VPC Peering Guide Instances in One VPC Peered to Instances in Two VPCs


Destination	Target
172.16.0.0/16	Local
10.0.1.0/24	pcx-aaaabbbb
10.0.0.0/24	рсх-аааасссс

Alternatively, depending on your use case, you can create a route to a specific IP address in VPC B to ensure that traffic routed back to the correct server (the route table uses longest prefix match to prioritize the routes):

Destination	Target
172.16.0.0/16	Local
10.0.1.66/32	pcx-aaaabbbb
10.0.0.0/16	рсх-аааасссс

Instances in One VPC Peered to Instances in Two VPCs

You have a central VPC (VPC A) with one subnet, and you have a VPC peering connection between VPC A and VPC B (pcx-aaaabbbb), and between VPC A and VPC C (pcx-aaaacccc). VPC A has one subnet that has multiple instances; one for each of the VPCs that it's peered with. You may want to use this kind of configuration to limit peering traffic to specific instances.




Each VPC route table points to the relevant VPC peering connection to access a single IP address (and therefore a specific instance) in the peer VPC.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.44/32	pcx-aaaabbbb
	10.0.0.55/32	рсх-аааасссс
VPC B	10.0.0.0/16	Local
	172.16.0.88/32	pcx-aaaabbbb
VPC C	10.0.0.0/16	Local
	172.16.0.99/32	рсх-аааасссс

One VPC Peered with Two VPCs Using Longest Prefix Match

You have a central VPC (VPC A) with one subnet, and you have a VPC peering connection between VPC A and VPC B (pcx-aaaabbbb), and between VPC A and VPC C (pcx-aaaacccc). VPC B and VPC C have matching CIDR blocks. You want to use VPC peering connection pcx-aaaabbbb to route traffic between VPC A and specific instance in VPC B. All other traffic destined for the 10.0.0.0/16 IP address range is routed through pcx-aaaacccc between VPC A and VPC C.



VPC route tables use longest prefix match to select the most specific route across the intended VPC peering connection. All other traffic is routed through the next matching route, in this case, across the VPC peering connection pex-aaaacccc.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.77/32	pcx-aaaabbbb

Amazon Virtual Private Cloud VPC Peering Guide Multiple VPC Configurations

Route Table	Destination	Target
	10.0.0.0/16	рсх-аааасссс
VPC B	10.0.0.0/16	Local
	172.16.0.0/16	pcx-aaaabbbb
VPC C	10.0.0.0/16	Local
	172.16.0.0/16	рсх-аааасссс

Important


If an instance other than 10.0.0.77/32 in VPC B sends traffic to VPC A, the response traffic may be routed to VPC C instead of VPC B. For more information, see Routing for Response Traffic (p. 41).

Multiple VPC Configurations

In this example, a central VPC (VPC A) is peered with multiple VPCs in a spoke configuration. For more information about this type of configuration, see One VPC Peered with Multiple VPCs (p. 23). You also have three VPCs (VPCs M, N, and P) peered together in a full mesh configuration. For more information about this type of configuration, see Three VPCs Peered Together (p. 21).

VPC C also has a VPC peering connection with VPC M (pcx-cccmmm). VPC A and VPC M have overlapping CIDR blocks. This means that peering traffic between VPC A and VPC C is limited to a specific subnet (subnet A) in VPC C. This is to ensure that if VPC C receives a request from VPC A or VPC M, it sends the response traffic to the correct VPC. AWS currently does not support unicast reverse path forwarding in VPC peering connections that checks the source IP of packets and routes reply packets back to the source. For more information, see Routing for Response Traffic (p. 41).

Similarly, VPC C and VPC P have overlapping CIDR blocks. Peering traffic between VPC M and VPC C is limited to subnet B in VPC C, and peering traffic between VPC M and VPC P is limited to subnet A in VPC P. This is to ensure that if VPC M receives peering traffic from VPC C or VPC P, it sends the response traffic back to the correct VPC.



The route tables for VPCs B, D, E, F, and G point to the relevant peering connections to access the full CIDR block for VPC A, and the VPC A route table points to the relevant peering connections for VPCs B, D, E, F, and G to access their full CIDR blocks. For peering connection pcx-aaaacccc, the VPC A route table routes traffic only to subnet A in VPC C (192.168.0.0/24) and the subnet A route table in VPC C points to the full CIDR block of VPC A.

The VPC N route table points to the relevant peering connections to access the full CIDR blocks of VPC M and VPC P, and the VPC P route table points to the relevant peering connection to access the full CIDR block of VPC N. The subnet A route table in VPC P points to the relevant peering connection to access the full CIDR block of VPC M. The VPC M route table points to the relevant peering connection to access subnet B in VPC C, and subnet A in VPC P.

Route Table	Destination	Target
VPC A	172.16.0.0/16	Local
	10.0.0.0/16	pcx-aaaabbbb
	192.168.0.0/24	рсх-аааасссс
	10.2.0.0/16	pcx-aaaadddd
	10.3.0.0/16	pcx-aaaaeeee
	172.17.0.0/16	pcx-aaaaffff

Route Table	Destination	Target	
	10.4.0.0/16	pcx-aaaagggg	
VPC B	10.0.0.0/16	Local	
	172.16.0.0/16	pcx-aaaabbbb	
Subnet Ain VPC C	192.168.0.0/16	Local	
	172.16.0.0/16	рсх-аааасссс	
Subnet B in VPC C	192.168.0.0/16	Local	
	172.16.0.0/16	pcx-cccmmmm	
VPC D	10.2.0.0/16	Local	
	172.16.0.0/16	pcx-aaaadddd	
VPC E	10.3.0.0/16	Local	
	172.16.0.0/16	pcx-aaaaeeee	
VPC F	172.17.0.0/16	Local	
	172.16.0.0/16	pcx-aaaaaffff	
VPC G	10.4.0.0/16	Local	
	172.16.0.0/16	pcx-aaaagggg	
VPC M	172.16.0.0/16	Local	
	192.168.1.0/24	pcx-cccmmmm	
	10.0.0.0/16	pcx-mmmmnnnn	
	192.168.0.0/24	pcx-mmmpppp	
VPC N	10.0.0.0/16	Local	
	172.16.0.0/16	pcx-mmmmnnnn	
	192.168.0.0/16	pcx-nnnnpppp	
VPC P	192.168.0.0/16	Local	
	10.0.0.0/16	pcx-nnnnpppp	
	172.16.0.0/16	pcx-mmmmpppp	

Configurations with ClassicLink

If you have a VPC peering connection between two VPCs, and there are one or more EC2-Classic instances that are linked to one or both of the VPCs via ClassicLink, you can extend the VPC peering connection to enable communication between the EC2-Classic instances and the instances in the VPC on the other side of the VPC peering connection. This enables the EC2-Classic instances and the instances in the VPC to communicate using private IP addresses. To do this, you enable a local VPC to communicate

Amazon Virtual Private Cloud VPC Peering Guide Configurations with ClassicLink

with a linked EC2-Classic instance in a peer VPC, or you enable a local linked EC2-Classic instance to communicate with VPC instances in a peer VPC.

Important

EC2-Classic instances cannot be enabled for IPv6 communication. You can enable VPC instances on either side of a VPC peering connection to communicate with each other over IPv6; however, an EC2-Classic instance that's ClassicLinked with a VPC can communicate with VPC instances on either side of the VPC peering connection over IPv4 only.

To enable your VPC peering connection for communication with linked EC2-Classic instances, you must modify the requester VPC peering options if you are the requester of the VPC peering connection, and you must modify the accepter VPC peering options if you are the accepter of the VPC peering connection. You can use the describe-vpc-peering-connections command to verify which VPC is the accepter and the requester for a VPC peering connection.

You can modify the VPC peering connection options as follows:

Enable a local linked EC2-Classic instance to communicate with instances in a peer VPC

In this case, you modify the VPC peering connection options to enable outbound communication from the local ClassicLink connection to the peer VPC on the other side of the VPC peering connection. The owner of the peer VPC modifies the VPC peering connection options to enable outbound communication from their local VPC to the remote ClassicLink connection.

• Enable a local VPC to communicate with a linked EC2-Classic instance in a peer VPC

In this case, you modify the VPC peering connection options to enable outbound communication from your local VPC to the remote ClassicLink connection on the other side of the VPC peering connection. The owner of the peer VPC with the linked EC2-Classic instance modifies the VPC peering connection options to enable outbound communication from their local ClassicLink connection to the remote VPC.

When you enable a local linked EC2-Classic instance to communicate with instances in a peer VPC, you must manually add a route to the main route table of your local VPC with a destination of the peer VPC CIDR block, and a target of the VPC peering connection. The linked EC2-Classic instance is not associated with any subnet in the VPC; it relies on the main route table for communication with the peer VPC.

Important

The route for the VPC peering connection must be added to the main route table, regardless of any custom route tables with existing routes to the peering connection. If not, the EC2-Classic instance cannot communicate with the peer VPC.

When you enable a local VPC for communication with a remote ClassicLink connection, a route is automatically added to all the local VPC route tables with a destination of 10.0.0.0/8 and a target of Local. This enables communication with the remote linked EC2-Classic instance. If your route table has an existing static route in the 10.0.0.0/8 IP address range (including VPC peering connection routes), you cannot enable the local VPC for communication with the remote ClassicLink connection.

Note

You can modify the VPC peering connection options in the following regions:


- US East (N. Virginia)
- US West (N. California)
- US West (Oregon)
- EU (Ireland)
- · Asia Pacific (Tokyo)
- Asia Pacific (Singapore)
- South America (São Paulo)
- Asia Pacific (Sydney)

Enabling Communication Between a ClassicLink Instance and a Peer VPC

In the following scenario, VPC A is enabled for ClassicLink, and instance A is linked to VPC A using ClassicLink. VPC B is in a different AWS account, and is peered to VPC A using VPC peering connection pcx-aaaabbbb. The VPC peering connection was requested by VPC A and accepted by VPC B. You want instance A to communicate with instances in VPC B over private IP, and you want instances in VPC B to communicate with instance A over private IP.

Note

In this scenario, VPC B can either be a VPC in an account that supports EC2-Classic, or an account that supports EC2-VPC only.



The route tables for VPC A contain routes for local VPC traffic, and routes to enable communication to the linked EC2-Classic instance. The custom route table for VPC A contains a route that enables instances in the subnet to communicate with the peer VPC over the VPC peering connection, and a route to route all Internet traffic to the Internet gateway. The custom route table for VPC B contains a route to enable instances in the subnet to communicate with the peer VPC over the VPC peering connection.

Route Table	Destination	Target	Notes
VPC A custom	172.31.0.0/16	Local	Default local route for VPC A.
	192.168.0.0/16	pcx-aaaabbbb	Route manually added for the peering connection between VPC A and VPC B.
	10.0.0.0/8	Local	Route automatically added to enable ClassicLink communication (added

Amazon Virtual Private Cloud VPC Peering Guide Enabling Communication Between a ClassicLink Instance and a Peer VPC

Route Table	Destination	Target	Notes
			when you linked the instance to VPC A).
	0.0.0.0/0	igw-11aa22bb	Route manually added to route Internet traffic to the Internet gateway.
VPC A main	172.31.0.0/16	Local	Default local route for VPC A.
	10.0.0.0/8	Local	Route automatically added to enable ClassicLink communication (added when you linked the instance to VPC A).
VPC B custom	192.168.0.0/16	Local	Default local route for VPC B.
	172.31.0.0/16	pcx-aaaabbbb	Route manually added for the peering connection between VPC A and VPC B.

The owner of VPC A must modify the VPC peering connection to enable instance A to communicate with VPC B, and update the main route table. The owner of VPC B must modify the VPC peering connection to enable VPC B to communicate with instance A.

Topics

- Modifying the VPC Peering Connection for VPC A (p. 51)
- Modifying the VPC Peering Connection for VPC B (p. 52)
- Viewing VPC Peering Connection Options (p. 53)

Modifying the VPC Peering Connection for VPC A

To enable communication from the EC2-Classic instance to VPC B, the AWS account owner of VPC A must modify the VPC peering connection options to enable the local ClassicLink connection to send traffic to instances in the peer VPC. You can modify the VPC peering connection using the Amazon VPC console or the AWS CLI.

To modify the VPC peering connection using the console

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
 - The owner of VPC A must sign in to the console.
- 2. In the navigation pane, choose **Peering Connections**.
- 3. Select the VPC peering connection, and choose Actions, Edit ClassicLink Settings.
- Choose the option to allow local linked EC2-Classic instances to communicate with the peer VPC, and choose Save.

To modify the VPC peering connection using the AWS CLI

Amazon Virtual Private Cloud VPC Peering Guide Enabling Communication Between a ClassicLink Instance and a Peer VPC

You can use the modify-vpc-peering-connection-options command. In this case, VPC A was the requester of the VPC peering connection; therefore, modify the requester options as follows:

aws ec2 modify-vpc-peering-connection-options --vpc-peering-connection-id pcx-aaaabbbb --requester-peering-connection-options AllowEgressFromLocalClassicLinkToRemoteVpc=true

To update the main route table

There are no changes to the route tables for VPC B or to the custom route table for VPC A. The owner of VPC A must manually add a route to the main route table that enables the linked EC2-Classic instance to communicate over the VPC peering connection.

Destination	Target
172.31.0.0/16	Local
10.0.0.0/8	Local
192.168.0.0/16	pcx-aaaabbbb

For more information about adding routes, see Adding and Removing Routes from a Route Table in the *Amazon VPC User Guide*.

Modifying the VPC Peering Connection for VPC B

Next, the AWS account owner of VPC B must modify the VPC peering connection options to enable VPC B to send traffic to EC2-Classic instance A.

To modify the VPC peering connection using the console

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
 - The owner of VPC B must sign in to the console.
- In the navigation pane, choose Peering Connections.
- 3. Select the VPC peering connection, and choose Actions, Edit ClassicLink Settings.
- 4. Choose the option to allow local VPC instances to communicate with EC2-Classic instances in the peer VPC, and choose **Save**.

To modify the VPC peering connection using the AWS CLI

VPC B accepted the VPC peering connection; therefore, modify the accepter options as follows:

aws ec2 modify-vpc-peering-connection-options --vpc-peering-connection-id pcx-aaaabbbb -- accepter-peering-connection-options AllowEgressFromLocalVpcToRemoteClassicLink=true

There are no changes to the route tables for VPC A. A new route is automatically added to the route table for VPC B that allows instances in VPC B to communicate with the linked EC2-Classic instance in VPC A.

Route Table	Destination	Target	Notes
VPC A custom	172.31.0.0/16	Local	Default local route for VPC A.
	192.168.0.0/16	pcx-aaaabbbb	Route manually added for the peering connection between VPC A and VPC B.

Amazon Virtual Private Cloud VPC Peering Guide Enabling Communication Between a ClassicLink Instance and a Peer VPC

Route Table	Destination	Target	Notes
	10.0.0.0/8	Local	Route automatically added to enable ClassicLink communication (added when you linked the instance to VPC A).
	0.0.0.0/0	igw-11aa22bb	Route manually added to route Internet traffic to the Internet gateway.
VPC A main	172.31.0.0/16	Local	Default local route for VPC A.
	10.0.0.0/8	Local	Route automatically added to enable ClassicLink communication (added when you linked the instance to VPC A).
	192.168.0.0/16	pcx-aaaabbbb	Route manually added to enable the linked EC2-Classic instance to communicate with VPC B over the VPC peering connection.
VPC B custom	192.168.0.0/16	Local	Default local route for VPC B.
	172.31.0.0/16	pcx-aaaabbbb	Route manually added for the peering connection between VPC A and VPC B.
	10.0.0.0/8	Local	Route automatically added to enable ClassicLink communication with the linked instance in VPC A.

Viewing VPC Peering Connection Options

You can view the VPC peering connection options for the accepter VPC and requester VPC using the Amazon VPC console or the AWS CLI.

To view VPC peering connection options using the console

- 1. Open the Amazon VPC console at https://console.aws.amazon.com/vpc/.
- 2. In the navigation pane, choose **Peering Connections**.
- 3. Select the VPC peering connection, and choose **ClassicLink**. Information about the enabled or disabled VPC peering connection options is displayed.

To view VPC peering connection options using the AWS CLI

You can use the describe-vpc-peering-connections command:

aws ec2 describe-vpc-peering-connections --vpc-peering-connection-id pcx-aaaabbbb

```
"VpcPeeringConnections": [
    {
        "Status": {
            "Message": "Active",
            "Code": "active"
        },
        "Tags": [
            {
                "Value": "MyPeeringConnection",
                "Key": "Name"
        1,
        "AccepterVpcInfo": {
            "PeeringOptions": {
                "AllowEgressFromLocalVpcToRemoteClassicLink": true,
                "AllowEgressFromLocalClassicLinkToRemoteVpc": false,
                "AllowDnsResolutionFromRemoteVpc": false
            "OwnerId": "123456789101",
            "VpcId": "vpc-80cb52e4",
            "CidrBlock": "172.31.0.0/16"
        "VpcPeeringConnectionId": "pcx-aaaabbbb",
        "RequesterVpcInfo": {
            "PeeringOptions": {
                "AllowEgressFromLocalVpcToRemoteClassicLink": false,
                "AllowEgressFromLocalClassicLinkToRemoteVpc": true,
                "AllowDnsResolutionFromRemoteVpc": false
            "OwnerId": "111222333444",
            "VpcId": "vpc-f527be91",
            "CidrBlock": "192.168.0.0/16"
    }
]
```

Invalid VPC Peering Connection Configurations

This section describes VPC peering connection configurations that are invalid.

For more information about VPC peering limitations, see VPC Peering Limitations (p. 4).

Topics


- Overlapping CIDR blocks (p. 55)
- Transitive Peering (p. 56)
- Edge to Edge Routing Through a Gateway or Private Connection (p. 56)

Overlapping CIDR blocks

You cannot create a VPC peering connection between VPCs with matching or overlapping IPv4 CIDR blocks.




This limitation also applies to VPCs that have non-overlapping IPv6 CIDR blocks. Even if you intend to use the VPC peering connection for IPv6 communication only, you cannot create a VPC peering connection if the VPCs have matching or overlapping IPv4 CIDR blocks.



Transitive Peering

You have a VPC peering connection between VPC A and VPC B (pcx-aaaabbbb), and between VPC A and VPC C (pcx-aaaacccc). There is no VPC peering connection between VPC B and VPC C. You cannot route packets directly from VPC B to VPC C through VPC A.



To route packets directly between VPC B and VPC C, you can create a separate VPC peering connection between them (provided they do not have overlapping CIDR blocks). For more information, see Three VPCs Peered Together (p. 21).

Edge to Edge Routing Through a Gateway or Private Connection


If either VPC in a peering relationship has one of the following connections, you cannot extend the peering relationship to that connection:

- A VPN connection or an AWS Direct Connect connection to a corporate network
- An Internet connection through an Internet gateway
- An Internet connection in a private subnet through a NAT device
- A VPC endpoint to an AWS service; for example, an endpoint to Amazon S3.
- (IPv6) A ClassicLink connection. You can enable IPv4 communication between a linked EC2-Classic instance and instances in a VPC on the other side of a VPC peering connection; however, IPv6 is not supported in EC2-Classic, so you cannot extend this connection for IPv6 communication.

For example, if VPC A and VPC B are peered, and VPC A has any of these connections, then instances in VPC B cannot use the connection to access resources on the other side of the connection. Similarly, resources on the other side of a connection cannot use the connection to access VPC B.


Example: Edge to Edge Routing Through a VPN Connection or an AWS Direct Connect Connection

You have a VPC peering connection between VPC A and VPC B (pcx-aaaabbbb). VPC A also has a VPN connection or an AWS Direct Connect connection to a corporate network. Edge to edge routing is not supported; you cannot use VPC A to extend the peering relationship to exist between VPC B and the corporate network. For example, traffic from the corporate network can't directly access VPC B by using the VPN connection or the AWS Direct Connect connection to VPC A.



Example: Edge to Edge Routing Through an Internet Gateway

You have a VPC peering connection between VPC A and VPC B (pcx-abababab). VPC A has an Internet gateway; VPC B does not. Edge to edge routing is not supported; you cannot use VPC A to extend the peering relationship to exist between VPC B and the Internet. For example, traffic from the Internet can't directly access VPC B by using the Internet gateway connection to VPC A.



Similarly, if VPC A has a NAT device that provides Internet access to instances in private subnets in VPC A, instances in VPC B cannot use the NAT device to access the Internet.