## CHAPTERS 31 AND 32 NOTES

## ANISH SUNDARAM

### Contents

| 31 Alternating Current                             | 1  |
|--|----|
| 31.1 Phasors and Alternating Currents              | 2  |
| 31.1.1 Phasor Diagrams                             | 2  |
| 31.1.2 Recitified Alternating Current              | 3  |
| 31.1.3 Root-Mean-Square(rms) Values                | 3  |
| 31.2 Resistance and Reactance                      | 4  |
| 31.3 The L-R-C Series Circuit                      | 5  |
| 31.4 Power in AC Circuits                          | 5  |
| 31.5 Resonance in AC Circuits                      | 6  |
| 31.6 Tranformers                                   | 6  |
| 32 Electromagnetic Waves                           | 7  |
| 32.1 Maxwell's Equations and Electromagnetic Waves | 7  |
| 32.2 Plane EM Waves and the Speed of Light         | 8  |
| 32.3 Sinusoidal EM Waves                           | 10 |
| 32.3.1 EM waves in Matter                          | 11 |
| 32.4 Energy and Momentum in EM Waves               | 11 |
| 32.4.1 The Poynting Vector, Power, and Intensity   | 12 |
| 32.4.2 EM Momentum Flow and Radiation Pressure     | 12 |
| 32.5 Standing EM Waves                             | 13 |

# 31 Alternating Current

In this chapter we will learn how resistors, inductors, and capacitors behave in circuits with sinusoidally varying voltages and currents. Many of the principles that we found useful in Chapter 30 are applicable, along with several new con- cepts related to the circuit behavior of inductors and capacitors. A key concept in this discussion is *resonance*, which we studied in Chapter 14 for mechanical systems.

Date: July 20, 2021.

## 31.1 Phasors and Alternating Currents.

**Definition 1. Alternating Current**: an electric current that reverses its direction many times a second at regular intervals, typically used in power supplies. Alternating current has a peak voltage and current, as well as an average. Alternating current is provided by an **AC Source** 

**Definition 2. Voltage Amplitude**: Because Voltage alternated due to fluctuation in AC current it has a sinusoidally shape, being described by the equation

$$u = V cos(\omega t)$$

where u is the instantaneous potential difference and V is the maximum or peak voltage, sometimes designated as  $V_0$ 

**Remark.** In the US and Canada the common frequency for distribution systems is f = 60Hz or 377 rad/s, while the rest of the world uses f = 50 Hz ( $\omega = 314$  rad/s)

**Definition 3.** Angular Frequency  $(\omega)$ : Angular Frequency is a scalar measure of rotation rate. It refers to the rate of change of the argument of the sine function Angular Frequency can be found by the equation

$$\omega = 2\pi f$$

where f is the frequency measured in Hz.

**Definition 4. Current Amplitude**: Much like Voltage the Current outputted by an AC battery varies with time and fluctuates in a sinusoidal fashion which can be described by the equation

$$i = Icos(\omega t)$$

where i is instantaneous current and I is peak current, sometimes designated as  $I_0$ 

### 31.1.1 Phasor Diagrams.

**Definition 5. Phasors and Phasor Diagrams**: To represent sinusoidally varying voltages and currents, we use rotating vector diagrams wherein the instantaneous value is represented by the projection onto a horizontal axis of a vector with a length equal to the amplitude of the quantity which rotates CCW with angular speed  $\omega$ . These rotating vectors are called **Phasors**.

# **31.2** A phasor diagram.




FIGURE 1. Phase Diagram

## 31.1.2 Recitified Alternating Current.

**Definition 6. Rectified Average Current**( $I_{rav}$ ): Because it is dificult to measure alternating current in a Galvanometer we can use Recitified Average Current instead to measure. It can be computed by averaging the absolute value of a waveform over one full period of the waveform. or put into an equation as

$$I_{rav} = \frac{2}{\pi}I = .637I$$

where I is the current amplitude.

31.1.3 Root-Mean-Square(rms) Values.

**Definition 7. RMS Current and Voltage**: Another more useful way to describe the current and voltage(which can be both positive or negative) is the root-mean-square value, of which is never 0 unless i/u is zero at every instant. RMS Current can be defined as

$$I_{rms} = \frac{I}{\sqrt{2}}$$

and RMS Voltage can be defined as

$$V_{rms} = \frac{V}{\sqrt{2}}$$

In other words dividing the peak value by  $\sqrt{2}$ .

#### 31.2 Resistance and Reactance.

**Definition 8. Inductive Reactance** ( $X_L$ ): Inductive reactance is the name given to the opposition to a changing current flow by an inductor, it is measured in Ohms like resistance. Inductive Reactance is calculated by the equation

$$X_L = 2\pi f L = \omega L$$

where L is the inductance. The amplitude of voltage across an inductor for AC Current can be found by

$$V_L = IX_L$$

**Remark.** The peaks of Inductor voltage and current are out of phase by a quarter-cycle. Since the voltage peaks occur a quarter-cycle earlier than the current peaks, we say that the voltage leads the current by  $90^{\circ}$ 

**Definition 9. Capacitive Reactance** ( $X_L$ ): Capacitive reactance is the name given to the opposition to a changing current flow by an Capacitor, it is measured in Ohms like resistance. Capacitive Reactance is calculated by the equation

$$X_C = \frac{1}{2\pi f L} = \frac{1}{\omega C}$$

where C is the Capacitance. The amplitude of voltage across an Capacitor for AC Current can be found by

$$V_L = IX_C$$

**Remark.** The peaks of Capacitor voltage and current are out of phase by a quarter-cycle. Since the voltage peaks occur a quarter-cycle before than the current peaks, we say that the voltage trails the current by 90°

**Remark.** Greater reactance leads to smaller currents for the same voltage applied.

**Definition 10. Phase Angle** ( $\phi$ ): The Phase Angle represents the fraction of the period that y lags or leads the function. In our case it is the phase of the voltage relative to current.

- (1) For a pure Resistor  $\phi = 0$
- (2) For a pure Inductor  $\phi = 90$
- (3) For a pure Capacitor  $\phi = -90$

**Remark.** If the Circuit is more Capacitive then Inductive the Phase angle will be negative, opposite holds true as well.

#### 31.3 The L-R-C Series Circuit.

**Definition 11. Impedance**(Z): The Impedance of an AC circuit is the effective resistance of an electric circuit or component to alternating current, arising from the combined effects of ohmic resistance and reactance. The general equation for Impedence is

$$Z = \sqrt{R^2 + (X_l - X_c)^2}$$

where R is Resistance,  $X_L$  is Inductive Reactance and  $X_C$  is Capacitive Reactance. This can be used to find the total Current through an L-R-C or any derivative circuit through the equation

$$V = IZ$$

**Remark.** To Find the Phase Angle of an L-R-C series Circuit the equation following can be used:

$$tan\phi = \frac{X_L - X_c}{R}$$

| TABLE 31.1 Circuit Elements with Alternating Current |                        |                    |                 |  |
|--|------------------------|--------------------|-----------------|--|
| Circuit Element                                      | Amplitude Relationship | Circuit Quantity   | Phase of v      |  |
| Resistor   | $V_R = IR$             | R                  | In phase with i |  |
| Inductor   | $V_L = IX_L$           | $X_L = \omega L$   | Leads i by 90°  |  |
| Capacitor  | $V_C = IX_C$           | $X_C = 1/\omega C$ | Lags $i$ by 90° |  |

FIGURE 2. Phase rules of Circuit Elements

#### 31.4 Power in AC Circuits.

**Remark.** There is no power dissipated by a Capacitor or an Inductor as both absorb and release charge similar to a battery, and thus no power dissipates unlike a resistor.

**Definition 12. Average Power into a AC Circuit**: The average power into a general AC circuit can be calculated using the following equations:

$$P_{aV} = .5VIcos\phi = V_{rms}I_{rms}cos\phi$$

**Definition 13. Power Factor**: The ratio of the actual electrical power dissipated by an AC circuit to the product of the r.m.s. values of current and voltage. The factor  $\cos \phi$  is called the power factor.

#### 6

### 31.5 Resonance in AC Circuits.

**Definition 14. Resonance**: The peaking of the current amplitude. The angular frequency  $\omega_0$  at which the resonance peak occurs is called the **resonance angular frequency**. The Resonance Angular Frequency can be found by the equation

$$\omega_0 = \frac{1}{\sqrt{LC}}$$

**Definition 15. Resonance Frequency**  $(f_0)$ : is when  $X_L$  is equal to  $X_C$ . Resonance Frequency is found by the equation

$$f_0 = \frac{\omega_0}{2\pi} = \frac{1}{2\pi\sqrt{LC}}$$

**Remark.** When a circuit is at resonance frequency the inductive reactance and capacitive reactace are the same and thus negate eachother, so the only impedence comes from the resistor and the reactance is null.

#### 31.6 Tranformers.

**Definition 16. Transformers:** A transformer is used to transform the voltage and current levels in an ac circuit. In an ideal transformer with no energy losses, if the primary winding has N1 turns and the secondary winding has N2 turns, the amplitudes (or rms values) of the two voltages are related. The relations used by transformers are:

$$\frac{V_2}{V_1} = \frac{N_2}{N_1}$$

and

$$V_1I_1 = V_2I_2$$

and

$$\frac{N_1}{N_2} = \frac{I_2}{I_1}$$

For all of which 1 is the primary and 2 is the secondary.

**Remark.** The Efficiency of a Transformer can be found by the following:

$$\frac{P_1}{P_2} * 100$$

where  $P_1$  is initial power for the primary coil and  $P_2$  is the power of the secondary coil.

#### 32 Electromagnetic Waves

Maxwell's equations show that a time-varying magnetic field acts as a source of electric field and that a time-varying electric field acts as a source of magnetic field. These  $\vec{E}$  and  $\vec{B}$  fields can sustain each other, forming an *electromagnetic wave* that propagates through space. Visible light is one example of an electromagnetic wave; other kinds are produced by wi-fi base stations, x-ray machines, and radioactive nuclei.

## 32.1 Maxwell's Equations and Electromagnetic Waves.

Definition 17. Electromagnetic Wave/ Electromagnetic Radiation: When either an electric or a magnetic field is changing with time, a field of the other kind is induced in adjacent regions of space as shown by Ampere's Law. This disturbance of time-varying electric and magnetic fields that can propagate through space from one region to another have the properties of a wave, an EM wave.

**Remark.** An EM wave can travel even when there is no matter in the intervening region.

**Definition 18. Maxwell's Equations**: The Complete versions of previous equations

(1) Gauss's Law for  $\vec{E}$ :

$$\oint \vec{E} \cdot d\vec{A} = \frac{Q_{encl}}{\epsilon_0}$$

(2) Gauss's Law for  $\vec{B}$ :

$$\oint \vec{B} \cdot d\vec{A} = 0$$

(3) Farada's Law for stationary integration path:

$$\oint \vec{E} \cdot d\vec{l} = -\frac{d\Phi_B}{dt}$$

(4) Ampere's law for a stationary integration path:

$$\oint \vec{B} \cdot d\vec{l} = \mu_0 (i_c + \epsilon_0 \frac{d\Phi_E}{dt}) encl$$

where  $i_c$  is the conduction current through the path.

**Definition 19. EM Spectrum**: The length of EM waves of all frequencies and wavelengths, ranging from Radio and Tv waves on the high end of wavelength to Gamma rays on the low end.

**Remark.** Recall that the equation relating Wavelength, Frequency, and velocity is

$$v = f\lambda$$

where in a vacuum all waves have the same propagation speed

$$c = 299,792,458m/s = 3 * 10^8 m/s$$

so we get

$$c = \lambda f$$

**32.4** The electromagnetic spectrum. The frequencies and wavelengths found in nature extend over such a wide range that we have to use a logarithmic scale to show all important bands. The boundaries between bands are somewhat arbitrary.




FIGURE 3. Diagram of EM Spectrum

**Remark.** Energy of a Photon can be found by the equation

$$E = hF$$

where h is Plank's constant  $h = 6.626 * 10^{-34} js$ 

## 32.2 Plane EM Waves and the Speed of Light.

**Definition 20. Plane Wave**: A physical quantity whose fields are constant over any plane that is perpendicular to the direction of propagation. The relation between the speed of such a wave and the resulting  $\vec{B}$  and  $\vec{E}$  fields can be found by the equation

$$E = cB$$

where c is the speed of light in vacuum mentioned above. However, this relation only holds if E and B are related in some manner, additional methods to calculated  $\vec{B}$  and c are as follows:

$$B - \epsilon_0 \mu_0 cE$$

and

$$c = \frac{1}{\sqrt{\epsilon_0 \mu_0}}$$

of which  $\epsilon_0$  and  $\mu_0$  are the electric and magnetic constants respectively.

**Remark.** To satisfy Maxwell's equations any wave discussed must be a **Transverse wave**, which is a wave whose oscillations are perpendicular to the direction of the wave's advance. This is in contrast to a **longitudinal wave** which travels in the direction of its oscillations.

**32.13** Representation of the electric and magnetic fields as functions of x for a linearly polarized sinusoidal plane electromagnetic wave. One wavelength of the wave is shown at time t = 0. The fields are shown for only a few points along the x-axis.




FIGURE 4. Depiction of EM Wave

# Definition 21. Key Properties of EM Waves:

- (1) The wave is transverse; The direction of propagation is the direction of the vector product  $\vec{E} \times \vec{B}$
- (2) There is a definite ratio between the magnitudes of  $\vec{E}$  and  $\vec{B}$ : E = cB.
- (3) The wave travels in vacuum with a definite and uniform speed.
- (4) Electromagnetic waves require no medium.

**32.9** A right-hand rule for electromagnetic waves relates the directions of  $\vec{E}$  and  $\vec{B}$  and the direction of propagation.

### Right-hand rule for an electromagnetic wave:

- 1) Point the thumb of your right hand in the wave's direction of propagation.
- 2 Imagine rotating the  $\vec{E}$ -field vector 90° in the sense your fingers curl. That is the direction of the  $\vec{B}$  field.




FIGURE 5. RHR for EM waves

## 32.3 Sinusoidal EM Waves.

**Definition 22. Wave Functions in vacuum**: The functions to map the movement of the sinusoidal fields of EM plane waves propagating in the  $+\mathbf{x}$  direction are as follows:

$$\vec{E}(x,t) = \hat{j}E_{max}cos(kx - \omega t)$$

and

$$\vec{B}(x,t) = \hat{k}B_{max}cos(kx - \omega t)$$

where for both k is the wave number and  $\omega$  is the angular frequency.

**Remark.** Eaves propagating in the **-x** direction are as follows:

$$\vec{E}(x,t) = \hat{j}E_{max}cos(kx + \omega t)$$

and

$$\vec{B}(x,t) = -\hat{k}B_{max}cos(kx + \omega t)$$

32.3.1 EM waves in Matter.

**Definition 23. Speed of EM in Dialectric**: Although matter is not necessary for travel, it does impact speed. The new equation is as follows:

$$v = \frac{1}{\sqrt{\epsilon \mu}} = \frac{1}{\sqrt{KK_m}} \frac{1}{\sqrt{\epsilon_0 \mu_0}} = \frac{c}{\sqrt{KK_m}}$$

wherein  $\epsilon$  and  $\mu$  are the permeability and permittivity and K is the Dialectric constant and  $K_m$  is relative permeability.c is the speed of light in vacuum.

**Remark.** Because we are no longer in a vacuum  $\mu_0$  must be replaced by  $\mu = K_m \mu_0$  and thereby E = vb and  $B = \epsilon \mu v E$ 

**Definition 24. Index of Refraction**: The ratio of the speed c in a material versus speed v in vacuum:

$$\frac{c}{v} = n = \sqrt{KK_m}$$

# 32.4 Energy and Momentum in EM Waves.

**Definition 25. Energy Density and Energy Absorbed**: The energy density of an Electric field can be found by the equation

$$u_E = .5\epsilon_0 E^2$$

and the equation for the energy density of a Magnetic Field can be found by

$$u_B = \frac{B^2}{2\mu_0}$$

Thus the total energy density for a AM wave in vacuum is

$$u = 5\epsilon_0 E^2 + \frac{B^2}{2\mu_0}$$

but because  $u_E = u_B$  the equation is simplified to

$$u = \epsilon_0 E^2$$

**Remark.** The total amount of energy absorbed by a surface can be found from the equation

$$\Delta U = \epsilon_0 c E^2 A t$$

32.4.1 The Poynting Vector, Power, and Intensity.

**Definition 26. Poynting Vector**( $\vec{S}$ ): A vector quantity that describes both the magnitude and direction of the energy flow rate. Found by the equation

$$\vec{S} = \frac{1}{\mu_0} \vec{E} \times \vec{B}$$

where the magnitude

$$S = EB/\mu_0 = \frac{dU}{Adt} = \sqrt{\frac{\epsilon_0}{\mu_0}}E^2 = \epsilon_0 CE^2$$

in a vacuum where the unit is  $W/m^2$ 

**Remark.** The Average Poynting vector magnitude can be found by using:

$$\bar{S} = .5S_0 = .5\epsilon_0 C E_0^2 = .5\frac{c}{\mu_0} B_0^2 = \frac{E_0 B_0}{2\mu_0} = E_{rms} B_r ms/\mu_0$$

**Definition 27. Power**: The total energy flow per unit time (power, P) out of any closed surface is the integral of S over the surface:

$$P = \frac{\Delta U}{\Delta t} = \oint \vec{S} \cdot d\vec{A}$$

**Definition 28. Intensity**: Wave intensity is the average power that travels through a given area as the wave travels through space. The intensity of a sinusoidal EM wave in vacuum is

$$I = S_{av} = \frac{E_{max}B_{max}}{2\mu_0} = \frac{E_{max}^2}{2\mu_0c} = .5\sqrt{\frac{\epsilon_0}{\mu_0}}E_{max}^2 = .5\epsilon_0cE_{max^2}$$

where  $S_{av}$  is the magnitude of average Poynting vector. Units are  $W/m^2$ 

32.4.2 EM Momentum Flow and Radiation Pressure.

**Definition 29. Flow rate of EM Momentum**: We've shown that electromagnetic waves transport energy. It can also be shown that electromagnetic waves carry momentum p. This Momemntum can be described by

$$\frac{dp}{dV} = \frac{EB}{\mu_0 c^2} = \frac{S}{c^2}$$

This momentum has a corresponding flow rate which can be described by

$$\frac{1}{A}\frac{dp}{dt} = \frac{S}{c} = \frac{EB}{\mu_0 c}$$

where  $\frac{1}{A}\frac{dp}{dt}$  is the Momentum transferred per unit surface area per unit time.

**Definition 30. Radiation Pressure**: Radiation pressure is the mechanical pressure exerted upon any surface due to the exchange of momentum between the object and the electromagnetic field. This includes the momentum of light or electromagnetic radiation of any wavelength that is absorbed, reflected, or otherwise emitted by matter on any scale.

$$\rho_{rad} = \frac{S_{av}}{c} = \frac{I}{c}$$

where I is intensity for a wave totally absorbed and

$$\rho_{rad} = \frac{2S_{av}}{c} = \frac{2I}{c}$$

for a wave totally reflected

# 32.5 Standing EM Waves.

**Definition 31. Standing Wave**: A Standing Wave is a wave which oscillates in time but whose peak amplitude profile does not move in space. The peak amplitude of the wave oscillations at any point in space is constant with time, and the oscillations at different points throughout the wave are in phase.

**Definition 32. Nodal Planes**: A node is a point along a standing wave where the wave has minimum amplitude.

**Remark.** (1) The Nodal Planes of  $\vec{E}$  are

$$x=0,\frac{\lambda}{2},\lambda,\frac{3\lambda}{2},\dots$$

(2) The Nodal Planes of  $\vec{B}$  are

$$x = \frac{\lambda}{4}, \frac{3\lambda}{4}, \frac{5\lambda}{4}, \dots$$