# Specs of governance contracts

| Contract GovernorOLAS  Dependencies | 4  |
|-------------------------------------|----|
|                                     | 5  |
| Constructor                         | 5  |
| State                               | 6  |
| Propose                             | 6  |
| Proposal Threshold                  | 7  |
| Execute                             | 7  |
| Cancel                              | 8  |
| Executor                            | 8  |
| SupportsInterface                   | 9  |
| Contract VotingEscrow               | 9  |
| Dependencies                        | 10 |
| Contract-defined data types         | 10 |
| Events                              | 11 |
| Variables                           | 11 |
| Mappings                            | 12 |
| Constructor                         | 13 |
| getLastUserPoint                    | 13 |
| getNumUserPoint                     | 14 |
| getUserPoint                        | 14 |
| _checkpoint                         | 14 |
| checkpoint                          | 18 |
| _depositFor                         | 19 |
| depositFor                          | 20 |
| createLock                          | 21 |
| createLockFor                       | 22 |
| _createLock                         | 22 |
| increaseAmount                      | 24 |
| increaseUnlockTime                  | 25 |
| withdraw                            | 26 |
| _findPointByBlock                   | 27 |
| _balanceOfLocked                    | 29 |
| balanceOf                           | 29 |
| lockendEnd                          | 29 |
| balanceOfAt                         | 30 |
| aetVotes                            | 30 |

| _getBlockTime   | 31 |
|---|----|
| getPastVotes  | 32 |
| _supplyLockedAt   | 32 |
| totalSupply   | 33 |
| totalSupplyAt   | 33 |
| totalSupplyLockedAtT  | 34 |
| totalSupplyLocked   | 34 |
| getPastTotalSupply  | 35 |
| supportInterface  | 35 |
| Transfer  | 35 |
| Approve   | 36 |
| TransferFrom  | 36 |
| Allowance   | 36 |
| Delegates   | 37 |
| Delegate  | 37 |
| DelegateBySig   | 38 |
| Contract buOLAS   | 38 |
| Contract-defined Interface                                  | 38 |
| Contract-defined data types                                 | 38 |
| Dependencies  | 39 |
| Events  | 39 |
| Variables   | 40 |
| Mappings  | 40 |
| mapping(address => LockedBalance) public mapLockedBalances; | 40 |
| Constructor   | 40 |
| ChangeOwner   | 41 |
| CreateLockFor   | 41 |
| Withdraw  | 43 |
| Revoke  | 46 |
| BalanceOf   | 47 |
| totalSupply   | 47 |
| ReleasableAmount  | 48 |
| _releasableAmount   | 48 |
| lockendEnd  | 49 |
| supportInterface  | 49 |
| Transfer  | 50 |
| Approve   | 50 |
| TransferFrom  | 50 |
| Allowance   | 50 |
| Contract wveOLAS  | 51 |

| Contract-defined data type | 51 |
|----------------------------|----|
| Contract-defined error     | 52 |
| Variables                  | 52 |
| Constructor                | 53 |
| totalNumPoints             | 53 |
| mapSupplyPoints            | 53 |
| mapSlopeChanges            | 54 |
| getLastUserPoint           | 54 |
| getNumUserPoints           | 54 |
| getUserPoint               | 54 |
| getVotes                   | 55 |
| getPastVotes               | 55 |
| balanceOf                  | 56 |
| balanceOfAt                | 56 |
| lockedEnd                  | 57 |
| totalSupply                | 57 |
| totalSupplyAt              | 57 |
| totalSupplyLockedAtT       | 57 |
| totalSupplyLocked          | 58 |
| getPastTotalSupply         | 58 |
| supportInterface           | 58 |
| Transfer                   | 59 |
| Approve                    | 59 |
| TransferFrom               | 59 |
| Allowance                  | 59 |
| Delegates                  | 60 |
| Delegate                   | 60 |
| Delegate                   | 60 |
| Fallback                   | 61 |
| Contract OLAS              | 61 |
| Contract-defined error     | 61 |
| Dependencies               | 61 |
| Events                     | 61 |
| Variables                  | 62 |
| Constructor                | 62 |
| ChangeOwner                | 63 |
| ChangeMinter               | 63 |
| Mint                       | 64 |
| InflationControl           | 64 |
| InflationControl           | 64 |

| Burn               | 65 |
|--------------------|----|
| DecreasesAllowance | 65 |
| IncreasesAllowance | 66 |

### **Contract** Timelock

The contract inherits from the OpenZeppelin contract TimelockController.

The constructor of Timelock takes the inputs minDelay, proposers, executors and passes these parameters to the constructor of its parent contract TimelockController.

# Contract GovernorOLAS

The contract GovernorOLAS allows the deployment of voting protocols similar to Compound. This contract is derived from OpenZeppelin modular system of governance contracts (see Governance - OpenZeppelin for a detailed description). In particular, it imports the abstract contract Governor customized with the votes module GovernorVotes that, in this governance system, extracts voting weight from a ERC20Votes combined with GovernorVotesQuorumFraction to set the quorum as a fraction of the total token supply.

GovernorOLA inherits from the contract GovernorTimelockControl which binds the execution process to an instance of the TimelockController. The latter imposes a delay for governance decisions to be executed. Thus, the usual workflow is extended to require a queue step before execution. Moreover the timelock extension, in addition to the Governor itself, allows multiple proposers and executors.

GovernorOLAS inherited from GovernorSetting in order to manage some of the settings (voting delay, voting period duration, and proposal threshold) in a way that can be updated through a governance proposal, without requiring an upgrade.

Finally, the GovernorOLAS inherited from the contract GovernorCompatibilityBravo the GovernorBravo compatibility<sup>1</sup>.

### Dependencies

From OpenZeppelin, the contracts Governor, GovernorSettings, GovernorCompatibilityBravo, GovernorVotes, GovernorVotesQuorumFraction, GovernorTimelockControl are inherited (in this inheritance order<sup>2</sup>) by GovernorOLAS

```
contract GovernorOLAS is Governor, GovernorSettings,
GovernorCompatibilityBravo, GovernorVotes,
GovernorVotesQuorumFraction, GovernorTimelockControl
```

#### Constructor

The parent's constructor contracts are called in the inheritance order described above. The constructor of <code>GovernorOLAS</code> takes the inputs governanceToken, timelock, initialVotingDelay, initialVotingPeriod, initialProposalThreshold, quorumFraction and it passes

- the string "GovernorOLAS" to the constructor of Governor
- the parameters initialVotingDelay, initialVotingPeriod, initialProposalThreshold to the constructor of GovernorSettings
- the parameter governanceToken to the constructor of GovernorVotes
- the parameter quorumFraction to the constructor of GovernorVotesOuorumFraction
- the parameter timelock to the constructor of GovernorTimelockControl

```
constructor(
    IVotes governanceToken,
    TimelockController timelock,
    uint256 initialVotingDelay,
    uint256 initialVotingPeriod,
    uint256 initialProposalThreshold,
    uint256 quorumFraction
)
Governor("GovernorOLAS")
```

<sup>&</sup>lt;sup>1</sup>Some examples of what Governor Bravo compatibility entails again. First of all the number of votes required in order for a voter to become a proposal, denoted by proposalThreshold(), is part of Governor Bravo's interface. Being bravo compatible the following feature are included: the abstain vote option, settable parameters (proposal threshold, voting period, voting delay), optional string voting reason, proposer can cancel their proposal (until execution), continuous proposal id logic.

<sup>&</sup>lt;sup>2</sup> When we use the inheritance of multiple contracts, after the word "is", it is required to write the parents' contracts from the less derived one to the most derived one. However, in Solidity, the resolution order is inverted (for more details consult <a href="https://medium.com/coinmonks/inheritance-in-solidity-debunked-3d8dd32d3a99">https://medium.com/coinmonks/inheritance-in-solidity-debunked-3d8dd32d3a99</a> and <a href="https://forum.openzeppelin.com/t/solidity-diamond-inheritance/2694">https://forum.openzeppelin.com/t/solidity-diamond-inheritance/2694</a>)

```
GovernorSettings(initialVotingDelay, initialVotingPeriod, initialProposalThreshold)
GovernorVotes(governanceToken)
GovernorVotesQuorumFraction(quorumFraction)
GovernorTimelockControl(timelock)
{}
```

#### State

The function state is overridden because it is an inherited state from multiple contracts IGovernor, Governor, GovernorTimelockControl.

The statement super.state (proposalId) at the end will invoke GovernorTimelockControl's original version of the state.

In particular, GovernorTimelockControl's original version of the state is an overridden version of the Governor function state (the current state of a proposal) with added support for "Queued" status.

# **Propose**

The function propose is overridden because it is an inherited state from multiple contracts IGovernor, Governor, GovernorCompatibilityBravo.

The statement super.propose (targets, values, calldatas, description) at the end will invoke GovernorCompatibilityBravo's original version of the state.

```
function propose(
    address[] memory targets,
    uint256[] memory values,
    bytes[] memory calldatas,
    string memory description
) public override(Governor, GovernorCompatibilityBravo,
IGovernor) returns (uint256)
```

```
{
    return super.propose(targets, values, calldatas,
description);
}
```

In particular, GovernorCompatibilityBravo's original version of the propose is an overridden version of the Governor function state (that creates a new proposal) with added a call to the function storeProposal that stores a proposal metadata.

# **Proposal Threshold**

The function proposalThreshold is overridden because is an inherited state from multiple contract Governor, GovernorSettings.

The statement super.proposalThreshold at the end will invoke GovernorSettings's original version of the state.

```
function proposalThreshold() public view override(Governor,
GovernorSettings) returns (uint256)
{
    return super.proposalThreshold();
}
```

In particular, GovernorSettings's original version of the proposalThreshold() return the number of votes required in order for a voter to become a proposer.

#### **Execute**

The function \_execute is overridden because is an inherited state from multiple contract Governor, GovernorTimelockControl.

The statement super.\_execute at the end will invoke GovernorTimelockControl's original version of the state.

```
function _execute(
    uint256 proposalId,
    address[] memory targets,
    uint256[] memory values,
    bytes[] memory calldatas,
    bytes32 descriptionHash
```

```
) internal override(Governor, GovernorTimelockControl)
{
        super._execute(proposalId, targets, values, calldatas,
descriptionHash);
}
```

In particular, GovernorTimelockControl's original version of \_execute is an overridden execute function that run the already queued proposal through the timelock.

#### Cancel

The function \_cancel is overridden because is an inherited state from multiple contract Governor, GovernorTimelockControl.

The statement super.\_cancel at the end will invoke GovernorTimelockControl's original version of the state.

```
function _cancel(
    address[] memory targets,
    uint256[] memory values,
    bytes[] memory calldatas,
    bytes32 descriptionHash
    ) internal override(Governor, GovernorTimelockControl) returns
(uint256)
    {
        return super._cancel(targets, values, calldatas,
    descriptionHash);
    }
}
```

In particular, GovernorTimelockControl's original version of \_cancel is an overridden version of the Governor function \_cancel to cancel the timelocked proposal if it has already been queued.

### Executor

The function \_executor is overridden because is an inherited state from multiple contracts Governor, GovernorTimelockControl.

The statement super.\_executor at the end will invoke GovernorTimelockControl's original version of the state.

```
function _executor() internal view override(Governor,
GovernorTimelockControl) returns (address)
```

```
{
    return super._executor();
}
```

In particular, GovernorTimelockControl's original version of \_executor return the address of the timelock through which the governor executes action.

# SupportsInterface

The function supportsInterface is overridden because is an inherited state from multiple contracts IERC165, Governor, GovernorTimelockControl.

The statement super.supportsInterface at the end will invoke GovernorTimelockControl's original version of the state.

In particular, GovernorTimelockControl inherits from the interface IERC165 and overrides supportsInterface to check for the additional interface Id that are supported.

# Contract VotingEscrow

Participating in Autononolas governance requires that an account have a balance of veOLAS (locked claim of the OLAS tokens). The veOLAS holder has non-delegatable voting rights. The veOLAS contract is inspired by the <a href="Curve DAO VotingEscrow contract">Curve DAO VotingEscrow contract</a>. The voting power of each user and the global voting power are recorded in the contract. User voting power is both amounts- and time-weighted, and linearly decreasing since the moment of lock. So does the global voting power. Every time the user deposits, withdraws, or changes the locktime, it is recorded the user's voting power in <a href="mapUserPoints">mapUserPoints</a>. And the changes in the global voting power are recorded in <a href="mapSupplyPoints">mapSupplyPoints</a>. In addition, when the user's lock is scheduled to end, there is a schedule change in the slopes of the global vote power in <a href="mapSlopeChanges">mapSlopeChanges</a>. The end time of user locks is rounded off by whole weeks.

### Dependencies

The contract VotingEscrow inherited the interface <u>lErrors</u> and the OpenZeppelin' interfaces <u>lVotes</u><sup>3</sup>, <u>lERC20</u><sup>4</sup>, and <u>lERC165</u><sup>5</sup>.

# Contract-defined data types

It is created the data type LockedBalance in the form of a structure for storing balance and unlocking time. The struct contains a group of elements amount with data type int128 and endTime with data type uint64.

```
struct LockedBalance {
    // Token amount. It will never practically be bigger. Initial
OLAS cap is 1 bn tokens, or 1e27.
    // After 10 years, the inflation rate is 2% per year. It would
take 1340+ years to reach 2^128 - 1
    uint128 amount;
    // Unlock time. It will never practically be bigger
    uint64 endTime;
}
```

It is created the data type PointVoting in the form of structure.

```
struct PointVoting {
    // w(i) = at + b (bias)
    int128 bias;
    // dw / dt = a (slope)
    int128 slope;
    // Timestamp. It will never practically be bigger than 2^64 - 1
    uint64 ts;
    // Block number. It will not be bigger than the timestamp
```

<sup>&</sup>lt;sup>3</sup> Common interface for ERC20Votes. Using this, VotingEscrow manteins the compatibility with Tally.

<sup>&</sup>lt;sup>4</sup> Interface of the ERC20 standard. Using this, VotingEscrow manteins the compatibility with Tally.

<sup>&</sup>lt;sup>5</sup> So VotingEscrow contract will inherited form IERC165 a supportsInterface function that returns:

<sup>•</sup> true when interfaceID is 0×01ffc9a7 (EIP165 interface)

<sup>•</sup> false when interfaceID is 0xffffffff

<sup>•</sup> true for any other interfaceID this contract implements

false for any other interfaceID

```
uint64 blockNumber;
  // Token amount. It will never practically be bigger. Initial
OLAS cap is 1 bn tokens, or 1e27.
  // After 10 years, the inflation rate is 2% per year. It would
take 1340+ years to reach 2^128 - 1
  uint128 balance;
}
```

It is created the data type <code>DepositType</code> in the form of an enumerated list. The enum contains an enumerated list of elements that are going to be represented with integer values starting from zero.

```
(e.g. return DepositType.DEPOSIT_FOR_TYPE; returns 0
    return DepositType.CREATE_LOCK_TYPE; returns 1, etc.)
enum DepositType {
    DEPOSIT_FOR_TYPE,
    CREATE_LOCK_TYPE,
    INCREASE_LOCK_AMOUNT,
    INCREASE_UNLOCK_TIME
}
```

### **Events**

The events Deposit, Withdraw, and Supply are declared.

```
event Deposit(address provider, uint256 amount, uint256 locktime,
DepositType depositType, uint256 ts);
   event Withdraw(address indexed provider, uint256 amount, uint256
ts);
   event Supply(uint256 prevSupply, uint256 supply);
```

#### **Variables**

The internal constant WEEK is 7 days.

```
uint256 internal constant WEEK = 1 weeks;
```

The internal constant MAXTIME sets the maximum locking time at 4 years calculated in seconds

```
uint256 internal constant MAXTIME = 4 * 365 * 86400;
```

The token is a public and immutable variable that indicates the token address

```
address immutable public token;
```

The supply is a public variable that indicates the total token supply uint256 public supply;

The totalNumPoints is a public variable that indicates the total number of checkpoints

```
uint256 public totalNumPoints;
```

# **Mappings**

The public mapping mapLockedBalances maps the user's address to his corresponding LockedBalance

```
mapping(address => LockedBalance) public mapLockedBalances;
```

The public mapping mapSupplyPoints maps a point to the corresponding PointVoting

```
// Mapping of point Id => point
mapping(uint256 => PointVoting) public mapSupplyPoints;
```

The public mapping mapUserPoints maps the user's address to his corresponding PointVoting at various points

```
// Mapping of account address => PointVoting[point Id]
mapping(address => PointVoting[]) public mapUserPoints;
```

The public mapping mapSlopeChanges maps a time to its corresponding slope change

```
// Mapping of time => signed slope change
mapping(uint256 => int128) public mapSlopeChanges;
```

#### Constructor

Sets the values for the address, name, and symbol. The initial point is at block.timestamp and at block.number and, at that point, the bias, the slope, and the balance are 0.

```
constructor(address _token, string memory _name, string memory
_symbol)
{
    token = _token;
    name = _name;
    symbol = _symbol;
    decimals = ERC20(_token).decimals();
    // Create initial point such that default timestamp and block
number are not zero
    mapSupplyPoints[0] = PointVoting(0, 0, block.timestamp,
block.number, 0);
}
```

# getLastUserPoint

The external function <code>getLastUserPoint(address account)</code>, when there are at least two <code>PointVoting</code> recorded for the user with the address account, returns the most recent <code>PointVoting</code> recorded for that user

```
function getLastUserPoint(address account) external view returns
(PointVoting memory pv) {
     uint256 lastPointNumber = mapUserPoints[account].length;
     if (lastPointNumber > 0) {
        pv = mapUserPoints[account][lastPointNumber - 1];
     }
}
```

# getNumUserPoint

The external function getNumUserPoints (address account) returns the number of PointVoting recorded for the user with the address account

```
function getNumUserPoints(address account) external view returns
(uint256 accountNumPoints) {
        accountNumPoints = mapUserPoints[account].length;
    }
```

# getUserPoint

The external function <code>getUserPoints(address account, uint256 idx)</code> returns the <code>PointVoting</code> at the point with the number <code>idx</code> recorded for the user with the address account.

```
function getUserPoint(address account, uint256 idx) external view
returns (PointVoting memory) {
        return mapUserPoints[account][idx];
}
```

# \_checkpoint

The function \_checkpoint (address account, LockedBalance memory oldLocked, LockedBalance memory newLocked) is internal to the contract and its inputs parameters are the user's address account, the user's precedent locked amount - the user's precedent end of the lock time (oldLocked), the user's new locked amount - the user's new end of lock time (newLocked). The function records the users (with non-zero addresses) data and global data to the checkpoint.

```
function _checkpoint(
   address account,
   LockedBalance memory oldLocked,
   LockedBalance memory newLocked,
   uint128 curSupply
) internal {
   PointVoting memory uOld;
   PointVoting memory uNew;
   int128 oldDSlope;
   int128 newDSlope;
   uint256 curNumPoint = totalNumPoints;
```

```
if (account != address(0)) {
            // Calculate slopes and biases
            // Kept at zero when they have to
            if (oldLocked.endTime > block.timestamp &&
oldLocked.amount > 0) {
                uOld.slope = int128(oldLocked.amount) / IMAXTIME;
                uOld.bias = uOld.slope *
int128(uint128(oldLocked.endTime - uint64(block.timestamp)));
            if (newLocked.endTime > block.timestamp &&
newLocked.amount > 0) {
                uNew.slope = int128(newLocked.amount) / IMAXTIME;
                uNew.bias = uNew.slope *
int128(uint128(newLocked.endTime - uint64(block.timestamp)));
            // Reads values of scheduled changes in the slope
            // oldLocked.endTime can be in the past and in the future
            // newLocked.endTime can ONLY be in the FUTURE unless
everything is expired: then zeros
            oldDSlope = mapSlopeChanges[oldLocked.endTime];
            if (newLocked.endTime > 0) {
                if (newLocked.endTime == oldLocked.endTime) {
                    newDSlope = oldDSlope;
                } else {
                    newDSlope = mapSlopeChanges[newLocked.endTime];
                }
            }
        }
        PointVoting memory lastPoint;
        if (curNumPoint > 0) {
            lastPoint = mapSupplyPoints[curNumPoint];
        } else {
            // If no point is created yet, we take the actual time
and block parameters
            lastPoint = PointVoting(0, 0, uint64(block.timestamp),
uint64(block.number), 0);
        uint64 lastCheckpoint = lastPoint.ts;
        // initialPoint is used for extrapolation to calculate the
block number and save them
```

```
// as we cannot figure that out in exact values from inside
of the contract
        PointVoting memory initialPoint = lastPoint;
        uint256 block slope; // dblock/dt
        if (block.timestamp > lastPoint.ts) {
            // This 1e18 multiplier is needed for the numerator to be
bigger than the denominator
            // We need to calculate this in > uint64 size (1e18 is >
2^59 multiplied by 2^64).
            block slope = (1e18 * uint256(block.number -
lastPoint.blockNumber)) / uint256(block.timestamp - lastPoint.ts);
        // If last point is already recorded in this block, slope ==
0, but we know the block already in this case
        // Go over weeks to fill in the history and (or) calculate
what the current point is
            // The timestamp is rounded and < 2^64-1
            uint64 tStep = (lastCheckpoint / WEEK) * WEEK;
            for (uint256 i = 0; i < 255; ++i) {
                // Hopefully it won't happen that this won't get used
in 5 years!
                // If it does, users will be able to withdraw but
vote weight will be broken
                // This is always practically < 2^64-1
                unchecked {
                    tStep += WEEK;
                int128 dSlope;
                if (tStep > block.timestamp) {
                    tStep = uint64(block.timestamp);
                } else {
                    dSlope = mapSlopeChanges[tStep];
                lastPoint.bias -= lastPoint.slope *
int128(int64(tStep - lastCheckpoint));
                lastPoint.slope += dSlope;
                if (lastPoint.bias < 0) {</pre>
                    // This could potentially happen, but fuzzer
didn't find available "real" combinations
                    lastPoint.bias = 0;
                if (lastPoint.slope < 0) {</pre>
                    // This cannot happen - just in case. Again,
fuzzer didn't reach this
```

```
lastPoint.slope = 0;
                lastCheckpoint = tStep;
                lastPoint.ts = tStep;
                // After division by 1e18 the uint64 size can be
reclaimed
                lastPoint.blockNumber = initialPoint.blockNumber +
uint64((block slope * uint256(tStep - initialPoint.ts)) / 1e18);
                lastPoint.balance = initialPoint.balance;
                // In order for the overflow of total number of
economical checkpoints (starting from zero)
                // The checkpoint() call must happen n > (2^256
-1)/255 or n > \sim 1e77/255 > \sim 1e74 times
                unchecked {
                    curNumPoint += 1;
                if (tStep == block.timestamp) {
                    lastPoint.blockNumber = uint64(block.number);
                    lastPoint.balance = curSupply;
                    break;
                } else {
                    mapSupplyPoints[curNumPoint] = lastPoint;
            }
        }
        totalNumPoints = curNumPoint;
        // Now mapSupplyPoints is filled until current time
        if (account != address(0)) {
            // If last point was in this block, the slope change has
been already applied. In such case we have 0 slope(s)
            lastPoint.slope += (uNew.slope - uOld.slope);
            lastPoint.bias += (uNew.bias - uOld.bias);
            if (lastPoint.slope < 0) {</pre>
                lastPoint.slope = 0;
            if (lastPoint.bias < 0) {</pre>
                lastPoint.bias = 0;
            }
        }
```

```
// Record the last updated point
        mapSupplyPoints[curNumPoint] = lastPoint;
        if (account != address(0)) {
            // Schedule the slope changes (slope is going down)
            // We subtract new user slope from [newLocked.endTime]
            // and add old user slope to [oldLocked.endTime]
            if (oldLocked.endTime > block.timestamp) {
                // oldDSlope was <something> - uOld.slope, so we
cancel that
                oldDSlope += uOld.slope;
                if (newLocked.endTime == oldLocked.endTime) {
                    oldDSlope -= uNew.slope; // It was a new deposit,
not extension
                mapSlopeChanges[oldLocked.endTime] = oldDSlope;
            }
            if (newLocked.endTime > block.timestamp &&
newLocked.endTime > oldLocked.endTime) {
                newDSlope -= uNew.slope; // old slope disappeared at
this point
                mapSlopeChanges[newLocked.endTime] = newDSlope;
                // else: we recorded it already in oldDSlope
            // Now handle user history
            uNew.ts = uint64(block.timestamp);
            uNew.blockNumber = uint64(block.number);
            uNew.balance = newLocked.amount;
            mapUserPoints[account].push(uNew);
        }
```

# checkpoint

The external <code>checkpoint()</code> records the global data to the checkpoint

```
function checkpoint() external {
    _checkpoint(address(0), LockedBalance(0, 0), LockedBalance(0,
0), uint128(supply));
```

# \_depositFor

The internal function \_depositFor(address account, uint256 amount, uint256 unlockTime, LockedBalance memory lockedBalance, DepositType depositType ) has input the address account to which deposit, the amount to deposit, the existing lockedBalance of the address account, and the deposit type.

The function gets the old locked data and either creates a new lock or, when there is already a locked amount for the account, the amount is added to the previously locked one. If unlockTime is non-zero, unlockTime becomes the end of the locking, otherwise, the end of the locking is the previous unlocking time. The function calls the checkpoint to register the user's address account and global data, the oldLocked, and the lockedBalance. Whether the amount is non-zero, an IERC20 (token).transferFrom (msg.sender, address (this), amount) of the amount from the user's account, to this VotingEsrow is made. It follows an emission of the following events Deposit(account, amount, lockedBalance.end, depositType, block.timestamp); Supply(supplyBefore, supplyBefore + amount); function depositFor( address account, uint256 amount, uint256 unlockTime, LockedBalance memory lockedBalance, DepositType depositType ) internal { uint256 supplyBefore = supply; uint256 supplyAfter; // Cannot overflow because the total supply << 2^128-1</pre> unchecked { supplyAfter = supplyBefore + amount; supply = supplyAfter; // Get the old locked data LockedBalance memory oldLocked; (oldLocked.amount, oldLocked.endTime) =

(lockedBalance.amount, lockedBalance.endTime);

```
// Adding to the existing lock, or if a lock is expired -
creating a new one
        // This cannot be larger than the total supply
        unchecked {
            lockedBalance.amount += uint128(amount);
        if (unlockTime > 0) {
            lockedBalance.endTime = uint64(unlockTime);
        mapLockedBalances[account] = lockedBalance;
        // Possibilities:
        // Both oldLocked.endTime could be current or expired (>/<
block.timestamp)
        // amount == 0 (extend lock) or amount > 0 (add to lock or
extend lock)
        // lockedBalance.endTime > block.timestamp (always)
        checkpoint (account, oldLocked, lockedBalance,
uint128(supplyAfter));
        if (amount > 0) {
            // OLAS is a solmate-based ERC20 token with optimized
transferFrom() that either returns true or reverts
            IERC20(token).transferFrom(msg.sender, address(this),
amount);
        }
        emit Deposit (account, amount, lockedBalance.endTime,
depositType, block.timestamp);
        emit Supply(supplyBefore, supplyAfter);
    }
```

# depositFor

The function depositFor (address account, uint256 amount) is an external function. Whether the amount is non-zero, the account has already a locked amount that is not expired yet, it is made a call to the function \_depositFor (account, amount, 0, lockedBalance, DepositType.DEPOSIT\_FOR\_TYPE) that increases the amount of tokens of the account but not extending account's unlocking time. Since in depositFor() there is an unchecked sum of amounts, priory to the call of the

function \_depositFor() is is checked that amount < type(uint96).max prior
otherwise the request is reverted.</pre>

```
function depositFor(address account, uint256 amount) external
{
        LockedBalance memory lockedBalance =
mapLockedBalances[account];
        // Check if the amount is zero
        if (amount == 0) {
            revert ZeroValue();
        // The locked balance must already exist
        if (lockedBalance.amount == 0) {
            revert NoValueLocked(account);
        // Check the lock expiry
        if (lockedBalance.endTime < (block.timestamp + 1)) {</pre>
            revert LockExpired (msg.sender, lockedBalance.endTime,
block.timestamp);
        // Since in the depositFor() we have the unchecked sum of
amounts, this is needed to prevent unsafe behavior.
        // After 10 years, the inflation rate is 2% per year. It
would take 220+ years to reach 2^96 - 1 total supply
        if (amount > type(uint96).max) {
            revert Overflow(amount, type(uint96).max);
        }
        depositFor(account, amount, 0, lockedBalance,
DepositType.DEPOSIT FOR TYPE);
    }
    }
```

#### createLock

The function createLock(uint256 amount, uint256 unlockTime) is an external function and it is made a call to the function \_createLockFor(msg.sender, amount, unlockTime) that creates a new locking for the msg.sender of the amount for unlockTime.

```
/// @dev Deposits `amount` tokens for `msg.sender` and locks for
`unlockTime`.
    /// @param amount Amount to deposit.
    /// @param unlockTime Time when tokens unlock, rounded down to a
whole week.
    function createLock(uint256 amount, uint256 unlockTime) external
{
        _createLockFor(msg.sender, amount, unlockTime);
}
```

#### createLockFor

The function createLockFor (address account, uint256 amount, uint256 unlockTime) is an external function that allows anyone to deposit the amount of tokens for a (non-zero) account and lock those for unlockTime via the function createLockFor (account, amount, unlockTime).

```
/// @dev Deposits `amount` tokens for `account` and locks for
`unlockTime`.
    /// @notice Tokens are taken from `msg.sender`'s balance.
    /// @param account Account address.
    /// @param amount Amount to deposit.
    /// @param unlockTime Time when tokens unlock, rounded down to a
whole week.
    function createLockFor(address account, uint256 amount, uint256
unlockTime) external {
        // Check if the account address is zero
        if (account == address(0)) {
            revert ZeroAddress();
        }

        __createLockFor(account, amount, unlockTime);
}
```

# createLock

The function \_createLock(uint256 amount, uint256 amount, uint256 unlockTime). Whether the amount is non-zero and not bigger than 2^96 - 1, the account has zero locked amount, the unlockTime is bigger than the

block.timestamp+1, and smaller than the maximum allowed unlockeTime (i.e. 4 years), it is made a call to the function \_\_depositFor(account, amount, unlockTime, lockedBalance, DepositType.CREATE\_LOCK\_TYPE) that creates a new locking for the account of the amount for unlockTime.

```
/// @dev Deposits `amount` tokens for `account` and locks for
`unlockTime`.
    /// @notice Tokens are taken from `msq.sender`'s balance.
    /// @param account Account address.
    /// @param amount Amount to deposit.
    /// @param unlockTime Time when tokens unlock, rounded down to a
whole week.
    function createLockFor(address account, uint256 amount, uint256
unlockTime) private {
        // Check if the amount is zero
        if (amount == 0) {
            revert ZeroValue();
        // Lock time is rounded down to weeks
        // Cannot practically overflow because block.timestamp +
unlockTime (max 4 years) << 2^64-1
        unchecked {
            unlockTime = ((block.timestamp + unlockTime) / WEEK) *
WEEK;
        LockedBalance memory lockedBalance =
mapLockedBalances[account];
        // The locked balance must be zero in order to start the lock
        if (lockedBalance.amount > 0) {
            revert LockedValueNotZero(account,
uint256(lockedBalance.amount));
        // Check for the lock time correctness
        if (unlockTime < (block.timestamp + 1)) {</pre>
            revert UnlockTimeIncorrect(account, block.timestamp,
unlockTime);
        // Check for the lock time not to exceed the MAXTIME
        if (unlockTime > block.timestamp + MAXTIME) {
            revert MaxUnlockTimeReached(account, block.timestamp +
MAXTIME, unlockTime);
        }
```

```
// After 10 years, the inflation rate is 2% per year. It
would take 220+ years to reach 2^96 - 1 total supply
    if (amount > type(uint96).max) {
        revert Overflow(amount, type(uint96).max);
    }

    _depositFor(account, amount, unlockTime, lockedBalance,
DepositType.CREATE_LOCK_TYPE);
}
```

#### increaseAmount

The function increaseAmount (uint256 amount) is an external function. Whether the amount is non-zero and not bigger than 2^96 - 1, the msg.sender calling the function has already a locked amount that is scheduled to unlock 'later' the call of this function, it is made a call to the function \_depositFor(msg.sender, amount, 0, lockedBalance, DepositType.INCREASE\_LOCK\_AMOUNT) that increase the locked amount for the msg.sender of the amount without modifying the unlock time.

```
function increaseAmount(uint256 amount) external {
    LockedBalance memory lockedBalance =
mapLockedBalances[msg.sender];
    // Check if the amount is zero
    if (amount == 0) {
        revert ZeroValue();
    }
    // The locked balance must already exist
    if (lockedBalance.amount == 0) {
        revert NoValueLocked(msg.sender);
    }
    // Check the lock expiry
    if (lockedBalance.endTime < (block.timestamp + 1)) {
        revert LockExpired(msg.sender, lockedBalance.endTime,
block.timestamp);
    }
    // Check the max possible amount to add, that must be less
than the total supply</pre>
```

```
// After 10 years, the inflation rate is 2% per year. It
would take 220+ years to reach 2^96 - 1 total supply
    if (amount > type(uint96).max) {
        revert Overflow(amount, type(uint96).max);
    }

    _depositFor(msg.sender, amount, 0, lockedBalance,
DepositType.INCREASE_LOCK_AMOUNT);
}
```

#### increaseUnlockTime

The function increaseUnlockTime (uint256 unlockTime) is an external function. Whether the locked amount of the msg.sender calling the function is non-zero, the unlockTime is bigger than the old unlock time of the msg.sender plus one, and the unlockTime does not exceed the maximum time to unlock, then a \_depositFor(msg.sender, amount, 0, lockedBalance, DepositType.INCREASE\_UNLOCK\_TIME) increases the unlockTime for the msg.sender without modifying its locked amount.

```
function increaseUnlockTime(uint256 unlockTime) external {
        LockedBalance memory lockedBalance =
mapLockedBalances[msg.sender];
        // Cannot practically overflow because block.timestamp +
unlockTime (max 4 years) << 2^64-1
        unchecked {
            unlockTime = ((block.timestamp + unlockTime) / WEEK) *
WEEK;
        }
        // The locked balance must already exist
        if (lockedBalance.amount == 0) {
            revert NoValueLocked(msg.sender);
        // Check the lock expiry
        if (lockedBalance.endTime < (block.timestamp + 1)) {</pre>
            revert LockExpired (msg.sender, lockedBalance.endTime,
block.timestamp);
        // Check for the lock time correctness
        if (unlockTime < (lockedBalance.endTime + 1)) {</pre>
```

#### withdraw

```
The function withdraw() is an external function. Whether the old locked balance of the
msg.sender has expired (at least at the block.timestamp of the function call) the
function call by the msg.sender, the user-data are recorded at the checkpoint where
the old amount/unlock time of msg.sende are fixed at zero, a
IERC20 (token) .transfer (msg.sender, amount) transfers all the tokens of the
msg.sender to its account. The following events are emitted
  emit Withdraw(msg.sender, amount, block.timestamp);
  emit Supply(supplyBefore, supplyAfter);
    function withdraw() external {
         LockedBalance memory lockedBalance =
mapLockedBalances[msg.sender];
         if (lockedBalance.endTime > block.timestamp) {
             revert LockNotExpired (msg.sender, lockedBalance.endTime,
block.timestamp);
        uint256 amount = uint256(lockedBalance.amount);
        mapLockedBalances[msg.sender] = LockedBalance(0, 0);
        uint256 supplyBefore = supply;
        uint256 supplyAfter;
```

```
// The amount cannot be less than the total supply
        unchecked {
            supplyAfter = supplyBefore - amount;
            supply = supplyAfter;
        }
        // oldLocked can have either expired <= timestamp or zero end
        // lockedBalance has only 0 end
        // Both can have >= 0 amount
        checkpoint(msg.sender, lockedBalance, LockedBalance(0, 0),
uint128(supplyAfter));
        emit Withdraw(msg.sender, amount, block.timestamp);
        emit Supply(supplyBefore, supplyAfter);
        // OLAS is a solmate-based ERC20 token with optimized
transfer() that either returns true or reverts
        IERC20(token).transfer(msg.sender, amount);
    }
```

# \_findPointByBlock

The function \_findPointByBlock(uint256 blockNumber, address account) is an internal function that finds the closest point with a specific blockNumber. This function returns the PointVoting with the index closest to the point for the specified blockNumber and the PointVoting number.

```
function _findPointByBlock(uint256 blockNumber, address account)
internal view
    returns (PointVoting memory point, uint256 minPointNumber)
{
    // Get the last available point number
    uint256 maxPointNumber;
    if (account == address(0)) {
        maxPointNumber = totalNumPoints;
    } else {
        maxPointNumber = mapUserPoints[account].length;
        if (maxPointNumber == 0) {
```

```
return (point, minPointNumber);
            }
            // Already checked for > 0 in this case
            unchecked {
                maxPointNumber -= 1;
            }
        }
        // Binary search that will be always enough for 128-bit
numbers
        for (uint256 i = 0; i < 128; ++i) {
            if ((minPointNumber + 1) > maxPointNumber) {
                break;
            }
            uint256 mid = (minPointNumber + maxPointNumber + 1) / 2;
            // Choose the source of points
            if (account == address(0)) {
                point = mapSupplyPoints[mid];
            } else {
                point = mapUserPoints[account][mid];
            }
            if (point.blockNumber < (blockNumber + 1)) {</pre>
                minPointNumber = mid;
            } else {
                maxPointNumber = mid - 1;
        }
        // Get the found point
        if (account == address(0)) {
            point = mapSupplyPoints[minPointNumber];
        } else {
            point = mapUserPoints[account][minPointNumber];
        }
    }
```

# balanceOfLocked

The function \_balanceOfLocked(address account, uint256 ts) is an internal function that returns the voting power of a user with an address account at the block with timestamp ts.

```
function _balanceOfLocked(address account, uint64 ts) internal
view returns (uint256 vBalance) {
      uint256 pointNumber = mapUserPoints[account].length;
      if (pointNumber > 0) {
            PointVoting memory uPoint =
            mapUserPoints[account][pointNumber - 1];
            uPoint.bias -= uPoint.slope * int128(int64(ts) -
            int64(uPoint.ts));
            if (uPoint.bias > 0) {
                 vBalance = uint256(int256(uPoint.bias));
            }
        }
    }
}
```

### balanceOf

The function function balanceOf (address account) is an public function. It is marked as override because the contract <a href="VotingEscrow">VotingEscrow</a> calls the interface <a href="OpenZeppelin">OpenZeppelin</a> - IERC20 containing the function "function balanceOf (address account)".

This function simply returns the amount of tokens that the user with the address account has.

```
function balanceOf(address account) public view override returns
(uint256 balance) {
    balance = uint256(mapLockedBalances[account].amount);
}
```

#### lockendEnd

The function lockedEnd(address account) is an external function. This function returns the scheduled end of the locking time for the user with the address account.

```
function lockedEnd(address account) external view returns
(uint256 unlockTime) {
    unlockTime = uint256(mapLockedBalances[account].endTime);
}
```

#### balanceOfAt

The function function balanceOfAt (address account, uint256 blockNumber) is an external function. This function gets the account balance at a specific block number.

# getVotes

The function <code>getVotes(address account)</code> is a public function. It is marked as override because the contract <code>VotingEscrow</code> calls the interface <code>OpenZeppelin - IVotes</code> containing the function "function <code>getVotes(address account)</code>". This function, when it is called, returns the voting power of the user with the address account.

```
function getVotes(address account) public view override returns
(uint256) {
    return _balanceOfLocked(account, uint64(block.timestamp));
}
```

# \_getBlockTime

The function \_getBlockTime(uint256 blockNumber) is an internal function. Whether the blockNumber is smaller or equal to the block number corresponding to when such a function gets called, then the function returns the point with the specified blockNumber (or closest to it) and the adjusted block time of the neighboring point.

```
function getBlockTime(uint256 blockNumber) internal view returns
(PointVoting memory point, uint256 blockTime) {
        // Check the block number to be in the past or equal to the
current block
        if (blockNumber > block.number) {
            revert WrongBlockNumber(blockNumber, block.number);
        // Get the minimum historical point with the provided block
number
        uint256 minPointNumber;
        (point, minPointNumber) = findPointByBlock(blockNumber,
address(0));
        uint256 dBlock;
        uint256 dt;
        if (minPointNumber < totalNumPoints) {</pre>
            PointVoting memory pointNext =
mapSupplyPoints[minPointNumber + 1];
            dBlock = pointNext.blockNumber - point.blockNumber;
            dt = pointNext.ts - point.ts;
        } else {
            dBlock = block.number - point.blockNumber;
            dt = block.timestamp - point.ts;
        blockTime = point.ts;
        if (dBlock > 0) {
            blockTime += (dt * (blockNumber - point.blockNumber)) /
dBlock;
        }
    }
```

# getPastVotes

The function <code>getPastVotes(address account, uint256 blockNumber)</code> is a public function. It is marked as override because the contract <code>VotingEscrow</code> calls the interface <code>OpenZeppelin - IVotes</code> containing the function "function <code>getPastVotes(address account, uint256 blockNumber)</code>".

Whether the voting power is non-zero, the function returns the voting power of the account at blockNumber.

```
function getPastVotes(address account, uint256 blockNumber)
public view override returns (uint256 balance) {
    // Find the user point for the provided block number
        (PointVoting memory uPoint, ) =
    _findPointByBlock(blockNumber, account);

    // Get block time adjustment.
    (, uint256 blockTime) = _getBlockTime(blockNumber);

    // Calculate bias based on a block time
        uPoint.bias -= uPoint.slope * int128(int64(uint64(blockTime)))
- int64(uPoint.ts));
    if (uPoint.bias > 0) {
        balance = uint256(uint128(uPoint.bias));
    }
}
```

# \_supplyLockedAt

The function \_supplyLockedAt(PointVoting memory lastPoint, uint256 ts) is an internal function. The input lastPoint is the starting point to start the search for calculating the global voting power at the time ts. The function returns the global voting power when the latter is bigger than zero.

```
function _supplyLockedAt(PointVoting memory lastPoint, uint64 ts)
internal view returns (uint256 vSupply) {
    // The timestamp is rounded and < 2^64-1
    uint64 tStep = (lastPoint.ts / WEEK) * WEEK;
    for (uint256 i = 0; i < 255; ++i) {
        // This is always practically < 2^64-1</pre>
```

```
unchecked {
                tStep += WEEK;
            int128 dSlope;
            if (tStep > ts) {
                tStep = ts;
            } else {
                dSlope = mapSlopeChanges[tStep];
            lastPoint.bias -= lastPoint.slope * int128(int64(tStep) -
int64(lastPoint.ts));
            if (tStep == ts) {
                break;
            lastPoint.slope += dSlope;
            lastPoint.ts = tStep;
        }
        if (lastPoint.bias > 0) {
            vSupply = uint256(uint128(lastPoint.bias));
        }
```

# totalSupply

The function totalSupply() is a public function that returns the total token supply. It is marked as override because the contract  $\underline{\text{VotingEscrow}}$  calls the interface  $\underline{\text{IERC20}}$  and the latter contains the function "totalSupply()".

```
function totalSupply() public view override returns (uint256) {
    return supply;
}
```

# totalSupplyAt

The function totalSupplyAt (uint256 blockNumber) is an external function. If the block number of the last point closest to blockNumber is smaller or equal to blockNumber itself, then the function returns the global voting power at the specific blockNumber.

# totalSupplyLockedAtT

The function totalSupplyLockedAtT(uint256 ts) is a public function and it calculates the global voting power at the specific time ts.

```
function totalSupplyLockedAtT(uint256 ts) public view returns
(uint256) {
        PointVoting memory lastPoint =
mapSupplyPoints[totalNumPoints];
        return _supplyLockedAt(lastPoint, uint64(ts));
}
```

# totalSupplyLocked

The function totalSupplyLocked() is a public function that returns the current global voting power.

```
function totalSupplyLocked() public view returns (uint256) {
  return totalSupplyLockedAtT(block.timestamp);
```

# getPastTotalSupply

The function <code>getPastTotalSupply(uint256 blockNumber)</code> is a public function that returns the global voting power at the specific <code>blockNumber</code>. It is marked as override because the contract <code>VotingEscrow</code> calls the interfaces <code>IVotes</code> that contains the function "totalSupply()".

# supportInterface

The function supportsInterface(bytes4 interfaceId) is a public function that gets information about additional interface-id that are supported by the contract. It is marked as override because the contract calls the interface  $\underline{\texttt{IERC165}}$  that contains the function "supportsInterface".

### Transfer

The function transfer (address to, uint256 amount) is a public function and it is marked as override because the contract <a href="VotingEscrow">VotingEscrow</a> calls the interfaces <a href="IERC20">IERC20</a>

that contains the function "transfer (address to, uint256 amount)". This function reverts any transfer of any amount to an address.

```
function transfer(address to, uint256 amount) external
virtual override returns (bool) {
   revert NonTransferable(address(this));
}
```

# **Approve**

The function approve (address spender, uint256 amount) is a public function and it is marked as override because the contract <u>VotingEscrow</u> calls the interfaces <u>IERC20</u> that contains the function "approve (address spender, uint256 amount)". This function reverts any approval of the spent amount from an address spender

```
function approve(address spender, uint256 amount) external
virtual override returns (bool) {
    revert NonTransferable(address(this));
}
```

#### TransferFrom

The function transferFrom(address from, address to, uint256 amount) is a public function and it is marked as override because the contract <u>VotingEscrow</u> calls the interfaces <u>IERC20</u>. This function reverts transfer from an address to an address of any amount.

```
function transferFrom(address from, address to, uint256 amount)
external virtual override returns (bool) {
    revert NonTransferable(address(this));
}
```

### Allowance

The function allowance (address owner, address spender) is a public function and it is marked as override because the contract <a href="VotingEscrow">VotingEscrow</a> calls the interfaces

<u>IERC20</u>. This function reverts any change of allowance of the remaining tokens that the spender would be allowed to spend on the owner's behalf if approve or transferFrom were called

```
function allowance(address owner, address spender) external view
virtual override returns (uint256)
{
    revert NonTransferable(address(this));
}
```

# Delegates

The function delegates (address account) is a public function and it is marked as override because the contract <a href="VotingEscrow">VotingEscrow</a> calls the interfaces <a href="IVotes">IVotes</a>. This function reverts any address to which an account would have chosen to delegate.

```
function delegates(address account) external view virtual
override returns (address)
{
    revert NonDelegatable(address(this));
}
```

# Delegate

The function <code>delegate(address delegatee)</code> is a public function and it is marked as override because the contract <code>VotingEscrow</code> calls the interfaces <code>IVotes</code>. This function reverts any delegate of votes from the sender

```
function delegate(address delegatee) external virtual override
{
    revert NonDelegatable(address(this));
}
```

## DelegateBySig

The function delegateBySig (address delegatee, uint256 nonce, uint256 expiry, uint8 v, bytes32 r, bytes32 s) is a public function and it is marked as override because the contract <u>VotingEscrow</u> calls the interfaces <u>IVotes</u>. This function reverts any delegate votes from a signer.

# Contract buOLAS

### Contract-defined Interface

The interface IOLAS is an interface for burn functionality.

```
interface IOLAS {
    /// @dev Burns OLAS tokens.
    /// @param amount OLAS token amount to burn.
    function burn(uint256 amount) external;
}
```

# Contract-defined data types

It is created the data type LockedBalance in the form of a structure for storing balance and unlocking time. The struct contains a group of elements: totalAmount with data type uint96, transferredAmount with data type uint96, startTime with data type uint32, endTime with data type uint32.

```
struct LockedBalance {
```

```
// Token amount locked. Initial OLAS cap is 1 bn tokens, or 1e27.
    // After 10 years, the inflation rate is 2% per year. It would
take 220+ years to reach 2^96 - 1
    uint96 totalAmount;
    // Token amount transferred to its owner. It is of the value of
at most the total amount locked
    uint96 transferredAmount;
    // Lock time start
    uint32 startTime;
    // Lock end time
    // 2^32 - 1 is enough to count 136 years starting from the year
of 1970. This counter is safe until the year of 2106
    uint32 endTime;
}
```

## Dependencies

The contract buolas inherited the interface <u>IErrors</u> and the OpenZeppelin' interfaces <u>IERC20</u><sup>6</sup> and <u>IERC165</u><sup>7</sup>.

## **Events**

The events Lock, Withdraw, Revoke, Burn, Supply, and OwnerUpdated are declared.

```
event Lock(address indexed account, uint256 amount, uint256
startTime, uint256 endTime);
    event Withdraw(address indexed account, uint256 amount, uint256
ts);
    event Revoke(address indexed account, uint256 amount, uint256
ts);
    event Burn(address indexed account, uint256 amount, uint256 ts);
    event Supply(uint256 previousSupply, uint256 currentSupply);
    event OwnerUpdated(address indexed owner);
```

<sup>&</sup>lt;sup>6</sup> Interface of the ERC20 standard.

<sup>&</sup>lt;sup>7</sup> So buOLAS contract will inherited form IERC165 a supportsInterface function.

### **Variables**

The internal constant STEP\_TIME fixes the step time calculated in seconds

```
uint32 internal constant STEP TIME = 365 * 86400;
```

The internal constant MAX\_NUM\_STEPS fixes the maximal number of steps for locking calculated in seconds

```
uint32 internal constant MAX_NUM_STEPS = 10;
```

The supply is a public variable that indicates the total token supply

```
uint256 public supply;
```

The decimal is a public variable that set 18 decimals

```
uint8 public constant decimals = 18;
```

The token is a public and immutable variable that indicates the token address

```
address public immutable token;
```

The owner is a public variable that indicates the owner's address

```
address public owner;
```

## Mappings

The public mapping mapLockedBalances maps the user's address to his corresponding LockedBalance

```
mapping(address => LockedBalance) public mapLockedBalances;
```

### Constructor

Sets the values for the address, name, symbol, and makes the contract ownable with owner = msq.sender.

```
constructor(address _token, string memory _name, string memory
_symbol)

{
    token = _token;
    name = _name;
    symbol = _symbol;
    owner = msg.sender;
}
```

# ChangeOwner

The function changeOwner (address newOwner) is an external function that allows the previous owner of the contract to sets a new owner (with a no-zero address) and emit the event

```
emit OwnerUpdated(newOwner);

function changeOwner(address newOwner) external {
   if (msg.sender != owner) {
      revert OwnerOnly(msg.sender, owner);
   }

   if (newOwner == address(0)) {
      revert ZeroAddress();
   }

   owner = newOwner;
   emit OwnerUpdated(newOwner);
}
```

## CreateLockFor

The function createLockFor(address account, uint256 amount, uint256 numSteps) is an external function that allows depositing to the address account the

amount of tokens taken from the msg.sender's balance and locking those for numSteps time periods.

The function checks that the address account is not the zero address, the amount is non-zero and less or equal that 2^96 - 1, the numSteps is non-zero and less than the MAX\_NUM\_STEPS, the account has not yet a locked amount, and revert if one of the previous is not satisfied. The mapLockedBalances is updated with the new lockedBalances information for the account such as the startTime, block.timestamp, the endTime, and the totalAmount of the locking. The total supply is then calculated and the events and there is a transferFrom of the amount from the msg.sender to this contract. Then the following events are emitted emit Lock(account, amount, block.timestamp, unlockTime); emit Supply(supplyBefore, supplyAfter);

```
function createLockFor(address account, uint256 amount, uint256
numSteps) external {
        // Check if the account is zero
        if (account == address(0)) {
            revert ZeroAddress();
        // Check if the amount is zero
        if (amount == 0) {
            revert ZeroValue();
        }
        // The locking makes sense for one step or more only
        if (numSteps == 0) {
            revert ZeroValue();
        // Check the maximum number of steps
        if (numSteps > MAX NUM STEPS) {
            revert Overflow(numSteps, MAX NUM STEPS);
        // Lock time is equal to the number of fixed steps multiply
on a step time
        uint256 unlockTime = block.timestamp + uint256(STEP TIME) *
numSteps;
        // Max of 2^32 - 1 value, the counter is safe until the year
of 2106
        if (unlockTime > type(uint32).max) {
            revert Overflow(unlockTime, type(uint32).max);
        // After 10 years, the inflation rate is 2% per year. It
would take 220+ years to reach 2^96 - 1 total supply
        if (amount > type(uint96).max) {
```

```
revert Overflow(amount, type(uint96).max);
        }
        LockedBalance memory lockedBalance =
mapLockedBalances[account];
        // The locked balance must be zero in order to start the lock
        if (lockedBalance.totalAmount > 0) {
            revert LockedValueNotZero(account,
lockedBalance.totalAmount);
        // Store the locked information for the account
        lockedBalance.startTime = uint32(block.timestamp);
        lockedBalance.endTime = uint32(unlockTime);
        lockedBalance.totalAmount = uint96(amount);
        mapLockedBalances[account] = lockedBalance;
        // Calculate total supply
        uint256 supplyBefore = supply;
        uint256 supplyAfter;
        // Cannot overflow because we do not add more tokens than the
OLAS supply
        unchecked {
            supplyAfter = supplyBefore + amount;
            supply = supplyAfter;
        }
        // OLAS is a solmate-based ERC20 token with optimized
transferFrom() that either returns true or reverts
        IERC20(token).transferFrom(msg.sender, address(this),
amount);
        emit Lock(account, amount, block.timestamp, unlockTime);
        emit Supply(supplyBefore, supplyAfter);
    }
```

### Withdraw

The function withdraw() is an external function that allows the msg.sender to realise its matured locked tokens.

Specifically, if the lockedBalance.startTime of the msg.sender is bigger than zero and the realisable amount is non-zero, that is the balances are still active and not yet fully withdrawn, then either the lockedBalance.endTime of the msg.sender is bigger than zero meaning that no unrealized amount of the msg.sender was revoked or lockedBalance.endTime of the msg.sender is zero meaning that some tokens of the msg.sender was revoked so will be burned with the burn function. In this second case, it is emitted the event

```
emit Burn (msg.sender, amountBurn, block.timestamp). In both cases, the map mapLockedBalances is updating with the new locking information for msg.sender. The realisable amount is sent to the msg.sender and the total supply is computed. The following events are emitted
```

```
emit Withdraw(msg.sender, amount, block.timestamp);
            emit Supply(supplyBefore, supplyAfter);
    function withdraw() external {
        LockedBalance memory lockedBalance =
mapLockedBalances[msg.sender];
        // If the balances are still active and not fully withdrawn,
start time must be greater than zero
        if (lockedBalance.startTime > 0) {
            // Calculate the amount to release
            uint256 amount = releasableAmount(lockedBalance);
            // Check if at least one locking step has passed
            if (amount == 0) {
                revert LockNotExpired (msg.sender,
lockedBalance.endTime, block.timestamp);
            }
            uint256 supplyBefore = supply;
            uint256 supplyAfter = supplyBefore;
            // End time is greater than zero if withdraw was not
fully completed and `revoke` was not called on the account
            if (lockedBalance.endTime > 0) {
                unchecked {
                    // Update the account locked amount.
                    // Cannot practically overflow since the amount
to release is smaller than the locked amount
                    lockedBalance.transferredAmount +=
uint96 (amount);
                }
```

```
// The balance is fully unlocked. Released amount
must be equal to the locked one
                if ((lockedBalance.transferredAmount + 1) >
lockedBalance.totalAmount) {
                    mapLockedBalances[msg.sender] = LockedBalance(0,
0, 0, 0);
                } else {
                    mapLockedBalances[msg.sender] = lockedBalance;
            } else {
                // This means revoke has been called on this account
and some tokens must be burned
                uint256 amountBurn =
uint256(lockedBalance.totalAmount);
                // Burn revoked tokens
                if (amountBurn > 0) {
                    IOLAS(token).burn(amountBurn);
                    // Update total supply
                    unchecked {
                        // Amount to burn cannot be bigger than the
supply before the burn
                        supplyAfter = supplyBefore - amountBurn;
                    emit Burn (msg.sender, amountBurn,
block.timestamp);
                // Set all the data to zero
                mapLockedBalances[msg.sender] = LockedBalance(0, 0,
0, 0);
            }
            // The amount cannot be bigger than the total supply
            unchecked {
                supplyAfter -= amount;
                supply = supplyAfter;
            }
            emit Withdraw(msg.sender, amount, block.timestamp);
            emit Supply(supplyBefore, supplyAfter);
            // OLAS is a solmate-based ERC20 token with optimized
transfer() that either returns true or reverts
            IERC20(token).transfer(msg.sender, amount);
```

```
}
```

### Revoke

The function revoke() is an external function that allows the owner of the contract to revoke non-matured locked tokens for the list of addressess accounts. The function gets the realisable amount of the accounts and lets the

lockedBalance.totalAmount represents the burnable amount. The realisable amount accounts of the is sets in lockedBalance.transferredAmount. This latter will be transferred to the accounts when they call the withdraw function. To flag that non-matured locked tokens are burnable lockedBalance.endTime is set to zero. Finally, it is emitted the event

```
emit Revoke (account, uint256 (lockedBalance.totalAmount),
block.timestamp).
    function revoke(address[] memory accounts) external {
        // Check for the ownership
        if (owner != msg.sender) {
            revert OwnerOnly(msg.sender, owner);
        }
        for (uint256 i = 0; i < accounts.length; ++i) {
            address account = accounts[i];
            LockedBalance memory lockedBalance =
mapLockedBalances[account];
            // Get the amount to release
            uint256 amountRelease = releasableAmount(lockedBalance);
            // Amount locked now represents the burn amount, which
can not become less than zero
            unchecked {
                lockedBalance.totalAmount -= (uint96(amountRelease) +
lockedBalance.transferredAmount);
            // This is the release amount that will be transferred to
the account when they withdraw
            lockedBalance.transferredAmount = uint96(amountRelease);
            // Termination state of the revoke procedure
```

```
lockedBalance.endTime = 0;
    // Update the account data
    mapLockedBalances[account] = lockedBalance;

    emit Revoke(account, uint256(lockedBalance.totalAmount),
block.timestamp);
    }
}
```

### BalanceOf

The function balanceOf (address account) is public and gets the locking balance details of the address account. The function is marked as override because the contract call the interface OpenZeppelin - IERC20.

```
function balanceOf(address account) public view override returns
(uint256 balance) {
        LockedBalance memory lockedBalance =
mapLockedBalances[account];
        // If the end is equal 0, this balance is either left after
revoke or expired
        if (lockedBalance.endTime == 0) {
            // The maximum balance in this case is the released
amount value
           balance = uint256(lockedBalance.transferredAmount);
        } else {
            // Otherwise the balance is the difference between locked
and released amounts
            balance = uint256(lockedBalance.totalAmount -
lockedBalance.transferredAmount);
    }
```

# totalSupply

The function totalSupply() is a public function that returns the total token supply. It is marked as override because this calls the interface  $\underline{\texttt{IERC20}}$ .

```
function totalSupply() public view override returns (uint256) {
    return supply;
}
```

#### ReleasableAmount

The function releasableAmount (address account) is an external function that returns the realisable token amount of the address account

```
function releasableAmount(address account) external view returns
(uint256 amount) {
        LockedBalance memory lockedBalance =
mapLockedBalances[account];
        amount = _releasableAmount(lockedBalance);
}
```

## releasableAmount

The function \_releasableAmount (LockedBalance memory lockedBalance) is a private that computes and returns the releasable amount of the account lockedBalance struct.

```
function releasableAmount(LockedBalance memory lockedBalance)
private view returns (uint256 amount) {
        // If the end is equal 0, this balance is either left after
revoke or expired
        if (lockedBalance.endTime == 0) {
            return lockedBalance.transferredAmount;
        // Number of steps
        uint32 numSteps;
        // Current locked time
        uint32 releasedSteps;
        // Time in the future will be greater than the start time
        unchecked {
            numSteps = (lockedBalance.endTime -
lockedBalance.startTime) / STEP TIME;
            releasedSteps = (uint32(block.timestamp) -
lockedBalance.startTime) / STEP_TIME;
        }
        // If the number of release steps is greater or equal to the
number of steps, all the available tokens are unlocked
```

### lockendEnd

The function lockedEnd(address account) is an external function. This function returns the scheduled end of the locking time for the user with the address account.

```
function lockedEnd(address account) external view returns
(uint256 unlockTime) {
    unlockTime = uint256(mapLockedBalances[account].endTime);
}
```

## supportInterface

The function supportsInterface (bytes4 interfaceId) is a public function that gets information about additional interface id that are supported by the contract. It is marked as override because the contract calls the interface  $\underline{\texttt{IERC165}}$  that contains the function "supportsInterface".

### Transfer

The function transfer (address to, uint256 amount) is a public function and it is marked as override because the contract calls the interfaces <u>IERC20</u>. This function reverts any transfer of any amount to an address.

```
function transfer(address to, uint256 amount) external
virtual override returns (bool) {
   revert NonTransferable(address(this));
}
```

## **Approve**

The function approve (address spender, uint256 amount) is a public function and it is marked as override because the contract calls the interfaces <u>IERC20</u>. This function reverts any approval of the spent amount from an address spender

```
function approve(address spender, uint256 amount) external
virtual override returns (bool) {
    revert NonTransferable(address(this));
}
```

## TransferFrom

The function transferFrom(address from, address to, uint256 amount) is a public function and it is marked as override because the contract calls the interfaces IERC20. This function reverts transfer from an address to an address of any amount.

```
function transferFrom(address from, address to, uint256 amount)
external virtual override returns (bool) {
    revert NonTransferable(address(this));
}
```

#### Allowance

The function allowance (address owner, address spender) is a public function and it is marked as override because the contract calls the interfaces <a href="IERC20">IERC20</a>. This function reverts any change of allowance of the remaining tokens that the spender would be allowed to spend on the owner behalf if approve or transferFrom were called

```
function allowance(address owner, address spender) external view
virtual override returns (uint256)
{
    revert NonTransferable(address(this));
}
```

# **Contract wveOLAS**

This contract has been added to address several issues regarding some view functions on the veOLAS contract (cf. <u>Vulnerabilities\_list#1.pdf</u>). Specifically, this contract works as follows

- 1. Maintains the original veOLAS storage behavior;
- 2. The write-to-storage functions of the wveOLAS contract will be reverted with the message that they have to be called by the original veOLAS contract;
- 3. All (non-internal) view functions of the veOLAS contact are wrapped in the wveOLAS contact;
- 4. The view functions of the veOLAS with issues are wrapped and corrected in such a way the corresponding veOLAS functions are only called in their correct behavior.

Thus, the wrapper contract serves the purpose of fixing view functions with issues and forwarding all other view functions to the original veOLAS contract. All the write-to-storage functions must be called directly by the veOLAS contract. The default fallback will revert with the statement mentioning the original veOLAS address.

## Contract-defined data type

It is created the data type PointVoting in the form of a structure.

```
struct PointVoting {
   int128 bias;
```

```
int128 slope;
uint64 ts;
uint64 blockNumber;
uint128 balance;
}
```

### Contract-defined error

```
error ZeroAddress();
The address can't be the zero.

error WrongTimestamp(uint256 minTimeStamp, uint256
providedTimeStamp);
The provided timestamp is smaller than the minimal one.

error ImplementedIn(address veToken);
The called function is implemented in the original veOLAS contract with address veToken.

error NonTransferable(address veToken);
The veToken is non-transferable

error NonDelegable(address veToken);
The veToken is non-delegable
```

#### **Variables**

The following is a public and immutable variable that indicates the veOLAS token address address public immutable ve;

The following is a public and immutable variable that indicates the OLAS token address address public immutable token;

```
The following sets the token name
    string public constant name = "Voting Escrow OLAS";
The following sets the token symbol
    string public constant symbol = "veOLAS";
```

The following sets 18 decimals

```
uint8 public constant decimals = 18;
```

### Constructor

Sets the values for the address of the original veOLAS contract

```
constructor(address _ve, address _token) {
    // Check for the zero address
    if (_ve == address(0)|| _token == address(0)) {
        revert ZeroAddress();
    }
    ve = _ve;
    token = _token;
}
```

### totalNumPoints

The external view function totalNumPoints calls the corresponding original veOLAS state variables.

```
function totalNumPoints() external view returns (uint256
numPoints) {
    numPoints = IVEOLAS(ve).totalNumPoints();
}
```

# mapSupplyPoints

The external view function mapSupplyPoints calls the corresponding original veOLAS state variables (e.g. it returns the supply point with the index number idx)

```
function mapSupplyPoints(uint256 idx) external view returns
(PointVoting memory sPoint);
{
    sPoint = IVEOLAS(ve).mapSupplyPoints(idx);
}
```

## mapSlopeChanges

The external view function mapsSlopeChanges calls the corresponding original veOLAS state variables.

```
function marSlopeChanges(uint64 ts) external view returns
(uint128 slopeChange) {
      slopeChange = IVEOLAS(ve).mapSlopesChanges(ts);
}
```

# getLastUserPoint

The function <code>getLastUserPoint</code> is an external function. This calls the original veOLAS <code>getLastUserPoint</code> method.

```
function getLastUserPoint(address account) external view returns
(PointVoting memory pv) {
         pv = IVEOLAS(ve).getLastUserPoint(account);
    }
```

# getNumUserPoints

The function getNumUserPoints (address account) is an external function. This calls the original veOLAS getNumUserPoints method.

```
function getNumUserPoints(address account) external view returns (uint256
userNumPoints) {
    userNumPoints = IVEOLAS(ve).getNumUserPoints(account);
}
```

# getUserPoint

The public view function getUserPoints (address account, uint256 idx) returns the PointVoting at the point with the number idx recorded for the user with the

address account, if the account has at least one point the function returns the checkpoint structure at the number idx for account (e.g. the original veOLAS getUserPoint is called). Otherwise, an empty structure is returned.

```
function getUserPoint(address account, uint256 idx) public view
returns (PointVoting memory uPoint) {
          // Get the number of user points
          uint256 userNumPoints =

IVEOLAS(ve).getNumUserPoints(account);
          if (userNumPoints > 0) {
                uPoint = IVEOLAS(ve).getUserPoint(account, idx);
          }
}
```

## getVotes

The function getVotes (address account) is an external function. This calls the original veOLAS getVotes method.

```
function getVotes(address account) external view returns (uint256 balance) {
   balance = IVEOLAS(ve).getVotes(account);
}
```

# getPastVotes

The function <code>getPastVotes(address account, uint256 blockNumber)</code> is an external function. When at least one point exists for the account and the <code>blockNumber</code> is not smaller than the block number in which the very first lock for account was made this returns the voting power (e.g. the number of veOLAS) of the account at <code>blockNumber(e.g)</code> the original veOLAS <code>getPastVotes</code> is called). Otherwise, zero is returned.

```
function getPastVotes(address account, uint256 blockNumber)
external view returns (uint256 balance) {
    // Get the zero account point
    PointVoting memory uPoint = getUserPoint(account, 0);
    // Check that the point exists and the zero point block
number is not smaller than the specified blockNumber
```

#### balanceOf

The function balanceOf (address account) is an external function. This calls the original veOLAS balanceOf method.

```
function balanceOf(address account) external view returns
(uint256 balance) {
    balance = IVEOLAS(ve).balanceOf(account);
}
```

### balanceOfAt

The function balanceOfAt (address account, uint256 blockNumber) is an external function. When the blockNumber is not smaller than the block number in which the very first lock for account was made this function returns the (OLAS) balance of the account at the blockNumber (e.g the original veOLAS balanceOfAt is called). Otherwise, zero is returned.

#### lockedEnd

The function lockedEnd(address account) is an external function. This calls the original veOLAS lockedEnd method.

```
function totalSupply() external view returns (uint256 supply) {
    supply = IVEOLAS(ve).totalSupply();
}
```

# totalSupply

The function totalSupply is an external function. This calls the original veOLAS totalSupply method.

```
function totalSupply() external view returns (uint256 supply) {
   supply = IVEOLAS(ve).totalSupply();
}
```

## totalSupplyAt

The function totalSupplyAt (uint256 blockNumber) is an external function. This calls the original veOLAS totalSupplyAt method.

```
function totalSupplyAt(uint256 blockNumber) external view returns
(uint256 supplyAt) {
      supplyAt = IVEOLAS(ve).totalSupplyAt(blockNumber);
   }
```

## totalSupplyLockedAtT

The functionn totalSupplyLockedAtT (uint256 ts) is an external view function. When ts is not smaller than the very last supply point, the function returns the global voting power at time ts (e.g the original veOLAS totalSupplyLockedAtT is called). Otherwise, it is reverted with the WrongTimestamp error.

```
function totalSupplyLockedAtT(uint256 ts) external view returns
(uint256 vPower) {
      // Get the total number of supply points
      uint256 numPoints = IVEOLAS(ve).totalNumPoints();
      PointVoting memory sPoint =
IVEOLAS(ve).mapSupplyPoints(numPoints);
```

```
// Check the last supply point timestamp is not smaller than
the specified ts
    if (ts >= sPoint.ts) {
        vPower = IVEOLAS(ve).totalSupplyLockedAtT(ts);
} else {
        revert WrongTimestamp(sPoint.ts, ts);
}
```

# totalSupplyLocked

The function totalSupplyLocked is an external function. This calls the original veOLAS totalSupplyLocked method.

## getPastTotalSupply

The function <code>getPastTotalSupply(uint256 blockNumber)</code> is an external function. When the <code>blockNumber</code> is not smaller than the very first supply point (e.g. the veOLAS zero supply point) the function returns the global voting power at the specific <code>blockNumber</code> (e.g the original veOLAS <code>getPastTotalSupply</code> is called). Otherwise, the function reverts (instead of returning 0). Note that the latter is kept to preserve the native Curve Voting Escrow behavior that reverts in the case of the wrong <code>blockNumber</code>.

## supportInterface

The function supportsInterface (bytes4 interfaceId) is an external function. This calls the original veOLAS totalSupplyLocked method.

```
function supportsInterface(bytes4 interfaceId) external view returns
(bool) {
    return IVEOLAS(ve).supportsInterface(interfaceId);
}
```

### Transfer

The function transfer (address, uint256) is an external function that reverts any transfer of any amount to an address.

```
function transfer(address, uint256) external virtual (bool)
{
   revert NonTransferable(ve);
}
```

# **Approve**

The function approve (address, uint256) is an external function that reverts any approval of the amount from an address spender

```
function approve(address, uint256) external returns (bool) {
   revert NonTransferable(ve));
}
```

### TransferFrom

The function transferFrom(address address, uint256) is external that reverts transfer from an address to an address of any amount.

```
function transferFrom(address, address, uint256) external (bool)
{
    revert NonTransferable(ve);
}
```

### Allowance

The function allowance (address, address) is an external function that reverts any change of allowance of the remaining tokens that the spender would be allowed to spend on the owner behalf if approve or transferFrom were called

```
function allowance(address, address) external view returns
(uint256)
{
    revert NonTransferable(ve);
}
```

## Delegates

The function delegates (address) is an external function that reverts delegation of the token to the address

```
function delegates(address) external view returns (uint256)
{
    revert NonDelegable(ve));
}
```

# Delegate

The function delegate (address) is an external function that reverts delegate for this token

```
function delegate(address) external
{
    revert NonDelegable(ve);
}
```

# Delegate

The function delegatebySig (address) is an external function that reverts delegatebySig for this token

```
function delegateBySig(address, uint256, uint256, uint8, bytes32,
bytes32) external {
    revert NonDelegable(ve);
}
```

## **Fallback**

The default fallback reverts with the statement mentioning the original veOLAS address.

```
/// @dev Reverts other calls such that the original veOLAS is
used.
    fallback() external {
        revert ImplementedIn(ve);
    }
}
```

# Contract OLAS

The contract imports the Solmate ERC20 token library.

### Contract-defined error

```
error ManagerOnly(address sender, address manager);
Only `manager` has a privilege to take some actions. So ManagerOnly(address sender, address manager) is emitted when an address sender different from the address manager tries an action reserved to the manager.
```

```
error ZeroAddress();
```

Some actions require that the address can't be the zero address.

## **Dependencies**

The contract is a Solmate-based ERC20 token.

### **Events**

The events MinterUpdated and OwnerUpdated are declared.

```
event MinterUpdated(address indexed minter);
event OwnerUpdated(address indexed owner);
```

### **Variables**

The public constant one Year sets one year calculated one year in days

```
uint256 public constant oneYear = 1 days * 365;
```

The public constant tenYearSupplyCap sets the total supply cap for the first ten years at 1 bn (including 18 decimal, as for ERC20 standard, this gives a total of 10^27 units)

```
uint256 public constant tenYearSupplyCap = 1_000_000_000e18;
```

The maxMintCapFraction is a public constant thet fix the maximum of annual inflation after ten years

```
uint256 public constant maxMintCapFraction = 2;
```

The timeLaunch is a public and immutable variable that indicates the initial timestamp of the token deployment

```
uint256 public immutable timeLaunch;
```

The owner is a public variable that indicates the owner's address

```
address public owner;
```

The minter is a public variable that indicates the minter's address

```
address public minter;
```

## Constructor

This contract is ownable with owner =minter = msg.sender and the timeLaunch is the timestamp of the token deployment

```
constructor() ERC20("Autonolas", "OLAS", 18) {
   owner = msg.sender;
   minter = msg.sender;
   timeLaunch = block.timestamp;
}
```

# ChangeOwner

The function changeOwner (address newOwner) is an external function that allows the previous owner of the contract to sets a new owner (with a no-zero address) and emit the event

```
emit OwnerUpdated(newOwner);

function changeOwner(address newOwner) external {
    if (newOwner == address(0)) {
        revert ZeroAddress();
    }

    if (msg.sender != owner) {
        revert OwnerOnly(msg.sender, owner);
    }

    owner = newOwner;
    emit OwnerUpdated(newOwner);
}
```

# ChangeMinter

The function changeMinter (address newMinter) is an external function that allows the owner of the contract to sets a new minter (with a no-zero address) and emit the event

```
emit MinterUpdated(newMinter)

function changeMinter(address newMinter) external {
   if (msg.sender != owner) {
      revert ManagerOnly(msg.sender, owner);
   }

   if (newMinter == address(0)) {
      revert ZeroAddress();
   }
```

```
minter = newMinter;
emit MinterUpdated(newMinter);
}
```

## Mint

The function mint (address account, uint256 amount) is an external function that allows the minter to mint new tokens respecting the inflation constraints.

```
function mint(address account, uint256 amount) external {
    // Access control
    if (msg.sender != minter) {
        revert ManagerOnly(msg.sender, minter);
    }

    // Check the inflation schedule and mint
    if (inflationControl(amount)) {
        _mint(account, amount);
    }
}
```

## InflationControl

The function inflationControl (uint256 amount) is a public function that checks if the amount is less than inflationRemainder.

```
function inflationControl(uint256 amount) public view returns
(bool) {
    uint256 remainder = inflationRemainder();
    return (amount <= remainder);
}</pre>
```

## InflationControl

The function inflationRemainder() is a public function that checks the remainder of OLAS that can be minted with respect to the inflation schedule.

```
function inflationRemainder() public view returns (uint256
remainder) {
        uint256 totalSupply = totalSupply;
        // Current year
        uint256 numYears = (block.timestamp - timeLaunch) / oneYear;
        // Calculate maximum mint amount to date
        uint256 supplyCap = tenYearSupplyCap;
        // After 10 years, adjust supplyCap according to the yearly
inflation % set in maxMintCapFraction
        if (numYears > 9) {
            // Number of years after ten years have passed (including
ongoing ones)
            numYears -= 9;
            for (uint256 i = 0; i < numYears; ++i) {
                supplyCap += (supplyCap * maxMintCapFraction) / 100;
        // Check for the requested mint overflow
        remainder = supplyCap - totalSupply;
    }
```

#### Burn

The function burn() is a public function that calls the Solmate function \_burn(address from, uint256 amount) that burns the amount of tokens from the msg.sender and then subtracts the amount from the total supply.

## DecreasesAllowance

The functiondecreaseAllowance (address spender, uint256 amount) is an external function that allows reducing the quantity amount from the allowance previously given by the msg.sender to the address spender. The following event is emitted emit Approval (msg.sender, spender, spenderAllowance); and the function returns if the operation succeeded.

```
function decreaseAllowance(address spender, uint256 amount)
external returns (bool) {
    uint256 spenderAllowance = allowance[msg.sender][spender];

if (spenderAllowance != type(uint256).max) {
```

```
spenderAllowance -= amount;
allowance[msg.sender][spender] = spenderAllowance;
emit Approval(msg.sender, spender, spenderAllowance);
}
return true;
}
```

## IncreasesAllowance

The function increasesAllowance (address spender, uint256 amount) is an external function that allows increasing the quantity amount form the allowance previously given by the msg.sender to the address spender. The following event is emitted

 $\,$  emit Approval (msg.sender, spender, spenderAllowance); and the function returns if the operation succeeded.

```
function increaseAllowance(address spender, uint256 amount)
external returns (bool) {
    uint256 spenderAllowance = allowance[msg.sender][spender];

    spenderAllowance += amount;
    allowance[msg.sender][spender] = spenderAllowance;
    emit Approval(msg.sender, spender, spenderAllowance);

    return true;
    }
}
```