Your Incentive Guide

Initiative ERP / IDSPL | A simple guide to every calculation sheet

This guide explains how your monthly sales become an incentive amount, how the IDS Fund is built, and how that fund is shared with support teams.

Start with three questions

How much did the outlet sell? The uploaded report provides the sales amount.

How much sales incentive does that produce? The system estimates profit, calculates a base incentive, then applies the outlet's payout share.

How much goes into the IDS Fund? A separate set of category rates builds the fund used for non-sales staff allocations.

> **A useful distinction**
> Base incentive, exact sales payout and IDS Fund are three different amounts. Give each amount its own name when discussing a report, so everyone knows which calculation you mean.

The seven sheets you will see

Sheet name	What it helps you understand
Outlet Summary	The basic calculation for each outlet
Category Incentive	The basic incentive for each main category
Grouped Incentive	Sales and incentive for each category/group in the upload
Sales Incentive	The sales payout after applying the outlet/group share
IDS Fund	How each category contributes to the fund
IDS Fund Outlet Summary	The total fund contributed by each outlet
Non-sales Staff Incentive	How the fund is shared with support departments

How to use this guide

Read the basic example first, then follow the sheet that you need to check. All amounts in the examples are in rupees and use made-up sales figures. They are not actual employee payments.

Based on the local incentive code reviewed on 8 October 2026. This explains the current system; it does not change the company's incentive policy.

Get the Sales File Ready

01 / A good upload makes the calculation easier to trust

Before you upload

1. Choose the month or reporting period you want to calculate.
2. Prepare an Excel .xlsx / .xlsm file, or a PDF with readable text.
3. Check the outlet, category and sales amount in each row.
4. Make sure the same sales are not repeated on several sheets.
5. After uploading, compare the system's sales totals with your original report.

Names the system recognizes

Outlet name	Short name in the report
Alambagh	ALM
Ashiyana	ASH
Hazratganj	HZT
Gomtinagar	GNG
Vikas Nagar	VKN

The incentive calculation uses these five outlets. Rows for other outlets are excluded from the calculation.

Category codes are **HA, HE, MOB, COM, DC, ACC and ACC COM**. The system recognizes ACC COM separately from COM and ACC.

Small details that affect totals

One period per file is easiest to check. The system can read a month field, but its calculation combines all uploaded months. It does not produce a separate incentive total for each month.

Repeated rows need attention. Identical parsed rows can be removed within a single sheet. Repeated sales on different sheets can still be added together.

Excel formulas need saved results. The importer reads the last saved formula values. Open and save the file in Excel first if those values are missing or outdated.

Check PDFs carefully. This importer reads text, not scanned pictures. On a matching line, it takes the last number as the sales amount. A line with several amounts may need checking.

> The parser prefers recognized detail rows over total rows when details exist. Uploaded applied percentages or payout amounts do not replace the fixed payout rules used by the sales calculation.

Numbers in brackets are treated as negative. Currency symbols and commas are removed when reading amounts. Rate parsing treats values from 0 to 1 as fractions, so numeric 1 becomes 100%.

From Sales to Base Incentive

02 / Outlet Summary, Category Incentive and Grouped Incentive

Imagine your outlet sold Rs. 100,000 during the month. Here is how the basic calculation works at the default rates.

Step 1: estimate the average profit

> **Rs. 100,000 × 7% = Rs. 7,000**

The 7% is an editable estimate used for incentives. It is not a calculation from the actual cost of each product.

Step 2: calculate the base incentive

> **Rs. 7,000 × 2.5% = Rs. 175**

The 2.5% rate is also editable. The system rounds profit to two decimal places first, then calculates and rounds the base incentive.

Where the same calculation appears

Sheet	What sales are used?
Outlet Summary	All accepted sales for one outlet
Category Incentive	Sales for one outlet and one of the six main categories
Grouped Incentive	Sales for one outlet/category group in the upload

Why category totals can differ

The Category Incentive sheet lists HA, HE, MOB, COM, DC and ACC. It does not list ACC COM. Outlet Summary and Grouped Incentive can include ACC COM.

For example, Rs. 100,000 in each of all seven categories gives outlet sales of **Rs. 700,000** and a base incentive of **Rs. 1,225**. The six-category calculation uses Rs. 600,000 and produces Rs. 1,050. The Rs. 175 difference belongs to ACC COM.

When you edit a downloaded sheet
These three sheets contain calculated amounts, rather than formulas that update every value. Changing a sales cell does not automatically update its profit or incentive. Re-upload corrected data to obtain a fresh calculation.

Grand totals are calculated from combined sales, rather than by adding all rounded row incentives. A small rounding difference can therefore be expected. The exported category sheet lists category rows, without the API's category-total row.

Your Sales Payout

03 / Sales Incentive sheet: apply the outlet share

The base incentive is the starting amount. The Sales Incentive sheet applies the share assigned to each outlet or category group.

> **Exact sales payout = Base incentive × Applied share**

Outlet	Sales included	Share
ALM	HA + HE	85%
ALM	MOB + DC + ACC + ACC COM	13%
ALM	COM	78%
ASH	All categories	100%
GNG	All categories	52%
HZT	HA + HE	65%
HZT	MOB + COM + DC + ACC + ACC COM	60%
VKN	All categories	55%

Walk through an ALM example

Suppose ALM has Rs. 100,000 of HA sales and Rs. 100,000 of HE sales.

1. Add the sales: Rs. 200,000.
2. Estimate profit at 7%: Rs. 14,000.
3. Calculate the base incentive at 2.5%: Rs. 350.
4. Apply ALM's 85% share: **Rs. 297.50**.

Compare all five outlets

With Rs. 100,000 sales in each of seven categories at every outlet:

Outlet	Total exact sales payout
ALM	Rs. 525.00
ASH	Rs. 1,225.00
GNG	Rs. 637.00
HZT	Rs. 752.50
VKN	Rs. 673.75
Total	Rs. 3,813.75

Each group's payout is rounded to two decimals. Zero-sales groups are omitted. The shorter accessories group labels in the app also include ACC COM. The exported sales sheet stores calculated values; it does not recalculate when you edit sales elsewhere.

How the IDS Fund Is Built

04 / A separate category-based calculation

The IDS Fund uses fixed category rates. The editable 7% profit and 2.5% base incentive rates do not drive this calculation.

Two steps for each category

1. **Category sales × Category rate = Category incentive**
2. **Category incentive × Fund share = IDS Fund contribution**

Category	ALM / ASH / GNG / VKN rate	HZT rate	Fund share
MOB	0.125%	0.125%	30%
COM	0.25%	0.25%	20%
DC	0.25%	0.25%	25%
HA	0.25%	0.25%	20%
HE	0.25%	0.25%	25%
ACC	1%	0.5%	25%
ACC COM	1%	0.25%	25%

A mobile-sales example

If mobile sales are Rs. 100,000, the category incentive is Rs. 100,000 × 0.125% = **Rs. 125**. The fund receives 30% of Rs. 125, which is **Rs. 37.50**.

Why HZT's accessories contribution is different

For Rs. 100,000 in ACC sales, ALM contributes Rs. 1,000 × 25% = Rs. 250. HZT contributes Rs. 500 × 25% = Rs. 125 because its ACC rate is 0.5%.

Example fund totals

With Rs. 100,000 sales in each of seven categories at every outlet:

Outlet	Category incentive total	IDS Fund
Each of ALM, ASH, GNG, VKN	Rs. 3,125.00	Rs. 762.50
HZT	Rs. 1,875.00	Rs. 450.00
All five outlets	Rs. 14,375.00	Rs. 3,500.00

Both calculation steps are rounded to two decimals. Category fund amounts are then added by outlet. If a retained row has no rate or fund share, related fund totals are marked pending. If no recognized fund rows can be made from an upload, the system flags insufficient data.

Sharing the Fund with Teams

05 / Non-sales Staff Incentive sheet

Once each outlet's IDS Fund is known, the system calculates department allocations using the following percentages.

Outlet	Accounts	Customer Care	Support	HO
ALM	35%	12%	15%	15%
ASH	35%	12%	15%	10%
HZT	35%	12%	15%	12%
GNG	35%	12%	15%	10%
VKN	35%	12%	15%	10%

Example: ALM's fund is Rs. 762.50

Accounts receives Rs. 762.50 × 35% = Rs. 266.875, rounded to **Rs. 267**. Customer Care receives Rs. 92; Support receives Rs. 114; HO receives Rs. 114.

Example allocations for all five outlets

Outlet	Fund	Accounts	Customer Care	Support	HO
ALM	762.50	267	92	114	114
ASH	762.50	267	92	114	76
HZT	450.00	158	54	68	54
GNG	762.50	267	92	114	76
VKN	762.50	267	92	114	76
Totals	3,500.00	1,226	422	524	396

Ware House uses the combined fund

> **Rs. 3,500 × 16% = Rs. 560.00 for Ware House**

The warehouse amount appears on a separate MWH row. It is calculated once from the combined fund. Outlet allocations are rounded to whole rupees; Ware House is rounded to two decimals.

These example department amounts total **Rs. 3,128**. The system does not automatically assign the remaining fund balance to a department.

If one outlet is missing
The backend leaves that outlet's amounts blank and adds the funds that are available for Ware House. Department totals can be partial. Check that all expected outlets have data before treating a total as complete.

Rounding can differ between backend values and Excel formulas at exact halfway amounts: Python round(2.5) gives 2, while Excel ROUND(2.5,0) gives 3. Floating-point precision can also affect a result.

What the Excel Formulas Do

06 / A practical reference for checking the calculation sheets

IDS Fund: follow one row

The first data row is row 5. C holds sales, D the category rate, E the category incentive, F the fund share and G the fund amount. Rates are stored as fractions: 30% is stored as 0.30.

```
E5 = IF(ISNUMBER(D5),ROUND(C5*D5,2),"Pending")
G5 = IF(AND(ISNUMBER(E5),ISNUMBER(F5)),
  ROUND(E5*F5,2),"Pending")
```

In ordinary language: calculate the amount only when the required rate or value is numeric. Otherwise, display Pending. The grand incentive and fund totals require every data row to contain a number.

IDS Fund Outlet Summary: add one outlet's rows

Column B adds the matching G cells from the IDS Fund sheet. For example:

```
='IDS Fund'!G5+'IDS Fund'!G6
```

This sheet starts its data on row 3. Adding a text Pending value directly can cause an Excel error, so check the source fund rows when an outlet total looks wrong.

Non-sales sheet: percentages first, amounts below

Rows 2-6 contain outlet fund links and allocation percentages. Row 7 contains the warehouse pool. Rows 11-15 calculate outlet department amounts; row 16 calculates Ware House. Central Service totals appear on row 18, with the HO subtotal first placed in G17.

```
C11 = IF(ISNUMBER(B2),ROUND(B2*C2,0),"Pending")
B7 = IF(COUNT(B2:B6)=5,SUM(B2:B6),"Pending")
D16 = IF(ISNUMBER(B7),ROUND(B7*D7,2),"Pending")
```

C is Accounts, D Ware House, E Customer Care, F Support and G HO. Other department calculations follow the same pattern as C11.

Open the workbook in Excel before relying on formulas
The exporter writes formulas but does not calculate them. Excel must recalculate the workbook. Formula-linked fund and non-sales sheets can update after edits; the basic and exact sales sheets remain the originally calculated values.

An upload with no recognized fund rows produces an unusual empty total range in the full workbook. Check this case rather than treating the output as a completed report.

Check Your Report Before Sharing

07 / Choose the right export and review the results

Choose what you need

Export	What you receive
Full report	Seven-sheet Excel workbook with summaries, IDS Fund formulas and non-sales formulas
SALES	Calculated exact sales payout report, in Excel or PDF
NON SALES	Calculated support-team allocations, in Excel or PDF
BOTH	Sales and non-sales reports together, in Excel or PDF

A current full-workbook issue to check

HZT and GNG can receive the wrong linked fund
The fund summary lists all five outlets in the order ALM, ASH, GNG, HZT, VKN. The non-sales formula sheet labels them ALM, ASH, HZT, GNG, VKN but links by row number. With all five present, HZT and GNG therefore receive each other's fund. Missing outlets can shift other links as well.

The backend calculation matches funds by outlet name. The selected SALES / NON SALES / BOTH exports use those backend amounts. This guide identifies the full-workbook linking issue; no application code has been changed.

Why exports may differ

The full workbook's warehouse formula waits for five numeric outlet funds. The backend selected report uses funds that are available. Excel department totals may also omit Pending text and show partial totals. Rounding rules can produce further differences.

A simple final checklist

1. Confirm that the file covers the period you intended.
2. Match outlet sales to the original report.
3. Check whether ACC COM explains a category-total difference.
4. Confirm the profit, incentive and payout percentages.
5. Check all expected outlet funds, especially HZT and GNG in the full workbook.
6. Recalculate Excel and investigate Pending or error cells.
7. Label the figures clearly: base incentive, exact sales payout or IDS Fund.

Technical reference: /api/incentive/export creates the full workbook. /api/incentive/selected-export creates sales, non-sales or both. /api/incentive/exact-export creates the sales report only.

Source: main.py calculation and export functions, plus static/incentive.html. Examples explain the current implementation and are not approved payroll amounts.