TOS Arno Puder



#### Objectives


- Introduction to process management of an operating system
- Explain step-by-step how processes are created in TOS

#### Introduction to Processes

- What is a process?
  - A process consists of the program code, the data, the heap and the stack
  - A process image is created out of a program with the intention to be executed (e.g., \*.exe files under Windows)
- Single tasking
  - There is only one process. The CPU dedicates complete processing time to one process


#### From Single to Multitasking

- Two identical computers each run a process independently.
- Each computer has its own RAM and CPU, and therefore its own registers EIP, ESP, etc.
- Note that each process has its own code, heap and stack space.
- Idea: move both processes into one computer.
- Problem: then we only have one CPU and one set of registers but two processes!
- Solution: multitasking (time sharing; work a bit on one process and then work a bit on the other process)




#### Multitasking

- Being able to run more than one process "at the same time"
- Several processes time-share one CPU
- Each process has its own program code, memory and stack as shown in the picture



#### Sharing the CPU



#### Types of Multitasking

- Cooperative multitasking running process voluntarily relinquishes control
- Preemptive multitasking running process is suspended involuntary (e.g., because of a hardware interrupt) and control given to another process
- In both cases, "program scheduler" decides next process to run
- Deciding which process to run next is called Scheduling

#### **Process Context**


- What is the process context?
  - State of a process consisting of all the x86 registers, heap and stack.
- Where is process context used?
  - Each process needs its own EIP and ESP registers. Since there is only one "copy" of those registers, they must be shared by all processes. EIP and ESP are set for the currently running process. If another process is scheduled to run, the values of EIP and ESP are saved and re-loaded for the next process to run. This is called a *context switch*.

#### Introducing TOS Processes

- TOS can have up to 20 processes.
- A process is a C-function (remember pointers to functions?)
- All TOS processes share the global variables, but each process has its own stack
- The context of each process is stored in a PCB (Process Control Block)
- Each process has a priority.
  - Priorities are used to decide which process to run next
  - Priorities must be between 0 (lowest) and 7 (highest)
- All runnable processes are added to a ready queue
- Relevant API:
  - create process(): Creates a new process
  - add ready queue(): Add a process to the ready queue
  - remove\_ready\_queue(): Remove a process from the ready queue
  - dispatcher(): Select a runnabel process
  - resign(): Voluntarily relinquish control of the CPU

#### Process Control Block (PCB)

- Each TOS process has a PCB record
- One PCB record describes the context of exactly one TOS process
- Since there are a maximum of 20 processes, the PCB is an array with 20 PCB records.




## TOS PCB: struct PCB

- This is the definition of the PCB structure in TOS as defined in the common header ~/tos/kernel/kernel.h
- PROCESS is a C-pointer to a PCB entry
- Many of the fields will become clear later
- Where are the x86 registers saved? On the stack!

```
typedef struct PCB {
    unsigned
                     magic;
    unsigned
                     used;
    unsigned short priority;
    unsigned short
                     state;
    MEM ADDR
                     esp;
    PROCESS
                     param proc;
    void*
                     param data;
                     first port;
    PORT
                     next blocked;
    PROCESS
    PROCESS
                     next;
    PROCESS
                     prev;
    char*
                     name;
} PCB;
typedef PCB* PROCESS;
```

#### **TOS Ready Queue**

- TOS Ready Queue maintains list of runnable processes
- ready\_queue is an 8 elementsized array ordered by process priority (0 == lowest; 7 == highest)
- Priority is required to react quickly to interrupts
- Processes with same priority form circular double-linked list within that level
- Ready queue used to select next process to run
- Global variable active\_proc points to process that the CPU is currently executing
- PCB.next and PCB.prev are used to implement the double linked list.



# Maintaining the Ready Queue

- void add ready queue (PROCESS p)
  - Changes the state of process p to ready (p->state = STATE\_READY)
  - Process p is added to the ready queue
  - Process p is added at the tail of the double linked list for the appropriate priority level.
  - p->priority determines to which priority level the process is added in the ready queue
  - automatically maintains the double-linked list
- void remove\_ready\_queue (PROCESS p)
  - Process p is removed from the ready queue
  - After the removal of the process, the ready queue should be a doublelinked list again with process p removed.

#### CPU Scheduling

- Round Robin Scheduling: Tasks just take turns, rotate through all tasks
- Priority Scheduling: Higher-priority tasks are scheduled before lower-priority tasks (e.g., interactive applications get favored over background computation)
- Real-Time Scheduling: OS makes specific guarantees about when a task will be scheduled




#### Scheduling

- PROCESS dispatcher() returns the next to be executed process.
- Only processes that are on the ready queue are eligible for selection. The assumption is that there is always at least one process on the ready queue.
- Global variable active\_proc of type PROCESS always points to the process (i.e., PCB slot) that currently owns the CPU.
- The next process is selected based on active proc:
  - If there is a process with a higher priority than active\_proc->priority, then that process will be chosen.
  - Otherwise, active\_proc->next will be chosen (Round-Robin within the same priority level).

#### **TOS Process Creation**

- TOS is one executable file that gets created by the linker
- The name of this executable is tos.img
- During booting, this file gets loaded to address 4000 into RAM.
- A process in TOS is a C-function with the following signature:

 All TOS processes share the same code and heap space but still need different stack space.



#### TOS Process Entry Point

- A C-function designates a process in TOS.
- The process needs to be explicitly created (next slide).
- If void process\_a (PROCESS, PARAM) is a TOS process, then process\_a defines the entry point of this process, i.e. the new process will start executing from process\_a().
- The new process is given the input parameters of type PROCESS and PARAM. The latter is defined as an unsigned long in ~/tos/include/kernel.h
- The first parameter points to the PCB entry for the newly created process and the second parameter is an application-specific parameter passed from parent to child process.

### Creating a TOS process

- New TOS process can be created via create process()
- This function is located in file ~/tos/kernel/process.c
- Signature: PORT create\_process(void (\*func) (PROCESS, PARAM), int prio, PARAM param, char\* name)

**Input:** func: function pointer that defines the entry point of

the process to be created.

param: a parameter that the parent process can pass

to the child process.

prio: Priority of the process.  $0 \le \text{prio} \le 7$ 

name: Clear text name for the process (e.g. "Boot

process")

Output: For now, this function simply returns a NULL pointer.

The meaning of data type PORT will be explained later.

#### Example: create\_process()

```
void test process (PROCESS self, PARAM param)
    // assert(k memcmp(self->name,
                        "Test process",
                        k strlen("Test process")+1)
                                       == 0);
    // assert (param == 42)
void kernel main()
    // ...
    create_process(test_process, 5, 42,
                    "Test process");
```

#### create\_process()


What does create process (func, prio, param, name) do?

- -Allocates an available PCB entry
- -Initializes the elements of this PCB entry

```
PCB.magic = MAGIC_PCB
PCB.used = TRUE
PCB.state = STATE_READY
PCB.priority = prio
PCB.first_port = NULL
PCB.name = name
```

- Allocates an available 30KB stack frame for this process
- Initializes an initial stack frame (see next slide)
- Saves the stack pointer to PCB.esp
- Adds the new process to the ready queue
- Returns a NULL pointer

#### Stack of the new process




Address ∞ will be saved in PCB.esp

# TOS

#### Printing the PCB

- It is useful to get a list of all processes. Similar to 'ps' command in Unix
- This is done via functions print process() and print all processes() located in file ~/tos/kernel/process.c
- TOS functions:
  - void print\_process (WINDOW\* wnd, PROCESS proc)
    print the details of process proc to window wnd
  - void print\_all\_processes (WINDOW\* wnd)
     print the details of all processes currently existing in TOS to window wnd
- The following process information should be displayed:
  - Name of the process (PCB.name)
  - State of the process (PCB.state)
  - Priority of the process (PCB.priority)
- The process that is currently active (I.e., the process where active\_proc is pointing to) should also be marked by a flag
- The following screenshot show how the output could look like. You don't necessarily have to follow the exact same layout. The screenshot is taken from test create process 3.

## Sample Layout for print\_all\_processes()



#### Note on Initializing

- There are some global variables in TOS that need to be initialized at startup.
- Those variables are initialized in C-functions called init \*():
  - init\_dispatcher(): initialize the global variables associated with the ready queue
  - init\_process(): initialize the global variables associated with process creation
- Those init-functions need to be called from kernel\_main() in order to initialize everything correctly.
- The test functions included in TOS call these functions for you. If you run a test program there is no need to call the init-functions explicitly

#### ~/tos/kernel/main.c

```
#include <kernel.h>
void kernel main()
    init process();
    init dispatcher();
    init ipc();
    init interrupts();
    init null process();
    init timer();
    init com();
    init keyb();
    init shell();
    while (1);
```

#### init\_process()

- When initializing the process sub-system, the first (i.e., current) process becomes the boot process.
- Use PCB[0] for the boot process. Use the following parameters to initialize the PCB entry for the boot process:

```
PCB[0].magic = MAGIC_PCB
PCB[0].used = TRUE
PCB[0].state = STATE_READY
PCB[0].priority = 1
PCB[0].first_port = NULL
PCB[0].name = "Boot process"
```

Note: PCB[0].esp does not need to be initialized (why?)



#### Assignment 3

- Implement the functions located in ~/tos/kernel/dispatch.c: add\_ready\_queue(), remove\_ready\_queue(), dispatcher(), init dispatcher()
- Implement the functions located in ~/tos/kernel/process.c: create\_process(), print\_process(), print\_all\_processes(), init\_process()
- Test cases:


```
test_create_process_1test_create_process_2test_create_process_3test_create_process_4test_create_process_5
```

Hint: no inline assembly necessary for this assignment!



#### PacMan (1)

- Remember: The purpose of the PacMan application is a simple game as a showcase for some of the TOS API. You are encouraged to implement it in order to gain a deeper understanding of the TOS API.
- The next stage of PacMan can be implemented when assignment 3 is completed.
- In this next stage, a new TOS process is created for each ghost.



#### PacMan (2)

Here is how to define the ghost process:

```
void ghost_proc(PROCESS self, PARAM param)
{
    create_new_ghost();
}
```

- Note that the signature of ghost\_proc follows the conventions of a TOS process.
- Now you can create several ghost processes in init\_pacman()
   via:

```
int i;
for (i = 0; i < num_ghosts; i++)
    create_process(ghost_proc, 3, 0, "Ghost");</pre>
```

 Note: since we have not yet implemented a context switch, creating a ghost will not do anything! Ghost processes will be created, but not yet scheduled. This will only be possible after the next assignment!