```
- MODULE CSComm -
EXTENDS Sequence Utils
CONSTANTS
    Client.
               the set of clients
    Server,
               the (unique) server
    Msg
                the set of messages
VARIABLES
    cincoming,
                     cincoming[c]: incoming FIFO channel at client c \in Client
    sincoming
                     incoming FIFO channel at the Server
TypeOK \; \stackrel{\triangle}{=} \;
     \land cincoming \in [Client \rightarrow Seq(Msg)]
          sincoming \in Seq(Msg)
Init \triangleq
     \land cincoming = [c \in Client \mapsto \langle \rangle]
     \land sincoming = \langle \rangle
EmptyChannel \triangleq Init
CSend(m) \triangleq A client sends a message m to the Server.
     \land sincoming' = Append(sincoming, m)
     ∧ UNCHANGED cincoming
CRev(c) \stackrel{\Delta}{=} Client c receives and consumes a message from the Server.
       \land cincoming[c] \neq \langle \rangle
       \land \ cincoming' = [cincoming \ \texttt{EXCEPT} \ ! [c] = Tail(@)]
       \land UNCHANGED sincoming
SRev \triangleq
            The Server receives and consumes a message.
     \land sincoming \neq \langle \rangle
     \land sincoming' = Tail(sincoming)
SSend(c, cm) \stackrel{\Delta}{=} The Server sents a message <math>cm[cl] to client cl (other than c).
    cincoming' = [cl \in Client \mapsto if \ cl = c \ Then \ cincoming[cl]]
                                         ELSE Append(cincoming[cl], cm[cl])
SSendSame(c, m) \stackrel{\Delta}{=} The Server broadcasts the message m to all clients other than c.
    SSend(c, [cl \in Client \mapsto m])
\* Modification History
\ Last modified Sat Jan 19 16:28:48 CST 2019 by anonymous
* Created Sun Jun 24 10:25:34 CST 2018 by anonymous
```