SUPPORT (HTTPS://SUPPORT.F5.COM)

■ CloudDocs Home (/) > F5 BIG-IP Container Ingress Services (../../index.html) > OpenShift/Kubernetes

Multi-Cluster

PDF

OpenShift/Kubernetes Multi-Cluster¶

This page documents a new feature in CIS for Multi-Cluster.

O Note

To provide feedback on Container Ingress Services or this documentation, please file a GitHub Issue (https://github.com/F5Networks/k8s-bigip-ctlr/issues).

Contents¶

Overview

Topologies

Configuration

multicluster_extended_configmap

multicluster_examples

multicluster_userguides

multicluster_known_issues

multicluster_faq

Overview¶

CIS Multi-Cluster support allow users to expose multiple applications spread across OpenShift/Kubernetes clusters using a single BIG-IP Virtual Server. An application can be deployed in different OpenShift/Kubernetes clusters exposing them using a ServiceTypeLB/Route/VS/TS CR resource. Using a Multi-Cluster implementation, the CIS can be deployed in a High Availability topology or Standalone CIS (see Topologies) to expose the application spread across OpenShift/Kubernetes clusters.

Note

At present, nodePort mode is supported and Cluster mode is available with static route configuration on BIG-IP (No tunnels).


Prerequisites¶

- The API server of all OpenShift/Kubernetes clusters must be accessible by the cluster node where CIS is installed.
- ExtendedConfigMap should be created to run the CIS in Multi-Cluster mode.
- The CIS should have access to Kube-config files for each cluster in order to reach resources such as Pods, Services, Endpoints, and Nodes.

Topologies¶

Standalone CIS¶

When using a Standalone setup, CIS is solely installed on a single cluster. There are two modes supported in the Standalone CIS, namely *default* and *ratio*. - The *default* mode is supported with VS/TS CRs and ServiceType LB, see Default Mode (default.html#defaultmode-overview). - The *ratio* mode is supported with VS/TS CRs and routes, see Ratio Mode (ratio-acive-mode.html#ratio-mode).



High Availability CIS¶

The High Availability (HA) CIS offers three supported modes: default, active-active, and ratio.

- The *default* mode is supported with VS/TS CRs and ServiceType LB, see Default Mode (default.html#defaultmode-overview).
- The *Active-Active* mode is supported with VS/TS CRs and routes, see Active-Active Mode (ratio-acive-mode.html#active-mode).
- The ratio mode is supported with VS/TS CRs and routes, see Ratio Mode (ratio-acive-mode.html#ratio-mode).


Prerequisites¶

- A pair of high availability OpenShift/Kubernetes clusters should be available, which have the same applications running in both clusters.
- The primary cluster should have an available HealthCheck endpoint for checking its health. Currently, Health endpoints using TCP/HTTP are supported.

 For a HA deployment of CIS, it is necessary to install CIS on both the primary and secondary cluster. Additionally, the extendedConfigMap must be deployed on both clusters as well.

O Note

- For HA mode [namely default, active-active, ratio], CIS monitored resource manifests such as routes, CRDs, extendedConfigmaps, and multiCluster serviceTypeLB must be available on both the clusters.
- The CIS monitored resource manifests must be identical on both the primary and secondary clusters. So that, incase of CIS failover, CIS on secondary cluster will take control and start processing the CIS monitored resource manifests.
- CIS on secondary cluster will not process the CIS monitored resource manifests if they are not available in secondary cluster.



Configuration¶

If you are using multi-cluster mode, *—multi-cluster-mode* and *—local-cluster-name* are required parameters.

Parameter	Туре	Required	Description	Allowed Values
Multi- cluster-	String	Required	Specify whether CIS is running standalone or as	Standalone or primary or
mode			primary/secondary in the case of a high availability topology.	secondary
Local- cluster- name	String	Required	Specify the cluster name where CIS is running.	A valid cluster name defined in the extendedConfigMap
extended- spec- configmap	String	Required	extendedSpecConfigMap is required to configure the multi-cluster configuration	1

O Note

Here **standalone** refers to standalone topology of CIS deployment, see Standalone CIS.

Following is the sample deployment for primary CIS deployment:

```
spec:
 containers:
 - args:
   --bigip-partition
   - <partition>
    - --bigip-url
    - <ip-address>
   - --bigip-username
    - <user-name>
    --bigip-password
    - <password>
    --log-level
   - DEBUG
    --insecure
    --controller-mode=openshift
    --extended-spec-configmap=kube-system/extended-spec-config
    - --route-label=systest
    --pool-member-type
    nodeport
    --multi-cluster-mode=primary
    - --local-cluster-name=cluster1
    command:
    - /app/bin/k8s-bigip-ctlr
    image: <image-name>
```

O Note

- Update the multi-cluster-mode to secondary for secondary CIS deployment in high availablility topology, see :ref: `ha_cis.
- Update the multi-cluster-mode to standalone for standalone topology, see
 Standalone CIS.
- Update the local-cluster-name to the cluster name where CIS is running.
- To configure the extendedConfigMap in default mode in standalone topology, see
 Configuring Extended ConfigMap for StandAlone (default.html#extended-configmap-standalone).
- To configure the extendedConfigMap in default mode in high availability topology, see

Configuring Extended ConfigMap for High Availability (HA) (default.html#extended-configmap-ha).

- To configure the extendedConfigMap in active-active mode, see Active-Active Mode (ratio-acive-mode.html#active-mode).
- To configure the extendedConfigMap in ratio mode in standalone topology, see Ratio Mode (ratio-acive-mode.html#ratio-mode).
- To configure the extendedConfigMap in ratio mode in high availability topology, see
 Ratio Mode (ratio-acive-mode.html#ratio-mode).
- To configure the VS CR in default mode, see Virtual Server Support (default.html#vs-defaultsupport).
- . To configure the VS CR in active-active and ratio mode, see

Virtual Server Support (ratio-acive-mode.html#vs-activeratiosupport).

- To configure the TS CR in default mode, see Transport Server Support (default.html#tsdefaultsupport).
- To configure the TS CR in active-active and ratio mode, see Transport Server Support (ratio-acive-mode.html#ts-activeratiosupport).
- To configure the routes in default mode, see Routes Support (default.html#routedefaultsupport).
- To configure the routes in active-active and ratio mode, see Routes Support (ratio-active-mode.html#route-activeratiosupport).
- To configure the ServiceTypeLB in default mode, see Service Type Load Balancer Support (default.html#stlb-defaultsupport).
- ServiceTypeLB is not supported in active-active and ratio mode.

FAQ¶

Is -multi-cluster-mode a required parameter for Multi-Cluster support?

Yes. Multi-Cluster support only works if *—multi-cluster-mode* is defined in the CIS deployment.

Is extended configMap mandatory for Multi-Cluster support?

Yes. Multi-Cluster support only works with extended configmap.

Is local-cluster-name mandatory for Multi-Cluster support?

Yes. Multi-Cluster support only works if *—local-cluster-name* is defined in the CIS deployment.

Does extended configmap update require CIS restart?

No. It is recommended to restart CIS if any HA configuration or external cluster configurations are updated in extended Configmap. However, CIS restart is not required when updating ratio in the extended Configmap.

Does mode update require CIS restart?

Yes. CIS has to be restarted when there is a change in the mode.

How do you add a new cluster?

On this page:

To add a new cluster, create a *kube-config* file with read only permissions. Then create a Kubernetes secret using the *kube-config* file. Refer this in secret in the extended ConfigMap to add the new cluster. CIS dynamically reads the new *kube-roenfig* of the new cluster and starts listening to the services and endpoints in the new cluster when a route refers this new cluster.

▼ Topologies

Where do you manage the manifest or Configuration Objects like Routes, CRDs, Standalone CIS ExtendedConfigmaps etc.?

High Availability CIS Manifests or Configuration objects are managed centrally in Primary Cluster. If CIS HA is desired, the same manifests are expected to be in Secondary Cluster. Prerequisites

What are the supported CNIs?

Configuration

Currently, NodePort mode is supported. For cluster mode, static routing mode is supported to enable configuration of static routes on BIG-IP for pod network subnets for direct routing from BIG-IP to k8s Pods.

What kind of providers are supported?

CIS supports Hybrid Cloud, any public Cloud providers such as; AWS, Azure, GCP, On-Prem, VmWare, and Tanzu etc. which is in same network/datacenter and can communicate with each other.

What kind of clusters are supported?

CIS multicluster solution is currently validated with openshift clusters and Kubernetes clusters.

How does CIS start as a secondary Cluster?

CIS recognizes a Secondary cluster when it starts with a deployment parameter —multicluster-mode is set to secondary.

How does Secondary CIS learn about the Primary Cluster endpoint state in HA mode?

Both of the CIS will communicate with both K8s API servers and prepares the AS3 declaration. But, the secondary CIS only sends the declaration when the Primary cluster's health probe fails. As soon as primary cluster comes up, the secondary CIS stops sending the declaration.

What kind of permission is required for HA or StandAlone deployment of CIS?

No RBAC change for CIS deployment with multiCluster support. Only additional *kube-config* configuration with read only permission is required to access the endpoints from external cluster.

What kind of permission is required to access external clusters (apart from HA and StandAlone)?

CIS requires read-only permission in *kube-config* of external clusters to access resources like Pods/Services/Endpoints/Nodes.

Can CIS manage multiple BIG-IPs?

No. CIS can manage only Standalone BIG-IP or HA BIG-IP. In other words, CIS acts as a single point of BIG-IP Orchestrator and supports Multi-Cluster.

Does Secondary CIS require resource manifests existing in Primary Cluster?

Yes. CIS on Secondary Cluster will not process the CIS monitored resource manifests [NextGen Routes, CRDs, ServiveTypeLB, extendedConfigmap] if they are not available in Primary Cluster. This is required in case of CIS failover, CIS on Secondary Cluster will take control and will start processing the CIS monitored resource manifests. It is suggested to maintain identical CIS monitored resource manifests in both the clusters to avoid any issues during CIS failover. This requirement is applicable in case of CIS HA mode [namely default, active-active, ratio].

How to configure the primaryEndPoint in HA mode?

The primaryEndPoint is a mandatory parameter if CIS is intended to run in Multi-Cluster HA mode [namely default, active-active, ratio]. If this is not specified, the secondary CIS will not run. Secondary CIS will continuously monitor the health of the primary cluster based on the primaryEndPoint value. If it is down, then the secondary CIS takes the responsibility of posting declarations to BIG-IP. Supported Protocols for the primaryEndPoint are HTTP and TCP. Generally, it is suggested to use the primaryEndPoint as:

- a. Any available endpoint to check the health of the primary cluster.
- b. Primary CIS cluster's health check endpoint (/health) if accessible.
- c. Primary CIS cluster's kube-api server endpoint if accessible. Response code 200 OK is expected from the primaryEndPoint in case of HTTP Protocol. Successful TCP connection is expected from the primaryEndPoint in case of TCP Protocol. Secondary CIS become active if the primaryEndPoint is not accessible. PrimaryEndPoint is optional to configure for Primary CIS.

• Note

Primary CIS will not monitor the health of the Secondary CIS cluster.

How to configure the primaryEndPoint in Standalone mode?

The primaryEndPoint is not applicable in Standalone mode. It is only applicable in HA mode.

How to use CIS / health endpoint to check the health of CIS?

Retrieve the CIS PodIP and incorporate it into the curl command displayed below from any of the cluster nodes.

```
curl http://<CIS-PodIP>:8080/health
```

Response code 200 OK is expected from the CIS /health endpoint if kube-api server is accessible. Example:

```
[root@cluster-1-worker0 ~]# curl http://10.244.1.213:8080/health
Ok[root@cluster-1-worker0 ~]# curl http://10.244.1.213:8080/health -v
* About to connect() to 10.244.1.213 port 8080 (#0)
    Trying 10.244.1.213...
* Connected to 10.244.1.213 (10.244.1.213) port 8080 (#0)
> GET /health HTTP/1.1
> User-Agent: curl/7.29.0
> Host: 10.244.1.213:8080
> Accept: */*
>
< HTTP/1.1 200 0K
< Date: Thu, 07 Dec 2023 08:28:57 GMT
< Content-Length: 2
< Content-Type: text/plain; charset=utf-8
<
* Connection #0 to host 10.244.1.213 left intact
0k[root@cluster-1-worker0 ~]#
```

where 10.244.1.213 is the CIS PodIP.

Are the custom resources like TS and VS are same in all modes(default, active-active, ratio)?

No, Custom resources like TS and VS are different in default mode and non-default mode. See Default Mode (default.html#defaultmode-overview) for default mode and Overview (ratio-acive-mode.html#ratiomode-overview) for active-active and ratio mode.

Are the routes supported in all modes (default, active-active, ratio)?

No, Routes are only supported in active-active and ratio mode See Overview (ratio-acive-mode.html#ratiomode-overview) for active-active and ratio mode.

Are policy CR supported in all modes (default, active-active, ratio)?

Yes, Policy CR is supported in all modes same as non-multi-cluster mode.

• Previous (../ipam/faq.html)

Next **②** (../../reference/index.html)

HAVE A QUESTION? | Support and Sales > (https://www.f5.com/company/contact)

FOLLOW US

ABOUT F5

Corporate Information (https://www.f5.com/company)

Newsroom (https://www.f5.com/company/news)

Investor Relations (https://www.f5.com/company/investor-relations)

Careers (https://www.f5.com/company/careers)

About Clouddocs (/csp/about)

EDUCATION

Training (https://www.f5.com/services/training)

Certification (https://www.f5.com/services/certification)

LearnF5 (https://account.f5.com/learnf5)

Free Online Training (https://www.f5.com/services/training/free-training-courses)

F5 SITES

F5.com (https://www.f5.com)

DevCentral (https://community.f5.com)

Support Portal (https://my.f5.com/)

Partner Central (https://partnercentral.f5.com)

F5 Labs (https://www.f5.com/labs)

SUPPORT TASKS

Read Support Policies (https://www.f5.com/services/support/support-offerings/support-policies)

Create Service Request (https://my.f5.com/manage/s/createcase)

Leave Feedback [+]

©2024 F5, Inc. All rights reserved.

Cookie Preferences